

AIX 5L Version 5.1



System User's Guide: Operating System and Devices

AIX 5L Version 5.1



System User's Guide: Operating System and Devices

Second Edition (April 2001)

Before using the information in this book, read the general information in "Appendix B. Notices" on page 263.

This edition applies to AIX 5L Version 5.1 and to all subsequent releases of this product until otherwise indicated in new editions.

(c) Copyright KnowledgeSet Corporation, Mountainview, California, 1990.

(c) Copyright AT&T, 1984, 1985, 1986, 1987, 1988, 1989. All rights reserved.

This software and documentation is based in part on the Fourth Berkeley Software Distribution under license from The Regents of the University of California. We acknowledge the following institutions for their role in its development: the Electrical Engineering and Computer Sciences Department at the Berkeley Campus.

The Rand MH Message Handling System was developed by the Rand Corporation and the University of California. Portions of the code and documentation described in this book were derived from code and documentation developed under the auspices of the Regents of the University of California and have been acquired and modified under the provisions that the following copyright notice and permission notice appear:

Copyright Regents of the University of California, 1986, 1987, 1988, 1989. All rights reserved.

Redistribution and use in source and binary forms are permitted provided that this notice is preserved and that due credit is given to the University of California at Berkeley. The name of the University may not be used to endorse or promote products derived from this software without specific prior written permission. This software is provided "as is" without express or implied warranty.

Copyright (c) 1993, 1994 Hewlett-Packard Company

Copyright (c) 1993, 1994 International Business Machines Corp.

Copyright (c) 1993, 1994 Sun Microsystems, Inc.

Copyright (c) 1993, 1994 Novell, Inc.

All rights reserved. This product and related documentation are protected by copyright and distributed under licenses restricting its use, copying, distribution, and decompilation. No part of this product or related documentation may be reproduced in any form by any means without prior written authorization.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the United States Government is subject to the restrictions set forth in DFARS 252.227-7013 (c)(1)(ii) and FAR 52.227-19.

THIS PUBLICATION IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT.

THIS PUBLICATION COULD INCLUDE TECHNICAL INACCURACIES OR TYPOGRAPHICAL ERRORS. CHANGES ARE PERIODICALLY ADDED TO THE INFORMATION HEREIN; THESE CHANGES WILL BE INCORPORATED IN NEW EDITIONS OF THE PUBLICATION. HEWLETT-PACKARD COMPANY, INTERNATIONAL BUSINESS MACHINES CORP., SUN MICROSYSTEMS, INC., AND UNIX SYSTEMS LABORATORIES, INC., MAY MAKE IMPROVEMENTS AND/OR CHANGES IN THE PRODUCT(S) AND/OR THE PROGRAM(S) DESCRIBED IN THIS PUBLICATION AT ANY TIME.

© Copyright International Business Machines Corporation 1997, 2001. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About This Book	xiii
Who Should Use This Book	xiii
Highlighting	xiii
ISO 9000	xiii
Related Publications	xiii
Trademarks	xiii
Chapter 1. Login Names, System IDs, and Passwords	1
Related Information	2
Login and Logout Overview	2
Logging In to the Operating System	2
Logging in More Than One Time (login Command)	3
Becoming Another User on a System (su Command)	3
Suppressing Login Messages	4
Logging Out of the Operating System (exit and logout Commands)	4
Stopping the Operating System (shutdown Command)	4
Related Information	5
User and System Identification	5
Displaying Your Login Name (whoami and logname Commands)	5
Displaying the Operating System's Name (uname Command)	6
Displaying Your System's Name (uname Command)	6
Displaying Who Is Logged In (who Command)	6
Displaying User IDs (id Command)	7
Related Information	7
Passwords	8
Password Guidelines	8
Changing Your Password (passwd Command)	8
Setting Your Password to Null (passwd Command)	9
Related Information	10
Command Summary for Login Names, System IDs, and Passwords	10
Login and Logout Commands	10
User and System Identification Commands	10
Password Command	10
Related Information	10
Chapter 2. User Environment and System Information	11
Listing the Devices in Your System (lscfg Command)	11
Displaying the Name of Your Console (lscons Command)	12
Displaying the Name of Your Terminal (tty Command)	13
Listing Available Displays (lsdisp Command)	13
Listing the Available Fonts (lsfont Command)	13
Listing Keyboard Maps (lskbd Command)	14
Listing Software Products (lspp Command)	14
Listing Control Key Assignments for Your Terminal (stty Command)	15
Listing All Your Environment Variables (env Command)	15
Related Information	16
Displaying the Value of an Environment Variable (printenv Command)	16
Working with Bidirectional Languages (aixterm Command)	17
Related Information	17
Command Summary for User Environment and System Information	17
Related Information	17
Chapter 3. Commands and Processes	19

Related Information	20
Commands Overview	20
Command Syntax	20
Reading Usage Statements	22
Using Web-based System Manager	22
Using the smit Command	23
Locating a Command or Program (whereis Command)	23
Displaying Information about a Command (man Command)	23
Displaying the Function of a Command (whatis Command)	24
Listing Previously Entered Commands (history Shell Command)	24
Repeating Commands Using the Shell history Command	25
Substituting Strings Using the Shell history Command	26
Editing the Command History	26
Creating a Command Alias (alias Shell Command)	27
Working with Text-Formatting Commands	28
Related Information	29
Processes Overview	30
Foreground and Background Processes	30
Daemons	31
Zombie Process	31
Starting a Process	31
Checking Processes (ps Command)	32
Setting the Initial Priority of a Process (nice Command)	33
Changing the Priority of a Running Process (renice Command)	33
Canceling a Foreground Process	34
Stopping a Foreground Process	34
Restarting a Stopped Process	34
Scheduling a Process for Later Operation (at Command)	35
Listing All Scheduled Processes (at or atq Command)	36
Removing a Process from the Schedule (at Command)	37
Removing a Background Process (kill Command)	37
Related Information	38
Command Summary for Commands and Processes	38
Commands	38
Processes	38
Related Information	39
Chapter 4. Input and Output Redirection	41
Standard Input, Standard Output, and Standard Error	41
Redirecting Standard Output	42
Redirecting Output to a File	42
Redirecting Output and Appending It to a File	43
Creating a Text File with Redirection from the Keyboard	43
Concatenating Text Files	43
Redirecting Standard Input	43
Discarding Output with the /dev/null File	44
Redirecting Standard Error and Other Output	44
Inline Input (Here) Documents	45
Pipes and Filters	45
Displaying Program Output and Copying It to a File (tee command)	46
Clearing Your Screen (clear Command)	46
Sending a Message to Standard Output (echo Command)	47
Appending a Single Line of Text to a File (echo Command)	47
Copying Your Screen to a File (capture and script Commands)	47
Displaying Text in Large Letters on Your Screen (banner Command)	48
Related Information	49

Command Summary for Input and Output Redirection	49
Related Information.	49
Chapter 5. File Systems and Directories	51
Related Information.	51
File Systems	52
File System Types	52
File System Structure	53
Showing Space Available on File System (df Command)	54
Related Information.	54
Directory Overview	55
Types of Directories	55
Directory Organization.	56
Directory Naming Conventions	56
Directory Path Names	56
Directory Abbreviations	57
Related Information.	57
Directory Handling Procedures	58
Creating a Directory (mkdir Command)	58
Moving or Renaming a Directory (mvdir Command)	59
Displaying Your Current Directory (pwd Command)	59
Changing to Another Directory (cd Command)	59
Copying a Directory (cp Command).	60
Displaying Contents of a Directory (ls Command).	61
Deleting or Removing a Directory (rmdir Command).	62
Comparing Contents of Directories (dircmp Command).	63
Related Information.	63
Command Summary for File Systems and Directories	64
File Systems	64
Directory Abbreviations	64
Directory Handling Procedures	64
Related Information.	64
Chapter 6. Files	67
Types of Files	68
Regular Files	68
Directory Files.	68
Special Files	68
File Naming Conventions	69
File Path Names.	69
Pattern Matching with Wildcards and Metacharacters	69
Pattern Matching versus Regular Expressions	70
Related Information.	71
File Handling Procedures	71
Deleting Files (rm Command)	72
Moving and Renaming Files (mv Command)	72
Copying Files (cp Command)	73
Finding Files (find Command)	74
Showing File Type (file Command)	75
Displaying File Contents (pg, more, page, and cat Commands)	76
Finding Strings in Text Files (grep Command)	77
Sorting Text Files (sort Command)	77
Comparing Files (diff Command)	78
Counting Words, Lines, and Bytes in Files (wc Command)	79
Displaying the First Lines of Files (head Command).	79
Displaying the Last Lines of Files (tail Command)	80

Cutting Sections of Text Files (cut Command)	80
Pasting Sections of Text Files (paste Command)	81
Numbering Lines in Text Files (nl Command)	82
Removing Columns in Text Files (colrm Command)	82
Related Information.	83
Linking Files and Directories	83
Types of Links	84
Linking Files (ln Command).	84
Removing Linked Files	85
Related Information.	85
DOS Files	86
Copying DOS Files to Base Operating System Files.	86
Copying Base Operating System Files to DOS Files.	87
Deleting DOS Files	87
Listing Contents of a DOS Directory	87
Related Information.	88
Command Summary for Files	88
File Handling Procedures	88
Linking Files and Directories	89
DOS Files	89
Chapter 7. Printers, Print Jobs, and Queues	91
Printer Terminology	91
Print Job.	91
Queue	91
Queue Device.	92
qdaemon	92
Print Spooler	92
Real Printer	92
Virtual Printer	92
Local and Remote Printers	93
Printer Backend	93
Starting a Print Job (qprt Command)	93
Prerequisites	94
qprt Command	94
smit Command	96
Canceling a Print Job (qcan Command)	96
Prerequisites	96
qcan Command	96
smit Command	97
Checking Print Job Status (qchk Command)	97
Prerequisites	97
Web-based System Manager Fast Path	97
qchk Command	97
smit Command	98
Printer Status Conditions.	98
Prioritizing a Print Job (qpri Command)	98
Prerequisites	98
qpri Command	99
smit Command	99
Holding and Releasing a Print Job (qhld Command).	99
Prerequisites	99
Web-based System Manager Fast Path	99
qhld Command	99
smit Command	100
Moving a Print Job to Another Print Queue (qmov Command).	100

Prerequisites	100
qmov Command	100
smit Command	100
Formatting Files for Printing (pr Command)	100
Printing ASCII Files on a PostScript Printer	102
Prerequisites	102
Automating the Conversion of ASCII to PostScript	103
Overriding Automatic Determination of Print File Types	103
Related Information	104
Command Summary for Printers, Print Jobs, and Queues	104
Related Information	104
Chapter 8. Backup Files and Storage Media	105
Backup Policy	105
Backup Media	106
Formatting Diskettes (format or fdformat Command)	107
Checking the Integrity of the File System (fsck Command)	108
Copying to or from Diskettes (fscopy Command)	109
Copying Files to Tape or Disk (cpio -o Command)	109
Copying Files from Tape or Disk (cpio -i Command)	110
Copying to or from Tapes (tcopy Command)	111
Checking the Integrity of a Tape (tapechk Command)	111
Compressing Files (compress and pack Commands)	111
compress Command	112
pack Command	112
Expanding Compressed Files (uncompress and unpack Commands)	113
uncompress Command	113
unpack Command	113
Backing Up Files (backup Command)	114
backup Command	114
smit Command	115
Restoring Backed-Up Files (restore Command)	115
restore Command	115
smit Command	116
Archiving Files (tar Command)	116
Related Information	117
Command Summary for Backup Files and Storage Media	117
Related Information	118
Chapter 9. File and System Security	119
Security Threats	119
Basic Security	119
File Ownership and User Groups	121
Changing File or Directory Ownership (chown Command)	121
File and Directory Access Modes	121
Displaying Group Information (lsgroup Command)	123
Changing File or Directory Permissions (chmod Command)	125
Access Control Lists	126
Base Permissions	126
Extended Permissions	126
Access Control List Example	127
Access Authorization	128
Displaying Access Control Information (aclget Command)	129
Setting Access Control Information (aclput Command)	129
Editing Access Control Information (acledit Command)	130
Locking Your Terminal (lock or xlock Command)	130

Command Summary for File and System Security	130
Related Information	131
Chapter 10. Customizing the User Environment.	133
Related Information	133
System Startup Files Overview	134
/etc/profile File	134
/etc/environment File	135
.profile File	135
.env File	136
AIXwindows Startup Files Overview	136
.xinitrc File	137
.Xdefaults File	138
.mwmrc File	139
Related Information	140
Customization Procedures	141
Exporting Shell Variables (export Shell Command)	141
Changing the Display's Font (chfont Command)	141
Changing Control Keys (stty Command)	142
Changing Your System Prompt	143
Related Information	143
Customizing the InfoExplorer Windows Program	144
Changing Defaults in the InfoExplorer Window Interface	144
Changing Preferences in the InfoExplorer Window Interface	145
Summary for User Environment Customization	147
System Startup Files	147
AIXwindows Startup Files	147
Customization Procedures	147
Related Information	147
Chapter 11. Shells	149
Shell Features	150
Available Shells.	151
Shells Terms	152
Creating and Running a Shell Script	153
Specifying a Shell for a Script File	154
Related Information	154
Korn Shell or POSIX Shell Commands	155
Korn Shell Compound Commands	156
Functions	157
Quoting in the Korn Shell or POSIX Shell	158
Reserved Words in the Korn Shell or POSIX Shell	159
Command Aliasing in the Korn Shell or POSIX Shell	160
Tracked Aliases.	161
Tilde Substitution	161
Parameter Substitution in the Korn Shell or POSIX Shell	161
Parameters in the Korn Shell.	161
Parameter Substitution	162
Predefined Special Parameters	163
Variables Set by the Korn Shell or POSIX Shell	164
Variables Used by the Korn Shell or POSIX Shell	164
Command Substitution in the Korn Shell or POSIX Shell	165
Arithmetic Evaluation in the Korn Shell or POSIX Shell	166
Field Splitting in the Korn Shell or the POSIX Shell	168
File Name Substitution in the Korn Shell or POSIX Shell	168
Quote Removal.	169

Input and Output Redirection in the Korn Shell or POSIX Shell	169
Coprocess Facility	171
Exit Status in the Korn Shell or POSIX Shell	172
Korn Shell or POSIX Shell Commands	172
Korn Shell Environment	173
Shell Startup	173
Korn Shell or POSIX Shell Command History	174
Korn Shell or POSIX Shell Built-In Commands	174
Special Built-in Command Descriptions	175
Regular Built-in Command Descriptions	180
List of Korn Shell or POSIX Shell Built-in Commands	184
Special Built-in Commands	184
Regular Built-in Commands	184
Conditional Expressions for the Korn Shell or POSIX Shell	185
Job Control in the Korn Shell or POSIX Shell	186
Signal Handling	187
Inline Editing in the Korn Shell or POSIX Shell	187
emacs Editing Mode	188
vi Editing Mode	189
Enhanced Korn Shell (ksh93)	192
Features of ksh93	192
Korn Shell Related Information	195
Bourne Shell	196
Bourne Shell Environment	196
Restricted Shell	197
Bourne Shell Commands	198
Quoting Characters	199
Signal Handling	199
Bourne Shell Compound Commands	200
Reserved Words	200
Bourne Shell Built-In Commands	201
Special Command Descriptions	201
Command Substitution in the Bourne Shell	204
Variable and File Name Substitution in the Bourne Shell	205
Variable Substitution in the Bourne Shell	205
User-Defined Variables	205
Conditional Substitution	209
Positional Parameters	210
File Name Substitution in the Bourne Shell	210
Character Classes	210
Input and Output Redirection in the Bourne Shell	211
List of Bourne Shell Built-in Commands	211
Bourne Shell Related Information	212
C Shell	212
C Shell Limitations	213
Signal Handling	214
C Shell Commands	214
C Shell Built-In Commands	214
C Shell Command Descriptions	215
C Shell Expressions and Operators	220
Command Substitution in the C Shell	221
Nonbuilt-in C Shell Command Execution	222
History Substitution in the C Shell	222
History Lists	222
Event Specification	223
Quoting with Single and Double Quotes	224

Alias Substitution in the C Shell	225
Variable and File Name Substitution in the C Shell	226
Variable Substitution in the C Shell	226
File Name Substitution in the C Shell	227
File Name Expansion	227
File Name Abbreviation	228
Character Classes.	229
Environment Variables in the C Shell	229
Input and Output Redirection in the C Shell	231
Control Flow	232
Job Control in the C Shell	232
List of C Shell Built-in Commands	232
C Shell Related Information	234
Chapter 12. Miscellaneous Tools and Utilities	235
Locating a Command by Keyword (apropos Command)	235
Displaying a Calendar (cal Command)	235
Displaying Reminder Messages (calendar Command)	236
Displaying Help Information for New Users (help Command)	236
Starting Computer-Aided Instruction Courses (learn Command)	237
Reminding Yourself When to Leave (leave Command)	237
Factoring a Number (factor Command)	238
Converting Units of Measure (units Command)	238
Sending Messages to Another Logged-In User (write Command)	240
Related Information	242
Command Summary for Miscellaneous Tools and Utilities	243
Related Information	243
Chapter 13. Documentation Library Service	245
Introduction	245
Using the Documentation Library Service	245
How to Change the Documentation Library Service Language	246
Appendix A. Accessing Information with InfoExplorer	249
Using the InfoExplorer ASCII Interface	249
Using InfoExplorer Screens	249
Using Menus.	250
Getting Help	250
Getting Started	250
Starting the InfoExplorer ASCII Program	251
Recognizing Screen Types	251
Selecting a Hypertext Link.	252
Scrolling Information	252
Selecting a Menu Option	253
Returning to a Previous Location	253
Searching for Information	254
Printing Information	256
Accessing Help.	257
Using Special Keys and Key Sequences	258
Starting an Alternate InfoExplorer Library	259
Stopping the InfoExplorer ASCII Program	259
Customizing the InfoExplorer ASCII Program	260
Changing Defaults in the InfoExplorer ASCII Interface	260
Changing Preferences in the InfoExplorer ASCII Interface	261
X Resources Available for the InfoExplorer Program	262

Appendix B. Notices	263
Index	265

About This Book

This book contains information for novice system users who want to acquire greater expertise with the operating system. It covers information such as running commands, handling processes, handling files and directories, and printing. In addition, it introduces system commands covering tasks such as securing files, using storage media, customizing environment files (**.profile**, **.Xdefaults**, **.mwmrc**), and writing shell scripts. For DOS users, this guide presents procedures on using DOS files in this environment.

Users in a networked environment who are interested in learning more about operating system communications commands should read the *AIX 5L Version 5.1 System User's Guide: Communications and Networks*.

Who Should Use This Book

This book is intended for all system users.

Highlighting

The following highlighting conventions are used in this book:

Bold	Identifies commands, keywords, files, directories, and other items whose names are predefined by the system.
<i>Italics</i>	Identifies parameters whose actual names or values are to be supplied by the user.
Monospace	Identifies examples of specific data values, examples of text similar to what you might see displayed, examples of portions of program code similar to what you might write as a programmer, messages from the system, or information you should actually type.

ISO 9000

ISO 9000 registered quality systems were used in the development and manufacturing of this product.

Related Publications

The following books contain pertinent information:

- *Quick Beginnings*
- *AIX 5L Version 5.1 System User's Guide: Communications and Networks*
- *AIX 5L Version 5.1 System Management Guide: Operating System and Devices*
- *AIX 5L Version 5.1 Guide to Printers and Printing*
- *AIX 5L Version 5.1 Commands Reference*
- *AIX 5L Version 5.1 Files Reference*
- *Common Desktop Environment 1.0: User's Guide*

Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States, other countries, or both:

- AIX
- AIXwindows
- IBM
- RS/6000

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, or service names may be the trademarks or service marks of others.

Chapter 1. Login Names, System IDs, and Passwords

The operating system must know who you are in order to provide you with the correct environment. To identify yourself to the operating system, log in by entering your *login name* (also known as your user ID or user name) and a *password*. Passwords are a form of security. People who know your login name cannot log in to your system unless they know your password.

If your system is set up as a multiuser system, each authorized user will have an account, password, and login name on the system. The operating system keeps track of the resources used by each user. This is known as *system accounting*. Each user will be given a private area in the storage space of the system, called the *file system*. When you log in, the file system appears to contain only your files, although there are thousands of other files on the system.

It is possible to have more than one valid login name on a system. If you want to change from one login name to another, you do not have to log out of the system. Rather, you can use the different login names simultaneously in different shells or consecutively in the same shell without logging out. In addition, if your system is part of a network with connections to other systems, you can log in to any of the other systems where you have a login name. This is referred to as a *remote login*.

When you have finished working on the operating system, you log out to ensure that your files and data are secure.

This section discusses the following:

- “Login and Logout Overview” on page 2
 - “Logging In to the Operating System” on page 2
 - “Logging in More Than One Time (login Command)” on page 3
 - “Becoming Another User on a System (su Command)” on page 3
 - “Suppressing Login Messages” on page 4
 - “Logging Out of the Operating System (exit and logout Commands)” on page 4 (exit and logout Commands)
 - “Stopping the Operating System (shutdown Command)” on page 4
- “User and System Identification” on page 5
 - “Displaying Your Login Name (whoami and logname Commands)” on page 5
 - “Displaying the Operating System’s Name (uname Command)” on page 6
 - “Displaying Your System’s Name (uname Command)” on page 6
 - “Displaying Who Is Logged In (who Command)” on page 6
 - “Displaying User IDs (id Command)” on page 7
- “Passwords” on page 8
 - “Password Guidelines” on page 8
 - “Changing Your Password (passwd Command)” on page 8
 - “Setting Your Password to Null (passwd Command)” on page 9
- “Command Summary for Login Names, System IDs, and Passwords” on page 10

Related Information

“Chapter 3. Commands and Processes” on page 19

“Chapter 9. File and System Security” on page 119

“Chapter 2. User Environment and System Information” on page 11

“Chapter 10. Customizing the User Environment” on page 133

“Chapter 11. Shells” on page 149

“Korn Shell or POSIX Shell Commands” on page 172

“Bourne Shell” on page 196

“C Shell” on page 212

Login and Logout Overview

To use the operating system, your system must be running and you must be logged in. When you log in to the operating system, you identify yourself to the system and allow the system to set up your environment.

This section describes the following procedures:

- “Logging In to the Operating System”
- “Logging in More Than One Time (login Command)” on page 3
- “Becoming Another User on a System (su Command)” on page 3
- “Suppressing Login Messages” on page 4
- “Logging Out of the Operating System (exit and logout Commands)” on page 4
- “Stopping the Operating System (shutdown Command)” on page 4

Logging In to the Operating System

You need to start a session on your system before beginning to work on your system. After your system is turned on, just log in to the system to start a session.

Your system might be set up so that you can only log in during certain hours of the day and on certain days of the week. If you attempt to log in at a time other than the time allowed, your access will be denied. Your system administrator can verify what your login times are.

You log in at the login prompt. When you log in to the operating system, you are automatically placed into your home directory (also called your *login directory*).

If Your Machine Is Not Turned On

1. Set the power switches of each attached device to On.
2. Set the key mode switch on the system unit to Normal.
3. Start the system unit by setting the power switch to On (I).
4. Look at the three-digit display. When the self-tests complete without error, the three-digit display is blank.

If an error requiring attention occurs, a three-digit code remains, and the system unit stops. Consult your system administrator or refer to the *Messages Guide and Reference* for more information about error codes and recovery.

When the self-tests complete successfully, a login prompt similar to the following appears on your screen:

```
login:
```

If the login prompt does not display, consult your system administrator.

If Your System Is Already Turned On

1. Type your login name following the `login:` prompt and press Enter:

```
login: LoginName
```

For example, if your login name is `denise`:

```
login: denise
```

2. If the `password:` prompt appears, type your password and press Enter. (The screen does not display your password as you type it in.)

```
password: [your password]
```

If the password prompt does not appear, you have no password defined; you can begin working in the operating system.

After you have logged in, depending on how your operating system is set up, your system will start up in a command line interface (shell) or a graphical interface (for example, AIXwindows or Common Desktop Environment (CDE)).

Logging in More Than One Time (login Command)

You can have more than one concurrent login. You do this by using the same login name or by using different login names to log in to your system. This can be useful if you are working on more than one project and want to maintain separate accounts.

Note: Each system has a maximum number of login names that can be active at any given time. This number is determined by your license agreement and varies among installations.

For example, if your other login name is `denise2`, at the prompt, type:

```
login denise2
```

If the `password:` prompt appears, type your password and press Enter. (The screen does not display your password as you type it in.)

You now have two logins running on your system.

See the **login** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Becoming Another User on a System (su Command)

The **su** (switch user) command enables you to change the user ID associated with a session, if you know that user's login name.

For example, if you want to switch and become user `joyce`, at the prompt type:

```
su joyce
```

If the `password:` prompt appears, type `joyce`'s password and press Enter. If you don't know the password, the request is denied.

Your user ID is now `joyce`.

To verify that your user ID is joyce, use the **id** command. For more information on the **id** command, see “Displaying User IDs (id Command)” on page 7.

See the **su** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Suppressing Login Messages

After a successful login, the **login** command displays the message of the day, the date and time of the last successful and unsuccessful login attempts for this user, and the total number of unsuccessful login attempts for this user since the last change of authentication information (usually a password). These messages are suppressed if there is a **.hushlogin** file in your home directory.

At the prompt in your home directory, type:

```
touch .hushlogin
```

The **touch** command creates the empty file named **.hushlogin** if it doesn't exist.

The next time you log in, all login messages will be suppressed. You can instruct the system to retain the message of the day, while suppressing other login messages.

See the **touch** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Logging Out of the Operating System (exit and logout Commands)

At the prompt, do one of the following:

Press the end-of-file control key-sequence (Ctrl-D keys).

OR

Type **exit** and press Enter.

OR

Type **logout** and press Enter.

After you log out, the system displays the **login:** prompt.

See the **logout** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Attention: Do not turn off the system. Turning off the system ends all processes running on the system. If other users are working on the system, or if jobs are running in the background, data might be lost. Perform proper shutdown procedures before you stop the system.

Stopping the Operating System (shutdown Command)

If you have root user authority, you can use the **shutdown** command to stop the system. Do not turn off the power to your system without using the **shutdown** command. This can result in lost data. If you are not authorized to use the **shutdown** command, simply log out of the operating system and leave it running. .

At the prompt, type:

```
shutdown
```

When the **shutdown** command completes and the operating system stops running, you receive the following message:

```
....Shutdown completed....
```

See the **shutdown** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Related Information

“Chapter 3. Commands and Processes” on page 19

“Chapter 9. File and System Security” on page 119

“Chapter 2. User Environment and System Information” on page 11

“Chapter 10. Customizing the User Environment” on page 133

User and System Identification

The following procedures describe different commands available for displaying information that identifies users on your system and the system you are using.

- “Displaying Your Login Name (whoami and logname Commands)”
- “Displaying the Operating System’s Name (uname Command)” on page 6
- “Displaying Your System’s Name (uname Command)” on page 6
- “Displaying Who Is Logged In (who Command)” on page 6
- “Displaying User IDs (id Command)” on page 7

Displaying Your Login Name (whoami and logname Commands)

When you have more than one concurrent login, it is often easy to lose track of the login names or, in particular, the login name being used at the time.

whoami Command

To determine which login name is being used, at the prompt, type:

```
whoami
```

The system displays information similar to the following:

```
denise
```

In this example, the login name is denise.

See the **whoami** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

who am i Command

A variation of the **who** command, the **who am i** command displays the login name, terminal name, and time of the login.

At the prompt, type:

```
who am i
```

The system displays information similar to the following:

```
denise pts/0 Jun 21 07:53
```

In this example, the login name is denise, the name of the terminal is pts/0, and this user logged in at 7:53 a.m. on June 21.

See the **who** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

logname Command

Another variation of the **who** command, the **logname** command displays the same information as the **who** command.

At the prompt, type:

```
logname
```

The system displays information similar to the following:

```
denise
```

In this example, the login name is denise.

See the **logname** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying the Operating System's Name (uname Command)

The **uname** command displays the name of the operating system that you are using.

For example, at the prompt, type:

```
uname
```

The system displays information similar to the following:

```
AIX
```

In this example, the operating system name is AIX.

See the **uname** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying Your System's Name (uname Command)

The **uname** command used with the **-n** flag displays the name of your system if you are on a network. Your system name identifies your system to the network, it is not the same as your login ID.

For example, at the prompt, type:

```
uname -n
```

The system displays information similar to the following:

```
barnard
```

In this example, the system name is barnard.

See the **uname** command in the *AIX 5L Version 5.1 Commands Reference Book* for more information and the exact syntax.

Displaying Who Is Logged In (who Command)

The **who** command displays information about all users currently on the local system. The following information is displayed: login name, workstation name, and date and time of login.

Note: This command only identifies users on the local node.

To display information about who is using the local system node, type:

```
who
```

The system displays information similar to the following:

```
joe 1ft/0 Jun 8 08:34  
denise pts/1 Jun 8 07:07
```

In this example, the user `joe`, on terminal `1ft/0`, logged in at 8:34 a.m. on June 8.

See the **who** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying User IDs (id Command)

The **id** command displays the system identifications (IDs) for a specified user. The system IDs are numbers that identify users and user groups to the system. The **id** command displays the following information, when applicable:

- User name and real user ID
- Name of the user's group and real group ID
- Name of the user's supplementary groups and supplementary group IDs, if any.

For example, at the prompt, type:

```
id
```

The system displays information similar to the following:

```
uid=1544(sah) gid=300(build) euid=0(root) egid=9(printq) groups=0(system),10(audit)
```

In this example, the user has user name `sah` with an ID number of 1544; a primary group name of `build` with an ID number of 300; an effective user name of `root` with an ID number of 0; an effective group name of `printq` with an ID number of 9; and two supplementary group names of `system` and `audit`, with ID numbers 0 and 10, respectively.

For example, at the prompt, type:

```
id denise
```

The system displays information similar to the following:

```
uid=2988(denise) gid=1(staff)
```

In this example, the user `denise` has an ID number of 2988 and only has a primary group name of `staff` with an ID number of 1.

See the **id** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Related Information

“Chapter 3. Commands and Processes” on page 19

“Chapter 9. File and System Security” on page 119

“Chapter 2. User Environment and System Information” on page 11

“Chapter 10. Customizing the User Environment” on page 133

Passwords

Your system associates a password with each account. A unique password provides some system security for your files. System use and data are valuable resources that require protection. Security is an important part of computer systems because it keeps unauthorized people from gaining access to the system and from tampering with other users' files. Security can also allow some users exclusive privileges to which commands they can use and which files they can access. For protection, some system administrators only permit the users access to certain commands or files.

This section describes the following procedures:

- "Password Guidelines"
- "Changing Your Password (passwd Command)"
- "Setting Your Password to Null (passwd Command)" on page 9

Password Guidelines

You should have a unique password. *Passwords should not be shared.* Protect passwords as any other company asset. When creating passwords, make sure they are difficult to guess, but not so difficult that you have to write them down to remember them.

Using obscure passwords keeps your user ID secure. Passwords based on personal information, such as your name or birthday, are poor passwords. Even common words can be easily guessed.

Good passwords have at least six characters and include nonalphabetic characters. Strange word combinations and words purposely misspelled are also good.

Note: If your password is so hard to remember that you have to write it down, it is not a good password.

Use the following guidelines when selecting a password:

- Do not write passwords down. However, if you must write them down, place them in a physically secure place, such as a locked cabinet.
- Do not use your user ID as a password. Do not use it reversed, doubled, or otherwise modified.
- Do not reuse passwords. The system might be set up to deny the reuse of passwords.
- Do not use any person's name as your password.
- Do not use words that can be found in the online spelling-check dictionary as your password.
- Do not use passwords shorter than six characters.
- Do not use obscene words; they are some of the first ones checked when guessing passwords.
- Do use passwords that are easy to remember, so you won't have to write them down.
- Do use passwords that use both letters and numbers and that have both lowercase and uppercase letters.
- Do use two words, separated by a number, as a password.
- Do use pronounceable passwords. They are easier to remember.

Changing Your Password (passwd Command)

Use the **passwd** command to change your password.

1. At the prompt, type:

```
passwd
```

If you do not have a password, skip step 2.

2. The following prompt appears:

```
Changing password for UserID
UserID's Old password:
```

This request keeps an unauthorized user from changing your password while you are away from your system. Type your current password and press Enter.

3. The following prompt appears:

```
UserID's New password:
```

Type the new password you want and press Enter.

4. The following prompt appears, asking for you to reenter your new password.

```
Enter the new password again:
```

This request protects you from setting your password to a mistyped string that you can not recreate.

Examples

1. To change the password of the user denise, type:

```
passwd
```

Press Enter.

The system displays information similar to the following:

```
Changing password for "denise"
denise's Old password:
denise's New password:
Type the new password again:
$
```

2. The following example enters the current password incorrectly:

```
$ passwd
Changing password for "denise"
denise's Old password:
Your entry does not match the old password.
You are not authorized to change "denise's" password.
$
```

3. The following example reenters the new password incorrectly:

```
$ passwd
Changing password for "denise"
denise's Old password:
denise's New password:
Enter the new password again:
The password entry does not match, please try again.
denise's New password:
Enter the new password again:
$
```

See the **passwd** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Setting Your Password to Null (passwd Command)

If you do not want to enter a password each time you login, set your password to null.

To set your password to NULL (blank), type:

```
passwd
```

When prompted for the new password, press Enter or Ctrl-D.

The **passwd** command does not prompt again for a password entry. A message verifying the NULL password is displayed.

See the **passwd** command in the *AIX 5L Version 5.1 Commands Reference Book* for more information and the exact syntax.

Related Information

“Chapter 3. Commands and Processes” on page 19

“Chapter 9. File and System Security” on page 119

“Chapter 2. User Environment and System Information” on page 11

“Chapter 10. Customizing the User Environment” on page 133

Command Summary for Login Names, System IDs, and Passwords

Login and Logout Commands

login	Initiates your session.
logout	Stops all your processes.
shutdown	Ends system operation.
su	Changes the user ID associated with a session.
touch	Updates the access and modification times of a file, or creates an empty file.

User and System Identification Commands

id	Displays the system identifications of a specified user.
logname	Displays login name.
uname	Displays the name of the current operating system.
who	Identifies the users currently logged in.
whoami	Displays your login name.

Password Command

passwd	Changes a user's password.
---------------	----------------------------

Related Information

“Chapter 3. Commands and Processes” on page 19

“Chapter 9. File and System Security” on page 119

“Chapter 2. User Environment and System Information” on page 11

“Chapter 10. Customizing the User Environment” on page 133

Chapter 2. User Environment and System Information

Each login name has its own system environment. The system environment is an area where information common to all processes running in a session is stored. There are also commands you can use to display information about your system.

This section discusses the following procedures for displaying information about your environment.

- “Listing the Devices in Your System (lscfg Command)”
- “Displaying the Name of Your Console (lscons Command)” on page 12
- “Displaying the Name of Your Terminal (tty Command)” on page 13
- “Listing Available Displays (lsdisp Command)” on page 13
- “Listing the Available Fonts (lsfont Command)” on page 13
- “Listing Keyboard Maps (lskbd Command)” on page 14
- “Listing Software Products (lspp Command)” on page 14
- “Listing Control Key Assignments for Your Terminal (stty Command)” on page 15
- “Listing All Your Environment Variables (env Command)” on page 15
- “Displaying the Value of an Environment Variable (printenv Command)” on page 16
- “Working with Bidirectional Languages (aixterm Command)” on page 17.
- “Command Summary for User Environment and System Information” on page 17

Listing the Devices in Your System (lscfg Command)

You use the **lscfg** command to display the name, location, and description of each device found in the current configuration. The list is sorted by device location.

For example, to list the devices configured in your system, at the prompt, type:

```
lscfg
```

Press Enter.

The system displays a message similar to the following:

```
INSTALLED RESOURCE LIST
```

The following resources are installed on your machine.

+/- = Added/Deleted from Diagnostic Test List.

* = NOT Supported by Diagnostics.

```
+ sysplanar0  00-00          CPU Planar
+ fpa0        00-00          Floating Point Processor
+ mem0        00-0A          Memory Card
+ mem1        00-0B          Memory Card
+ ioplanar0   00-00          I/O Planar
* f2bus0      00-00          Micro Channel Bus
+ rs2320      00-01          RS232 Card
+ tty0        00-01-0-01     RS232 Card Port
- tty1        00-01-0-02     RS232 Card Port
..
..
..
```

To display information about a specific device, you can use the **-l** flag. For example, to list the information on device **sysplanar0**, at the prompt, type:

```
lscfg -l sysplanar0
```

Press Enter.

The system displays a message similar to the following:

DEVICE	LOCATION	DESCRIPTION
sysplanar0	00-00	CPU Planar

You can also use the **lscfg** command to display vital product data (VPD), such as part numbers, serial numbers, and engineering change levels. For some devices, the VPD is collected automatically and added to the system configuration. For other devices, the VPD is entered manually. An ME preceding the data signifies that the data was entered manually.

For example, to list the devices configured in your system with vital product data, at the prompt, type:

```
lscfg -v
```

Press Enter.

The system displays a message similar to the following:

```
INSTALLED RESOURCE LIST WITH VPD
The following devices are installed in your system.
sysplanar0  00-00  CPU Planar
  Part Number.....342522
  EC Level.....254921
  Serial Number.....353535
fpa0  00-00  Floating Point Processor
mem0  00-0A  Memory Card
  EC Level.....990221
.
.
.
```

See the **lscfg** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying the Name of Your Console (Iscons Command)

The **iscons** command writes the name of the current console device to standard output, usually your screen.

For example, at the prompt, type:

```
lscns
```

Press Enter.

The system displays a message similar to the following:

```
/dev/lft0
```

See the **iscons** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying the Name of Your Terminal (tty Command)

The **tty** command displays the name of your terminal.

For example, at the prompt, type:

```
tty
```

Press Enter.

The system displays information similar to the following:

```
/dev/tty06
```

In this example, `tty06` is the name of the terminal, and `/dev/tty06` is the device file that contains the interface to this terminal.

See the **tty** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Listing Available Displays (lsdisp Command)

The **lsdisp** command lists the displays currently available on your system, providing a display identification name, slot number, display name, and description of each of the displays.

For example, to list all available displays, type:

```
lsdisp
```

Press Enter.

Following is an example of the displayed list showing the display identification name, slot number, display name, and description. The list displays in ascending order according to slot number.

Name	Slot	Name	Description
ppr0	00-01	POWER_G4	Midrange Graphics Adapter
gda0	00-03	colorgda	Color Graphics Display Adapter
ppr1	00-04	POWER_Gt3	Midrange Entry Graphics Adapter

See the **lsdisp** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Listing the Available Fonts (lsfont Command)

The **lsfont** command displays a list of the fonts available to your display.

For example, to list all fonts available to the display in list format, type:

```
lsfont -l
```

Press Enter.

Following is an example of the displayed list showing the font identifier, font type, and number of characters per screen:

ID	Name	Style	Weight	Encoding	Col X Lines
0	Normal-R-N	Roman	Normal	PC850	80 X 251
1	Normal-I-N	Italic	Normal	PC850	120 X 35
2	Bold-R-Bo1	Roman	Bold	PC850	120 X 35

See the **lsfont** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Listing Keyboard Maps (Iskbd Command)

The **Iskbd** command lists the keyboard maps currently available, displaying a predefined keyboard identifier name and number.

For example, to list all keyboard maps, type:

```
lskbd
```

Press Enter.

The following list is displayed showing the predefined keyboard number and name:

```
0 USA
```

See the **Iskbd** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Listing Software Products (Islpp Command)

The **Islpp** command displays information about software products available for your system.

For example, to list all the software products in your system, at the system prompt, type:

```
lslpp -l -a
```

Press Enter.

Following is an example of the displayed list:

Name	Fix Id	State	Description

Path: /usr/lib/objrepos			
INed.obj		APPLIED	INed Editor
X11_3d.gl.dev.obj		APPLIED	AIXwindows/3D GL Development Utilities
Fonts			
X11fnt.oldX.fnt		APPLIED	AIXwindows Miscellaneous X Fonts
X11mEn_US.msg		APPLIED	AIXwindows NL Message files
.			
.			
.			

If the listing is very long, the top portion scrolls off the screen. To prevent this from happening, use the **Islpp** command piped to the **pg** command. At the prompt, type:

```
lslpp | pg
```

Press Enter.

See the **Islpp** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Listing Control Key Assignments for Your Terminal (stty Command)

The **stty** command displays your terminal settings. Most of these settings you can ignore, but the important information is what keys your terminal uses for control keys.

For example, at the prompt, type:

```
stty -a
```

Press Enter.

The system displays information similar to the following:

```
.  
. .  
intr = ^C; quit = ^\; erase = ^H; kill = ^U; eof = ^D;  
eol = ^@ start = ^Q; stop = ^S; susp = ^Z; dsusp = ^Y;  
reprint = ^R discard = ^O; werase = ^W; lnext = ^V  
. . .
```

In this example, lines such as `intr = ^C; quit = ^\; erase = ^H;` are your control key settings. The `^H` key is the Backspace key, and `erase` is the function it is set to perform. .

If the listing is very long, the top portion scrolls off the screen. To prevent this from happening, use the **stty** command piped to the **pg** command. At the prompt, type:

```
stty -a | pg
```

Press Enter.

See the **stty** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Listing All Your Environment Variables (env Command)

The **env** command allows you to display your current environment variables. An environment variable that is accessible to all your processes is called a *global variable*.

All variables (with their associated values) known to a command at the beginning of its execution constitute its *environment*. This environment includes variables that a command inherits from its parent process and variables specified as keyword parameters on the command line that calls the command. The shell interacts with the environment in several ways. When started, the shell scans the environment and creates a parameter for each name found, giving the parameter the corresponding value and marking it for export. Executed commands inherit the environment.

For example, to list all environment variables, type:

```
env
```

Press Enter.

Following is an example of the displayed list:

```
TMPDIR=/usr/tmp  
myid=denise  
LANG=en_US  
UNAME=barnard
```

```
PAGER=/bin/pg
VISUAL=vi
PATH=/usr/ucb:/usr/lpp/X11/bin:/bin:/usr/bin:/etc:/u/denise:/u/denise/bin:/u/bin1
MAILPATH=/usr/mail/denise?denise has mail !!!
MAILRECORD=/u/denise/.Outmail
EXINIT=set beautify noflash nomesg report=1 showmode showmatch
EDITOR=vi
PSCH=>
HISTFILE=/u/denise/.history
LOGNAME=denise
MAIL=/usr/mail/denise
PS1=denise@barnard:${PWD}>
PS3=#
PS2=>
epath=/usr/bin
USER=denise
SHELL=/bin/ksh
HISTSIZE=500
HOME=/u/denise
FCEDIT=vi
TERM=1ft
MAILMSG=**YOU HAVE NEW MAIL. USE THE mail COMMAND TO SEE YOUR PWD=/u/denise
ENV=/u/denise/.env
```

If the listing is very long, the top portion scrolls off the screen. To prevent this from happening, use the **env** command piped to the **pg** command. At the prompt, type:

```
env | pg
```

Press Enter.

See the **env** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Related Information

“Korn Shell Environment” on page 173

“Bourne Shell Environment” on page 196

Displaying the Value of an Environment Variable (printenv Command)

The **printenv** command displays the values of environment variables. If you specify the *Name* parameter, the system only prints the value associated with the parameter you requested. If you do not specify the *Name* parameter, the **printenv** command displays all current environment variables, showing one *Name = Value* sequence per line.

For example, to find the current setting of the **MAILMSG** environment variable, type:

```
printenv MAILMSG
```

Press Enter.

The command returns the value of the **MAILMSG** environment variable. For example:

```
YOU HAVE NEW MAIL
```

See the **printenv** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Working with Bidirectional Languages (aixterm Command)

The **aixterm** command supports Arabic and Hebrew, which are bidirectional languages. Bidirectional languages have the ability to be read and written in two directions, such as from left to right, and from right to left. You can work with Arabic and Hebrew applications by opening a window specifying an Arabic or Hebrew locale.

See the **aixterm** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Related Information

“Chapter 3. Commands and Processes” on page 19

“Chapter 4. Input and Output Redirection” on page 41

“User and System Identification” on page 5

“Chapter 10. Customizing the User Environment” on page 133

Command Summary for User Environment and System Information

aixterm	Enables you work with bidirectional languages.
env	Displays the current environment or sets the environment for the execution of a command.
lscfg	Displays diagnostic information about a device.
lscons	Displays the name of the current console.
lsdisp	Lists the displays currently available on the system.
lsfont	Lists the fonts available for use by the display.
lskbd	Lists the keyboard maps currently loaded in the system.
lspp	Lists software products.
printenv	Displays the values of environment variables.
stty	Displays system settings.
tty	Displays the full path name of your terminal.

Related Information

“Chapter 3. Commands and Processes” on page 19

“Chapter 4. Input and Output Redirection” on page 41

“User and System Identification” on page 5

“Chapter 10. Customizing the User Environment” on page 133

Chapter 3. Commands and Processes

A *command* is a request to perform an operation or run a program. You use commands to tell the operating system what task you want it to perform. When commands are entered, they are deciphered by a command interpreter (also known as a *shell*) and that task is processed.

A program or command that is actually running on the computer is referred to as a *process*. The operating system can run many different processes at the same time.

The operating system allows you to manipulate the input and output (I/O) of data to and from your system by using specific I/O commands and symbols. You can control input by specifying the location from which to gather data. For example, you can specify to read input as data is entered on the keyboard (standard input) or to read input from a file. You can control output by specifying where to display or store data. For example, you can specify to write output data to the screen (standard output) or to write it to a file.

This section discusses the following:

- “Commands Overview” on page 20
 - “Command Syntax” on page 20
 - “Reading Usage Statements” on page 22
 - “Using Web-based System Manager” on page 22
 - “Using the smit Command” on page 23
 - “Locating a Command or Program (whereis Command)” on page 23
 - “Displaying Information about a Command (man Command)” on page 23
 - “Displaying the Function of a Command (whatis Command)” on page 24
 - “Listing Previously Entered Commands (history Shell Command)” on page 24
 - “Repeating Commands Using the Shell history Command” on page 25
 - “Substituting Strings Using the Shell history Command” on page 26
 - “Editing the Command History” on page 26
 - “Creating a Command Alias (alias Shell Command)” on page 27
 - “Working with Text-Formatting Commands” on page 28
- “Processes Overview” on page 30
 - “Foreground and Background Processes” on page 30
 - “Daemons” on page 31
 - “Zombie Process” on page 31
 - “Starting a Process” on page 31
 - “Checking Processes (ps Command)” on page 32
 - “Setting the Initial Priority of a Process (nice Command)” on page 33
 - “Changing the Priority of a Running Process (renice Command)” on page 33
 - “Canceling a Foreground Process” on page 34
 - “Stopping a Foreground Process” on page 34
 - “Restarting a Stopped Process” on page 34
 - “Scheduling a Process for Later Operation (at Command)” on page 35
 - “Listing All Scheduled Processes (at or atq Command)” on page 36
 - “Removing a Process from the Schedule (at Command)” on page 37
 - “Removing a Background Process (kill Command)” on page 37
- “Command Summary for Commands and Processes” on page 38

Related Information

“Commands Overview”

“Processes Overview” on page 30

“Chapter 11. Shells” on page 149

Commands Overview

Some commands can be entered simply by typing one word. It is also possible to combine commands so that the output from one command becomes the input for another command. This is known as *piping*.

Flags further define the actions of commands. A *flag* is a modifier used with the command name on the command line, usually preceded by a dash.

Commands can also be grouped together and stored in a file. These are known as *shell procedures* or *shell scripts*. Instead of executing the commands individually, you execute the file that contains the commands. More information on scripts and procedures can be found in “Creating and Running a Shell Script” on page 153

To enter a command, type in the command name at the prompt, and press Enter.

```
$ CommandName
```

This section discusses:

- “Command Syntax”
- “Reading Usage Statements” on page 22
- “Using Web-based System Manager” on page 22
- “Using the smit Command” on page 23
- “Locating a Command or Program (whereis Command)” on page 23
- “Displaying Information about a Command (man Command)” on page 23
- “Displaying the Function of a Command (whatis Command)” on page 24
- “Listing Previously Entered Commands (history Shell Command)” on page 24
- “Repeating Commands Using the Shell history Command” on page 25
- “Substituting Strings Using the Shell history Command” on page 26
- “Editing the Command History” on page 26
- “Creating a Command Alias (alias Shell Command)” on page 27
- “Working with Text-Formatting Commands” on page 28

Command Syntax

Although some commands can be entered by simply typing one word, other commands use flags and parameters. Each command has a syntax that designates the required and optional flags and parameters. The general format for a command is:

```
CommandName flag(s) parameter(s)
```

Some general rules about commands are:

- Spaces between commands, flags, and parameters are important.
- Two commands can be entered on the same line by separating the commands with a semicolon (;). For example:

```
$ CommandOne;CommandTwo
```

The shell runs the commands sequentially.

- Commands are case sensitive. The shell distinguishes between uppercase and lowercase letters. To the shell, print is not the same as PRINT or Print.
- A very long command can be entered on more than one line by using the backslash (\) character. A backslash signifies line continuation to the shell. The following example is one command that spans two lines:

```
$ ls Mail info temp \  
(press Enter)
```

```
> diary  
(the > prompt appears)
```

The > character is your secondary prompt (\$ is the non-root user's default primary prompt), indicating that the current line is the continuation of the previous line. Note that **cs**h gives no secondary prompt, and the break must be at a word boundary, and its primary prompt is %.

- To run a command, type the command name at the prompt, and press Enter.

Command Name

The first word of every command is the command name. Some commands only have a command name.

Command Flags

After the command name, there might be a number of flags. Flags are sometimes called *options*. A flag is set off by spaces or tabs and usually starts with a dash (-). Exceptions are **ps**, **tar**, and **ar**, which do not require a dash in front of some of the flags. Flags modify the operation of a command. For example, in the following command:

```
ls -a -F
```

ls is the command name and -a -F are the flags.

When a command uses flags, they come directly after the command name. Single-character flags in a command can be combined with one dash. For example, the previous command can also be written as:

```
ls -aF
```

There are some circumstances when a parameter actually begins with a dash (-). In this case, use the delimiter dash dash (--) before the parameter. The -- tells the command that whatever follows is not a flag but a parameter.

For example, if you wanted to create a directory named -tmp and you entered the following command:

```
mkdir -tmp
```

The system would display an error message similar to the following:

```
mkdir: Not a recognized flag: t  
Usage: mkdir [-p] [-m mode] Directory ...
```

The correct way of entering the command is:

```
mkdir -- -tmp
```

Your new directory, -tmp, is now created.

Command Parameters

After the command name, there might be a number of flags, followed by parameters. Parameters are sometimes called *arguments* or *operands*. Parameters specify information the command needs in order to run. If you don't specify a parameter, the command might assume a default value. For example, in the following command:

```
ls -a temp
```

`ls` is the command name, `-a` is the flag, and `temp` is the parameter. This command displays all (`-a`) the files in the directory `temp`. In the following example:

```
ls -a
```

because no parameter is given, the default value is the current directory. In the following example:

```
ls temp mail
```

no flags are given, and `temp` and `mail` are parameters. In this case, `temp` and `mail` are two different directory names. The **ls** command will display all but the hidden files in each of these directories.

Whenever a parameter or option-argument is, or contains, a numeric value, the number is interpreted as a decimal integer, unless otherwise specified. Numerals in the range 0 to **INT_MAX**, as defined in **/usr/include/sys/limits.h**, are syntactically recognized as numeric values.

If a command you want to use accepts negative numbers as parameters or option-arguments, you can use numerals in the range **INT_MIN** to **INT_MAX**, both as defined in **/usr/include/sys/limits.h**. This does not necessarily mean that all numbers within that range are semantically correct. Some commands have a built-in specification permitting a smaller range of numbers, for example, some of the print commands. If an error is generated, the error message lets you know the value is out of the supported range, not that the command is syntactically incorrect.

Reading Usage Statements

Usage statements are another way to represent command syntax. Like syntax diagrams, usage statements tell you how to enter commands from the command line. Although usage statements provide the same type of syntax information as diagrams, they are not in diagram format. Rather, they consist of symbols such as brackets (`[]`), braces (`{ }`), and vertical bars (`|`). The following is a sample of a usage statement for the **unget** command:

```
unget [ -rSID ] [ -s ] [ -n ] File ...
```

The conventions for **bold** and *italics* are the same as for syntax diagrams. The following additional conventions are used in the command usage statements:

- Parameters enclosed in brackets are optional.
- Parameters enclosed in braces are required.
- Parameters not enclosed in either brackets or braces are required.
- A vertical bar signifies that you choose only one parameter. For example, `[a | b]` indicates that you *can* choose a, b, or nothing. Similarly, `{ a | b }` indicates that you *must* choose either a or b.
- Ellipses (`...`) signify the parameter can be repeated on the command line.
- The dash (`-`) represents standard input.

Using Web-based System Manager

Web-based System Manager is a graphical user interface for managing the system, either from a locally attached display or remotely from another system or personal computer equipped with a web browser. You can start Web-based System Manager in a variety of ways:

- from a command line terminal in the Common Desktop Environment (CDE) by entering the `wsm` command.
- from a command line terminal in the AIXwindows environment by entering the `wsm` command.
- from the CDE Application Manager by going to the `System_Admin` folder and clicking the Management Console icon.
- from an HTML 3.2-compatible web browser on a personal computer that is configured as described in the "Web-based System Manager Administration Guide".

Using the `smit` Command

The **`smit`** command is a tool you can use to run other commands. Command names entered as a parameter to the **`smit`** command might take you to a submenu or panel for that command. For example, `smit lsuser` takes you directly to **List All Users**, which lists the attributes of users on your system.

See the **`smit`** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Locating a Command or Program (`whereis` Command)

The **`whereis`** command locates the source, binary, and manuals sections for specified files. The command attempts to find the desired program from a list of standard locations.

To find files in the current directory that have no documentation, type:

```
whereis -m -u *
```

Press Enter.

To find all of the files that contain the name `Mail`, type:

```
whereis Mail
```

Press Enter.

The system displays information similar to the following:

```
Mail: /usr/bin/Mail /usr/lib/Mail.rc
```

See the **`whereis`** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying Information about a Command (`man` Command)

The **`man`** command displays information on commands, subroutines, and files. The general format for the **`man`** command is:

```
man CommandName
```

To obtain information about the **`pg`** command, type:

```
man pg
```

Press Enter.

The system displays information similar to the following:

```
pg Command
```

```
Purpose
```

```
Formats files to the display.
```

Syntax

```
pg [ - Number ] [ -c ] [ -e ] [ -f ] [ -n ] [ -p String ]  
[ -s ] [ +LineNumber | +/Pattern/ ] [ File ... ]
```

Description

The **pg** command reads a file name from the **File** parameter and writes the file to standard output one screen at a time. If you specify a **-** (dash) as the **File** parameter, or run the **pg** command without options, the **pg** command reads standard input. Each screen is followed by a prompt. If you press the Enter key, another page is displayed. Subcommands used with the **pg** command let you review or search in the file.

The information the **man** command provides can also be obtained using the InfoExplorer program.

See the **man** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying the Function of a Command (whatis Command)

The **whatis** command looks up a given command, system call, library function, or special file name, as specified by the *Command* parameter, from a database you create using the **catman -w** command. The **whatis** command displays the header line from the manual section. You can then issue the **man** command to obtain additional information.

The **whatis** command is equivalent to using the **man -f** command.

To find out what the **ls** command does, type:

```
whatis ls
```

Press Enter.

The system displays information similar to the following:

```
ls(1) -Displays the contents of a directory.
```

See the **whatis** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Listing Previously Entered Commands (history Shell Command)

The **history** command is a Korn shell built-in that lists the last 16 commands entered. The Korn shell saves commands that you entered to a command history file, usually named **\$HOME/sh_history**. This saves time when you need to repeat a previous command.

By default, the Korn shell saves the text of the last 128 commands. The history file size (specified by the **HISTSIZE** environment variable) is not limited, although a very large history file size can cause the Korn shell to start up slowly.

Note: The **history** shell command is not the same **history** command used with the **INed** editor. Also note that the Bourne shell does not support command history.

For detailed information about shells, see ""Chapter 11. Shells" on page 149"

To list the previous commands you entered, at the prompt, type:

```
history
```

Press Enter.

The **history** command entered by itself lists the previous 16 commands entered. The system displays information similar to the following:

```
928 ls
929 mail
930 printenv MAILMSG
931 whereis Mail
932 whatis ls
933 cd /usr/include/sys
934 ls
935 man pg
936 cd
937 ls | pg
938 lscons
939 tty
940 ls *.txt
941 printenv MAILMSG
942 pwd
943 history
```

The listing first displays the position of the command in the **\$HOME/.sh_history** file followed by the command.

To list the previous five commands, at the prompt, type:

```
history -5
```

Press Enter.

A listing similar to the following appears:

```
939 tty
940 ls *.txt
941 printenv MAILMSG
942 pwd
943 history
944 history -5
```

The **history** command followed by a number lists all the previous commands entered starting at that number.

To list the commands since 938, at the prompt, type:

```
history 938
```

Press Enter.

A listing similar to the following appears:

```
938 lscons
939 tty
940 ls *.txt
941 printenv MAILMSG
942 pwd
943 history
944 history -5
945 history 938
```

Repeating Commands Using the Shell history Command

Use the **r** Korn shell alias to repeat previous commands. Type **r** and press Enter, and you can specify the number or the first character or characters of the command.

If you want to list the displays currently available on the system, you would type **lsdisp** and press Enter at the prompt. The system returns the information to you on the screen. If you want the same information returned to you again, at the prompt, type:

```
r
```

Press Enter.

The system runs the most recently entered command again. In this example, the **lsdisp** command would run.

To repeat the **ls *.txt** command, at the prompt, type:

```
r ls
```

Press Enter.

The **r** Korn shell alias locates the most recent command that begins with the character or characters specified.

Substituting Strings Using the Shell history Command

You can also use the **r** Korn shell alias to modify a command before it is run. In this case, a substitution parameter of the form *Old=New* can be used to modify the command before it is run.

For example, if command line 940 is **ls *.txt**, and you want to run **ls *.exe**, at the prompt, type:

```
r txt=exe 940
```

Press Enter.

This runs command 940, substituting **exe** for **txt**.

For example, if the command on line 940 is the most recent command that starts with a lower-case letter **l**, you can also type:

```
r txt=exe l
```

Press Enter.

Note: Only the first occurrence of the *Old* string is replaced by the *New* string. Entering the **r** Korn shell alias without a specific command number or character does the substitution to the previous command entered.

Editing the Command History

Use the **fc** Korn shell built-in command to list or edit portions of the command history file. To select a portion of the file to edit or list, specify the number or the first character or characters of the command. You can specify a single command or range of commands.

If you do not specify an editor program as an argument to the **fc** Korn shell built-in command, the editor specified by the **FCEDIT** variable is used. If the **FCEDIT** variable is not defined, then the **/usr/bin/ed** editor is used. The edited command or commands are printed and run when you exit the editor. Use the **printenv** command to display the value of the **FCEDIT** variable.

For example, if you want to run the command:

```
cd /usr/tmp
```

which is very similar to command line 933, at the prompt type:

```
fc 933
```

Press Enter.

At this point, your default editor appears with the command line 933. You would change `include/sys` to `tmp`, and when you exit your editor, the edited command is run.

You can also specify the editor you want to use in the **fc** command.

For example, if you want to edit a command using the `/usr/bin/vi` editor, at the prompt, type:

```
fc -e vi 933
```

Press Enter.

At this point, the **vi** editor appears with the command line 933.

You can also specify a range of commands to edit.

For example, if you want to edit the commands 930 through 940, at the prompt, type:

```
fc 930 940
```

Press Enter.

At this point, your default editor appears with the command lines 930 through 940. When you exit the editor, all the commands that appear in your editor are run sequentially.

Creating a Command Alias (alias Shell Command)

An *alias* lets you create a shortcut name for a command, a file name, or any shell text. By using aliases, you save a lot of time when doing tasks you do frequently. The **alias** Korn shell built-in command defines a word as an alias for some command. You can use aliases to redefine built-in commands but not to redefine reserved words.

The first character of an alias name can be any printable character except the metacharacters. Any remaining characters must be the same as for a valid file name.

The format for creating an alias is:

```
alias Name=String
```

in which the *Name* parameter specifies the name of the alias and the *String* parameter specifies a string of characters. If *String* contains blank spaces, enclose it in quotation marks.

To create an alias for the command **rm -i** (prompts you before deleting files), at the prompt, type:

```
alias rm="/usr/bin/rm -i"
```

Press Enter.

In this example, whenever you type the command **rm** and press Enter, the actual command performed is **/usr/bin/rm -i**.

To create an alias for the command **ls -a1F | pg** (displays detailed information of all the files in the current directory, including the invisible files; marks executable files with an `*` and directories with a `/`; and scrolls per screen), at the prompt, type:

```
alias dir="/usr/bin/ls -a1F | pg"
```

Press Enter.

In this example, whenever you type the command `dir` and press Enter, the actual command performed is `/usr/bin/ls -aF | pg`.

To display all the aliases you have, at the prompt, type:

```
alias
```

Press Enter.

The system displays information similar to the following:

```
rm="/usr/bin/rm -i"  
dir="/usr/bin/ls -aF | pg"
```

Working with Text-Formatting Commands

You can use text-formatting commands to work with text composed of the international extended character set used for European languages.

International Character Support in Text Formatting

The international extended character set provides the characters and symbols used in many European languages, as well as an ASCII subset composed of English-language characters, digits, and punctuation.

All characters in the European extended character set have ASCII forms. These forms can be used to represent the extended characters in input, or the characters can be entered directly with a device such as a keyboard that supports the European extended characters.

The following text-formatting commands support all international languages that use single-byte characters. These commands are located in `/usr/bin`. (The commands identified with an asterisk (*) support text processing for multibyte languages. For more information on multibyte languages, see “Multibyte Character Support in Text Formatting” on page 29.)

addbib*	hyphen	pic*	pstext
checkmm	ibm3812	ps4014	refer*
checknr*	ibm3816	ps630	roffbib*
col*	ibm5587G*	psbanne	soelim*
colcrt	ibm5585H-T*	psdit	sortbib*
deroff*	indxbib*	psplot	tbl*
enscript	lookbib*	psrev	troff*
eqn*	makedev*	psroff	vgrind
grap*	neqn*	psrv	xpreview*
hplj	nroff*		

Text-formatting commands and macro packages not in the preceding list have not been enabled to process international characters.

Entering Extended Single-Byte Characters

If your input device supports characters from the European-language extended character set, you can enter them directly. Otherwise, use the following ASCII escape sequence form to represent these characters:

The form `\[N]`, where `N` is the 2- or 4-digit hexadecimal code for the character.

Note: The NCesc form `\<xx>` is no longer supported.

Text containing extended characters is output according to the formatting conventions of the language in use. Characters that are not defined for the interface to a specific output device produce no output or error indication.

Although the names of the requests, macro packages, and commands are based on English, most of them can accept input (such as file names and parameters) containing characters in the European extended character set.

For the **nroff** and **troff** commands and their preprocessors, the command input must be ASCII, or an irrecoverable syntax error will result. International characters, either single-byte or multibyte, can be entered when enclosed within quotation marks and without other text to be formatted. For example, using macros from the **pic** command:

```
define foobar % SomeText %
```

After the `define` directive, the first name, `foobar`, must be ASCII. However, the replacement text, *SomeText*, can contain non-ASCII characters.

Multibyte Character Support in Text Formatting

Certain text-formatting commands can be used to process text for multibyte languages. These commands are identified with an asterisk (*) in the list under “International Character Support in Text Formatting” on page 28. Text-formatting commands not in the list have not been enabled to process international characters.

Entering Multibyte Characters

If supported by your input device, multibyte characters can be entered directly. Otherwise, you can enter any multibyte character in the ASCII form `\[N]`, where N is the 2-, 4-, 6-, 7-, or 8-digit hexadecimal encoding for the character.

Although the names of the requests, macros, and commands are based on English, most of them can accept input (such as file names and parameters) containing any type of multibyte character.

If you are already familiar with using text-formatting commands with single-byte text, the following list summarizes characteristics that are noteworthy or unique to the multibyte locales:

- Text is not hyphenated.
- Special format types are required for multibyte numerical output. Japanese format types are available.
- Text is output in horizontal lines, filled from left to right.
- Character spacing is constant, so characters automatically align in columns.
- Characters that are not defined for the interface to a specific output device produce no output or error indication.

As for the **nroff** and **troff** commands and their preprocessors, the command input must be ASCII, or a syntax error will result. International characters, either single-byte or multibyte, can be entered when enclosed within quotation marks and within other text to be formatted. For example, using macros from the **pic** command:

```
define foobar % SomeText %
```

After the `define` directive, the first name, `foobar`, must be ASCII. However, the replacement text, *SomeText*, can contain non-ASCII characters.

Related Information

“Chapter 3. Commands and Processes” on page 19

“Processes Overview” on page 30

“Chapter 11. Shells” on page 149

“Korn Shell or POSIX Shell Commands” on page 172

“Bourne Shell” on page 196

Processes Overview

A program or command that is actually running on the computer is referred to as a *process*. Processes exist in parent-child hierarchies. A process started by a program or command is a *parent process*; a *child process* is the product of the parent process. A parent process can have several child processes, but a child process can only have one parent.

The system assigns a process identification number (PID number) to each process when it starts. If you start the same program several times, it will have a different PID number each time.

When a process is started on a system, the process uses a part of the available system resources. When more than one process is running, a scheduler that is built into the operating system gives each process its share of the computer’s time, based on established priorities. These priorities can be changed by using the **nice** or **renice** commands.

Note: Only someone with root user authority can change a process priority to a higher one. All users can lower priorities on a process they start by using the **nice** command, or on a process they have already started by using the **renice** command.

This section discusses:

- “Foreground and Background Processes”
- “Daemons” on page 31
- “Zombie Process” on page 31
- “Starting a Process” on page 31
- “Checking Processes (ps Command)” on page 32
- “Setting the Initial Priority of a Process (nice Command)” on page 33
- “Changing the Priority of a Running Process (renice Command)” on page 33
- “Canceling a Foreground Process” on page 34
- “Stopping a Foreground Process” on page 34
- “Restarting a Stopped Process” on page 34
- “Scheduling a Process for Later Operation (at Command)” on page 35
- “Listing All Scheduled Processes (at or atq Command)” on page 36
- “Removing a Process from the Schedule (at Command)” on page 37
- “Removing a Background Process (kill Command)” on page 37

Foreground and Background Processes

Processes that are started from and require a user’s interaction are called *foreground processes*. Processes that are run independently of a user are referred to as *background processes*. Programs and commands run as foreground processes by default. To run a process in the background, place an ampersand (&) at the end of the command name that you use to start the process.

Daemons

Daemons are processes that run unattended. They are constantly in the background and are available at all times. Daemons are usually started when the system starts and run until the system stops. A daemon process performs system services and is available at all times to more than one task or user. Daemon processes are started by the root user or root shell and can be stopped only by the root user. For example, the **qdaemon** process provides access to system resources such as printers. Another common daemon is the **sendmail** daemon.

Zombie Process

A *zombie process* is a dead process that is no longer executing but is still recognized in the process table (in other words, it has a PID number). It has no other system space allocated to it. Zombie processes have been killed or have exited and continue to exist in the process table until the parent process dies or the system is shut down and restarted. Zombie processes show up as <defunct> when listed by the **ps** command.

Starting a Process

You start a foreground process from a display station by either entering a program name or command name at the system prompt. Once a foreground process has started, the process interacts with you at your display station until it is complete. This means no other interaction (for example, entering another command) can take place at the display station until the process is finished or you halt it.

A single user can run more than one process at a time up to a default maximum of 40 processes per user.

To Start a Process in the Foreground

To run a process in the foreground, type the name of the command with all the appropriate parameters and flags:

```
$ CommandName
```

Press Enter.

To Start a Process in the Background

To run a process in the background, type the name of the command with all the appropriate parameters and flags, followed by an ampersand (&):

and press Enter.

```
$ CommandName&
```

When the process is running in the background, you can perform additional tasks by entering other commands at your display station.

Generally, background processes are most useful for commands that take a long time to run. However, because they increase the total amount of work the processor is doing, background processes also slow down the rest of the system.

Most processes direct their output to standard output, even when they run in the background. Unless redirected, standard output goes to the display station. Because the output from a background process can interfere with your other work on the system, it is usually good practice to redirect the output of a background process to a file or a printer. You can then look at the output whenever you are ready.

Note: Under certain circumstances, a process might generate its output in a different sequence when run in the background than when run in the foreground. Programmers might want to use the **fflush** subroutine to ensure that output occurs in the proper order regardless of whether the process runs in foreground or background.

As long as a background process is running, you can check its status with the **ps** command.

Checking Processes (ps Command)

Any time the system is running, several processes are also running. You can use the **ps** command to find out which processes are running and to display information about those processes.

ps Command

The **ps** command has several flags that enable you to specify which processes to list and what information to display about each process.

To show all processes running on your system, at the prompt, type:

```
ps -ef
```

Press Enter.

The system displays information similar to the following:

```
USER  PID  PPID  C   STIME  TTY  TIME CMD
root   1    0    0   Jun 28  -   3:23 /etc/init
root  1588 6963  0   Jun 28  -   0:02 /usr/etc/biod 6
root  2280 1    0   Jun 28  -   1:39 /etc/syncd 60
mary  2413 16998 2 07:57:30 -   0:05 aixterm
mary  11632 16998 0 07:57:31 lft/1 0:01 xbiff
mary  16260 2413 1 07:57:35 pts/1 0:00 /bin/ksh
mary  16469 1 0 07:57:12 lft/1 0:00 ksh /usr/lpp/X11/bin/xinit
mary  19402 16260 20 09:37:21 pts/1 0:00 ps -ef
```

The column heading definitions are as follows:

USER	User login name
PID	Process ID
PPID	Parent process ID
C	CPU utilization of process
STIME	Start time of process
TTY	Controlling workstation for the process
TIME	Total execution time for the process
CMD	Command

In the previous example, the process ID for the **ps -ef** command is 19402. Its parent process ID is 16260, the **/bin/ksh** command.

If the listing is very long, the top portion scrolls off the screen. To prevent this from happening, use the **ps** command piped to the **pg** command. At the prompt, type:

```
ps -ef | pg
```

Press Enter.

To show status information of all processes running on your system, at the prompt, type:

```
ps gv
```

Press Enter.

This form of the command lists a number of statistics for each active process. Output from this command looks something like this:

PID	TTY	STAT	TIME	PGIN	SIZE	RSS	LIM	TSIZ	TRS	%CPU	%MEM	COMMAND
0	-	A	0:44	7	8	8	xx	0	0	0.0	0.0	swapper
1	-	A	1:29	518	244	140	xx	21	24	0.1	1.0	/etc/init
771	-	A	1:22	0	16	16	xx	0	0	0.0	0.0	kproc
1028	-	A	0:00	10	16	8	xx	0	0	0.0	0.0	kproc
1503	-	A	0:33	127	16	8	xx	0	0	0.0	0.0	kproc
1679	-	A	1:03	282	192	12	32768	130	0	0.7	0.0	pcidossvr
2089	-	A	0:22	918	72	28	xx	1	4	0.0	0.0	/etc/sync
2784	-	A	0:00	9	16	8	xx	0	0	0.0	0.0	kproc
2816	-	A	5:59	6436	2664	616	8	852	156	0.4	4.0	/usr/lpp/
3115	-	A	0:27	955	264	128	xx	39	36	0.0	1.0	/usr/lib/
3451	-	A	0:00	0	16	8	xx	0	0	0.0	0.0	kproc
3812	-	A	0:00	21	128	12	32768	34	0	0.0	0.0	usr/lib/lpd/
3970	-	A	0:00	0	16	8	xx	0	0	0.0	0.0	kproc
4267	-	A	0:01	169	132	72	32768	16	16	0.0	0.0	/etc/sysl
4514	lft/0	A	0:00	60	200	72	xx	39	60	0.0	0.0	/etc/gett
4776	pts/3	A	0:02	250	108	280	8	303	268	0.0	2.0	-ksh
5050	-	A	0:09	1200	424	132	32768	243	56	0.0	1.0	/usr/sbin
5322	-	A	0:27	1299	156	192	xx	24	24	0.0	1.0	/etc/cron
5590	-	A	0:00	2	100	12	32768	11	0	0.0	0.0	/etc/writ
5749	-	A	0:00	0	208	12	xx	13	0	0.0	0.0	/usr/lpp/
6111	-	T	0:00	66	108	12	32768	47	0	0.0	0.0	/usr/lpp/

See the **ps** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Other commands you can use are **smit process** and **smit monitors**.

Setting the Initial Priority of a Process (nice Command)

You can set the initial priority of a process to a value lower than the base scheduling priority by using the **nice** command to start the process.

Note: To run a process at a higher priority, you must have root user authority.

nice Command

To set the initial priority of a process, type:

```
nice -n Number CommandString
```

where *Number* is in the range of 0 to 39, with 39 being the lowest priority. The higher the number, the lower the priority. If you use zero, the process will run at its base scheduling priority. *CommandString* is the command and flags and parameters you want to run.

See the **nice** command in the *AIX 5L Version 5.1 Commands Reference* for more information and the exact syntax.

You can also use the **smit nice** command to perform this task.

Changing the Priority of a Running Process (renice Command)

You can change the scheduling priority of a running process to a value lower or higher than the base scheduling priority by using the **renice** command from the command line. This command changes the nice value of a process.

Note: To run a process at a higher priority or to change the priority for a process you did not start, you must have root user authority.

From the Command Line

To change the initial priority of a running process, type:

```
renice Priority -p ProcessID
```

where *Priority* is in the range of -20 to 20. The higher the number, the lower the priority. If you use zero, the process will run at its base scheduling priority. *ProcessID* is the PID you want to change the priority of.

You can also use the **smit renice** command to perform this task.

Canceling a Foreground Process

If you start a foreground process and then decide you do not want to let it finish, you can cancel it by pressing INTERRUPT. This is usually Ctrl-C or Ctrl-Backspace. To find out what your INTERRUPT key is set to, see “Listing Control Key Assignments for Your Terminal (stty Command)” on page 15 .

Note: INTERRUPT (Ctrl-C) does not cancel background processes. To cancel a background process, you must use the **kill** command.

Most simple commands are not good examples for demonstrating how to cancel a process—they run so quickly that they finish before you have time to cancel them. The examples in this section, therefore, use a command that takes more than a few seconds to run: `find / -type f`. This command displays the path names for all files on your system. You do not need to study the **find** command in order to complete this section; it is used here simply to demonstrate how to work with processes.

In the following example, the **find** command starts a process. After the process runs for a few seconds, you can cancel it by pressing the INTERRUPT key:

```
$ find / -type f
/usr/sbin/acct/lastlogin
/usr/sbin/acct/prctmp
/usr/sbin/acct/prdaily
/usr/sbin/acct/runacct
/usr/sbin/acct/sdisk
/usr/sbin/acct/shutacct INTERRUPT (Ctrl-C)
$ _
```

The system returns the prompt to the screen. Now you can enter another command.

Stopping a Foreground Process

It is possible for a process to be stopped but not have its process ID (PID) removed from the process table. You can stop a foreground process with a Ctrl-Z from the keyboard.

Note: Ctrl-Z works in the Korn shell (**ksh**) and C shell (**csch**), but not in the Bourne shell (**bsh**).

Restarting a Stopped Process

This procedure describes how to restart a process that has been stopped with a Ctrl-Z.

Note: Ctrl-Z works in the Korn shell (**ksh**) and C shell (**csch**), but not in the Bourne shell (**bsh**). To restart a stopped process, you must either be the user who started the process or have root user authority.

1. To show all the processes running or stopped but not killed on your system, type:

```
ps -ef
```

You might want to pipe this command through a **grep** command to restrict the list to those processes most likely to be the one you want to restart. For example, if you want to restart a **vi** session, you could type:

```
ps -ef | grep vi
```

Press Enter. This command would display only those lines from the **ps** command output that contained the word **vi**. The output would look something like this:

```
UID    PID  PPID  C    STIME      TTY  TIME  COMMAND
root   1234  13682  0     00:59:53  -    0:01  vi test
root   14277 13682  1     01:00:34  -    0:00  grep vi
```

2. In the **ps** command output, find the process you want to restart and note its PID number. In the example, the PID is 1234.
3. To send the CONTINUE signal to the stopped process, type:

```
kill -19 1234
```

Substitute the PID of your process for the 1234. The -19 indicates the CONTINUE signal. This command restarts the process in the background. If it is okay for the process to run in the background, you are finished with the procedure. If the process needs to run in the foreground (as a **vi** session would), you must proceed with the next step.

4. To bring the process in to the foreground, type:

```
fg 1234
```

Once again, substitute the PID of your process for the 1234. Your process should now be running in the foreground. (You are now in your **vi** edit session).

Scheduling a Process for Later Operation (at Command)

You can set up a process as a *batch process* to run in the background at a scheduled time. The **at** and **smit** commands let you enter the names of commands to be run at a later time and allow you to specify when the commands should be run.

Note: The **/var/adm/cron/at.allow** and **/var/adm/cron/at.deny** files control whether you can use the **at** command. A person with root user authority can create, edit, or delete these files. Entries in these files are user login names with one name to a line. The following is an example of an **at.allow** file:

```
root
nick
dee
sarah
```

If the **at.allow** file exists, only users whose login names appear in it can use the **at** command. A system administrator can explicitly stop a user from using the **at** command by listing the user's login name in the **at.deny** file. If only the **at.deny** file exists, any user whose name does not appear in the file can use the **at** command.

You cannot use the **at** command if one of the following is true:

- The **at.allow** file and the **at.deny** file do not exist (allows root user only).
- The **at.allow** file exists but the user's login name is not listed in it.
- The **at.deny** file exists and the user's login name is listed in it.

If the **at.allow** file does not exist and the **at.deny** file does not exist or is empty, only someone with root user authority can submit a job with the **at** command.

The **at** command syntax allows you to specify a date string, a time and day string, or an increment string for when you want the process to run. It also allows you to specify which shell or queue to use. The following examples show some typical uses of the command.

at Command

For example, if your login name is joyce and you have a script named WorkReport that you want to run at midnight, do the following:

1. Type in the time you want the program to start running.
at midnight
2. Type the names of the programs to run, pressing Enter after each name. After typing the last name, press the end-of-file character (Ctrl-D) to signal the end of the list.
WorkReport^D

After pressing Ctrl-D, the system displays information similar to the following:

```
job joyce.741502800.a at Fri Jul 6 00:00:00 CDT 1994.
```

The program WorkReport is given the job number joyce.741502800.a and will run at midnight July 6.

To list the programs you have sent to be run later, type:

```
at -l
```

The system displays information similar to the following:

```
joyce.741502800.a      Fri Jul 6 00:00:00 CDT 1994
```

To cancel a program you have set up to run later, first list the job numbers assigned to your programs with **at -l**. Once you know the job number of the program you want to cancel, type:

```
at -r joyce.741502800.a
```

This cancels job joyce.741502800.a.

See the **at** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

You can also use the **smit at** and **smit sjat** commands to perform this task.

Listing All Scheduled Processes (at or atq Command)

You can list all scheduled processes with the **-l** flag of the **at** command or with the **atq** command. Both commands give the same output, but the **atq** command can order the processes by the time the **at** command was issued and can display just the number of processes in the queue.

You can list all scheduled processes in the following ways:

- With the **at** command from the command line
- With the **atq** command

For user restrictions on using the **at** command, see the Note .

at Command

To list the scheduled processes, type:

```
at -l
```

This command lists all the scheduled processes in your queue. If you are a root user, this command lists all the scheduled processes for all users. For complete details of the syntax, see the **at** command.

atq Command

To list all scheduled processes in the queue, type:

```
atq
```

If you are a root user, you can list the scheduled processes in a particular user's queue by typing:

```
atq UserName
```

To list the number of scheduled processes in the queue, type:

```
atq -n
```

Removing a Process from the Schedule (at Command)

You can remove a scheduled process with the **at** command using the **-r** flag. For user restrictions on using the **at** command, see Note.

From the Command Line

1. To remove a scheduled process, you must know the process number. You can obtain the process number using the **at -l** command or the **atq** command. See “Listing All Scheduled Processes (at or atq Command)” on page 36 for details.
2. When you know the number of the process you want to remove, type:

```
at -r ProcessNumber
```

You can also use the **smit rmat** command to perform this task.

Removing a Background Process (kill Command)

If **INTERRUPT** does not halt your foreground process or if you decide, after starting a background process, that you do not want the process to finish, you can cancel the process with the **kill** command. Before you can cancel a process using the **kill** command, you must know its PID number. The general format for the **kill** command is:

```
kill ProcessID
```

Note: To remove a process, you must have root user authority or be the user who started the process. The default signal to a process from the **kill** command is **-15 (SIGTERM)**.

kill Command

1. Use the **ps** command to determine the process ID of the process you want to remove. You might want to pipe this command through a **grep** command to list only the process you want. For example, if you want the process ID of a **vi** session, you could type:
2. In the next example, you issue the **find** command to run in the background. You then decide to cancel the process. Issue the **ps** command to list the PID numbers.

```
ps -l | grep vi
```

```
$ find / -type f > dir.paths &  
[1] 21593
```

```
$ ps
```

```
  PID  TTY  TIME  COMMAND  
 1627 pts3  0:00  ps  
 5461 pts3  0:00  ksh  
17565 pts3  0:00  -ksh  
21593 pts3  0:00  find / -type f
```

```
$ kill 21593
```

```
$ ps
```

```
  PID  TTY  TIME  COMMAND  
 1627 pts3  0:00  ps
```

```
5461 pts3 0:00 ksh
17565 pts3 0:00 -ksh
[1] + Terminated 21593 find / -type f > dir.paths &
```

The command **kill 21593** stops the background **find** process, and the second **ps** command returns no status information about PID 21593. The system does not display the termination message until you enter your next command, unless that command is **cd**.

The **kill** command lets you cancel background processes. You might want to do this if you realize that you have mistakenly put a process in the background or a process is taking too long to run.

Notes:

- a. Removing a parent process automatically removes all its child processes.
- b. To remove a zombie process, you must remove its parent process.

See the **kill** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

You can also use the **smit kill** command.

Related Information

“Chapter 3. Commands and Processes” on page 19

“Commands Overview” on page 20

“Chapter 11. Shells” on page 149

“Korn Shell or POSIX Shell Commands” on page 172

“Bourne Shell” on page 196

“C Shell” on page 212

Command Summary for Commands and Processes

Commands

alias	Shell command that prints a list of aliases to standard output.
history	Shell command that displays the history event list.
man	Displays information about commands, subroutines, and files online.
wsm	Performs system management from a web browser.
whatis	Describes the function a command performs.
whereis	Locates the source, binary, or manual for installed programs.

Processes

at	Runs commands at a later time, lists all scheduled processes, or removes a process from the schedule.
atq	Displays the queue of jobs waiting to be run.
kill	Sends a signal to running processes.
nice	Runs a command at a lower or higher priority.
ps	Shows current status of processes.
renice	Alters priority of running processes.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 11. Shells” on page 149

“Korn Shell or POSIX Shell Commands” on page 172

“Bourne Shell” on page 196

“C Shell” on page 212

Chapter 4. Input and Output Redirection

The operating system allows you to manipulate the input and output (I/O) of data to and from your system by using specific I/O commands and symbols. You can control input by specifying the location from which to gather data. For example, you can specify to read input as data is entered on the keyboard (standard input) or to read input from a file. You can control output by specifying where to display or store data. You can specify to write output data to the screen (standard output) or to write it to a file.

The operating system, because it is multitasking, is designed to handle processes in combination with each other. This section discusses the advantages of redirecting input and output and tying processes together.

This section discusses the following:

- “Standard Input, Standard Output, and Standard Error”
- “Redirecting Standard Output” on page 42
- “Redirecting Output to a File” on page 42
- “Redirecting Output and Appending It to a File” on page 43
- “Creating a Text File with Redirection from the Keyboard” on page 43
- “Concatenating Text Files” on page 43
- “Redirecting Standard Input” on page 43
- “Discarding Output with the /dev/null File” on page 44
- “Redirecting Standard Error and Other Output” on page 44
- “Inline Input (Here) Documents” on page 45
- “Pipes and Filters” on page 45
- “Displaying Program Output and Copying It to a File (tee command)” on page 46
- “Clearing Your Screen (clear Command)” on page 46
- “Sending a Message to Standard Output (echo Command)” on page 47
- “Appending a Single Line of Text to a File (echo Command)” on page 47
- “Copying Your Screen to a File (capture and script Commands)” on page 47
- “Displaying Text in Large Letters on Your Screen (banner Command)” on page 48
- “Command Summary for Input and Output Redirection” on page 49

Standard Input, Standard Output, and Standard Error

When a command begins running, it usually expects that three files are already open: standard input, standard output, and standard error (sometimes called error output or diagnostic output). A number, called a *file descriptor*, is associated with each of these files, as follows:

File descriptor 0	Standard input
File descriptor 1	Standard output
File descriptor 2	Standard error (diagnostic) output

A child process normally inherits these files from its parent. All three files are initially assigned to the workstation (0 to the keyboard, 1 and 2 to the display). The shell permits them to be redirected elsewhere before control is passed to a command.

When you enter a command, if no file name is given, your keyboard is the *standard input*, sometimes denoted as *stdin*. When a command finishes, the results are displayed on your screen.

Your screen is the *standard output*, sometimes denoted as *stdout*. By default, commands take input from the standard input and send the results to standard output.

Standard error, sometimes denoted as *stderr*, is where error messages go. By default, this is your screen.

These default actions of input and output can be varied. You can use a file as input and write results of a command to a file. This is called *input/output redirection*, which is one of the powerful features of a UNIX operating system.

The output from a command, which normally goes to the terminal, can easily be redirected to a file instead. This is known as *output redirection*. This is useful when you have a lot of output that is difficult to read on the screen or when you want to put files together to create a larger file.

Though not used as much as output redirection, the input for a command, which normally comes from the keyboard, can also be redirected from a file. This is known as *input redirection*. Redirection of input lets you prepare a file in advance and then have the command read the file.

Redirecting Standard Output

When the notation `> filename` is added to the end of a command, the output of the command is written to the specified file name. The `>` symbol is known as the *output redirection operator*.

When the notation `> filename` is added to the end of a command, the output of the command is written to the specified file name. The `>` symbol is known as the *output redirection operator*.

Any command that outputs its results to the screen can have its output sent to a file.

Redirecting Output to a File

For example, to send the results of the **who** command to a file called `users`, type:

```
who > users
```

Press Enter.

Note: If the file `users` already exists, it is written over, unless the **noclobber** option of the **set** built-in **ksh** (Korn shell) or **cs**h (C shell) command is specified.

To see the contents of the file `users`, type:

```
cat users
```

Press Enter.

A list similar to the following appears:

```
denise 1ft/0 May 13 08:05
marta pts/1 May 13 08:10
endrica pts/2 May 13 09:33
```

For example, to send the current directory listing to a file, type:

```
ls > dirlist
```

Press Enter.

Redirecting Output and Appending It to a File

When the notation `> > filename` is added to the end of a command, the output of the command is appended to the specified file name rather than writing over any existing data. The `> >` symbol is known as the *append redirection operator*.

For example, to append `file2` to `file1`, type:

```
cat file2 > > file1
```

Press Enter.

Note: If the file `file1` does not exist, it is created, unless the **noclobber** option of the **set** built-in **ksh** (Korn shell) or **cs**h (C shell) command is specified.

Creating a Text File with Redirection from the Keyboard

Used alone, the **cat** command takes whatever you type at the keyboard as input. You can redirect this input to a file. Enter Ctrl-D on a new line to signal the end of the text.

At the system prompt, type:

```
cat > filename
This is a test.
^D
```

Concatenating Text Files

Combining various files into one file is known as *concatenation*.

For example, at the system prompt, type:

```
cat file1 file2 file3 > file4
```

Press Enter.

The previous example creates `file4`, which consists of `file1`, `file2`, and `file3` appended in the order given.

The following example shows a common error when concatenating files:

```
cat file1 file2 file3 > file1
```

Attention: In this example, you might think the **cat** command will append the contents of `file1`, `file2`, and `file3` into `file1`. The **cat** command creates the output file first, so it actually erases the contents of `file1` and then appends `file2` and `file3` to it.

Redirecting Standard Input

When the notation `< filename` is added to the end of a command, the input of the command is read from the specified file name. The `<` symbol is known as the *input redirection operator*.

Note: Only commands that normally take their input from the keyboard can have their input redirected.

For example, to send the file `letter1` as a message to user `denise` with the **mail** command, type:

```
mail denise < letter1
```

Press Enter.

Discarding Output with the `/dev/null` File

The `/dev/null` file is a special file. This file has a unique property; it is always empty. Any data you send to `/dev/null` is discarded. This is a useful feature when you run a program or command that generates output you want to ignore.

For example, you have a program named `myprog` that accepts input from the screen and generates messages while it is running that you would rather ignore. To read input from the file `myscript` and discard the standard output messages, type:

```
myprog < myscript >/dev/null
```

Press Enter.

In this example, `myprog` uses the file `myscript` as input and all standard output is discarded.

Redirecting Standard Error and Other Output

In addition to the standard input and standard output, commands often produce other types of output, such as error or status messages known as diagnostic output. Like standard output, standard error output is written to the screen unless redirected.

If you want to redirect standard error or other output, you must use a file descriptor. File descriptors can also be specified to redirect standard input and standard output, but are already the default values.

A *file descriptor* is a number associated with each of the I/O files a command ordinarily uses. The following numbers are associated with standard input, output, and error:

0	Standard input (keyboard)
1	Standard output (display)
2	Standard error (display)

To redirect standard error output, type the file descriptor number 2 in front of the output or append redirection symbols (`>` or `>>`) and a file name after the symbol. For example, the following command takes the standard error output from the `cc` command where it is used to compile `testfile.c` and appends it to the end of the `ERRORS` file:

```
cc testfile.c 2 >> ERRORS
```

Other types of output can also be redirected using the file descriptors from 0 through 9. For example, if the `cmd` command writes output to file descriptor 9, you can redirect that output to the `savedata` file with the following command:

```
cmd 9> savedata
```

If a command writes to more than one output, you can independently redirect each one. Suppose that a command directs its standard output to file descriptor 1, directs its standard error output to file descriptor 2, and builds a data file on file descriptor 9. The following command line redirects each of these outputs to a different file:

```
command > standard 2> error 9> data
```

Inline Input (Here) Documents

A command in the form of:

```
command << eofstring
```

in which *eofstring* is any string that does not contain pattern-matching characters, the shell takes the subsequent lines as the standard input of *command* until the shell reads a line consisting of only *eofstring* (possibly preceded by one or more tab characters). The lines between the first *eofstring* and the second are frequently referred to as an *inline input*, or *here*, document. If a hyphen (-) immediately follows the << redirection characters, the shell strips leading tab characters from each line of the here document before it passes the line to the *command*.

The shell creates a temporary file containing the here document and performs variable and command substitution on the contents before passing the file to the command. It performs pattern matching on file names that are part of command lines in command substitutions. To prohibit all substitutions, quote any character of the *eofstring*:

```
command << \eofstring
```

The here document is especially useful for a small amount of input data that is more conveniently placed in the shell procedure rather than kept in a separate file (such as editor scripts). For instance, you could type:

```
cat <<- xyz
  This message will be shown on the
  display with leading tabs removed.
  xyz
```

Press Enter.

This feature is most useful in shell procedures.

Pipes and Filters

UNIX lets you connect two or more commands in such a way that the standard output of one command is used as the standard input of another command. A set of commands connected this way is known as a *pipeline*. The connection that joins the commands is known as a *pipe*. Pipes are another important feature of UNIX because they let you tie many single-purpose commands into one powerful command.

You can direct the output from one command to become the input for another command using a pipeline. The commands are connected by a pipe (|) symbol.

When a command takes its input from another command, modifies it, and sends its results to standard output, it is known as a *filter*. Filters can be used alone but they are especially useful in pipelines. The most common filters are:

- sort
- more
- pg

For example, the **ls** command writes the contents of the current directory to the screen in one scrolling data stream. When more than one screen of information is presented, some data is lost from view. To control the output so the contents display screen by screen, you can use a pipeline to direct the output of the **ls** command to the **pg** command, which controls the format of output to the screen as shown in the following example:

```
ls | pg
```

In the example, the output of the **ls** command is the input for the **pg** command. Press Enter to continue to the next screen.

Pipelines operate in one direction only (left to right). Each command in a pipeline runs as a separate process and all processes can run at the same time. A process pauses when it has no input to read or when the pipe to the next process is full.

Another example of using pipes is with the **grep** command. **grep** searches a file for lines that contain strings of a certain pattern. To display all your files created or modified in July, type:

```
ls -l | grep Jul
```

Press Enter.

In the example, the output of the **ls** command is the input for the **grep** command.

Displaying Program Output and Copying It to a File (tee command)

The **tee** command, used with a pipe, reads standard input, then writes the output of a program to standard output and simultaneously copies it into the specified file or files. This gives you the advantage of viewing your output immediately and storing it for future use at the same time.

For example, to view and save the output from a command at the same time, type:

```
ps -ef | tee program.ps
```

Press Enter.

This displays the standard output of the command **ps -ef** at the work station, and at the same time saves a copy of it in the file `program.ps`. If `program.ps` already exists, it is deleted and replaced, unless the **noclobber** option of the **set** built-in command is specified.

For example, to view and save the output from a command to an existing file:

```
ls -l | tee -a program.ls
```

This displays the standard output of **ls -l** at the workstation and at the same time appends a copy of it to the end of `program.ls`. If the file `program.ls` does not exist, it is created, unless the **noclobber** option of the **set** built-in command is specified.

The system displays information similar to the following, and the `program.ls` file contains the same information:

```
-rw-rw-rw- 1 jones  staff  2301  Sep 19  08:53 161414
-rw-rw-rw- 1 jones  staff  6317  Aug 31  13:17 def.rpt
-rw-rw-rw- 1 jones  staff  5550  Sep 10  14:13 try.doc
```

See the **tee** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Clearing Your Screen (clear Command)

You can empty the screen of messages and keyboard input with the **clear** command.

At the prompt, type:

```
clear
```

Press Enter.

The system clears the screen and displays the prompt.

See the **clear** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Sending a Message to Standard Output (echo Command)

You can display messages on the screen with the **echo** command.

For example, to write a message to standard output, at the prompt, type:

```
echo Please insert diskette . . .
```

Press Enter.

The system displays the following:

```
Please insert diskette . . .
```

For example, to use the **echo** command with pattern-matching characters, at the prompt, type:

```
echo The back-up files are: *.bak
```

Press Enter.

The system displays the message The back-up files are: followed by the file names in the current directory ending with .bak.

See the **echo** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Appending a Single Line of Text to a File (echo Command)

You can add a single line of text to a file with the **echo** command, used with the append redirection operator.

For example, at the prompt, type:

```
echo Remember to backup mail files by end of week.>
```

```
>notes
```

Press Enter.

This adds the message Remember to backup mail files by end of week. to the end of the file notes.

See the **echo** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

See the **echo** command in the *AIX 5L Version 5.1 Commands Reference Book* for more information and the exact syntax.

Copying Your Screen to a File (capture and script Commands)

You can copy everything printed on your terminal to a file that you specify with the **capture** command, which emulates a VT100 terminal.

The **script** command also lets you copy everything printed on your terminal to a file that you specify, without emulating a VT100 terminal.

Both commands are useful for producing hardcopy records of terminal dialogs.

For example, to capture the screen of a terminal while emulating a VT100, at the prompt, type:

```
capture screen.01
```

Press Enter.

The system displays information similar to the following:

```
Capture command is started. The file is screen.01.  
Use ^P to dump screen to file screen.01.  
You are now emulating a vt100 terminal.  
Press Any Key to continue.
```

After entering data and dumping the screen contents, stop the **capture** command by pressing Ctrl-D or typing `exit` and pressing Enter. The system displays information similar to the following:

```
Capture command is complete. The file is screen.01.  
You are NO LONGER emulating a vt100 terminal.
```

Use the **cat** command to display the contents of your file.

For example, to capture the screen of a terminal, at the prompt, type:

```
script
```

Press Enter.

The system displays information similar to the following:

```
Script command is started. The file is typescript.
```

Everything displayed on the screen is now copied to the file `typescript`.

To stop the **script** command, press Ctrl-D or type `exit` and press Enter. The system displays information similar to the following:

```
Script command is complete. The file is typescript.
```

Use the **cat** command to display the contents of your file.

See the **capture** and **script** commands in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying Text in Large Letters on Your Screen (banner Command)

The **banner** command displays ASCII characters to your screen in large letters. Each line in the output can be up to 10 digits or uppercase or lowercase characters in length.

For example, at the prompt, type:

```
banner GOODBYE!
```

Press Enter.

The system displays `GOODBYE!` in large letters at your screen.

See the **banner** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 11. Shells” on page 149

“Korn Shell or POSIX Shell Commands” on page 172

“Bourne Shell” on page 196

“C Shell” on page 212

“Chapter 6. Files” on page 67

The null special file.

Command Summary for Input and Output Redirection

>	“Redirecting Standard Output” on page 42
<	“Redirecting Standard Input” on page 43
> >	“Redirecting Output and Appending It to a File” on page 43
	“Pipes and Filters” on page 45
banner	Writes ASCII character strings in large letters to standard output.
capture	Allows terminal screens to be dumped to a file.
clear	Clears the terminal screen.
echo	Writes character strings to standard output.
script	Allows terminal input and output to be copied to a file.
tee	Displays the standard output of a program and copies it into a file.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 11. Shells” on page 149

“Korn Shell or POSIX Shell Commands” on page 172

“Bourne Shell” on page 196

“C Shell” on page 212

“Chapter 6. Files” on page 67

Chapter 5. File Systems and Directories

File systems consist of groups of directories and the files within the directories. File systems are commonly represented as an inverted tree. The root directory, symbolized by the slash (/) symbol, defines a file system and appears at the top of a file system tree diagram. Directories branch downward from the root directory in the tree diagram and contain files and/or subdirectories. Branching creates unique paths through the directory structure to every object in the file system.

Collections of files are stored in *directories*. These collections of files are often related to each other; storing them in a structure of directories keeps them organized.

A *file* is a collection of data that can be read from or written to. A file can be a program you create, text you write, data you acquire, or a device you use. Commands, printers, terminals, correspondence, and application programs are all stored in files. This allows users to access diverse elements of the system in a uniform way and gives the file system great flexibility.

This section discusses the following:

- “File Systems” on page 52
 - “File System Types” on page 52
 - “File System Structure” on page 53
 - “Showing Space Available on File System (df Command)” on page 54
- “Directory Overview” on page 55
 - “Types of Directories” on page 55
 - “Directory Organization” on page 56
 - “Directory Naming Conventions” on page 56
 - “Directory Path Names” on page 56
 - “Directory Abbreviations” on page 57
- “Directory Handling Procedures” on page 58
 - “Creating a Directory (mkdir Command)” on page 58
 - “Moving or Renaming a Directory (mvdir Command)” on page 59
 - “Displaying Your Current Directory (pwd Command)” on page 59
 - “Changing to Another Directory (cd Command)” on page 59
 - “Copying a Directory (cp Command)” on page 60
 - “Displaying Contents of a Directory (ls Command)” on page 61
 - “Deleting or Removing a Directory (rmdir Command)” on page 62
 - “Comparing Contents of Directories (dircmp Command)” on page 63
- “Command Summary for File Systems and Directories” on page 64

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Linking Files and Directories” on page 83

“Chapter 8. Backup Files and Storage Media” on page 105

“Chapter 9. File and System Security” on page 119

File Systems

A *file system* is a hierarchical structure (file tree) of files and directories. This type of structure resembles an inverted tree with the roots at the top and the branches at the bottom. This file tree uses directories to organize data and programs into groups, allowing the management of many directories and files at one time.

Some tasks are performed more efficiently on a file system than on each directory within the file system. For example, you can back up, move, or secure an entire file system.

The basic type of file system is called the *Journalled File System (JFS)*. This file system uses database journaling techniques to maintain its structural consistency. This prevents damage to the file system when the system is halted abnormally.

Some of the most important system management tasks have to do with file systems, specifically:

- Allocating space for file systems on logical volumes
- Creating file systems
- Making file system space available to system users
- Monitoring file system space usage
- Backing up file systems to guard against data loss if the system fails
- Maintaining file systems in a consistent state

These tasks should be performed by your system administrator.

This section discusses:

- “File System Types”
- “File System Structure” on page 53
- “Showing Space Available on File System (df Command)” on page 54

File System Types

The operating system supports multiple file system types. These include:

Journalled File System (JFS)	The basic file system type, it supports the entire set of file system commands.
Network File System (NFS)	A file system type that permits files residing on remote machines to be accessed as though they reside on the local machine.
CD-ROM File System (CDRFS)	A file system type that allows the contents of a CD-ROM to be accessed through the normal file system interfaces (open, read, and close).

File System Structure

On standalone machines, the following file systems reside on the associated devices by default:

<code>/dev/hd1</code>	<code>/home</code>
<code>/dev/hd2</code>	<code>/usr</code>
<code>/dev/hd3</code>	<code>/tmp</code>
<code>/dev/hd4</code>	<code>/(root)</code>
<code>/dev/hd9var</code>	<code>/var</code>

The file tree has the following characteristics:

- Files that can be shared by machines of the same hardware architecture are located in the `/usr` file system.
- Variable per-client files, for example, spool and mail files, are located in the `/var` file system.
- The `/(root)` file system contains files and directories critical for system operation. For example, it contains
 - A device directory (`/dev`)
 - Mount points where file systems can be mounted onto the root file system, for example, `/mnt`
- The `/home` file system is the mount point for users' home directories.
- For servers, the `/export` directory contains paging-space files, per-client (unshared) root file systems, dump, home, and `/usr/share` directories for diskless clients, as well as exported `/usr` directories.

The following list provides information about the contents of some of the subdirectories of the `/(root)` file system.

<code>/bin</code>	Symbolic link to the <code>/usr/bin</code> directory. In prior UNIX file systems, the <code>/bin</code> directory contained user commands that now reside in <code>/usr/bin</code> in the new file structure.
<code>/dev</code>	Contains device nodes for special files for local devices. The <code>/dev</code> directory contains special files for tape drives, printers, disk partitions, and terminals.
<code>/etc</code>	Contains configuration files that vary for each machine. Examples include: <ul style="list-style-type: none">• <code>/etc/hosts</code>• <code>/etc/passwd</code> The <code>/etc</code> directory contains the files generally used in system administration. Most of the commands that used to reside in the <code>/etc</code> directory now reside in the <code>/usr/sbin</code> directory. However, for compatibility, it contains symbolic links to the new locations of some executable files. Examples include: <ul style="list-style-type: none">• <code>/etc/chown</code> is a symbolic link to the <code>/usr/bin/chown</code>.• <code>/etc/exportvg</code> is a symbolic link to the <code>/usr/sbin/exportvg</code>.
<code>/export</code>	Contains the directories and files on a server that are for remote clients.
<code>/home</code>	Serves as a mount point for a file system containing user home directories. The <code>/home</code> file system contains per-user files and directories. In a standalone machine, a separate local file system is mounted over the <code>/home</code> directory. In a network, a server might contain user files that should be accessible from several machines. In this case, the server's copy of the <code>/home</code> directory is remotely mounted onto a local <code>/home</code> file system.
<code>/lib</code>	Symbolic link to the <code>/usr/lib</code> directory, which contains architecture-independent libraries with names in the form <code>lib*.a</code> .
<code>/sbin</code>	Contains files needed to boot the machine and mount the <code>/usr</code> file system. Most of the commands used during booting come from the boot image's RAM disk file system; therefore, very few commands reside in the <code>/sbin</code> directory.
<code>/tmp</code>	Serves as a mount point for a file system that contains system-generated temporary files.
<code>/u</code>	Symbolic link to the <code>/home</code> directory.

/usr Serves as a mount point for a file system containing files that do not change and can be shared by machines (such as executables and ASCII documentation).

Standalone machines mount a separate local file system over the **/usr** directory. Diskless and disk-poor machines mount a directory from a remote server over the **/usr** file system.

/var Serves as a mount point for files that vary on each machine. The **/var** file system is configured as a file system since the files it contains tend to grow. For example, it is a symbolic link to the **/usr/tmp** directory, which contains temporary work files.

Showing Space Available on File System (df Command)

The **df** command displays information about total space and available space on a file system. The *FileSystem* parameter specifies the name of the device on which the file system resides, the directory on which the file system is mounted, or the relative path name of a file system. If you do not specify the *FileSystem* parameter, the **df** command displays information for all currently mounted file systems. If a file or directory is specified, then the **df** command displays information for the file system on which it resides.

Normally, the **df** command uses free counts contained in the superblock. Under certain exceptional conditions, these counts might be in error. For example, if a file system is being actively modified when the **df** command is running, the free count might not be accurate.

See the **df** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Note: On some remote file systems, such as Network File Systems (NFS), columns are blank if the server does not provide the information.

For example, to display information about all mounted file systems, type:

```
df
```

Press Enter.

If your system is configured so the **/**, **/usr**, **/site**, and **/usr/venus** directories reside in separate file systems, the output from the **df** command resembles the following:

Filesystem	1k-blocks	free	%used	1k-blocks	%used	Mounted on
/dev/hd4	20480	13780	32%	805	13%	/
/dev/hd2	385024	15772	95%	27715	28%	/usr
/dev/hd9var	40960	38988	4%	115	1%	/var
/dev/hd3	20480	18972	7%	81	1%	/tmp
/dev/hd1	4096	3724	9%	44	4%	/home

For example, to display available space on the file system in which your current directory resides, type:

```
df .
```

Press Enter.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Linking Files and Directories” on page 83

“Chapter 8. Backup Files and Storage Media” on page 105

“Chapter 9. File and System Security” on page 119

Directory Overview

A *directory* is a unique type of file that contains only the information needed to access files or other directories. As a result, a directory occupies less space than other types of files. It also gives the file system structure flexibility and depth. Directories enable you to group files and other directories, allowing you to organize the file system into a modular hierarchy. Unlike other types of files, a special set of commands control directories.

Directories contain directory entries. Each entry contains a file or subdirectory name and an index node reference number (*i-node* number). To increase speed and enhance use of disk space, the data in a file is stored at various locations in the computer's memory. The *i-node* number contains the addresses used to locate all the scattered blocks of data associated with a file. The *i-node* number also records other information about the file including time of modification and access, access modes, number of links, file owner, and file type. It is possible to link several names for a file to the same *i-node* number by creating directory entries with the **ln** command.

Because directories often contain information that should not be available to all users of the system, directory access can be protected. By setting a directory's permissions, you can control who has access to the directory, also determining which users (if any) can alter information within the directory. See “File and Directory Access Modes” on page 121 for more information.

This section discusses:

- “Types of Directories”
- “Directory Organization” on page 56
- “Directory Naming Conventions” on page 56
- “Directory Path Names” on page 56
- “Directory Abbreviations” on page 57
- “Directory Handling Procedures” on page 58

Types of Directories

Directories can be defined by the operating system, the system administrator, or users. The system-defined directories contain specific kinds of system files, such as commands. At the top of the file system hierarchy is the system-defined **/(root)** directory. The **/(root)** directory usually contains the following standard system-related directories:

/dev	Contains special files for I/O devices.
/etc	Contains files for system initialization and system management.
/home	Contains login directories for the system users.
/tmp	Contains files that are temporary and can be deleted in a specified number of days.
/usr	Contains the lpp , include , and other system directories.
/usr/bin	Contains user executable programs.

Some directories, such as your login or home directory (**\$HOME**), are defined and customized by the system administrator. When you log in to the operating system, the login directory is the current directory.

Directories that you create are called user-defined directories. These directories help you organize and maintain your files.

Directory Organization

Directories contain files, subdirectories, or a combination of both. A subdirectory is a directory within a directory. The directory containing the subdirectory is the parent directory.

For the operating system to track and find directories, each directory has an entry for the parent directory in which it was created, .. (dot dot), and an entry for the directory itself, . (dot). In most directory listings, these files are hidden.

Directory Tree

Structures of parent directories, subdirectories, and files are called *file systems*. Directory structures are often compared to an inverted tree. The root directory, symbolized by a slash (/), is the base and pictured at the top of the directory tree. Subdirectories and files branch downward from the root directory.

The file system structure of directories can easily become complex. Attempt to keep the file and directory structure as simple as possible. Also, create files and directories with easily recognizable names. This makes working with files easier.

Parent Directory

Each directory, except for **/(root)**, has one parent directory and can have one or more child directories. In the Example of Directory Structures illustration, **C** is parent to **E**, and **C** is child to **/(root)**.

Home Directory

When you log in, the system puts you in a directory called your *home directory* or login directory. This directory is set up by the system administrator for each user. Your home directory is where you keep your personal files. Normally, directories you create for your own use will be subdirectories of your home directory. To return to your home directory at any time, type the **cd** command and press Enter at the prompt.

Working Directory

You are always working within a directory. Whichever directory you are currently working in is called your *current* or *working* directory. The **pwd** (present working directory) command reports the name of your working directory. The **cd** command allows you to change working directories.

Directory Naming Conventions

The name of each directory must be unique within the directory where it is stored. This ensures that the directory also has a unique path name in the file system. Directories follow the same naming conventions as files as explained in “File Naming Conventions” on page 69.

Directory Path Names

Each file and directory can be reached by a unique path, known as the *path name*, through the file system tree structure. The path name specifies the location of a directory or file within the file system.

Note: Path names cannot exceed 1023 characters.

The file system uses two kinds of path names:

absolute path names	Traces the path from the /(root) directory. Absolute path names always begin with the slash (/) symbol.
relative path name	Traces the path from the current directory through its parent or its subdirectories and files.

An absolute path name represents the complete name of a directory or file from the **/(root)** directory downward. Regardless of where you are working in the file system, you can always find a directory or file by specifying its absolute path name. Absolute path names start with a slash (/), the symbol representing the root directory. The path name **/A/D/9** is the absolute path name for **9**. The first slash (/) represents the **/(root)** directory, which is the starting place for the search. The remainder of the path name directs the search to **A**, then to **D**, and finally to **9**.

There are two files named **9**. This is possible because the absolute path names to the files give each file a unique name within the file system. The path names **/A/D/9** and **/C/E/G/9** specify two unique files named **9**.

Unlike full path names, relative path names specify a directory or file based on the current working directory. For relative path names, you can use the notation dot dot (..) to move upward in the file system hierarchy. The dot dot (..) represents the parent directory. Because relative path names specify a path starting in the current directory, they do not begin with a slash (/). Relative path names are used to specify the name of a file in the current directory or the path name of a file or directory above or below the level of the current directory in the file system. If **D** is the current directory, the relative path name for accessing **10** is **F/10**, but the absolute path name is always **/A/D/F/10**. Also, the relative path name for accessing **3** is **../B/3**.

You can also represent the name of the current directory by using the notation dot (.). The dot (.) notation is commonly used when running programs that read the current directory name.

Directory Abbreviations

Abbreviations provide a quick and convenient way for specifying certain directories. The following is a list of abbreviations.

Abbreviation	Meaning
.	The current working directory.
..	The directory above the current working directory (the parent directory).
~	Your home directory (this is not true for the “Bourne Shell” on page 196).
\$HOME	Your home directory (this is true for all shells).

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“File Systems” on page 52

“Chapter 6. Files” on page 67

“Linking Files and Directories” on page 83

“Chapter 8. Backup Files and Storage Media” on page 105

“Chapter 9. File and System Security” on page 119

Directory Handling Procedures

There are a variety of ways to work with directories and their contents.

The command and an example are presented for each of the following directory tasks:

- “Creating a Directory (mkdir Command)”
- “Moving or Renaming a Directory (mvdir Command)” on page 59
- “Displaying Your Current Directory (pwd Command)” on page 59
- “Changing to Another Directory (cd Command)” on page 59
- “Copying a Directory (cp Command)” on page 60
- “Displaying Contents of a Directory (ls Command)” on page 61
- “Deleting or Removing a Directory (rmdir Command)” on page 62
- “Comparing Contents of Directories (dircmp Command)” on page 63

Creating a Directory (mkdir Command)

The **mkdir** command creates one or more new directories specified by the *Directory* parameter. Each new directory contains the standard entries dot (.) and dot dot (..). You can specify the permissions for the new directories with the **-m** *Mode* flag.

When a new directory is created, it is created within the current, or working, directory unless you specify an absolute path name to another location in the file system.

For example, to create a new directory called Test in the current working directory with default permissions, type:

```
mkdir Test
```

Press Enter.

For example, to create a new directory called Test with `rxr-xr-x` permissions in a previously created `/home/demo/sub1` directory, type:

```
mkdir -m 755 /home/demo/sub1/Test
```

Press Enter.

For example, to create a new directory called Test with default permissions in the `/home/demo/sub2` directory, type:

```
mkdir -p /home/demo/sub2/Test
```

Press Enter.

The **-p** flag creates the `/home`, `/home/demo`, and `/home/demo/sub2` directories if they do not already exist.

See the **mkdir** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Moving or Renaming a Directory (mvdir Command)

The **mvdir** command moves directories or renames a directory.

For example, to move a directory, type:

```
mvdir book manual
```

Press Enter.

This moves the book directory under the directory named manual, if manual exists. Otherwise, the book directory is renamed to manual.

>For example, to move and rename a directory, type:

```
mvdir book3 proj4/manual
```

Press Enter.

This moves book3 to the directory named proj4 and renames it manual (if manual did not previously exist).

See the **mvdir** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying Your Current Directory (pwd Command)

The **pwd** command writes to standard output the full path name of your current directory (from the **/(root)** directory). All directories are separated by a slash (/). The **/(root)** directory is represented by the first slash (/), and the last directory named is your current directory.

For example, to display your current directory, type:

```
pwd
```

Press Enter.

The full path name of your current directory is displayed similar to the following:

```
/home/thomas
```

See the **pwd** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Changing to Another Directory (cd Command)

The **cd** command moves you from your present directory to another directory. You must have execute (search) permission in the specified directory.

If you do not specify a *Directory* parameter, the **cd** command moves you to your login directory (**\$HOME** in the **ksh** and **bsh** environments, or **\$home** in the **csk** environment). If the specified directory name is a full path name, it becomes the current directory. A full path name begins with a slash (/) indicating the **/(root)** directory, a dot (.) indicating current directory, or a dot dot (..) indicating parent directory. If the directory name is not a full path name, the **cd** command searches for it relative to one of the paths specified by the **\$CDPATH** shell variable (or **\$cdpath csh** variable). This variable has the same syntax as, and similar semantics to, the **\$PATH** shell variable (or **\$path csh** variable).

For example, to change to your home directory, type:

```
cd
```

Press Enter.

For example, to change to the `/usr/include` directory, type:

```
cd /usr/include
```

Press Enter.

This changes the current directory to `/usr/include`.

For example, to go down one level of the directory tree to the `sys` directory, type:

```
cd sys
```

Press Enter.

If the current directory is `/usr/include` and it contains a subdirectory named `sys`, then `/usr/include/sys` becomes the current directory.

For example, to go up one level of the directory tree, type:

```
cd ..
```

Press Enter.

The special file name, dot dor (`..`), refers to the directory immediately above the current directory, its parent directory.

See the `cd` command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Copying a Directory (cp Command)

The `cp` or `copy` command creates a copy of the contents of the file or directory specified by the *SourceFile* or *SourceDirectory* parameters into the file or directory specified by the *TargetFile* or *TargetDirectory* parameters. If the file specified as the *TargetFile* exists, the copy writes over the original contents of the file. If you are copying more than one *SourceFile*, the target must be a directory.

To place a copy of the *SourceFile* into a directory, specify a path to an existing directory for the *TargetDirectory* parameter. Files maintain their respective names when copied to a directory unless you specify a new file name at the end of the path. The `cp` command also copies entire directories into other directories if you specify the `-r` or `-R` flags.

For example, to copy all the files in a directory to a new directory, type:

```
cp /home/janet/clients/* /home/nick/customers
```

Press Enter.

This copies only the files in the `clients` directory to the `customers` directory.

For example, to copy a directory, including all its files and subdirectories, to another directory, type:

```
cp -R /home/nick/clients /home/nick/customers
```

Press Enter.

This copies the `clients` directory, including all its files, subdirectories, and the files in those subdirectories, under the `customers` directory.

See the `cp` command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying Contents of a Directory (ls Command)

You can display the contents of a directory by using the **ls** command.

ls command

The **ls** command writes to standard output the contents of each specified *Directory* or the name of each specified *File*, along with any other information you ask for with the flags. If you do not specify a *File* or *Directory*, the **ls** command displays the contents of the current directory.

By default, the **ls** command displays all information in alphabetic order by file name. If the command is executed by a user with root authority, it uses the **-A** flag by default, listing all entries except dot (.) and dot dot (..). To show all entries for files, including those that begin with a . (dot), use the **ls -a** command.

There are three main ways to format the output:

- List one entry per line using the **-l** flag.
- List entries in multiple columns by specifying either the **-C** or **-x** flag. The **-C** flag is the default format when output is to a tty.
- List entries in a comma-separated series by specifying the **-m** flag.

To determine the number of character positions in the output line, the **ls** command uses the **\$COLUMNS** environment variable. If this variable is not set, the command reads the **terminfo** file. If the **ls** command cannot determine the number of character positions by either of these methods, it uses a default value of 80.

The information displayed with the **-e** and **-l** flags is interpreted as follows:

If the first character is:

- d** Entry is a directory.
- b** Entry is a block special file.
- c** Entry is a character special file.
- l** Entry is a symbolic link.
- p** Entry is a first-in, first-out (FIFO) pipe special file.
- s** Entry is a local socket.
- Entry is an ordinary file.

The next nine characters are divided into three sets of three characters each. The first three characters show the owner's permission. The next set of three characters shows the permission of the other users in the group. The last set of three characters shows the permission of anyone else with access to the file. The three characters in each set show read, write, and execute permission of the file. Execute permission of a directory lets you search a directory for a specified file.

Permissions are indicated as follows:

- r** Read permission granted
- t** Only the directory owner or the file owner can delete or rename a file within that directory, even if others have write permission to the directory.
- w** Write (edit) permission granted
- x** Execute (search) permission granted
- Corresponding permission not granted.

The information displayed with the **-e** flag is the same as with the **-l** flag, except for the addition of an 11th character interpreted as follows:

- + Indicates a file has extended security information. For example, the file might have extended **ACL**, **TCB**, or **TP** attributes in the mode.
- Indicates a file does not have extended security information.

When the size of the files in a directory are listed, the **ls** command displays a total count of blocks, including indirect blocks.

For example, to list all files in the current directory, type:

```
ls -a
```

Press Enter.

This lists all files, including

- dot (.)
- dot dot (..)
- Other files whose names might or might not begin with a dot (.)

For example, to display detailed information, type:

```
ls -l chap1 .profile
```

Press Enter.

This displays a long listing with detailed information about `chap1` and `.profile`.

For example, to display detailed information about a directory, type:

```
ls -d -l . manual manual/chap1
```

Press Enter.

This displays a long listing for the directories `.` and `manual`, and for the file `manual/chap1`. Without the **-d** flag, this would list the files in the `.` and `manual` directories instead of the detailed information about the directories themselves.

See the **ls** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Deleting or Removing a Directory (rmdir Command)

The **rmdir** command removes the directory, specified by the *Directory* parameter, from the system. The directory must be empty (it can only contain `.` and `..`) before you can remove it, and you must have write permission in its parent directory. Use the **ls -a** *Directory* command to check whether the directory is empty.

For example, to empty and remove a directory, type:

```
rm mydir/* mydir/.  
rmdir mydir
```

Press Enter.

This removes the contents of `mydir`, then removes the empty directory. The **rm** command displays an error message about trying to remove the directories `.` and `..`, and then the **rmdir** command removes them and the directory itself.

Note that `rm mydir/* mydir/.*` first removes files with names that do not begin with a dot, and then removes those with names that do begin with a dot. You might not realize that the directory contains file names that begin with a dot because the `ls` command does not normally list them unless you use the `-a` flag.

For example, to remove the `/tmp/jones/demo/mydir` directory structure and all the directories beneath it, type:

```
cd /tmp
rmdir -p jones/demo/mydir
```

Press Enter.

This removes the `jones/demo/mydir` directory from the `/tmp` directory. If a directory is not empty or you do not have write permission to it when it is to be removed, the command terminates with appropriate error messages.

See the `rmdir` command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Comparing Contents of Directories (dircmp Command)

The `dircmp` command compares the two directories specified by the *Directory1* and *Directory2* parameters and writes information about their contents to standard output. First, the `dircmp` command compares the file names in each directory. If the same file name appears in both, the `dircmp` command compares the contents of both files.

In the output, the `dircmp` command lists the files unique to each directory. It then lists the files with identical names in both directories, but with different contents. If no flag is specified, it also lists files that have identical contents as well as identical names in both directories.

For example, to summarize the differences between the files in the `proj.ver1` and `proj.ver2` directories, type:

```
dircmp proj.ver1 proj.ver2
```

Press Enter.

This displays a summary of the differences between the directories `proj.ver1` and `proj.ver2`. The summary lists separately the files found only in one directory or the other, and those found in both. If a file is found in both directories, the `dircmp` command notes whether the two copies are identical.

For example, to show the details of the differences between the files in the `proj.ver1` and `proj.ver2` directories, type:

```
dircmp -d -s proj.ver1 proj.ver2
```

Press Enter.

The `-s` flag suppresses information about identical files. The `-d` flag displays a `diff` listing for each of the differing files found in both directories.

See the `dircmp` command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Linking Files and Directories” on page 83

“Chapter 8. Backup Files and Storage Media” on page 105

“Chapter 9. File and System Security” on page 119

Command Summary for File Systems and Directories

File Systems

df Reports information about space on file systems.

Directory Abbreviations

. The current working directory.
.. The directory above the current working directory (the parent directory).
- Your home directory (this is not true for the “Bourne Shell” on page 196).
\$HOME Your home directory (this is true for all shells).

Directory Handling Procedures

cd Changes the current directory.
cp Copies files or directories.
dircmp Compares two directories and the contents of their common files.
ls Displays the contents of a directory.
mkdir Creates one or more new directories.
mvdir Moves (renames) a directory.
pwd Displays the path name of the working directory.
rmdir Removes a directory.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Linking Files and Directories” on page 83

“Chapter 8. Backup Files and Storage Media” on page 105

“Chapter 9. File and System Security” on page 119

Chapter 6. Files

Files are used for all input and output (I/O) of information in the operating system. This standardizes access to both software and hardware. Input occurs when the contents of a file is modified or written to. Output occurs when the contents of one file is read or transferred to another file. For example, to create a hardcopy printout of a file, the system reads the information from the text file and writes that information to the file representing the printer.

This section discusses:

- “Types of Files” on page 68
 - “File Naming Conventions” on page 69
 - “File Path Names” on page 69
 - “Pattern Matching with Wildcards and Metacharacters” on page 69
 - “Pattern Matching versus Regular Expressions” on page 70
- “File Handling Procedures” on page 71
 - “Deleting Files (rm Command)” on page 72
 - “Moving and Renaming Files (mv Command)” on page 72
 - “Copying Files (cp Command)” on page 73
 - “Finding Files (find Command)” on page 74
 - “Showing File Type (file Command)” on page 75
 - “Displaying File Contents (pg, more, page, and cat Commands)” on page 76
 - “Finding Strings in Text Files (grep Command)” on page 77
 - “Sorting Text Files (sort Command)” on page 77
 - “Comparing Files (diff Command)” on page 78
 - “Counting Words, Lines, and Bytes in Files (wc Command)” on page 79
 - “Displaying the First Lines of Files (head Command)” on page 79
 - “Displaying the Last Lines of Files (tail Command)” on page 80
 - “Cutting Sections of Text Files (cut Command)” on page 80
 - “Pasting Sections of Text Files (paste Command)” on page 81
 - “Numbering Lines in Text Files (nl Command)” on page 82
 - “Removing Columns in Text Files (colrm Command)” on page 82
- “Linking Files and Directories” on page 83
 - “Types of Links” on page 84
 - “Linking Files (ln Command)” on page 84
 - “Removing Linked Files” on page 85
- “DOS Files” on page 86
 - “Copying DOS Files to Base Operating System Files” on page 86
 - “Copying Base Operating System Files to DOS Files” on page 87
 - “Deleting DOS Files” on page 87
 - “Listing Contents of a DOS Directory” on page 87
- “Command Summary for Files” on page 88

Types of Files

There are three basic types of files:

regular	Stores data (text, binary, and executable).
directory	Contains information used to access other files.
special	Defines a FIFO (first-in, first-out) pipe file or a physical device.

All file types recognized by the system fall into one of these categories. However, the operating system uses many variations of these basic types.

Regular Files

Regular files are the most common files. Another name for regular files is ordinary files. Regular files contain data.

Text Files

Text files are regular files that contain information readable by the user. This information is stored in ASCII. You can display and print these files. The lines of a text file must not contain **NUL** characters, and none can exceed **{LINE_MAX}** bytes in length, including the new-line character.

The term *text file* does not prevent the inclusion of control or other nonprintable characters (other than **NUL**). Therefore, standard utilities that list text files as inputs or outputs are either able to process the special characters gracefully or they explicitly describe their limitations within their individual sections.

Binary Files

Binary files are regular files that contain information readable by the computer. Binary files might be executable files that instruct the system to accomplish a job. Commands and programs are stored in executable, binary files. Special compiling programs translate ASCII text into binary code.

The only difference between text and binary files is that text files have lines of less than **{LINE_MAX}** bytes, with no **NUL** characters, each terminated by a new-line character.

Directory Files

Directory files contain information the system needs to access all types of files, but they do not contain the actual file data. As a result, directories occupy less space than a regular file and give the file system structure flexibility and depth. Each directory entry represents either a file or a subdirectory. Each entry contains the name of the file and the file's index node reference number (i-node number). The i-node number points to the unique index node assigned to the file. The i-node number describes the location of the data associated with the file. Directories are created and controlled by a separate set of commands.

See "Directory Overview" on page 55 for more information.

Special Files

Special files define devices for the system or temporary files created by processes. There are three basic types of special files: FIFO (first-in, first-out), block, and character. FIFO files are also called pipes. Pipes are created by one process to temporarily allow communication with another process. These files cease to exist when the first process finishes. Block and character files define devices.

Every file has a set of permissions (called access modes) that determine who can read, modify, or execute the file.

To learn more about file access modes, see "File and Directory Access Modes" on page 121 .

File Naming Conventions

The name of each file must be unique within the directory where it is stored. This ensures that the file also has a unique path name in the file system. File-naming guidelines are:

- A file name can be up to 255 characters long and can contain letters, numbers, and underscores.
- The operating system is case-sensitive, which means it distinguishes between uppercase and lowercase letters in file names. Therefore, FILEA, FiLea, and filea are three distinct file names, even if they reside in the same directory.
- File names should be as descriptive and meaningful as possible.
- Directories follow the same naming conventions as files.
- Certain characters have special meaning to the operating system and should be avoided when naming files. These characters include the following:
`/ \ " ' * ; - ? [] () ^ ! $ { } < > # @ & |`
- A file name is hidden from a normal directory listing if it begins with a dot (.). When the **ls** command is entered with the **-a** flag, the hidden files are listed along with regular files and directories.

File Path Names

The path name for each file and directory in the file system consists of the names of every directory that precedes it in the tree structure.

Since all paths in a file system originate from the **/(root)** directory, each file in the file system has a unique relationship to the root directory known as the absolute path name. Absolute path names begin with the slash (/) symbol. The absolute path name of file **h** within the Example File System is **/B/C/h**. Notice that there are two files named **g**. Because the absolute paths to these files are different, **/B/g** and **/B/C/g**, each file named **g** has a unique name within the system. Every component of a path name is a directory except the final component. The final component of a path name can be a file name.

Note: Path names cannot exceed 1023 characters.

Pattern Matching with Wildcards and Metacharacters

Wildcard characters provide a convenient way for specifying multiple file or directory names with one character. The two wildcard characters are asterisk (*) and question mark (?). The metacharacters are open and close square brackets ([]), hyphen (-), and exclamation mark (!).

* Wildcard

Use the * to match any sequence or string of characters. The * means any characters, including no characters. For example, if you have the following files in your directory:

```
1test 2test afile1 afile2 bfile1 file file1 file10 file2 file3
```

and you want to refer to only to the files that begin with file, you would use:

```
file*
```

The files selected would be: file file1 file10 file2 file3

To refer to only the files that contain the word file, you would use:

```
*file*
```

The files selected would be: afile1 afile2 bfile1 file file1 file10 file2 file3

? Wildcard

Use the ? to match any one character. The ? means any single character.

To refer to only the files that start with file and end with a single character, use:

```
file?
```

The files selected would be: file1 file2 file3

To refer to only the files that start with file and end with any two characters, use:

```
file??
```

The file selected would be: file10

[] Shell Metacharacters

Metacharacters offer another type of wildcard notation by enclosing the desired characters within []. It is like using the ?, but it allows you to choose specific characters to be matched. The [] also allow you to specify a range of values using the hyphen (-). To specify all the letters in the alphabet, use [[:alpha:]]. To specify all the lowercase letters in the alphabet, use [[:lower:]].

To refer to only the files that end in 1 or 2, use:

```
*file[12]
```

The files selected would be: afile1 afile2 file1 file2

To refer only to the files that start with any number, use:

```
[0123456789]* or [0-9]*
```

The files selected would be: 1test 2test

To refer only to the files that don't begin with an a, use:

```
[!a]*
```

The files selected would be: 1test 2test bfile1 file file1 file10 file2 file3

Pattern Matching versus Regular Expressions

Regular expressions allow you to select specific strings from a set of character strings. The use of regular expressions is generally associated with text processing.

Regular expressions can represent a wide variety of possible strings. While many regular expressions can be interpreted differently depending on the current locale, internationalization features provide for contextual invariance across locales.

See the examples in the following comparison between File Matching Patterns and Regular Expressions:

Pattern Matching	Regular Expression
*	.*
?	.
[!a]	[^a]
[abc]	[abc]
[[:alpha:]]	[[:a]pha:]

See the **awk** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“Chapter 11. Shells” on page 149

“File Systems” on page 52

“Directory Overview” on page 55

“Linking Files and Directories” on page 83

“DOS Files” on page 86

“Chapter 7. Printers, Print Jobs, and Queues” on page 91

“Chapter 8. Backup Files and Storage Media” on page 105

“Chapter 9. File and System Security” on page 119

File Handling Procedures

There are many ways to work with the files on your system. Usually you create a text file with a text editor. The common editors in the UNIX environment are **vi** and **ed**. The operating system also includes its own text editor, **INed**. Because several text editors are available, you can choose to edit with the editor you feel comfortable with.

You can also create files by using input/output redirection, as described in “Chapter 4. Input and Output Redirection” on page 41. The output of a command can be sent to a new file or appended to an existing file.

After creating and modifying files, you might have to copy or move files from one directory to another, rename files to distinguish different versions of a file or give different names to the same file. You might also need to create new directories when working on different projects.

Also, you might need to delete certain files. Your directory can quickly get cluttered with files that contain old or useless information. Deleting files that are not needed frees up storage space on your system.

This section discusses:

- “Deleting Files (rm Command)” on page 72
- “Moving and Renaming Files (mv Command)” on page 72
- “Copying Files (cp Command)” on page 73
- “Finding Files (find Command)” on page 74
- “Showing File Type (file Command)” on page 75
- “Displaying File Contents (pg, more, page, and cat Commands)” on page 76
- “Finding Strings in Text Files (grep Command)” on page 77
- “Sorting Text Files (sort Command)” on page 77
- “Comparing Files (diff Command)” on page 78
- “Counting Words, Lines, and Bytes in Files (wc Command)” on page 79

- “Displaying the First Lines of Files (head Command)” on page 79
- “Displaying the Last Lines of Files (tail Command)” on page 80
- “Cutting Sections of Text Files (cut Command)” on page 80
- “Pasting Sections of Text Files (paste Command)” on page 81
- “Numbering Lines in Text Files (nl Command)” on page 82
- “Removing Columns in Text Files (colrm Command)” on page 82

Deleting Files (rm Command)

When you no longer need a file, you can remove it with the **rm** command. The **rm** command does not require user confirmation before removing the file. You can use **rm** to delete a group of files or to select certain files from a list for deletion.

rm Command

The **rm** command removes the entries for the specified file or files from a directory. You do not need read or write permission for the file you want to remove. However, you must have write permission for the directory containing that file.

For example, to delete the file named `myfile`, type:

```
rm myfile
```

Press Enter.

To delete all the files in the `mydir` directory one by one, type:

```
rm -i mydir/*
```

Press Enter.

After each file name is displayed, type `y` and press Enter to delete the file, or press the Enter key to keep it.

See the **rm** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Moving and Renaming Files (mv Command)

The **mv** command moves files and directories from one directory to another or renames a file or directory. If you move a file or directory to a new directory without specifying a new name, it retains its original name.

Attention: The **mv** command can overwrite many existing files unless you specify the **-i** flag. The **-i** flag prompts you to confirm before it overwrites a file. The **-f** flag does not prompt you. If both the **-f** and **-i** flags are specified in combination, the last flag specified takes effect.

Moving Files with mv Command

For example, to move a file to another directory and give it a new name, type:

```
mv intro manual/chap1
```

Press Enter.

This moves `intro` to `manual/chap1`. The name `intro` is removed from the current directory, and the same file appears as `chap1` in the directory `manual`. Note the previous **Attention** note.

For example, to move a file to another directory, keeping the same name, type:


```
mv chap3 manual
```

Press Enter.

This moves chap3 to manual/chap3. Note the previous **Attention** note.

Renaming Files with mv Command

For example, to rename a file, type:

```
mv appendix apndx.a
```

Press Enter.

This renames appendix to apndx.a. If a file named apndx.a already exists, its old contents are replaced with those of appendix. Note the previous **Attention** note.

See the **mv** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Copying Files (cp Command)

The **cp** or **copy** command creates a copy of the contents of the file or directory specified by the *SourceFile* or *SourceDirectory* parameters into the file or directory specified by the *TargetFile* or *TargetDirectory* parameters. If the file specified as the *TargetFile* exists, the copy writes over the original contents of the file without warning. If you are copying more than one *SourceFile*, the target must be a directory.

If a file with the same name exists at the new destination, the copied file will overwrite the file at the new destination. Therefore, it is a good practice to assign a new name for the copy of the file to ensure that a file of the same name does not exist in the destination directory.

To place a copy of the *SourceFile* into a directory, specify a path to an existing directory for the *TargetDirectory* parameter. Files maintain their respective names when copied to a directory unless you specify a new file name at the end of the path. The **cp** command also copies entire directories into other directories if you specify the **-r** or **-R** flags.

You can also copy special-device files. The preferred option for accomplishing this is the **-R** flag. Specifying **-R** causes the special files to be recreated under the new path name. Specifying the **-r** flag causes the **cp** command to attempt to copy the special files to regular files.

For example, to make a copy of a file in the current directory, type:

```
cp prog.c prog.bak
```

Press Enter.

This copies prog.c to prog.bak. If the prog.bak file does not already exist, then the **cp** command creates it. If it does exist, then the **cp** command replaces it with a copy of the prog.c file.

For example, to copy a file in your current directory into another directory, type:

```
cp jones /home/nick/clients
```

Press Enter.

This copies the jones file to /home/nick/clients/jones.

For example, to copy all the files in a directory to a new directory, type:

```
cp /home/janet/clients/* /home/nick/customers
```

Press Enter.

This copies only the files in the `clients` directory to the `customers` directory.

For example, to copy a specific set of files to another directory, type:

```
cp jones lewis smith /home/nick/clients
```

Press Enter.

This copies the `jones`, `lewis`, and `smith` files in your current working directory to the `/home/nick/clients` directory.

For example, to use pattern-matching characters to copy files, type:

```
cp programs/*.c .
```

This copies the files in the `programs` directory that end with `.c` to the current directory, signified by the single dot (`.`). You must type a space between the `c` and the final dot.

See the **cp** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Finding Files (find Command)

The **find** command recursively searches the directory tree for each specified *Path*, seeking files that match a Boolean expression written using the terms given in the following text. The output from the **find** command depends on the terms specified by the *Expression* parameter.

For example, to list all files in the file system with the name `.profile`, enter:

```
find / -name .profile
```

This searches the entire file system and writes the complete path names of all files named `.profile`. The slash (`/`) tells the **find** command to search the **/(root)** directory and all of its subdirectories. To avoid wasting time, it is best to limit the search by specifying the directories where you think the files might be.

For example, to list files having a specific permission code of `0600` in the current directory tree, enter:

```
find . -perm 0600
```

This lists the names of the files that have *only* owner-read and owner-write permission. The dot (`.`) tells the **find** command to search the current directory and its subdirectories. See the **chmod** command for an explanation of permission codes.

For example, to search several directories for files with certain permission codes, enter:

```
find manual clients proposals -perm -0600
```

This lists the names of the files that have owner-read and owner-write permission and possibly other permissions. The `manual`, `clients`, and `proposals` directories and their subdirectories are searched. In the previous example, `-perm 0600` selects only files with permission codes that match `0600` exactly. In this example, `-perm -0600` selects files with permission codes that allow the accesses indicated by `0600` and other accesses above the `0600` level. This also matches the permission codes `0622` and `2744`.

For example, to list all files in the current directory that have been changed during the current 24-hour period, enter:

```
find . -ctime 0
```

For example, to search for regular files with multiple links, enter:

```
find . -type f -links +1
```

Press Enter.

This lists the names of the ordinary files (-type f) that have more than one link (-links +1).

Note: Every directory has at least two links: the entry in its parent directory and its own .(dot) entry. See the **ln** command for more information on multiple file links.

For example, to print the path names of all files in or below the current directory, except the directories named SCCS or files in the SCCS directories, type:

Press Enter.

```
find . -name SCCS -prune
```

For example, to search for all files that are exactly 414 bytes long, type:

```
find . -size 414c
```

Press Enter.

See the **find** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Showing File Type (file Command)

The **file** command reads the files specified by the *File* or **-f FileList** parameter, performs a series of tests on each one, and attempts to classify them by types. The command then writes the file types to standard output.

If a file appears to be ASCII, the **file** command examines the first 512 bytes and determines its language. If a file does not appear to be ASCII, the **file** command further attempts to determine whether it is a binary data file or a text file that contains extended characters.

If the *File* parameter specifies an executable or object module file and the version number is greater than 0, the **file** command displays the version stamp.

The **file** command uses the **/etc/magic** file to identify files that have some sort of magic number, that is, any file containing a numeric or string constant that indicates type.

For example, to display the type of information the file named `myfile` contains, type:

```
file myfile
```

Press Enter.

This displays the file type of `myfile` (such as directory, data, ASCII text, C-program source, and archive).

For example, to display the type of each file named in `filenames.lst`, which contains a list of file names, type:

```
file -f filenames.lst
```

Press Enter.

This displays the type of each file named in the `filenames.lst` list. Each file name must appear alone on a line.

For example, to create the file `filenames.lst`, so that it contains all the file names in the current directory type:

```
ls > filenames.lst
```

Press Enter.

Then edit `filenames` as desired.

See the **file** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying File Contents (pg, more, page, and cat Commands)

The **pg**, **more**, and **page** commands allow you to view the contents of a file and control the speed at which your files are displayed. You can also use the **cat** command to display the contents of one or more files on your screen. Combining the **cat** command with the **pg** command allows you to read the contents of a file one full screen at a time.

You can also display the contents of files by using input/output redirection. See "Input and Output Redirection Overview ("Chapter 4. Input and Output Redirection" on page 41)" for more details on input/output redirection.

pg Command

The **pg** command reads the file names from the *File* parameter and writes them to standard output one screen at a time. If you specify hyphen (-) as the *File* parameter, or run the **pg** command without options, the **pg** command reads standard input. Each screen is followed by a prompt. If you press the Enter key, another screen displays. Subcommands used with the **pg** command let you review something that has already passed.

For example, to look at the contents of the file `myfile` one page at a time, type:

```
pg myfile
```

Press Enter.

See the **pg** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

more or page Command

The **more** or **page** command displays continuous text one screen at a time. It pauses after each screen and prints the *filename* and percent done (for example, `myfile (7%)`) at the bottom of the screen. If you then press the Enter key, the **more** command displays an additional line. If you press the Spacebar, the **more** command displays another screen of text.

Note: On some terminal models, the **more** command clears the screen, instead of scrolling, before displaying the next screen of data.

For example, to view a file named `myfile`, type:

```
more myfile
```

Press Enter.

Press the Spacebar to view the next screen.

See the **more** command in the *AIX 5L Version 5.1 Commands Reference* for more information and the exact syntax.

cat Command

The **cat** command reads each *File* parameter in sequence and writes it to standard output.

For example, to display the contents of the file `notes`, type:

```
cat notes
```

Press Enter.

If the file is more than 24 lines long, some of it scrolls off the screen. To list a file one page at a time, use the **pg** command.

For example, to display the contents of the files `notes`, `notes2`, and `notes3`, type:

```
cat notes notes2 notes3
```

Press Enter.

See the **cat** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Finding Strings in Text Files (grep Command)

The **grep** command searches for the pattern specified by the *Pattern* parameter and writes each matching line to standard output.

For example, to search in a file named `pgm.s` for a pattern that contains some of the pattern-matching characters `*`, `^`, `?`, `[`, `]`, `\(`, `\)`, `\{`, and `\}`, in this case lines starting with any lower or upper case letter, type:

```
grep "^[a-zA-Z]" pgm.s
```

Press Enter.

This displays all lines in `pgm.s` that begin with a letter.

To display all lines in a file named `sort.c` that do not match a pattern, type:

```
grep -v bubble sort.c
```

Press Enter.

This displays all lines that do not contain the word `bubble` in the file `sort.c`.

To display lines in the output of the **ls** command that match the string `staff`, type:

```
ls -l | grep staff
```

Press Enter.

See the **grep** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Sorting Text Files (sort Command)

The **sort** command alphabetizes or sequences lines in the files specified by the *File* parameters and writes the result to standard output. If the *File* parameter specifies more than one file, the **sort** command concatenates the files and alphabetizes them as one file.

Note: The **sort** command is case-sensitive and orders uppercase letters before lowercase (this is dependent on the locale).

In the following examples the contents of the file names are:

```
marta  
denise  
joyce  
endrica  
melanie
```

and the contents of the file states are:

```
texas  
colorado  
ohio
```

To display the sorted contents of the file named names, type:

```
sort names
```

Press Enter.

The system displays information similar to the following:

```
denise  
endrica  
joyce  
marta  
melanie
```

To display the sorted contents of the two files names and states, type:

```
sort names states
```

Press Enter.

The system displays information similar to the following:

```
colorado  
denise  
endrica  
joyce  
marta  
melanie  
ohio  
texas
```

To replace the original contents of the file named names with its sorted contents, type:

```
sort -o names names
```

Press Enter.

This replaces the file names with the same data but in sorted order.

See the **sort** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Comparing Files (diff Command)

The **diff** command compares text files. It can compare single files or the contents of directories.

When the **diff** command is run on regular files, and when it compares text files in different directories, the **diff** command tells which lines must be changed in the files to make them agree.

For example, to compare two files, type:

```
diff chap1.bak chap1
```

Press Enter.

This displays the differences between the files `chap1.bak` and `chap1`.

For example, to compare two files while ignoring differences in the amount of white space, type:

```
diff -w prog.c.bak prog.c
```

Press Enter.

If two lines differ only in the number of spaces and tabs between words, the **diff -w** command considers them to be the same.

See the **diff** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Counting Words, Lines, and Bytes in Files (wc Command)

By default, the **wc** command counts the number of lines, words, and bytes in the files specified by the *File* parameter. If a file is not specified for the *File* parameter, standard input is used. The command writes the results to standard output and keeps a total count for all named files. If flags are specified, the ordering of the flags determines the ordering of the output. A *word* is defined as a string of characters delimited by spaces, tabs, or newline characters.

When files are specified on the command line, their names will be printed along with the counts.

For example, to display the line, word, and byte counts of the file named `chap1`, type:

```
wc chap1
```

Press Enter.

This displays the number of lines, words, and bytes in the `chap1` file.

For example, to display only byte and word counts, type:

```
wc -cw chap*
```

Press Enter.

This displays the number of bytes and words in each file where the name starts with `chap`, and displays the totals.

See the **wc** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying the First Lines of Files (head Command)

The **head** command writes to standard output the first few lines of each of the specified files or of the standard input. If no flag is specified with the **head** command, the first 10 lines are displayed by default.

For example, to display the first five lines of the `Test` file, type:

```
head -5 Test
```

Press Enter.

See the **head** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Displaying the Last Lines of Files (tail Command)

The **tail** command writes the file specified by the *File* parameter to standard output beginning at a specified point.

For example, to display the last 10 lines of the notes file, type:

```
tail notes
```

Press Enter.

For example, to specify the number of lines to start reading from the end of the notes file, type:

```
tail -20 notes
```

Press Enter.

For example, to display the notes file one page at a time, beginning with the 200th byte, type:

```
tail -c +200 notes | pg
```

Press Enter.

For example, to follow the growth of the file named accounts, type:

```
tail -f accounts
```

Press Enter.

This displays the last 10 lines of the accounts file. The **tail** command continues to display lines as they are added to the accounts file. The display continues until you press the (Ctrl-C) key sequence to stop it.

See the **tail** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

See the **tail** command in the *AIX 5L Version 5.1 Commands Reference* for more information and the exact syntax.

Cutting Sections of Text Files (cut Command)

The **cut** command writes to standard output selected bytes, characters, or fields from each line of a file.

For example, to display several fields of each line of a file:

```
cut -f1,5 -d: /etc/passwd
```

This displays the login name and full user name fields of the system password file. These are the first and fifth fields (-f1,5) separated by colons (-d:).

For example, if the **/etc/passwd** file looks like this:

```
su:*:0:0:User with special privileges:./usr/bin/sh
daemon:*:1:1::/etc:
bin:*:2:2:./usr/bin:
sys:*:3:3:./usr/src:
adm:*:4:4:System Administrator:/var/adm:/usr/bin/sh
pierre:*:200:200:Pierre Harper:/home/pierre:/usr/bin/sh
joan:*:202:200:Joan Brown:/home/joan:/usr/bin/sh
```

the **cut** command produces:


```
su:User with special privileges
daemon:
bin:
sys:
adm:System Administrator
pierre:Pierre Harper
joan:Joan Brown
```

See the **cut** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Pasting Sections of Text Files (paste Command)

The **paste** command merges the lines of up to 12 files into one file.

For example, if you have a file named `names` that contains the following text:

```
rachel
jerry
mark
linda
scott
```

another file named `places` that contains the following text:

```
New York
Austin
Chicago
Boca Raton
Seattle
```

and another file named `dates` that contains the following text:

```
February 5
March 13
June 21
July 16
November 4
```

to paste the text of the files `names`, `places`, and `dates` together, type:

```
paste names places dates > npd
```

Press Enter.

This creates a file named `npd` that contains the data from the `names` file in one column, the `places` file in another, and the `dates` file in a third. The `npd` file now contains:

```
rachel      New York    February 5
jerry      Austin     March 13
mark       Chicago    June 21
linda      Boca Raton July 16
scott      Seattle    November 4
```

A tab character separates the name, place, and date on each line. These columns do not always line up because the tab stops are set at every eighth column.

For example, to separate the columns with a character other than a tab, type:

```
paste -d"!@" names places dates > npd
```

Press Enter.

This alternates `!` and `@` as the column separators. If the `names`, `places`, and `dates` files are the same as in example 1, then the `npd` file contains:

```
rachel!New York@February 5
jerry!Austin@March 13
mark!Chicago@June 21
linda!Boca Raton@July 16
scott!Seattle@November 4
```

For example, to list the current directory in four columns, type:

```
ls | paste - - - -
```

Press Enter.

Each hyphen (-) tells the **paste** command to create a column containing data read from the standard input. The first line is put in the first column, the second line in the second column, and so on.

See the **paste** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Numbering Lines in Text Files (nl Command)

The **nl** command reads the specified file (standard input by default), numbers the lines in the input, and writes the numbered lines to standard output.

For example, to number only the nonblank lines, type:

```
nl chap1
```

Press Enter.

This displays a numbered listing of chap1, numbering only the nonblank lines in the body sections.

For example, to number all lines:

```
nl -ba chap1
```

This numbers all the lines in the file named chap1, including blank lines.

See the **nl** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Removing Columns in Text Files (colrm Command)

The **colrm** command removes specified columns from a file. Input is taken from standard input. Output is sent to standard output.

If called with one parameter, the columns of each line from the specified column to the last column are removed. If called with two parameters, the columns from the first specified column to the second specified column are removed.

Note: Column numbering starts with column 1.

For example, to remove columns from the text.fil file, type:

```
colrm 6 < text.fil
```

Press Enter.

If text.fil contains:

```
123456789
```

then the **colrm** command displays:

See the **colrm** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“Chapter 11. Shells” on page 149

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Linking Files and Directories”

“DOS Files” on page 86

“Chapter 7. Printers, Print Jobs, and Queues” on page 91

“Chapter 8. Backup Files and Storage Media” on page 105

“Chapter 9. File and System Security” on page 119

Linking Files and Directories

Links are connections between a file name and an index node reference number (i-node number), the internal representation of a file. Because directory entries contain file names paired with i-node numbers, every directory entry is a link. The i-node number actually identifies the file, not the file name. By using links, any i-node number or file can be known by many different names.

For example, i-node number 798 contains a memo regarding June sales in the Omaha office. Presently, the directory entry for this memo is:

i-node Number	File Name
798	memo

Because this information relates to information stored in the `sales` and `omaha` directories, linking is used to share the information where it is needed. Using the **ln** command, links are created to these directories. Now the file has three file names:

i-node Number	File Name
798	memo
798	sales/june
798	omaha/junesales

When you use the **pg** or **cat** command to view the contents of any of the three file names, the same information is displayed. If you edit the contents of the i-node number from any of the three file names, the contents of the data displayed by all of the file names will reflect any changes.

This section discusses:

- “Types of Links”
- “Linking Files (ln Command)”
- “Removing Linked Files” on page 85

Types of Links

Links are created with the **ln** command. There are two kinds of links:

hard link	Allows access to the data of a file from a new file name. Hard links ensure the existence of a file. When the last hard link is removed, the i-node number and its data are deleted. Hard links can be created only between files that are in the same file system.
symbolic link	Allows access to data in other file systems from a new file name. The symbolic link is a special type of file that contains a path name. When a process encounters a symbolic link, the process may search that path. Symbolic links do not protect a file from deletion from the file system.

Note: The user who creates a file retains ownership of that file no matter how many links are created. Only the owner of the file or the root user can set the access mode for that file. However, changes can be made to the file from a linked file name with the proper access mode.

A file or directory exists as long as there is one hard link to the i-node number for that file. In the long listing displayed by the **ls -l** command, the number of links to each file and subdirectory is given. All hard links are treated equally by the operating system regardless of which link was created first.

Linking Files (ln Command)

Linking files with the **ln** command is a convenient way to work with the same data in more than one place. Links are created by giving alternate names to the original file. The use of links allows a large file, such as a database or mailing list, to be shared by several users without making copies of that file. Not only do links save disk space, but changes made to one file are automatically reflected in all the linked files.

The **ln** command links the file designated in the *SourceFile* parameter to the file designated by the *TargetFile* parameter or to the same file name in another directory specified by the *TargetDirectory* parameter. By default, the **ln** command creates hard links. To use the **ln** command to create symbolic links, designate the **-s** flag.

If you are linking a file to a new name, you can list only one file. If you are linking to a directory, you can list more than one file.

The *TargetFile* parameter is optional. If you do not designate a target file, the **ln** command creates a new file in your current directory. The new file inherits the name of the file designated in the *SourceFile* parameter.

Note: You cannot link files across file systems without using the **-s** flag.

For example, to create another link to a file named `chap1`, type:

```
ln -f chap1 intro
```

Press Enter.

This links `chap1` to the new name, `intro`. When the **-f** flag is used, the file name `intro` is created if it does not already exist. If `intro` does exist, the file is replaced by a link to `chap1`. Then both the `chap1` and `intro` file names will refer to the same file. Any changes made to one also appear in the other.

For example, to link a file named `index` to the same name in another directory named `manual`, type:

```
ln index manual
```

Press Enter.

This links `index` to the new name, `manual/index`.

For example, to link several files to names in another directory, type:

```
ln chap2 jim/chap3 /home/manual
```

Press Enter.

This links `chap2` to the new name `/home/manual/chap2` and `jim/chap3` to `/home/manual/chap3`.

For example, to use the **ln** command with pattern-matching characters, type:

```
ln manual/* .
```

Press Enter.

This links all files in the `manual` directory into the current directory, dot (`.`), giving them the same names they have in the `manual` directory.

Note: You must type a space between the asterisk and the period.

For example, to create a symbolic link, type:

```
ln -s /tmp/toc toc
```

Press Enter.

This creates the symbolic link, `toc`, in the current directory. The `toc` file points to the `/tmp/toc` file. If the `/tmp/toc` file exists, the **cat** `toc` command lists its contents.

To achieve identical results without designating the *TargetFile* parameter, type:

```
ln -s /tmp/toc
```

Press Enter.

See the **ln** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Removing Linked Files

The **rm** command removes the link from the file name you indicate. When one of several hard-linked file names is deleted, the file is not completely deleted since it remains under the other name. When the last link to an i-node number is removed, the data is removed as well. The i-node number is then available for reuse by the system.

See the **rm** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“Chapter 11. Shells” on page 149

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“DOS Files”

“Chapter 7. Printers, Print Jobs, and Queues” on page 91

“Chapter 8. Backup Files and Storage Media” on page 105

“Chapter 9. File and System Security” on page 119

DOS Files

This operating system allows you to work with DOS files on your system. Copy to a diskette the DOS files you want to work with. With the right commands, your system can read these files into a base operating system directory in the correct format and back onto the diskette in DOS format.

Note: The wildcard characters * and ? (asterisk and question mark) do not work with these commands (although they do with the base operating system shell). If you do not specify a file name extension, the file name is matched as if you had specified a blank extension.

This section describes:

- “Copying DOS Files to Base Operating System Files”
- “Copying Base Operating System Files to DOS Files” on page 87
- “Deleting DOS Files” on page 87
- “Listing Contents of a DOS Directory” on page 87

Copying DOS Files to Base Operating System Files

The **dosread** command copies the specified DOS file to the specified base operating system file.

Note: DOS file-naming conventions are used with one exception. Because the backslash (\) character can have special meaning to the base operating system, use a slash (/) character as the delimiter to specify subdirectory names in a DOS path name.

For example, to copy a text file named chap1.doc from a DOS diskette to the base operating file system, type:

```
dosread -a chap1.doc chap1
```

Press Enter.

This copies the DOS text file \CHAP1.DOC on default device **/dev/fd0** to the base operating system file chap1 in the current directory.

For example, to copy a binary file from a DOS diskette to the base operating file system, type:

```
dosread -D/dev/fd1 /survey/test.dta /home/fran/testdata
```

Press Enter.

This copies the DOS data file \SURVEY\TEST.DTA on **/dev/fd1** to the base operating system file /home/fran/testdata.

See the **dosread** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Copying Base Operating System Files to DOS Files

The **doswrite** command copies the specified base operating system file to the specified DOS file.

Note: DOS file-naming conventions are used with one exception. Because the backslash (\) character can have special meaning to the base operating system, use a slash (/) character as the delimiter to specify subdirectory names in a DOS path name.

For example, to copy a text file named chap1 from the base operating file system to a DOS diskette, type:

```
doswrite -a chap1 chap1.doc
```

Press Enter.

This copies the base operating system file chap1 in the current directory to the DOS text file \CHAP1.DOC on **/dev/fd0**.

For example, to copy a binary file named /survey/test.dta from the base operating file system to a DOS diskette, type:

```
doswrite -D/dev/fd1 /home/fran/testdata /survey/test.dta
```

Press Enter.

This copies the base operating system data file /home/fran/testdata to the DOS file \SURVEY\TEST.DTA on **/dev/fd1**.

See the **doswrite** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Deleting DOS Files

The **dosdel** command deletes the specified DOS file.

Note: DOS file-naming conventions are used with one exception. Because the backslash (\) character can have special meaning to the base operating system, use a slash (/) character as the delimiter to specify subdirectory names in a DOS path name.

The **dosdel** command converts lowercase characters in the file or directory name to uppercase before it checks the disk. Because all file names are assumed to be full (not relative) path names, you need not add the initial slash (/).

For example, to delete a DOS file named file.ext on the default device (**/dev/fd0**), type:

```
dosdel file.ext
```

Press Enter.

See the **dosdel** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Listing Contents of a DOS Directory

The **dosdir** command displays information about the specified DOS files or directories.

Note: DOS file-naming conventions are used with one exception. Because the backslash (\) character can have special meaning to the base operating system, use a slash (/) character as the delimiter to specify subdirectory names in a DOS path name.

The **dosdir** command converts lowercase characters in the file or directory name to uppercase before it checks the disk. Because all file names are assumed to be full (not relative) path names, you need not add the initial / (slash).

For example, to read a directory of the DOS files on **/dev/fd0**, type:

```
dosdir
```

Press Enter.

The command returns the names of the files and disk-space information.

```
PG3-25.TXT  
PG4-25.TXT  
PG5-25.TXT  
PG6-25.TXT  
Free space: 312320 bytes
```

See the **dosdir** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“Chapter 11. Shells” on page 149

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Linking Files and Directories” on page 83

“Chapter 7. Printers, Print Jobs, and Queues” on page 91

“Chapter 8. Backup Files and Storage Media” on page 105

“Chapter 9. File and System Security” on page 119

Command Summary for Files

*	Wildcard, matches any characters.
?	Wildcard, matches any single character.
[]	Metacharacters, matches enclosed characters.

File Handling Procedures

cat Concatenates or displays files.

cmp	Compares two files.
colrm	Extracts columns from a file.
cp	Copies files.
cut	Writes out selected bytes, characters, or fields from each line of a file.
diff	Compares text files.
file	Determines the file type.
find	Finds files with a matching expression.
grep	Searches a file for a pattern.
head	Displays the first few lines or bytes of a file or files.
more	Displays continuous text one screen at a time on a display screen.
mv	Moves files.
nl	Numbers lines in a file.
pg	Formats files to the display.
rm	Removes (unlinks) files or directories.
paste	Merges the lines of several files or subsequent lines in one file.
page	Displays continuous text one screen at a time on a display screen.
sort	Sorts files, merges files that are already sorted, and checks files to determine if they have been sorted.
tail	Writes a file to standard output, beginning at a specified point.
wc	Counts the number of lines, words, and bytes in a file.

Linking Files and Directories

ln Links files and directories.

DOS Files

dosdel	Deletes DOS files.
dosdir	Lists the directory for DOS files.
dosread	Copies DOS files to Base Operating System files.
doswrite	Copies Base Operating System files to DOS files.

Chapter 7. Printers, Print Jobs, and Queues

Depending on the printer, you can control the appearance and characteristics of the final output. The printers need not be located in the same area as the system unit and the system console. A printer can be attached directly to a local system, or a print job can be sent over a network to a remote system.

To handle print jobs with maximum efficiency, the system places each job into a queue to await printer availability. The system can save output from one or more files in the queue. As the printer produces the output from one file, the system processes the next job in the queue. This process continues until each job in the queue has been printed.

AIX 5L Version 5.1 Guide to Printers and Printing provides detailed information about printers, print jobs, and queues.

This section discusses:

- “Printer Terminology”
- “Starting a Print Job (qprt Command)” on page 93
- “Canceling a Print Job (qcan Command)” on page 96
- “Checking Print Job Status (qchk Command)” on page 97
- “Printer Status Conditions” on page 98
- “Prioritizing a Print Job (qpri Command)” on page 98
- “Holding and Releasing a Print Job (qhld Command)” on page 99
- “Moving a Print Job to Another Print Queue (qmov Command)” on page 100
- “Formatting Files for Printing (pr Command)” on page 100
- “Printing ASCII Files on a PostScript Printer” on page 102
- “Automating the Conversion of ASCII to PostScript” on page 103
- “Overriding Automatic Determination of Print File Types” on page 103
- “Command Summary for Printers, Print Jobs, and Queues” on page 104

Printer Terminology

The following describes terms commonly used with printing.

Print Job

A *print job* is a unit of work to be run on a printer. A print job can consist of printing one or more files, depending on how the print job is requested. The system assigns a unique job number to each job it runs.

Queue

The *queue* is where you direct a print job. It is a stanza in the */etc/qconfig* file whose name is the name of the queue and points to the associated queue device. The following is a sample listing:

```
Msa1:  
    device = lp0
```

In the previous example, Msa1 is the queue name, and lp0 is the device name.

Queue Device

The *queue device* is the stanza in the `/etc/qconfig` file that normally follows the local queue stanza. It specifies the `/dev` file (printer device) that should be printed to and the backend that should be used. Following is a sample listing:

```
lp0:
  file = /dev/lp0
  header = never
  trailer = never
  access = both
  backend = /usr/lpd/piobe
```

In the previous example, `lp0` is the device name and the rest of the lines define how the device is used.

Note: There can be more than one queue device associated with a single queue.

qdaemon

The **qdaemon** is a process that runs in the background and controls the queues. It is generally started when the system is turned on.

Print Spooler

The *spooler* is not specifically a print job spooler. Instead, it provides a generic spooling function that can be used for queuing various types of jobs, including print jobs queued to a printer.

The spooler does not normally know what type of job it is queuing. When the system administrator defines a spooler queue, the purpose of the queue is defined by the spooler backend program that is specified for the queue. For example, if the spooler backend program is the **piobe** command (the printer I/O backend), the queue is a print queue. Likewise, if the spooler backend program is a compiler, the queue is for compile jobs. When the spooler's **qdaemon** command selects a job from a spooler queue, it runs the job by invoking the backend program specified by the system administrator when the queue was defined.

The main spooler command is the **enq** command. Although you can invoke this command directly to queue a print job, three front-end commands are defined for submitting a print job: the **lp**, **lpr**, and **qprt** commands. A print request issued by one of these commands is first passed to the **enq** program, which then places the information about the file in the queue for the **qdaemon** to process.

Real Printer

A *real printer* is the printer hardware attached to a serial or parallel port at a unique hardware device address. The printer device driver in the kernel communicates with the printer hardware and provides an interface between the printer hardware and a virtual printer, but it is not aware of the concept of virtual printers.

Virtual Printer

A *virtual printer* is a set of attributes that define a specific software view of a real printer. This view of the virtual printer refers only to the high-level data stream (such as ASCII or PostScript) that the printer understands. It does not include any information about how the printer hardware is attached to the host computer or about the protocol used for transferring bytes of data to and from the printer. Virtual printers are defined by the system manager.

Local and Remote Printers

When you attach a printer to a node or host, the printer is referred to as a *local printer*. A *remote print system* allows nodes that are not directly linked to a printer to have printer access.

To use remote printing facilities, the individual nodes must be connected to a network using the Transmission Control Protocol/Internet Protocol (TCP/IP) and must support the required TCP/IP applications.

Printer Backend

The *printer backend* is a collection of programs called by the spooler's **qdaemon** command to manage a print job that is queued for printing. The printer backend performs the following functions:

- Receives from the **qdaemon** command a list of one or more files to be printed
- Uses printer and formatting attribute values from the database, overridden by flags entered on the command line
- Initializes the printer before printing a file
- Runs filters as necessary to convert the print data stream to a format supported by the printer
- Provides filters for simple formatting of ASCII documents
- Provides support for printing national language characters
- Passes the filtered print data stream to the printer device driver
- Generates header and trailer pages
- Generates multiple copies
- Reports paper out, intervention required, and printer error conditions
- Reports problems detected by the filters
- Cleans up after a print job is canceled
- Provides a print environment that a system administrator can customize to address specific printing needs

Starting a Print Job (qprt Command)

Use the “qprt Command” on page 94 “smit Command” on page 96 to request a print job and specify the following:

- Name of the file to print
- Print queue name
- Name of the output bin
- Number of copies to print
- Whether to make a copy of the file on the remote host
- Whether to erase the file after printing
- Whether to send notification of the job status
- Whether to send notification of the job status by the system mail
- Burst status
- User name for “Delivery To” label
- Console acknowledgment message for remote print
- File acknowledgment message for remote print
- Priority level.

Prerequisites

- For local print jobs, the printer must be physically attached to your system.
- For remote print jobs, your system must be configured to communicate with the remote print server.

qprt Command

The **qprt** command creates and queues a print job to print the file you specify. If you specify more than one file, all the files together make up one print job. These files are printed in the order specified on the command line.

Before you can print a file, you must have read access to it. To remove a file after it has printed, you must have write access to the directory that contains the file.

The basic format of the **qprt** command is:

-b <i>Number</i>	Specifies the bottom margin. The bottom margin is the number of blank lines to be left at the bottom of each page.
-B <i>Value</i>	Specifies whether burst pages (continuous-form pages separated at perforations) should be printed. The <i>Value</i> variable consists of a two-character string. The first character applies to header pages. The second character applies to trailer pages. Each of the two characters can be one of the following: a Always prints the (header or trailer) page for each file in each print job. n Never prints the (header or trailer) page. g Prints the (header or trailer) page once for each print job (group of files).
	For example, the -B ga flag specifies that a header page be printed at the beginning of each print job and that a trailer page be printed after each file in each print job.
	Note: In a remote print environment, the default is determined by the remote queue on the server.
-e <i>Option</i>	Specifies whether emphasized print is wanted. + Indicates emphasized print is wanted. ! Indicates emphasized print is not wanted.
-E <i>Option</i>	Specifies whether double-high print is wanted. + Indicates double-high print is wanted. ! Indicates double-high print is not wanted.
-f <i>FilterType</i>	A one-character identifier that specifies a filter through which your print file or files are to be passed before being sent to the printer. The available filter identifiers are p , which invokes the pr filter, and n , which processes output from the troff command.
-i <i>Number</i>	Causes each line to be indented the specified number of spaces. The <i>Number</i> variable must be included in the page width specified by the -w flag.
-K <i>Option</i>	Specifies whether condensed print is wanted. + Indicates condensed print is wanted. ! Indicates condensed print is not wanted.
-l <i>Number</i>	Sets the page length to the specified number of lines. If the <i>Number</i> variable is 0, page length is ignored, and the output is considered to be one continuous page. The page length includes the top and bottom margins and indicates the printable length of the paper.

-L <i>Option</i>	Specifies whether lines wider than the page width should be wrapped to the next line or truncated at the right margin. + Indicates that long lines should wrap to the next line. ! Indicates that long lines should not wrap but instead should be truncated at the right margin.
-N <i>Number</i>	Specifies the number of copies to be printed. If this flag is not specified, one copy is printed.
-p <i>Number</i>	Sets the pitch to <i>Number</i> characters per inch. Typical values for <i>Number</i> are 10 and 12. The actual pitch of the characters printed is also affected by the values for the -K (condensed) flag and the -W (double-wide) flag.
-P <i>Queue[:QueueDevice]</i>	Specifies the print queue name and the optional queue device name. If this flag is not specified, the default printer is assumed.
-Q <i>Value</i>	Specifies paper size for the print job. The <i>Value</i> for paper size is printer-dependent. Typical values are: 1 for letter-size paper, 2 for legal, and so on. Consult your printer manual for the values assigned to specific paper sizes.
-t <i>Number</i>	Specifies the top margin. The top margin is the number of blank lines to be left at the top of each page.
-w <i>Number</i>	Sets the page width to the number of characters specified by the <i>Number</i> variable. The page width must include the number of indentation spaces specified with the -i flag.
-W <i>Option</i>	Specifies whether double-wide print is wanted. + Indicates double-wide print is wanted. ! Indicates double-wide print is not wanted.
-z <i>Value</i>	Rotates page printer output the number of quarter-turns clockwise as specified by the <i>Value</i> variable. The length (-l) and width (-w) values are automatically adjusted accordingly. 0 Portrait 1 Landscape right 2 Portrait upside-down 3 Landscape left.
= <i>OutputBin</i>	Specifies the output bin destination for a print job. The possible values are listed below. However, the valid output bins are printer-dependent. 0 Top printer bin 1-49 High Capacity Output (HCO) bins 1 - 49 49 Printer-specific output bins
# <i>Value</i>	Specifies a special function. j Displays the job number for the specified print job. h Queues the print job, but puts it in the HELD state until it is released again. v Validates the specified printer backend flag values. This validation is useful in checking for illegal flag values at the time of submitting a print job. If the validation is not specified, an incorrect flag value will stop the print job later when the job is actually being processed.

For example, to request the `myfile` file to be printed on the first available printer configured for the default print queue using default values, type:

```
qprt myfile
```

For example, to request the file `somefile` to be printed on a specific queue using specific flag values and to validate the flag values at the time of print job submission, type:

```
qprt -f p -e + -Pfastest -# v somefile
```

This passes the `somefile` file through the `pr` filter command (the `-f p` flag) and prints it using emphasized mode (the `-e +` flag) on the first available printer configured for the queue named `fastest` (the `-Pfastest` flag).

For example, to print `myfile` on legal-size paper, type:

```
qprt -Q2 myfile
```

For example, to print three copies of each of the files `new.index.c`, `print.index.c`, and `more.c` at the print queue `Msp1`, type:

```
qprt -PMsp1 -N 3 new.index.c print.index.c more.c
```

For example, to print three copies of the concatenation of three files `new.index.c`, `print.index.c`, and `more.c`, type:

```
cat new.index.c print.index.c more.c | qprt -PMsp1 -N 3
```

Note: This operating system also supports the BSD UNIX print command (`lpr`) and the System V UNIX print command (`lp`). See the `lpr` and `lp` commands in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

See the `qprt` command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

smit Command

You can also issue the `qprt` command with `smit`. At the prompt, type:

```
smit qprt
```

then press Enter.

Canceling a Print Job (qcan Command)

You can cancel any job in the print queue with the “**qcan Command**” or “**smit Command**” on page 97. When you cancel a print job, you are prompted to provide the name of the print queue where the job resides and the job number to be canceled.

This procedure applies to both local and remote print jobs.

Prerequisites

- For local print jobs, the printer must be physically attached to your system.
- For remote print jobs, your system must be configured to communicate with the remote print server.

qcan Command

The `qcan` command cancels either a particular job number in a local or remote print queue, or all jobs in a local print queue. To determine the job number, type the `qchk` command.

The basic format of the `qcan` command is:

```
qcan -PQueueName -x JobNumber
```

See the `qcan` command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

For example, to cancel job number 123 on whichever printer the job is on, type:

```
qcan -x 123
```

For example, to cancel all jobs queued on printer `lp0`, type:


```
qcan -X -P1p0
```

Note: This operating system also supports the BSD UNIX cancel print command (**lprm**) and the System V UNIX cancel print command (**cancel**). See the **lprm** and **cancel** commands in the *AIX 5L Version 5.1 Commands Reference* for more information and the exact syntax.

smit Command

To cancel a print job using SMIT, type:

```
smit qcan
```

Checking Print Job Status (qchk Command)

You can display the current status information for specified job numbers, queues, printers, or users with the “**Web-based System Manager Fast Path**”, the “**qchk Command**”, or “**smit Command**” on **page 98**.

Prerequisites

- For local print jobs, the printer must be physically attached to your system.
- For remote print jobs, your system must be configured to communicate with the remote print server.

Web-based System Manager Fast Path

To check the status of a print job using the Web-based System Manager fast path, type:

```
wsm printers
```

In the Printer Queues container, select the print job, then use the menus to check its status.

qchk Command

The **qchk** command displays the current status information regarding specified print jobs, print queues, or users.

The basic format of the **qchk** command is:

```
qchk -P QueueName -# JobNumber -u OwnerName
```

See the **qchk** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

For example, to display the default print queue, type:

```
qchk -q
```

For example, to display the long status of all queues until empty, while updating the screen every 5 seconds, type:

```
qchk -A -L -w 5
```

For example, to display the status for print queue 1p0, type:

```
qchk -P 1p0
```

For example, to display the status for job number 123, type:

```
qchk -# 123
```

For example, to check the status of all jobs in all queues, type:

```
qchk -A
```

Note: This operating system also supports the BSD UNIX check print queue command (**lpq**) and the System V UNIX check print queue command (**lpstat**). See the **lpq** and **lpstat** commands in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

smit Command

To check a print job's status using SMIT, type:

```
smit qchk
```

Printer Status Conditions

Some of the status conditions that a print queue can have are:

DEV_BUSY	Indicates that: <ul style="list-style-type: none">• More than one queue is defined to a printer device (lp0), and another queue is currently using the printer device.• qdaemon attempted to use the printer port device (lp0), but another application is currently using that printer device. <p>To recover from a DEV_BUSY, wait until the queue or application has released the printer device or cancel the job or process that is using the printer port.</p>
DEV_WAIT	Indicates that the queue is waiting on the printer because the printer is offline, out of paper, jammed, or the cable is loose, bad, or wired incorrectly. <p>To recover from a DEV_WAIT, correct the problem that caused it to wait. Sometimes, the jobs have to be removed from the queue before the problem can be corrected.</p> <p>A queue that is in DEV_WAIT for longer than a defined number of seconds will go into a DOWN state.</p>
DOWN	A queue will usually go into a DOWN state after it has been in the DEV_WAIT state. This situation occurs when the printer device driver cannot tell if the printer is there due to absence of correct signalling. However, some printers might not have the capability to signal the queuing system that it is offline, and instead signals that it is off. If the printer device signals or appears to be off, the queue will go into the DOWN state. <p>To recover from a DOWN state, correct the problem that has brought the queue down and have the system administrator bring the queue back up. The queue <i>must</i> be manually brought up before it can be used again.</p>
HELD	Specifies that a print job is held. The print job will not be processed by the spooler until it is released.
QUEUED	Specifies that a print file is queued and is waiting in line to be printed.
READY	Specifies that everything involved with the queue is ready to queue and print a job.
RUNNING	Specifies that a print file is printing.

Prioritizing a Print Job (qpri Command)

You can change the priority of a job with the “**qpri Command**” on page 99, “**qpri Command**” on page 99, or “**smit Command**” on page 99. You can only assign job priority on local queues. Higher values indicate a higher priority for the print job. The default priority is 15. The maximum priority is 20 for most users, and 30 for users with root user privilege and members of the printq group (group 0).

Note: You cannot assign priority to a remote print job.

Prerequisites

- For local print jobs, the printer must be physically attached to your system.
- For remote print jobs, your system must be configured to communicate with the remote print server.

qpri Command

The **qpri** command reassigns the priority of a print job that you submitted. If you have root user authority or belong to the printq group, you can assign priority to any job while it is in the print queue.

The basic format of the **qpri** command is:

```
qpri -# JobNumber -a PriorityLevel
```

For example, to change job number 123 to priority number 18, type:

```
qpri -# 123 -a 18
```

For example, to prioritize a local print job as it is submitted, type:

```
qpri -PQueueName -R PriorityLevel FileName
```

See the **qpri** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

smit Command

To change the priority of a print job using SMIT, type:

```
smit qpri
```

Holding and Releasing a Print Job (qhld Command)

After you have sent a print job to a print queue, you can put the print job on hold with the “**Web-based System Manager Fast Path**”, the “**qhld Command**”, or the “**smit Command**” on page 100. You can later release the print job for printing with these same commands.

Prerequisites

- For local print jobs, the printer must be physically attached to your system.
- For remote print jobs, your system must be configured to communicate with the remote print server.

Web-based System Manager Fast Path

To hold or release a print job using the Web-based System Manager fast path, type:

```
wsm printers
```

In the Printer Queues container, select the print job, then use the menus to put it on hold or to release it for printing.

qhld Command

The **qhld** command puts a print job on hold after you have sent it. You can either put a particular print job on hold, or you can hold all the print jobs on a specified print queue. To determine the print job number, type the **qchk** (“Checking Print Job Status (qchk Command)” on page 97) command.

The basic format of the **qhld** command is:

```
qhld [ -r ] { [ -#JobNumber ] [ -PQueue ] [ -uUser ] }
```

See the **qhld** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

For example, to hold job number 452 on whichever print queue the job is on, type:

```
qhld -#452
```

For example, to hold all jobs queued on print queue hp2, type:

```
qhld -Php2
```

To release job number 452 on whichever print queue the job is on, type:

```
qh1d -#452 -r
```

To release all jobs queued on print queue hp2, type:

```
qh1d -Php2 -r
```

smit Command

To hold or release a print job using SMIT, type:

```
smit qh1d
```

Moving a Print Job to Another Print Queue (qmov Command)

After you have sent a print job to a print queue, you might want to move the print job to another print queue. You can move it with the “**qmov Command**” or the “**smit Command**”.

Prerequisites

- For local print jobs, the printer must be physically attached to your system.
- For remote print jobs, your system must be configured to communicate with the remote print server.

qmov Command

The **qmov** moves a print job to another print queue. You can either move a particular print job, or you can move all the print jobs on a specified print queue or all the print jobs sent by a specified user. To determine the print job number, type the **qchk** command.

The basic format of the **qmov** command is:

```
qmov  
-m  
NewQueue {[ -#JobNumber ] [ -PQueue ] [ -uUser ]}
```

See the **qmov** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

For example, to move job number 280 to print queue hp2, type:

```
qmov -mhp2 -#280
```

For example, to move all print jobs on print queue hp4D to print queue hp2, type:

```
qmov -mhp2 -Php4D
```

smit Command

To move a print job using SMIT, type:

```
smit qmov
```

Formatting Files for Printing (pr Command)

The **pr** command performs simple formatting of the files you sent to be printed. Pipe the output of the **pr** command to the **qprt** command to format your text.

Some useful **pr** command flags are:

- | | |
|--------------------|--|
| -d | Double-spaces the output. |
| -h "String" | Displays the specified string, enclosed in quotation marks (" "), instead of the file name as the page header. The flag and string should be separated by a space. |

-l <i>Lines</i>	Overrides the 66-line default and resets the page length to the number of lines specified by the <i>Lines</i> variable. If the <i>Lines</i> value is smaller than the sum of both the header and trailer depths (in lines), the header and trailer are suppressed (as if the -t flag were in effect).
-m	Merges files. Standard output is formatted so that the pr command writes one line from each file specified by a <i>File</i> variable, side by side into text columns of equal fixed widths, based on the number of column positions. This flag should not be used with the -Column flag.
-n [<i>Width</i>][<i>Character</i>]	Provides line numbering based on the number of digits specified by the <i>Width</i> variable. The default is 5 digits. If the <i>Character</i> (any non-digit character) variable is specified, it is appended to the line number to separate it from what follows on the line. The default character separator is the ASCII TAB character.
-o <i>Offset</i>	Indents each line by the number of character positions specified by the <i>Offset</i> variable. The total number of character positions per line is the sum of the width and offset. The default value of <i>Offset</i> is 0.
-s <i>Character</i>	Separates columns by the single character specified by the <i>Character</i> variable instead of by the appropriate number of spaces. The default value for <i>Character</i> is an ASCII TAB character.
-t	Does not display the five-line identifying header and the five-line footer. Stops after the last line of each file without spacing to the end of the page.
-w <i>Width</i>	Sets the number of column positions per line to the value specified by the <i>Width</i> variable. The default value is 72 for equal-width multicolumn output. There is no limit otherwise. If the -w flag is not specified and the -s flag is specified, the default width is 512 column positions.
-Column	Sets the number of columns to the value specified by the <i>Column</i> variable. The default value is 1. This option should not be used with the -m flag. The -e and -i flags are assumed for multicolumn output. A text column should never exceed the length of the page (see the -l flag). When this flag is used with the -t flag, use the minimum number of lines to write the output.
+Page	Begins the display with the page number specified by the <i>Page</i> variable. The default value is 1.

For example, to print a file named `prog.c` with headings and page numbers on the printer, type:

```
pr prog.c | qprt
```

Press Enter.

This adds page headings to `prog.c` and sends it to the **qprt** command. The heading consists of the date the file was last modified, the file name, and the page number.

For example, to specify a title for a file named `prog.c`, type:

```
pr -h "MAIN PROGRAM" prog.c | qprt
```

Press Enter.

This prints `prog.c` with the title `MAIN PROGRAM` in place of the file name. The modification date and page number are still printed.

For example, to print a file named `word.lst` in multiple columns, type:

```
pr -3 word.lst | qprt
```

Press Enter.

This prints the `word.lst` file in three vertical columns.

For example, to print several files side by side on the paper:

```
pr -m -h "Members and Visitors" member.lst visitor.lst | qprt
```

This prints `member.lst` and `visitor.lst` side by side with the title `Members and Visitors`.

For example, to modify a file named `prog.c` for later use, type:

```
pr -t -e prog.c > prog.notab.c
```

Press Enter.

This replaces tab characters in `prog.c` with spaces and puts the result in `prog.notab.c`. Tab positions are at columns 9, 17, 25, 33, and so on. The **-e** flag tells the **pr** command to replace the tab characters; the **-t** flag suppresses the page headings.

For example, to print a file named `myfile` in two columns, in landscape, and in 7-point text, type:

```
pr -l66 -w172 -2 myfile | qprt -z1 -p7
```

Press Enter.

See the **pr** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Printing ASCII Files on a PostScript Printer

The Text Formatting System includes the `enscript` filter for converting ASCII print files to PostScript for printing on a PostScript printer. This filter is called by the **qprt -da** command when submitting a print job to a PostScript print queue.

Prerequisites

- The printer must be physically attached to your system.
- The printer must be configured and defined.
- The transcript portion of Text Formatting Services must be installed.

There are several flags that might be specified with the **qprt** command to customize the output when submitting ASCII files to a PostScript print queue.

-1+	Adds page headings.
-2+	Formats the output in two columns.
-3+	Prints the page headings, dates, and page numbers in a fancy style. This is sometimes referred to as "gaudy" mode.
-4+	Prints the file, even if it contains unprintable characters.
-5+	Lists characters that are not included in a font.
-h string	Specifies a string to be used for page headings. If this flag is not specified, the heading consists of the file name, modification date, and page number.
-l value	Specifies the maximum number of lines printed per page. Depending on the point size, fewer lines per page might actually appear.
-L!	Truncates lines longer than the page width.
-p	Specifies the point size. If this flag is not specified, a point size of 10 is assumed, unless two-column rotated mode (-2+ -z1) is specified, in which case a value of 7 is used.
-s	Specifies the font style. If this flag is not specified, the Courier font is used. Acceptable values are: Courier-Oblique Helvetica Helvetica-Oblique Helvetica-Narrow Helvetica-Narrow-Oblique NewCenturySchlbk-Italic Optima Optima-Oblique Palatino-Roman

Palatino-Italic
Times-Roman
Times-Italic

Note: The PostScript printer must have access to the specified font.
Rotates the output 90 degrees (landscape mode).

-z1

For example, to send the ASCII file `myfile.ascii` to the PostScript printer named `Msp1`, type:

```
qprt -da -PMsp1 myfile.ascii
```

Press Enter.

For example, to send the ASCII file `myfile.ascii` to the PostScript printer named `Msp1` and print out in the Helvetica font, type:

```
qprt -da -PMsp1 -sHelvetica myfile.ascii
```

Press Enter.

For example, to send the ASCII file `myfile.ascii` to the PostScript printer named `Msp1` and print out in the point size 9, type:

```
qprt -da -PMsp1 -p9 myfile.ascii
```

Press Enter.

Automating the Conversion of ASCII to PostScript

Many applications that generate PostScript print files follow the convention of making the first two characters of the PostScript file `%!` which identifies the print file as a PostScript print file. To configure the system to detect ASCII print files submitted to a PostScript print queue and automatically convert them to PostScript files before sending them to the PostScript printer, perform these steps:

1. At the prompt, type:

```
smit chpq
```

Press Enter.

2. Type in the PostScript queue name, or use the List feature to select from a list of queues.
3. Select **Printer Setup** menu option.
4. Change value of **AUTOMATIC detection of print file TYPE to be done?** field to **yes**.

Any of the following commands now convert an ASCII file to a PostScript file and print it on a PostScript printer. To convert `myfile.ascii`, you would type any of the following at the command line:

```
qprt -Pps myfile.ps myfile.ascii
```

```
lpr -Pps myfile.ps myfile.ascii
```

```
lp -dps myfile.ps myfile.acsii
```

where `ps` is a PostScript print queue.

Overriding Automatic Determination of Print File Types

There are two instances where the automatic determination of print file type for PostScript printing might need to be overridden.

For example, to print a PostScript file named `myfile.ps` that does not begin with `%!` , type the following at the command line:

```
qprt -ds -Pps myfile.ps
```

For example, to print the source listing of a PostScript file named `myfile.ps` that begins with `%!` , type the following at the command line:

```
qprt -da -Pps myfile.ps
```

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 2. User Environment and System Information” on page 11

Command Summary for Printers, Print Jobs, and Queues

cancel	Cancels requests to a line printer.
lp	Sends requests to a line printer.
lpq	Examines the spool queue.
lpr	Enqueues print jobs.
lprm	Removes jobs from the line printer spooling queue.
lpstat	Displays line printer status information.
pr	Writes a file to standard output.
qcan	Cancels a print job.
qchk	Displays the status of a print queue.
qhld	Holds or releases a print job.
qmov	Moves a print job to another print queue.
qpri	Prioritizes a job in the print queue.
qprt	Starts a print job.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 2. User Environment and System Information” on page 11

Chapter 8. Backup Files and Storage Media

Once your system is in use, your next consideration should be to back up the file systems, directories, and files. Files and directories represent a significant investment of time and effort. At the same time, all computer files are potentially easy to change or erase, either intentionally or by accident. If you take a careful and methodical approach to backing up your file systems, you should always be able to restore recent versions of files or file systems with little difficulty.

Note: When a hard disk crashes, the information contained on that disk is destroyed. The only way to recover the destroyed data is to retrieve the information from your backup copy.

There are several different methods of backing up. The most frequently used method is a regular backup, which is a copy of a file system, directory, or file that is kept for file transfer or in case the original data is unintentionally changed or destroyed. Another form of backing up is the archive backup; this method is used for a copy of one or more files, or an entire database that is saved for future reference, historical purposes, or for recovery if the original data is damaged or lost. Usually an archive is used when that specific data is removed from the system.

This section discusses:

- “Backup Policy”
- “Formatting Diskettes (format or fdformat Command)” on page 107
- “Checking the Integrity of the File System (fsck Command)” on page 108
- “Copying to or from Diskettes (fcopy Command)” on page 109
- “Copying Files to Tape or Disk (cpio -o Command)” on page 109
- “Copying Files from Tape or Disk (cpio -i Command)” on page 110
- “Copying to or from Tapes (tcopy Command)” on page 111
- “Checking the Integrity of a Tape (tapechk Command)” on page 111
- “Compressing Files (compress and pack Commands)” on page 111
- “Expanding Compressed Files (uncompress and unpack Commands)” on page 113
- “Backing Up Files (backup Command)” on page 114
- “Restoring Backed-Up Files (restore Command)” on page 115
- “Archiving Files (tar Command)” on page 116
- “Command Summary for Backup Files and Storage Media” on page 117

Backup Policy

No single backup policy can meet the needs of all users. A policy that works well for a system with one user, for example, could be inadequate for a system that serves 5 or 10 different users. Likewise, a policy developed for a system on which many files are changed daily would be inefficient for a system on which data changes infrequently. Only you can determine the best backup policy for your system, but the following general guidelines should help:

Make sure you can recover from major losses.

Can your system continue to run after any single fixed disk fails? Can you recover your system if all the fixed disks should fail? Could you recover your system if you lost your backup diskettes or tape to fire or theft? Although these things are not likely, any of them are possible. Think through each of these possible losses and design a backup policy that would enable you to recover your system after any of them.

Check your backups periodically.

Backup media and its hardware can be unreliable. A large library of backup tapes or diskettes is useless if their data cannot be read back onto a fixed disk. To make certain that your backups are usable, try to display the table of contents from the backup tape periodically (using **restore -T**, or **tar -t** for archive tapes). If you use diskettes for your backups and have more than one diskette drive, try to read diskettes from a different drive than the one on which they were created. You also might want the security of repeating each level 0 backup with a second set of diskettes. If you use a streaming tape device for backups, you can use the **tapechk** command to perform rudimentary consistency checks on the tape.

Keep old backups.

Develop a regular cycle for reusing your backup media; however, do not reuse all of your backup media. Sometimes it might be months before you or some other user of your system notices that an important file is damaged or missing. Do save old backups for such possibilities. For example, you could have the following three cycles of backup tapes or diskettes:

- Once per week, recycle all daily diskettes except the one for Friday.
- Once per month, recycle all Friday diskettes except for the one from the last Friday of the month. This makes the last four Friday backups always available.
- Once per quarter, recycle all monthly diskettes except for the last one. Keep the last monthly diskette from each quarter indefinitely, perhaps in a different building.

Check file systems before backing them up.

A backup that was made from a damaged file system might be useless. Before making your backups, it is good policy to check the integrity of the file system with the **fsck** command.

Ensure files are not in use during a backup.

Ensure your system is not in use when you make your backups. If the system is in use, files can change while they are being backed up, and the backup copy will not be accurate.

Back up your system before major changes are made to the system.

Back up your entire system before any hardware testing or repair work is performed or before you install any new devices, programs, or other system features.

Other Factors

Other items to consider when planning and implementing a backup strategy are:

- How often does the data change? As pointed out earlier, the operating system data does not change very often so you do not need to back it up frequently. User data, on the other hand, usually changes frequently and you should back it up frequently.
- How many users are on the system? The number of users would affect the amount of storage media and frequency required for backups.
- How difficult would it be to recreate the data? It is important to consider that some data cannot be recreated if there is not a backup.

Whatever the appropriate backup strategy for your site, it is very important that one exists. Perform backups frequently and regularly. Recovering from data loss is very difficult if a good backup strategy has not been implemented.

Backup Media

Several different types of backup media are available for backups. The different types of backup media available to your specific system configuration depend upon both your software and hardware. The types most frequently used are the 5.25-inch diskette, 8-mm tape, 9-track tape, and the 3.5-inch diskette.

Attention: Running the **backup** command results in the loss of all material previously stored on the selected output medium.

Diskettes

Diskettes are the standard backup medium. Unless you specify a different device using the **backup -f** command, the **backup** command automatically writes its output to the **/dev/rfd0** device, which is the diskette drive. To back up to the default tape device, type **/dev/rmt0** and press Enter.

Be careful with your diskettes. Because each piece of information occupies such a small area on the diskette, small scratches, dust, food, or tobacco particles can make the information unusable. Be sure to remember the following:

- Do not touch the recording surfaces.
- Keep diskettes away from magnets and magnetic field sources such as telephones, dictation equipment, and electronic calculators.
- Keep diskettes away from extreme heat and cold. The recommended temperature range is 10 degrees Celsius to 60 degrees Celsius (50 degrees Fahrenheit to 140 degrees Fahrenheit).
- Proper care helps prevent loss of information.
- Make back-up copies of your diskettes regularly.

Attention: Diskette drives and diskettes must be the correct type to store data successfully. If you use the wrong diskette in your 3.5-inch diskette drive, the data on the diskette could be destroyed.

The diskette drive uses the following 3.5-inch diskettes:

- 1MB capacity (stores approximately 720KB of data)
- 2MB capacity (stores approximately 1.44MB of data).

Tapes

Tape is well-suited to certain tasks because of its high capacity and durability. It is often chosen for storing large files or many files, such as archive copies of file systems. It is also used for transferring many files from one system to another. Tape is not widely used for storing frequently accessed files because other media provide much faster access times.

Tape files are created using commands such as **backup**, **cpio**, and **tar**, which open a tape drive, write to it, and close it.

Formatting Diskettes (format or fdformat Command)

Attention: Formatting a diskette destroys any existing data on that diskette.

You can format diskettes in the diskette drive specified by the *Device* parameter (the **/dev/rfd0** device by default) with the **format** and **fdformat** commands. The **format** command determines the device type, which is one of the following:

- 5.25-inch low-density diskette (360KB) containing 40x2 tracks, each with 9 sectors
- 5.25-inch high-capacity diskette (1.2MB) containing 80x2 tracks, each with 15 sectors
- 3.5-inch low-density diskette (720KB) containing 80x2 tracks, each with 9 sectors
- 3.5-inch high-capacity diskette (2.88MB) containing 80x2 tracks, each with 36 sectors.

The sector size is 512 bytes for all diskette types.

The **format** command formats a diskette for high density unless the *Device* parameter specifies a different density.

The **fdformat** command formats a diskette for low density unless the **-h** flag is specified. The *Device* parameter specifies the device containing the diskette to be formatted (such as the **/dev/rfd0** device for drive 0).

Before formatting a diskette, the **format** and **fdformat** commands prompt for verification. This allows you to end the operation cleanly if necessary.

For example, to format a diskette in the **/dev/rfd0** device, type:

```
format -d /dev/rfd0
```

Press Enter.

For example, to format a diskette without checking for bad tracks, type:

```
format -f
```

Press Enter.

For example, to format a 360KB diskette in a 5.25-inch, 1.2MB diskette drive in the **/dev/rfd1** device, type:

```
format -l -d /dev/rfd1
```

Press Enter.

For example, to force high-density formatting of a diskette when using the **fdformat** command, type:

```
fdformat -h
```

Press Enter.

See the **format** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Checking the Integrity of the File System (fsck Command)

You can check and interactively repair inconsistent file systems with the **fsck** command. It should be run on every file system as part of system initialization. You must be able to read the device file on which the file system resides (for example, the **/dev/hd0** device). Normally, the file system is consistent, and the **fsck** command merely reports on the number of files, used blocks, and free blocks in the file system. If the file system is inconsistent, the **fsck** command displays information about the inconsistencies found and prompts you for permission to repair them. The **fsck** command is conservative in its repair efforts and tries to avoid actions that might result in the loss of valid data. In certain cases, however, the **fsck** command recommends the destruction of a damaged file.

Attention: Always run the **fsck** command on file systems after a system malfunction. Corrective actions can result in some loss of data. The default action for each consistency correction is to wait for the operator to enter yes or no. If you do not have write permission for an affected file, the **fsck** command defaults to a no response in spite of your actual response.

For example, to check all the default file systems, type:

```
fsck
```

Press Enter.

This form of the **fsck** command asks you for permission before making any changes to a file system.

For example, to fix minor problems with the default file systems automatically, type:

```
fsck -p
```

Press Enter.

For example, to check the file system `/dev/hd1`, type:

```
fsck /dev/hd1
```

Press Enter.

This checks the unmounted file system located on the `/dev/hd1` device.

Note: The **fsck** command will not make corrections to a mounted file system.

See the **fsck** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Copying to or from Diskettes (flcopy Command)

You can copy a diskette (opened as `/dev/rfd0`) to a file named `floppy` created in the current directory with the **flcopy** command. The message: `Change floppy, hit return when done` appears as needed. The **flcopy** command then copies the `floppy` file to the diskette.

For example, to copy `/dev/rfd1` to the `floppy` file in the current directory, type:

```
flcopy -f /dev/rfd1 -r
```

Press Enter.

For example, to copy the first 100 tracks of the diskette, type:

```
flcopy -f /dev/rfd1 -t 100
```

Press Enter.

See the **flcopy** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Copying Files to Tape or Disk (cpio -o Command)

You can read file path names from standard input and copy these files to standard output, along with path names and status information with the **cpio -o** command. Path names cannot exceed 128 characters. Avoid giving the **cpio** command path names made up of many uniquely linked files, as it might not have enough memory to keep track of them and would lose linking information.

For example, to copy files in the current directory whose names end with `.c` onto diskette, type:

```
ls *.c | cpio -ov >/dev/rfd0
```

Press Enter.

The **-v** flag displays the names of each file.

For example, to copy the current directory and all subdirectories onto diskette, type:

```
find . -print | cpio -ov >/dev/rfd0
```

Press Enter.

This saves the directory tree that starts with the current directory (`.`) and includes all of its subdirectories and files. Do this faster by typing:

```
find . -cpio /dev/rfd0 -print
```

Press Enter.

The `-print` entry displays the name of each file as it is copied.

See the **cpio** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Copying Files from Tape or Disk (**cpio -i** Command)

The **cpio -i** command reads from standard input an archive file created by the **cpio -o** command and copies from it the files with names that match the *Pattern* parameter. These files are copied into the current directory tree. You can list more than one *Pattern* parameter, using the file name notation described in the **ksh** command. The default for the *Pattern* parameter is an asterisk (*), selecting all files in the current directory. In an expression such as `[a-z]`, the hyphen (-) means *through* according to the current collating sequence.

Note: The patterns `"*.c"` and `"*.o"` must be enclosed in quotation marks to prevent the shell from treating the asterisk (*) as a pattern-matching character. This is a special case in which the **cpio** command itself decodes the pattern-matching characters.

For example, to list the files that have been saved onto a diskette with the **cpio** command, type:

```
cpio -itv </dev/rfd0
```

Press Enter.

This displays the table of contents of the data previously saved onto the `/dev/rfd0` file in the **cpio** command format. The listing is similar to the long directory listing produced by the **ls -l** command. To list only the file path names, use only the **-it** flags.

For example, to copy the files previously saved with the **cpio** command from a diskette, type:

```
cpio -idmv </dev/rfd0
```

Press Enter.

This copies the files previously saved onto the `/dev/rfd0` file by the **cpio** command back into the file system (specify the **-i** flag). The **-d** flag allows the **cpio** command to create the appropriate directories if a directory tree is saved. The **-m** flag maintains the last modification time in effect when the files are saved. The **-v** flag causes the **cpio** command to display the name of each file as it is copied.

For example, to copy selected files from diskette, type:

```
cpio -i "*.c" "*.o" </dev/rfd0
```

Press Enter.

This copies the files that end with `.c` or `.o` from diskette.

See the **cpio** command in the *AIX 5L Version 5.1 Commands Reference* for more information and the exact syntax.

Copying to or from Tapes (tcopy Command)

You can copy magnetic tapes with the **tcopy** command.

For example, to copy from one streaming tape to a 9-track tape, type:

```
tcopy /dev/rmt0 /dev/rmt8
```

Press Enter.

See the **tcopy** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Checking the Integrity of a Tape (tapechk Command)

You can perform rudimentary consistency checking on an attached streaming tape device with the **tapechk** command. Some hardware malfunctions of a streaming tape drive can be detected by simply reading a tape. The **tapechk** command provides a way to perform tape reads at the file level.

For example, to check the first three files on a streaming tape device, type:

```
tapechk 3
```

Press Enter.

See the **tapechk** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Compressing Files (compress and pack Commands)

You can compress files for storage with the “**compress Command**” on page 112 and “**pack Command**” on page 112, and use the “**uncompress Command**” on page 113 and “**unpack Command**” on page 113 to expand the restored files. The process of compressing and expanding files takes time but, once packed, the data uses less space on the backup medium.

There are several methods of compressing a file system:

- Use the **-p** option with the **backup** command.
- Use the **compress** or **pack** commands.

There are many reasons for compressing files, but generally they fall into two categories:

- Saving storage and archiving system resources:
 - Compress file systems before doing backups to preserve tape space.
 - Compress log files created by shell scripts that run at night; it is easy to have the script compress the file before it exits.
 - Compress files that are not currently being accessed. For example, the files belonging to a user who is away for extended leave can be compressed and placed into a **tar** archive on disk or to a tape and later be restored.
- Saving money and time by compressing files before sending them over a network.

Notes:

1. The command might run out of working space in the file system while compressing. The **compress** command creates the compressed files before it deletes any of the uncompressed files so it needs a space about 50% larger than the total size of the files.
2. A file might fail to compress because it is already compressed. If the **compress** command cannot reduce file sizes, it fails.

compress Command

The **compress** command reduces the size of files using adaptive Lempel-Zev coding. Each original file specified by the *File* parameter is replaced by a compressed file with a **.Z** appended to its name. The compressed file retains the same ownership, modes, and access and modification times of the original file. If no files are specified, the standard input is compressed to the standard output. If compression does not reduce the size of a file, a message is written to standard error and the original file is not replaced.

Compressed files can be restored to their original form using the **uncompress** command.

The amount of compression depends on the size of the input, the number of bits per code specified by the *Bits* variable, and the distribution of common substrings. Typically, source code or English text is reduced by 50 to 60 percent. The compression of the **compress** command is generally more compact and takes less time to compute than the compression achieved by the **pack** command which uses adaptive Huffman coding.

For example, to compress the `foo` file and write the percentage compression to standard error, type:

```
compress -v foo
```

Press Enter.

See the **compress** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

pack Command

The **pack** command stores the file or files specified by the *File* parameter in a compressed form using Huffman coding. The input file is replaced by a packed file with a name derived from the original file name (*File.z*), with the same access modes, access and modification dates, and owner as the original file. The input file name can contain no more than 253 bytes to allow space for the added **.z** suffix. If the **pack** command is successful, the original file is removed. Packed files can be restored to their original form using the **unpack** command.

If the **pack** command cannot create a smaller file, it stops processing and reports that it is unable to save space. (A failure to save space generally happens with small files or files with uniform character distribution.) The amount of space saved depends on the size of the input file and the character frequency distribution. Because a decoding tree forms the first part of each **.z** file, you do not save space with files smaller than three blocks. Typically, text files are reduced 25 to 40 percent.

The exit value of the **pack** command is the number of files that it could not pack. Packing is not done under any of the following conditions:

- The file is already packed.
- The input file name has more than 253 bytes.
- The file has links.
- The file is a directory.
- The file cannot be opened.
- No storage blocks are saved by packing.
- A file called *File.z* already exists.
- The **.z** file cannot be created.
- An I/O error occurred during processing.

For example, to compress the files `chap1` and `chap2`, type:

```
pack chap1 chap2
```

Press Enter.

This compresses chap1 and chap2, replacing them with files named **chap1.z** and **chap2.z**. The **pack** command displays the percent decrease in size for each file.

See the **pack** command in the *AIX 5L Version 5.1 Commands Reference* for more information and the exact syntax.

Expanding Compressed Files (uncompress and unpack Commands)

You can expand compressed files with the **uncompress** and **unpack** commands.

uncompress Command

The **uncompress** command restores original files that were compressed by the **compress** command. Each compressed file specified by the *File* variable is removed and replaced by an expanded copy. The expanded file has the same name as the compressed version, but without the **.z** extension. The expanded file retains the same ownership, modes, and access and modification times as the original file. If no files are specified, standard input is expanded to standard output.

Although similar to the **uncompress** command, the **zcat** command always writes the expanded output to standard output.

For example, to uncompress the foo file, type:

```
uncompress foo
```

Press Enter.

See the **uncompress** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

unpack Command

The **unpack** command expands files created by the **pack** command. For each file specified, the **unpack** command searches for a file called *File.z*. If this file is a packed file, the **unpack** command replaces it by its expanded version. The **unpack** command renames the new file by removing the **.z** suffix from *File*. The new file has the same access modes, access and modification dates, and owner as the original packed file.

The **unpack** command operates only on files ending in **.z**. As a result, when you specify a file name that does not end in **.z**, the **unpack** command adds the suffix and searches the directory for a file name with that suffix.

The exit value is the number of files the **unpack** command was unable to unpack. A file cannot be unpacked if any of the following occurs:

- The file name (exclusive of **.z**) has more than 253 bytes.
- The file cannot be opened.
- The file is not a packed file.
- A file with the unpacked file name already exists.
- The unpacked file cannot be created.

Note: The **unpack** command writes a warning to standard error if the file it is unpacking has links. The new unpacked file has a different i-node number than the packed file from which it was created. However, any other files linked to the original i-node number of the packed file still exist and are still packed.

For example, to unpack the packed files chap1.z and chap2, type:

```
unpack chap1.z chap2
```

Press Enter.

This expands the packed files chap1.z and chap2.z, and replaces them with files named chap1 and chap2. Note that you can give the **unpack** command file names either with or without the .z suffix.

See the **unpack** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Backing Up Files (backup Command)

Attention: If you attempt to back up a mounted file system a message is displayed. The **backup** command continues, but inconsistencies in the file system can occur. This situation does not apply to the root (/) file system.

You can create copies of your files on a backup medium, such as a magnetic tape or diskette, with the “**backup Command**” or “**smit Command**” on page 115. The copies are in one of the two following backup formats:

- Specific files backed up by name, using the **-i** flag.
- Entire file system backed up by i-node number, using the *-Level* and *FileSystem* parameters.

Notes:

1. There is always the possibility of data corruption when a file is modified during system backup. Therefore, system activity should be at a minimum during the system backup procedure.
2. If a backup is made to 8-mm tape with the device block size set to 0 (zero), it is not possible to directly restore from the tape. If you have done backups with the 0 setting, you can restore from them by using special procedures described under the **restore** command.

Attention: Be sure the flags you specify match the backup medium. Also, if you attempt to back up a mounted file system, inconsistencies can occur.

backup Command

For example, to back up selected files in your \$HOME directory by name, type:

```
find $HOME -print | backup -i -v
```

Press Enter.

The **-i** flag prompts the system to read from standard input the names of files to be backed up. The **find** command generates a list of files in the user’s **\$HOME** directory. This list is piped to the **backup** command as standard input. The **-v** flag displays a progress report as each file is copied. The files are backed up on the default backup device for the local system.

For example, to back up the root file system, type:

```
backup -0 -u /
```

Press Enter.

The 0 level and the / tell the system to back up the / (root) file system. The file system is backed up to the **/dev/rfd0** file. The **-u** flag tells the system to update the current backup level record in the **/etc/dumpdates** file.

For example, to back up all files in the / (root) file system modified since the last 0 level backup, type:

```
backup -1 -u /
```

Press Enter.

See the **backup** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

smit Command

The **backup** command can also be done using **smit**.

1. At the prompt, type:

```
smit backup
```

Press Enter.

2. Type the path name of the directory on which the file system is normally mounted in the DIRECTORY full pathname field:

```
/home/bill
```

Press Enter.

3. In the BACKUP device or FILE fields, type the output device name as in the following example for a raw magnetic tape device:

```
/dev/rmt0
```

Press Enter.

4. Use the Tab key to toggle the optional REPORT each phase of the backup field if you want error messages printed to the screen.
5. In a system management environment, use the default for the MAX number of blocks to write on backup medium field because this field does not apply to tape backups.
6. Press Enter to back up the named directory or file system.
7. Run the **restore -t** command. If this command generates an error message, you must repeat the entire backup.

Restoring Backed-Up Files (restore Command)

You can read files written by the **backup** command from a backup medium and restore them on your local system with the “**restore Command**” or “**smit Command**” on page 116.

Notes:

1. Files must be restored using the same method by which they were backed up. For example, if a file system was backed up by name, it must be restored by name.
2. When more than one diskette is required, the **restore** command reads the one mounted, prompts you for a new one, and waits for your response. After inserting the new diskette, press the Enter key to continue restoring files.

restore Command

For example, to list the names of files previously backed up, type:

```
restore -T
```

Press Enter.

Information is read from the **/dev/rfd0** default backup device. If individual files are backed up, only the file names are displayed. If an entire file system is backed up, the i-node number is also shown.

For example, to restore files to the main file system, type:

```
restore -x -v
```

Press Enter.

The **-x** flag extracts all the files from the backup medium and restores them to their proper places in the file system. The **-v** flag displays a progress report as each file is restored. If a file system backup is being restored, the files are named with their i-node numbers. Otherwise, just the names are displayed.

For example, to copy the file `/home/mike/manual/chap1`, type:

```
restore -xv /home/mike/manual/chap1
```

Press Enter.

This command extracts the `/home/mike/manual/chap1` file from the backup medium and restores it. The `/home/mike/manual/chap1` file must be a name that can be displayed by the **restore -T** command.

For example, to copy all the files in a directory named `manual`, type:

```
restore -xdv manual
```

Press Enter.

This command restores the `manual` directory and the files in it. If it does not exist, a directory named `manual` is created in the current directory to hold the files being restored.

See the **restore** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

smit Command

The **restore** command can also be done using **smit**.

1. At the prompt, type:

```
smit restore
```

Press Enter.

2. Make your entry in the Target DIRECTORY field. This is the directory where you want the restored files to reside.
3. Proceed to the BACKUP device or FILE field and type the output device name and press Enter as in the following example for a raw magnetic tape device:

```
/dev/rmt0
```

If the device is not available, a message similar to the following is displayed:

```
Cannot open /dev/rmtX, no such file or directory.
```

This message indicates that the system cannot reach the device driver because there is no file for `rmtX` in the `/dev` directory. Only items in the `available` state are in `/dev`.

4. For the NUMBER of blocks to read in a single input field, the default is recommended.
5. Press Enter to restore the specified file system or directory.

Archiving Files (tar Command)

You can write files to or retrieve files from an archive storage with the **tar** command. The **tar** command looks for archives on the default device (usually tape), unless you specify another device.

When writing to an archive, the **tar** command uses a temporary file (the `/tmp/tar*` file) and maintains in memory a table of files with several links. You receive an error message if the **tar** command cannot create the temporary file or if there is not enough memory available to hold the link tables.

For example, to write the `file1` and `file2` files to a new archive on the default tape drive, type:

```
tar -c file1 file2
```

Press Enter.

For example, to extract all files in the `/tmp` directory from the archive file on the `/dev/rmt2` tape device and use the time of extraction as the modification time, type:

```
tar -xm -f/dev/rmt2 /tmp
```

Press Enter.

For example, to display the names of the files in the `out.tar` disk archive file from the current directory, type:

```
tar -vtf out.tar
```

Press Enter.

See the **tar** command in the *AIX 5L Version 5.1 Commands Reference* for more information and the exact syntax.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 9. File and System Security” on page 119

Command Summary for Backup Files and Storage Media

backup	Backs up files and file systems.
compress	Compresses and expands data.
cpio	Copies files into and out of archive storage and directories.
fdformat	Formats diskettes.
flcopy	Copies to and from diskettes.
format	Formats diskettes.
fsck	Checks file system consistency and interactively repairs the file system.
pack	Compresses files.
restore	Copies previously backed-up file systems or files, created by the backup command, from a local device.
tapechk	Performs consistency checking of the streaming tape device.
tar	Manipulates archives.
tcopy	Copies a magnetic tape.
uncompress	Compresses and expands data.
unpack	Expands files.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“Chapter 4. Input and Output Redirection” on page 41

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 9. File and System Security” on page 119

Chapter 9. File and System Security

Computer security is very similar to other types of security. Its goal is the protection of information stored on the computer system, a valuable resource. Information security is aimed at:

Integrity	The value of all information depends upon its accuracy. If unauthorized changes are made to data, this data loses some or all of its value.
Privacy	The value of much information depends upon its secrecy.
Availability	Information must be readily available.

It is helpful to plan and implement your security policies before you begin using the system. Security policies are very time consuming to change later, so a little planning now can save a lot of time later.

This section discusses:

- “Security Threats”
- “File Ownership and User Groups” on page 121
 - “Changing File or Directory Ownership (chown Command)” on page 121
 - “File and Directory Access Modes” on page 121
 - “Displaying Group Information (lsgroup Command)” on page 123
 - “Changing File or Directory Permissions (chmod Command)” on page 125
- “Access Control Lists” on page 126
 - “Base Permissions” on page 126
 - “Extended Permissions” on page 126
 - “Access Control List Example” on page 127
 - “Access Authorization” on page 128
 - “Displaying Access Control Information (aclget Command)” on page 129
 - “Setting Access Control Information (aclput Command)” on page 129
 - “Editing Access Control Information (acledit Command)” on page 130
- “Locking Your Terminal (lock or xlock Command)” on page 130
- “Command Summary for File and System Security” on page 130

Security Threats

Threats to information security arise from three different types of behavior:

Carelessness	Information security is often violated due to the carelessness of the authorized users of the system. If you are careless with your password, for instance, no other security mechanisms can prevent unauthorized access to your account and data.
Browsing	Many security problems are caused by browsers, authorized users of the system exploring the system looking for carelessly protected data.
Penetration	Penetration represents deliberate attacks upon the system. An individual trying to penetrate the system will study it for security vulnerabilities and deliberately plan attacks designed to exploit those weaknesses.

The last form of behavior usually represents the greatest threat to information security, but problems caused by carelessness or browsing should not be underestimated.

Basic Security

Every system should maintain the level of security represented by these basic security policies.

Backups

Physically secure, reliable, and up-to-date system backups are the single most important security task. With a good system backup, you can recover from any system problems with minimal loss. Document your backup policy and include information regarding:

- How often backups will be made
- What types of backups (system, data, or incremental) will be made
- How backup tapes will be verified
- How backup tapes will be stored

For more information, see “Chapter 8. Backup Files and Storage Media” on page 105” .

Identification and Authentication

Identification and authentication establish your identity. You are required to log in to the system. You supply your user name and a password, if the account has one (in a secure system, all accounts should either have passwords or be invalidated). If the password is correct, you are logged in to that account; you acquire the access rights and privilege of the account.

Because the password is the only protection for your account, it is important that you select and guard your password carefully. Many attempts to break into a system start with attempts to guess passwords. The operating system provides significant password protection by storing user passwords separately from other user information. The encrypted passwords and other security-relevant data for users are stored in the `/etc/security/passwd` file. This file should be accessible only by the root user. With this restricted access to the encrypted passwords, an attacker cannot decipher the password with a program that simply cycles through all possible or likely passwords.

It is still possible to guess passwords by repeatedly attempting to log in to an account. If the password is trivial or is infrequently changed, such attacks might easily succeed.

Login User IDs

The operating system also identifies users by their login user ID. The login user ID allows the system to trace all user actions to their source. After a user logs in to the system but before running the initial user program, the system sets the login ID of the process to the user ID found in the user database. All subsequent processes during the login session are tagged with this ID. These tags provide a trail of all activities performed by the login user ID.

The user can reset the effective user ID, real user ID, effective group ID, real group ID, and supplementary group ID during the session, but cannot change the login user ID.

Unattended Terminals

All systems are vulnerable if terminals are left logged in and unattended. The most serious problem occurs when a system manager leaves a terminal unattended that has been enabled with root authority. In general, users should log out any time they leave their terminals.

You can force a terminal to log out after a period of inactivity by setting the **TMOUT** and **TIMEOUT** parameters in the `/etc/profile` file. The **TMOUT** parameter works in the **ksh** (Korn) shell, and the **TIMEOUT** parameter works in the **bsh** (Bourne) shell. For more information about the **TMOUT** parameter, see “Parameter Substitution in the Korn Shell or POSIX Shell” on page 161. For more information about the **TIMEOUT** parameter, see “Variable Substitution in the Bourne Shell” on page 205.

The following example, taken from a `.profile` file, forces the terminal to log out after an hour of inactivity:

```
T0=3600
echo "Setting Autologout to $T0"
TIMEOUT=$T0
TMOUT=$T0
export TIMEOUT TMOUT
```


Note: Users can override the **TMOU** and **TIMEOUT** values in the **/etc/profile** file by specifying different values in the **.profile** file in your home directory.

File Ownership and User Groups

Initially, a file's owner is identified by the user ID of the person who created the file. The owner of a file determines who may read, write (modify), or execute the file. Ownership can be changed with the **chown** command.

Every user ID is assigned to a group with a unique group ID. The system manager creates the groups of users when setting up the system. When a new file is created, the operating system assigns permissions to the user ID that created it, to the group ID containing the file owner, and to a group called others, consisting of all other users. The **id** command shows your user ID (UID), group ID (GID), and the names of all groups you belong to.

In file listings (such as the listings shown by the **ls** command), the three groups of users are always represented in the following order: user, group, and others. If you need to find out your group name, the **groups** command shows all the groups for a user ID.

Changing File or Directory Ownership (chown Command)

You can change the owner of your files with the **chown** command.

When the **-R** option is specified, the **chown** command recursively descends through the directory structure from the specified directory. When symbolic links are encountered, the ownership of the file or directory pointed to by the link is changed; the ownership of the symbolic link is not changed.

Note: Only the root user can change the owner of another file. No errors are reported when the **-f** option is specified.

For example, to change the owner of the file `program.c`, type:

```
chown jim program.c
```

Press Enter.

The user access permissions for `program.c` now apply to `jim`. As the owner, `jim` can use the **chmod** command to permit or deny other users access to `program.c`.

For example, to change the owner and group of all files in the directory `/tmp/src` to owner `john` and group `build`, type:

```
chown -R john:build /tmp/src
```

Press Enter.

See the **chown** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

File and Directory Access Modes

Every file has an owner. For new files, the user who creates the file is the owner of that file. The owner assigns an access mode to the file. Access modes grant other system users permission to read, modify, or execute the file. Only the file's owner or users with root authority can change the access mode of a file.

There are the three classes of users: user/owner, group, and all others. Access is granted to these groups in some combination of three modes: read, write, or execute. When a new file is created, the default

permissions are read, write, and execute permission for the user who created the file. The other two groups have read and execute permission. The following table illustrates the default file access modes for the three sets of user groups:

Classes	Read	Write	Execute
Owner	Yes	Yes	Yes
Group	Yes	No	Yes
Others	Yes	No	Yes

Files can be read (r), written (w), or executed (x). The system determines who has permission and the level of permission they have for each of these activities. Access modes are represented two ways in the operating system: symbolically and numerically.

Symbolic Representation of Access Modes

Access modes are represented symbolically, as follows:

- r** Indicates read permission, which allows users to view the contents of a file.
- w** Indicates write permission, which allows users to modify the contents of a file.
- x** Indicates execute permission. For executable files (ordinary files that contain programs), execute permission means that the program can be run. For directories, execute permission means the contents of the directory can be searched.

For example, a file with the access modes set to `rwxr-xr-x` gives read and execute permission to all three groups, but write permission only to the owner of the file. This is the symbolic representation of the default setting.

The **ls** command, when used with the **-l** (lower case L) flag, gives a detailed listing of the current directory. The first 10 characters in the **ls -l** listing show the file type and permissions for each of the three groups. The **ls -l** command also tells you the owner and group associated with each file and directory.

The first character indicates the type of file. The remaining nine characters contain the file permission information for each of the three classes of users. The following symbols are used to represent the type of file:

- Regular files
- d** Directory
- b** Block special files
- c** Character special files
- p** Pipe special files
- l** Symbolic links
- s** Sockets.

For example, this is a sample **ls -l** listing:

```
-rwxrwxr-x 2 janet acct 512 Mar 01 13:33 january
```

Here, the first hyphen (-) indicates a regular file. Characters 2 through 4, `rwx`, represent the user's access mode (read, write, and execute). Characters 5 through 7, `rwx`, indicate the group's access modes (read, write, and execute). Characters 8 through 10, `r-x`, indicate read and execute access for all other users. Hyphens within the last 9 characters indicate no permission is given.

janet is the file owner and acct is the name of Janet's group. 512 is the file size in bytes, Mar 01 13:33 is the last date and time of modification, and january is the file name. The 2 indicates how many links exist to the file.

Numeric Representation of Access Modes

Numerically, read access is represented by a value of 4, write permission is represented by a value of 2, and execute permission is represented by a value of 1. The total value between 1 and 7 represents the access mode for each group (user, group, and other). The following table illustrates how to determine the numerical values for each level of access:

Total Value	Read	Write	Execute
0	-	-	-
1	-	-	1
2	-	2	-
3	-	2	1
4	4	-	-
5	4	-	1
6	4	2	-
7	4	2	1

When a file is created, the default file access mode is 755. This means the user has read, write, and execute permissions (4+2+1=7), the group has read and execute permission (4+1=5), and all others have read and execute permission (4+1=5). Access permission modes can be changed for files you own by running the **chmod** (change mode) command.

Displaying Group Information (lsgroup Command)

You can display the attributes of all the groups on the system or of the groups specified with the **lsgroup** command. If one or more attributes cannot be read, the **lsgroup** command lists as much information as possible. The attribute information displays as *Attribute=Value* definitions, each separated by a blank space.

For example, to list all of the groups on the system, type:

```
lsgroup ALL
```

Press Enter.

The system displays each group, group ID, and all of the users in the group in a list similar to the following:

```
system 0      arne,pubs,ctw,geo,root,chucka,noer,su,dea,
backup,build,janice,denise
staff 1      john,ryan,flynn,daveb,jzitt,glover,maple,ken
gordon,mbrady
bin 2      root,bin
sys 3      root,su,bin,sys
```

To display specific attributes for all groups, you can use one of two styles for listing specific attributes for all groups:

- You can list attributes in the form *Attribute=Value* separated by a blank space. This is the default style. For example, to list the ID and users for all of the groups on the system, type:

```
lsgroup -a id users ALL | pg
```

Press Enter.

A list similar to the following displays:

```
system id=0
users=arne,pubs,ctw,geo,root,chucka,noer,su,dea,backup,build
staff id=1 users=john,ryan,flynn,daveb,jzitt,glover,maple,ken
```

- You can also list the information in stanza format. For example, to list the ID and users for all of the groups on the system in stanza format, type:

```
lsgroup -a -f id users ALL | pg
```

Press Enter.

A list similar to the following displays:

```
system:
  id=0
  users=pubs,ctw,geo,root,chucka,noer,su,dea,backup,build

staff:
  id=1
  users=john,ryan,flynn,daveb,jzitt,glover,maple,ken

bin:
  id=2
  users=root,bin

sys:
  id=3
  users=root,su,bin,sys
```

To display all attributes for a specific group, you can use one of two styles for listing specific attributes for all groups::

- You can list each attribute in the form Attribute=Value separated by a blank space. This is the default style. For example, to list all attributes for the group system, type:

```
lsgroup system
```

Press Enter.

A list similar to the following displays:

```
system id=0 users=arne,pubs,ctw,geo,root,chucka,noer,su,dea,
backup,build,janice,denise
```

- You can also list the information in stanza format. For example, to list all attributes for the group bin in stanza format, type:

```
lsgroup -f system
```

Press Enter.

A list similar to the following displays:

```
system:
  id=0
  users=arne,pubs,ctw,geo,root,chucka,noer,su,dea,
backup,build,janice,denise
```

To list specific attributes for a specific group, type:

```
lsgroup -a Attributes Group
```

Press Enter.

For example, to list the ID and users for group `bin`, type:

```
lsgroup -a id users bin
```

Press Enter.

A list similar to the following displays:

```
bin id=2 users=root,bin
```

See the **lsgroup** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Changing File or Directory Permissions (chmod Command)

You can modify the read, write, and execute permissions of specified files and modify the search permission codes of specified directories with the **chmod** command.

For example, to add a type of permission to files `chap1` and `chap2`, type:

```
chmod g+w chap1 chap2
```

Press Enter.

This adds write permission for group members to the files `chap1` and `chap2`.

For example, to make several permission changes at once to the `mydir` directory, type:

```
chmod go-w+x mydir
```

Press Enter.

This denies (-) group members (**g**) and others (**o**) the permission to create or delete files (**w**) in `mydir` and allows (+) group members and others to search `mydir` or use (**x**) it in a path name. This is equivalent to the command sequence:

```
chmod g-w mydir
chmod o-w mydir
chmod g+x mydir
chmod o+x mydir
```

For example, to permit only the owner to use a shell procedure named `cmd` as a command, type:

```
chmod u=rwx,go= cmd
```

Press Enter.

This gives read, write, and execute permission to the user who owns the file (**u=rwx**). It also denies the group and others the permission to access `cmd` in any way (**go=**).

For example, to use the numeric mode form of the **chmod** command to change the permissions of the file `text`, type:

```
chmod 644 text
```

Press Enter.

This sets read and write permission for the owner, and it sets read-only mode for the group and others.

See the **chmod** command in the *AIX 5L Version 5.1 Commands Reference* for more information and the exact syntax.

Access Control Lists

Access control is composed of protected information resources that specify who can be granted access to such resources. The operating system allows for need-to-know or discretionary security. The owner of an information resource can grant other users read or write access rights for that resource. A user who is granted access rights to a resource can transfer those rights to other users. This security allows for user-controlled information flow in the system; the owner of an information resource defines the access permissions to the object.

Users have user-based access only to the objects they own. Typically, users receive either the group permissions or the default permissions for a resource. The major task in administering access control is to define the group memberships of users, because these memberships determine the users' access rights to the files they do not own.

Access control lists (ACLs) increase the quality of file access controls by adding extended permissions that modify the "Base Permissions" assigned to individuals and groups. With "Extended Permissions", you can permit or deny file access to specific individuals or groups without changing the base permissions.

Note: The access control list for a file cannot exceed one memory page (approximately 4096 bytes) in size.

Access control lists are maintained by the **aclget**, **acledit**, and the **aclput** commands.

Although the **chmod** command in numeric mode (with octal notations) can set base permissions and attributes, the **chmod** subroutine, which the command calls, disables extended permissions. If you use the numeric mode of the **chmod** command on a file that has an ACL, extended permissions are disabled. The symbolic mode of the **chmod** command does not disable extended permissions. For information on numeric and symbolic mode, refer to the **chmod** command.

Base Permissions

Base permissions are the traditional file access modes assigned to the file owner, file group, and other users. The access modes are: read (r), write (w), and execute/search (x).

In an access control list, base permissions are in the following format, with the *Mode* parameter expressed as rwx (with a hyphen (-) replacing each unspecified permission):

```
base permissions:
  owner(name): Mode
  group(group): Mode
  others: Mode
```

Attributes

Three attributes can be added to an access control list: **setuid** (SUID), **setgid** (SGID), and **savetext** (SVTX). These attributes are in the following format:

```
attributes: SUID, SGID, SVTX
```

Extended Permissions

Extended permissions give the owner of a file the ability to define access to that file more precisely. Extended permissions modify the base file permissions (owner, group, others) by permitting, denying, or specifying access modes for specific individuals, groups, or user and group combinations.

The **permit**, **deny**, and **specify** keywords are defined as follows:

permit Grants the user or group the specified access to the file.

deny Restricts the user or group from using the specified access to the file.
specify Precisely defines the file access for the user or group.

If a user is denied a particular access by either a **deny** or a **specify** keyword, no other entry can override that access denial.

The **enabled** keyword must be specified in the access control list (ACL) for the extended permissions to take effect. The default value is the **disabled** keyword.

In an ACL, extended permissions are in the following format:

```
extended permissions:
  enabled | disabled
  permit  Mode UserInfo...:
  deny    Mode UserInfo...:
  specify Mode UserInfo...:
```

Use a separate line for each **permit**, **deny**, or **specify** entry. The *Mode* parameter is expressed as **rwX** (with a hyphen (-) replacing each unspecified permission). The *UserInfo* parameter is expressed as `u:UserName`, or `g:GroupName`, or a comma-separated combination of `u:UserName` and `g:GroupName`.

Note: If more than one user name is specified in an entry, that entry cannot be used in an access control decision, because a process has only one user ID.

Access Control List Example

The following is an example of an ACL:

```
attributes: SUID
base permissions:
  owner(frunk): rw-
  group(system): r-x
  others: ---
extended permissions:
  enabled
  permit rw- u:dhs
  deny r-- u:chas, g:system
  specify r-- u:john, g:gateway, g:mail
  permit rw- g:account, g:finance
```

The parts of the ACL and their meanings are the following:

- The first line indicates that the **setuid** bit is turned on.
- The next line, which introduces the base permissions, is optional.
- The next three lines specify the base permissions. The owner and group names in parentheses are for information only. Changing these names does not alter the file owner or file group. Only the **chown** command and the **chgrp** command can change these file attributes.
- The next line, which introduces the extended permissions, is optional.
- The next line specifies that the extended permissions that follow are enabled.
- The last four lines are the extended entries. The first extended entry grants user `dhs` read (`r`) and write (`w`) permission on the file.
- The second extended entry denies read (`r`) access to user `chas` when he is a member of the `system` group.
- The third extended entry specifies that as long as user `john` is a member of both the `gateway` group and the `mail` group, he can have read (`r`) access. If user `john` is not a member of both groups, this extended permission does not apply.

- The last extended entry grants any user in both the account group and the finance group read (r) and write (w) permission.

Note: More than one extended entry can be applied to a process, with restrictive modes taking precedence over permissive modes.

See the **acledit** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Access Authorization

Managing access rights is the responsibility of the owner of the information resource. Resources are protected by permission bits, which are included in the mode of the object. The permission bits define the access permissions granted to the owner of the object, the group of the object, and for the others default class. The operating system supports three different modes of access (read, write, and execute) that can be granted separately.

When a user logs in to an account (using the **login** or **su** commands), the user IDs and group IDs assigned to that account are associated with the user's processes. These IDs determine the access rights of the process.

For files, directories, named pipes, message queues, shared memory segments, semaphores, and devices (special files), access is authorized as follows:

- For each access control entry (ACE) in the access control list (ACL), the identifier list is compared to the identifiers of the process. If there is a match, the process receives the permissions and restrictions defined for that entry. The logical unions for both permissions and restrictions are computed for each matching entry in the ACL. If the requesting process does not match any of the entries in the ACL, it receives the permissions and restrictions of the default entry.
- If the requested access mode is permitted (included in the union of the permissions) and is not restricted (included in the union of the restrictions), access is granted; otherwise, it is denied.

A process with a user ID of 0 is known as a root user process. These processes are generally allowed all access permissions. But if a root user process requests execute permission for a program, access is granted only if execute permission is granted to at least one user.

The identifier list of an ACL matches a process if all identifiers in the list match the corresponding type of effective identifier for the requesting process. A USER-type identifier matched is equal to the effective user ID of the process, and a GROUP-type identifier matches if it is equal to the effective group ID of the process or to one of the supplementary group IDs. For instance, an ACE with an identifier list such as:

```
USER:fred, GROUP:philosophers, GROUP:yankee_fans
```

would match a process with an effective user ID of fred and a group set of:

```
philosophers, philanthropists, yankee_fans, good_sports
```

but would not match for a process with an effective user ID of fred and a group set of:

```
philosophers, iconoclasts, redsox_fans, poor_sports
```

Note that an ACE with an identifier list of the following would match for both processes:

```
USER:fred, GROUP:philosophers
```

In other words, the identifier list in the ACE functions is a set of conditions that must hold for the specified access to be granted.

All access permission checks for these objects are made at the system call level when the object is first accessed. Since SVIPC objects are accessed statelessly, checks are made for every access. For objects

with file system names, it is necessary to be able to resolve the name of the actual object. Names are resolved either relatively (to the process' working directory) or absolutely (to the process' root directory). All name resolution begins by searching one of these.

The discretionary access control mechanism allows for effective control of access to information resources and provides for separate protection of the confidentiality and integrity of the information. Owner-controlled access control mechanisms are only as effective as users make them. All users must understand how access permissions are granted and denied and how these are set.

Displaying Access Control Information (aclget Command)

You can display the access control information of a file with the **aclget** command. The information that you view includes attributes, base permissions, and extended permissions.

For example, to display the access control information for the status file, type:

```
aclget status
```

Press Enter.

The access control information that displays includes a list of attributes, base permissions, and extended permissions. For an example, see "Access Control List Example" on page 127 .

For example, to save the access control information of the plans file in the acl1 file to edit and use later, type:

```
aclget -o acl1 plans
```

Press Enter.

See the **aclget** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Setting Access Control Information (aclput Command)

You can set the access control information of a file with the **aclput** command.

Note: The access control list for a file cannot exceed one memory page (approximately 4096 bytes) in size.

For example, to set the access control information for the status file with information stored in the acldefs file, type:

```
aclput -i acldefs status
```

Press Enter.

For example, to set the access control information for the status file with the same information used for the plans file, type:

```
aclget plans | aclput status
```

Press Enter.

See the **aclput** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Editing Access Control Information (acledit Command)

You can change the access control information of a file with the **acledit** command. The command displays the current access control information and lets the file owner change it. Before making any changes permanent, the command asks if you want to proceed.

Note: The **EDITOR** environment variable must be specified with a complete path name; otherwise, the **acledit** command will fail.

The access control information that displays includes a list of attributes, base permissions, and extended permissions. For an example, see “Access Control List Example” on page 127 .

For example, to edit the access control information of the `plans` file, type:

```
acledit plans
```

Press Enter.

See the **acledit** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Locking Your Terminal (lock or xlock Command)

You can lock your terminal with the **lock** command. The **lock** command requests a password from the user, reads it, and requests the password a second time to verify it. In the interim, the command locks the terminal and does not relinquish it until the password is received the second time. The timeout default value is 15 minutes, but this can be changed with the *-Number* flag.

Note: If your interface is AIXwindows use the **xlock** command in the same manner.

For example, to lock your terminal under password control, type:

```
lock
```

Press Enter.

You are prompted for the password twice so the system can verify it. If the password is not repeated within 15 minutes, the command times out.

For example, to reserve a terminal under password control, with a timeout interval of 10 minutes, type:

```
lock -10
```

Press Enter.

See the **lock** or the **xlock** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Command Summary for File and System Security

acledit	Edits the access control information of a file.
aclget	Displays the access control information of a file.
aclput	Sets the access control information of a file.
chmod	Changes permission modes.
chown	Changes the user associated with a file.
lock	Reserves a terminal.
lsgroup	Displays the attributes of groups.
xlock	Locks the local X display until a password is entered.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 8. Backup Files and Storage Media” on page 105

Chapter 10. Customizing the User Environment

The operating system provides various commands and initialization files that enable you to customize the behavior and the appearance of your user environment to your preferences.

Some of the default resources of the applications you use on your system can also be customized. Defaults are initiated by the program at startup. When you change the defaults, you must exit and then restart the program to see the new defaults in effect.

Common Desktop Environment 1.0: Advanced User's and System Administrator's Guide provides detailed information about customizing the behavior and appearance of the Common Desktop Environment.

This section discusses:

- “System Startup Files Overview” on page 134
 - “/etc/profile File” on page 134
 - “/etc/environment File” on page 135
 - “.profile File” on page 135
 - “.env File” on page 136
- “AIXwindows Startup Files Overview” on page 136
 - “.xinitrc File” on page 137
 - “.Xdefaults File” on page 138
 - “.mwmrc File” on page 139
- “Customization Procedures” on page 141
 - “Exporting Shell Variables (export Shell Command)” on page 141
 - “Changing the Display's Font (chfont Command)” on page 141
 - “Changing Control Keys (stty Command)” on page 142
 - “Changing Your System Prompt” on page 143
- “Customizing the InfoExplorer Windows Program” on page 144
- “Summary for User Environment Customization” on page 147

Related Information

“Chapter 2. User Environment and System Information” on page 11

“Commands Overview” on page 20

“Processes Overview” on page 30

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 9. File and System Security” on page 119

“System Startup Files Overview” on page 134

“Customization Procedures” on page 141

“Customizing the InfoExplorer ASCII Program” on page 260

“Chapter 11. Shells” on page 149

“Korn Shell or POSIX Shell Commands” on page 172

“Bourne Shell” on page 196

“C Shell” on page 212

System Startup Files Overview

When you log in, the shell defines your user environment after reading the initialization files that you have set up. The characteristics of your user environment are defined by the values given to your environment variables. You maintain this environment until you log out of the system.

The shell uses two types of profile files when you log in to the operating system. It evaluates the commands contained in the files and then executes the commands to set up your system environment. The files have similar functions except that the **/etc/profile** file controls profile variables for all users on a system whereas the **.profile** file allows you to customize your own environment.

The shell first evaluates the commands contained in the **/etc/profile** file and then runs the commands to set up your system environment in the **/etc/environment** file. After these files are run, the system then checks to see if you have a **.profile** file in your home directory. If the **.profile** file exists, it runs this file. The **.profile** file will specify if there also exists an environment file. If an environment file exists, (usually called **.env**), the system then runs this file and sets up your environment variables.

The **/etc/profile**, **/etc/environment**, and the **.profile** files are run once at login time. The **.env** file, on the other hand, is run every time you open a new shell or a window.

This section discusses the following initialization files:

- “/etc/profile File”
- “/etc/environment File” on page 135
- “.profile File” on page 135
- “.env File” on page 136

/etc/profile File

The first file that the operating system uses at login time is the **/etc/profile** file. This file controls systemwide default variables such as:

- export variables
- file creation mask (umask)
- terminal types
- mail messages to indicate when new mail has arrived

The system administrator configures the **profile** file for all users on the system. Only the system administrator can change this file.

The following example is typical of an **/etc/profile** file:

```
#Set file creation mask
unmask 022
#Tell me when new mail arrives
MAIL=/usr/mail/$LOGNAME
#Add my /bin directory to the shell search sequence
PATH=/usr/bin:/usr/sbin:/etc::
```

```
#Set terminal type
TERM=lft
#Make some environment variables global
export MAIL PATH TERM
```

See `.profile` File Format in the *AIX 5L Version 5.1 Files Reference* for detailed information about the `/etc/profile` file.

`/etc/environment` File

The second file that the operating system uses at login time is the `/etc/environment` file. The `/etc/environment` file contains variables specifying the basic environment for all processes. When a new process begins, the `exec` subroutine makes an array of strings available that have the form `Name=Value`. This array of strings is called the environment. Each name defined by one of the strings is called an environment variable or shell variable. The `exec` subroutine allows the entire environment to be set at one time.

When you log in, the system sets environment variables from the `environment` file before reading your login profile, `.profile`. The following variables make up the basic environment:

HOME	The full path name of the user's login or HOME directory. The login program sets this to the name specified in the <code>/etc/passwd</code> file.
LANG	The locale name currently in effect. The LANG variable is initially set in the <code>/etc/profile</code> file at installation time.
NLSPATH	The full path name for message catalogs.
LOCPATH	The full path name of the location of National Language Support tables.
PATH	The sequence of directories that commands, such as sh , time , nice and nohup , search when looking for a command whose path name is incomplete.
TZ	The time zone information. The TZ environment variable is initially set by the <code>/etc/profile</code> file, the system login profile.

See `.environment` File in the *AIX 5L Version 5.1 Files Reference* for detailed information about the `/etc/environment` file.

`.profile` File

The third file that the operating system uses at login time is the `.profile` file. The `.profile` file is present in your home (**\$HOME**) directory and enables you to customize your individual working environment. Because the `.profile` file is hidden, use the `ls -a` command to list it.

After the **login** program adds the **LOGNAME** (login name) and **HOME** (login directory) variables to the environment, the commands in the `$HOME/.profile` file are executed if the file is present. The `.profile` file contains your individual profile that overrides the variables set in the `/etc/profile` file. The `.profile` file is often used to set exported environment variables and terminal modes. You can tailor your environment as desired by modifying the `.profile` file. Use the `.profile` file to control the following defaults:

- shells to open
- prompt appearance
- keyboard sound

The following example shows a typical `.profile` file:

```
PATH=/usr/bin:/etc:/home/bin1:/usr/lpp/tps4.0/user::
epath=/home/gsc/e3:
export PATH epath
csh
```

This example has defined two path variables (PATH and epath), exported them, and opened a C shell (csh).

You can also use the **.profile** file (or if it is not present, the **/etc/profile** file) to determine login shell variables. You can also customize other shell environments. For example, use the **.cshrc** file and **.kshrc** file to tailor a C shell and a Korn shell, respectively, when each type of shell is started.

.env File

A fourth file that the operating system uses at login time is the **.env** file, if your **.profile** has the following line: `export ENV=$HOME/.env`

The **.env** file enables you to customize your individual working environment variables. Because the **.env** file is hidden, use the **ls -a** command to list it. The **.env** file contains the individual user environment variables that override the variables set in the **/etc/environment** file. You can tailor your environment variables as desired by modifying your **.env** file. The following example shows a typical **.env** file:

```
export myid='id | sed -n -e 's/).*$/' -e 's/^(//p' \
      bold='tput smso' \
      norm='tput rmso'
#set prompt: login & system name (reverse video) & path (normal)
if [ $myid = root ]
  then typeset -x PSCH='${bold}#:${norm}\${PWD}> '
      PS1='${bold}#:${norm}\${PWD}> '
  else typeset -x PSCH='>'
      PS1='${bold}$LOGNAME@$UNAME:${norm}\${PWD}> '
      PS2=">"
      PS3="#?"
fi
export PS1 PS2 PS3
#setup my command aliases
alias ls="/bin/ls -CF" \
      d="/bin/ls -Fa | pg" \
      rm="/bin/rm -i" \
      up="cd .."
```

Note: When modifying the **.env** file, ensure that newly created environment variables do not conflict with standard variables such as **MAIL**, **PS1**, **PS2**, and **IFS**.

AIXwindows Startup Files Overview

Because different computer systems have different ways of starting the X server and AIXwindows, you should consult with your system administrator to learn how to get started. Usually, the X server and AIXwindows are started from a shell script that runs automatically when you log in. You might, however, find that you need to start the X server or AIXwindows or both.

If you log in and find that your display is functioning as a single terminal, with no windows displayed, you can start X by typing:

```
xinit
```

Press Enter.

If this command does not start X, check with your system administrator to ensure that the X11 directory containing executable programs is in your search path. The appropriate path might differ from one system to another.

If you log in and find one or more windows without frames, you can start AIXwindows Window Manager by typing:

```
mwm &
```


Press Enter.

Note: Before entering this command, make sure that the pointer rests within a window that has a system prompt.

Because AIXwindows permits customization both by programmers writing AIXwindows applications and by users, you might find that mouse buttons or other functions do not operate as you might expect from reading this documentation. You can reset your AIXwindows environment to the default behavior by pressing and holding the following four keys:

Alt-Ctrl-Shift-!

You can return to the customized behavior by pressing this key sequence again. If your system does not permit this combination of keystrokes, you can also restore default behavior from the default root menu.

This section discusses the following initialization files:

- “.xinitrc File”
- “.Xdefaults File” on page 138
- “.mwmrc File” on page 139

.xinitrc File

The **xinit** command uses a customizable shell script file that lists the X client programs to start. The **.xinitrc** file in your home directory controls the windows and applications that start up when you start AIXwindows.

The **xinit** command first looks for the **\$XINITRC** environment variable to start AIXwindows. If the **\$XINITRC** environment variable is not found, it looks for the **\$HOME/.xinitrc** shell script. If the **\$HOME/.xinitrc** shell script is not found, the **xinit** command starts the **/usr/lib/X11/\$LANG/xinitrc** shell script. If **/usr/lib/X11/\$LANG/xinitrc** is not found, it looks for the **/usr/lpp/X11/defaults/\$LANG/xinitrc** shell script. If that script is not found, it searches for the **/usr/lpp/X11/defaults/xinitrc** shell script.

The **xinitrc** shell script starts commands, such as the **mwm** (AIXwindows Window Manager), **aixterm**, and **xclock** commands.

The **xinit** command performs the following operations:

- Starts an X Server on the current display
- Sets up the **\$DISPLAY** environment variable
- Runs the **xinitrc** file to start the X client programs
- Automatically loads the Display PostScript (DPS) extension

Note: To prevent **DPS** from automatically loading, the **/usr/lpp/X11/xinit** file must be modified.

The following example shows the part of the **xinitrc** file you can customize:

```
# This script is invoked by /usr/lpp/X11/bin/xinit
.
.
.
#*****
# Start the X clients. Change the following lines to      *
# whatever command(s) you desire!                       *
# The default clients are an analog clock (xclock), an lft *
# terminal emulator (aixterm), the X Desktop Manager (xdt), *
# and the Motif Window Manager (mwm).                   *
#*****
```

```

# If not X-Station then invoke the DPS copyright
if [ -z "$XSTATION" ]
then
  /usr/lpp/DPS/bin/copyright -x &
fi
aixterm =80x25+0-0 -fg Wheat -bg MidnightBlue &
if [ -z "$XSTATION" ]
then
  sleep 3      # allow for DPS copyright to show up
fi
if [ -x /usr/lpp/X11/bin/xdt3 ]
then
  /usr/lpp/X11/bin/xdt3 &
fi
exec mwm

```

.Xdefaults File

If you work in an AIXwindows interface, you can customize this interface with the **.Xdefaults** file. AIXwindows allows you to specify your preferences for visual characteristics, such as colors and fonts.

Many aspects of a windows-based application's appearance and behavior are controlled by sets of variables called *resources*. The visual or behavioral aspect of a resource is determined by its assigned value. There are several different types of values for resources. For example, resources that control color can be assigned predefined values such as *DarkSlateBlue* or *Black*. Resources that specify dimensions are assigned numeric values. Some resources take Boolean values (*True* or *False*).

If you do not have a **.Xdefaults** file in your home directory, you can create one with any text editor. Once you have this file in your home directory, you can set resource values in it as you wish. A sample default file called **Xdefaults.tmpl** is in the **/usr/lpp/X11/defaults** directory.

The following example shows part of a typical **.Xdefaults** file:

```

*AutoRaise: on
*DeIconifyWarp: on
*warp:on
*TitleFont:andysans12
*scrollBar: true
*font: Rom10.500
Mwm*menu*foreground: black
Mwm*menu*background: CornflowerBlue
Mwm*menu*RootMenu*foreground: black
Mwm*menu*RootMenu*background: CornflowerBlue
Mwm*icon*foreground: grey25
Mwm*icon*background: LightGray
Mwm*foreground: black
Mwm*background: LightSkyBlue
Mwm*bottomShadowColor: Blue1
Mwm*topShadowColor: CornflowerBlue
Mwm*activeForeground: white
Mwm*activeBackground: Blue1
Mwm*activeBottomShadowColor: black
Mwm*activeTopShadowColor: LightSkyBlue
Mwm*border: black
Mwm*highlight:white

aixterm.foreground: green
aixterm.background: black
aixterm.fullcursor: true
aixterm.ScrollKey: on
aixterm.autoRaise: true
aixterm.autoRaiseDelay: 2
aixterm.boldFont:Rom10.500
aixterm.geometry: 80x25
aixterm.iconFont: Rom8.500

```

```

aixterm.iconStartup: false
aixterm.jumpScroll: true
aixterm.reverseWrap: true
aixterm.saveLines: 500
aixterm.scrollInput: true
aixterm.scrollKey: false
aixterm.title: AIX

```

.mwmrc File

Most of the features that you want to customize can be set with resources in your **.Xdefaults** file. However, key bindings, mouse button bindings, and menu definitions for your window manager are specified in the supplementary **.mwmrc** file, which is referenced by resources in the **.Xdefaults** file.

If you do not have a **.mwmrc** file in your home directory, you can copy it as follows:

```
cp /usr/lib/X11/system.mwmrc .mwmrc
```

Because the **.mwmrc** file overrides the systemwide effects of the **system.mwmrc** file, your specifications do not interfere with the specifications of other users.

The following example shows part of the typical **system.mwmrc** file:

```

# DEFAULT mwm RESOURCE DESCRIPTION FILE (system.mwmrc)
#
# menu pane descriptions
#
# Root Menu Description
Menu RootMenu
{ "Root Menu"      f.title
  no-label         f.separator
  "New Window"     f.exec "aixterm &"
  "Shuffle Up"     f.circle_up
  "Shuffle Down"   f.circle_down
  "Refresh"        f.refresh
  no-label         f.separator
  "Restart"        f.restart
  "Quit"           f.quit_mwm
}
# Default Window Menu Description

Menu DefaultWindowMenu MwmWindowMenu
{ "Restore"  _R  Alt<Key>F5    f.normalize
  "Move"     _M  Alt<Key>F7    f.move
  "Size"     _S  Alt<Key>F8    f.resize
  "Minimize" _n  Alt<Key>F9    f.minimize
  "Maximize" _x  Alt<Key>F10   f.maximize
  "Lower"    _L  Alt<Key>F3    f.lower
  no-label   f.separator
  "Close"    _C  Alt<Key>F4    f.kill
}
# no acclerator window menu
Menu NoAccWindowMenu
{
  "Restore"  _R    f.normalize
  "Move"     _M    f.move
  "Size"     _S    f.resize
  "Minimize" _n    f.minimize
  "Maximize" _x    f.maximize
  "Lower"    _L    f.lower
  no-label   f.separator
  "Close"    _C    f.kill
}

```

```

Keys DefaultKeyBindings
{
  Shift<Key>Escape      icon|window      f.post_wmenu
  Meta<Key>space        icon|window      f.post_wmenu
  Meta<Key>Tab          root|icon|window f.next_key
  Meta Shift<Key>Tab   root|icon|window f.prev_key
  Meta<Key>Escape       root|icon|window f.next_key
  Meta Shift<Key>Escape root|icon|window f.prev_key
  Meta Ctrl Shift<Key>exclam root|icon|window f.set_behavior
}
#
# button binding descriptions
#
Buttons DefaultButtonBindings
{
  <Btn1Down>          frame|icon      f.raise
  <Btn3Down>          frame|icon      f.post_wmenu
  <Btn1Down>          root            f.menu RootMenu
  <Btn3Down>          root            f.menu RootMenu
  Meta<Btn1Down>     icon|window     f.lower
  Meta<Btn2Down>     window|icon     f.resize
  Meta<Btn3Down>     window         f.move
}
Buttons PointerButtonBindings
{
  <Btn1Down>          frame|icon      f.raise
  <Btn2Down>          frame|icon      f.post_wmenu
  <Btn3Down>          frame|icon      f.lower
  <Btn1Down>          root            f.menu RootMenu
  Meta<Btn2Down>     window|icon     f.resize
  Meta<Btn3Down>     window|icon     f.move
}
#
# END OF mwm RESOURCE DESCRIPTION FILE
#

```

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 9. File and System Security” on page 119

“Chapter 2. User Environment and System Information” on page 11

“Customization Procedures” on page 141

“Customizing the InfoExplorer ASCII Program” on page 260

“Chapter 11. Shells” on page 149

“Korn Shell or POSIX Shell Commands” on page 172

“Bourne Shell” on page 196

Customization Procedures

There are many ways to customize your system environment. This section discusses the following procedures:

- “Exporting Shell Variables (export Shell Command)”
- “Changing the Display’s Font (chfont Command)”
- “Changing Control Keys (stty Command)” on page 142
- “Changing Your System Prompt” on page 143

Exporting Shell Variables (export Shell Command)

A *local* shell variable is a variable known only to the shell that created it. If you start a new shell, the old shell’s variables are unknown to it. If you want the new shells that you open to know the variables from an old shell, you need to make the variables *global* by exporting them.

You can use the **export** command to make local variables global. To make your local shell variables global automatically, export them in your **.profile** file.

Note: Variables can be exported down to child shells but not exported up to parent shells.

For example, to make the local shell variable **PATH** global, type:

```
export path
```

Press Enter.

For example, to list all your exported variables, type:

```
export
```

Press Enter.

The system displays information similar to the following:

```
DISPLAY=unix:0
EDITOR=vi
ENV=$HOME/.env
HISTFILE=/u/denise/.history
HISTSIZE=500
HOME=/u/denise
LANG=en_US
LOGNAME=denise
MAIL=/usr/mail/denise
MAILCHECK=0
MAILMSG=**YOU HAVE NEW MAIL. USE THE mail COMMAND TO SEE YOUR MAILPATH=/usr/mail/denise?denise has mail !!!
MAILRECORD=/u/denise/.Outmail
PATH=/usr/ucb:/usr/lpp/X11/bin:/bin:/usr/bin:/etc:/u/denise:/u/denise/bin:/u/bin1
PWD=/u/denise
SHELL=/bin/ksh
```

Changing the Display’s Font (chfont Command)

You can change the default font at system startup with the **chfont** or **smit** command. A *font palette* is a file that the system uses to define and identify the fonts it has available.

Note: You must have root authority to run the **chfont** command.

chfont Command

For example, to change the active font to the fifth font in the font palette, type:

```
chfont -a5
```

Press Enter.

Font ID 5 becomes the primary font.

For example, to change the font to an italic, roman, and bold face of the same size, type:

```
chfont -n /usr/lpp/fonts/It114.snf /usr/lpp/fonts/Bld14.snf /usr/lpp/fonts/Rom14.snf
```

Press Enter.

See the **chfont** command in the *AIX 5L Version 5.1 Commands Reference* for more information and the exact syntax. See also “Listing the Available Fonts (lsfont Command)” on page 13

smit Command

The **chfont** command can also be run using **smit**.

To select the active font, type:

```
smit chfont
```

Press Enter.

To select the font palette, type:

```
smit chfontpl
```

Press Enter.

Changing Control Keys (stty Command)

You can change the keys your terminal uses for control keys with the **stty** command. Your changes to control keys last until you log out. To make your changes permanent, place them in your **.profile** file.

For example, to assign Ctrl-Z as the interrupt key, type:

```
stty intr ^Z
```

Press Enter.

For example, to reset all control keys to their default values, type:

```
stty sane
```

Press Enter.

For example, to display your current settings, type:

```
stty -a
```

Press Enter.

See the **stty** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

Changing Your System Prompt

Your shell uses three prompt variables:

- PS1** Prompt used as the normal system prompt.
- PS2** Prompt used when the shell expects more input.
- PS3** Prompt used when you have root authority.

You can change any of your prompt characters by changing the value of its shell variable. Your changes to your prompts last until you log out. To make your changes permanent, place them in your **.env** file.

For example, to display the current value of the PS1 variable, type:

```
echo "prompt is $PS1"
```

Press Enter.

The system displays information similar to the following:

```
prompt is $
```

For example, to change your prompt to Ready> , type:

```
PS1="Ready> "
```

Press Enter.

For example, to change your continuation prompt to Enter more-> , type:

```
PS2="Enter more->"
```

Press Enter.

For example, to change your root prompt to Root-> , type:

```
PS3="Root-> "
```

Press Enter.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 9. File and System Security” on page 119

“Chapter 2. User Environment and System Information” on page 11

“System Startup Files Overview” on page 134

“Customizing the InfoExplorer ASCII Program” on page 260

“Customizing the InfoExplorer Windows Program” on page 144

“Chapter 11. Shells” on page 149

“Korn Shell or POSIX Shell Commands” on page 172

“Bourne Shell” on page 196

“C Shell” on page 212

Customizing the InfoExplorer Windows Program

You can customize the InfoExplorer program by setting defaults and preferences. For example, you can specify which information bases and printer to use by default. You can also specify such things as the number of history events to track and the type of print output.

The primary difference between defaults and preferences is that the InfoExplorer program initiates defaults at startup. When setting defaults, you must exit and restart the program to have the changes take effect (except for default printer settings). When setting preferences, the changes take place immediately.

The following sections describe customizing the InfoExplorer Window Interface:

- “Changing Defaults in the InfoExplorer Window Interface”
- “Changing Preferences in the InfoExplorer Window Interface” on page 145

Changing Defaults in the InfoExplorer Window Interface

In InfoExplorer, you can set many defaults. The InfoExplorer program uses the default settings at startup. Use the **Defaults** option in the Options pull-down menu to set defaults for:

- “Changing the Default Window Size”
- “Designating a Default Navigation Article”
- “Designating Default Files” on page 145
- “Designating a Default Note Template File” on page 145
- “Changing the Default Search Information Base” on page 145
- “Designating Default Printers” on page 145

Changing the Default Window Size

When you start the InfoExplorer program, window size is determined by system default. You can customize the default window size to suit your needs. Specifically, you can set the default window size for navigation and reading windows using the **Window Size** option in the Options pull-down menu. The new default then determines the window size for current and future InfoExplorer sessions.

For procedural information, see [Setting Window Size with the InfoExplorer Program \(InfoExplorer Help\)](#). For information on changing window size using the .Xdefaults file, see [Setting Window Size with X Resources \(InfoExplorer Help\)](#).

Designating a Default Navigation Article

By system default, the InfoExplorer program initially displays the Topic & Task Index as the primary navigation article. You can change this default to the navigation article that best suits your purposes. Then, at startup, the InfoExplorer program automatically displays the new default navigation article.

For procedural information, see [Setting Defaults \(InfoExplorer Windows\)](#).

Designating Default Files

You might want a trainee to follow a specific path while using the InfoExplorer program, or you might want to retrace your path from a previous session. To handle this, you can designate a specific history file as the default history file. Then, when you use the **History** option, the default history file leads you or the trainee down the designated path.

You can also designate a bookmarks file or a notes file as the default bookmarks or notes file and follow those specific paths in subsequent sessions.

For procedural information, see Setting Defaults (InfoExplorer Help).

Designating a Default Note Template File

When you create a note in InfoExplorer, the note editor window is initially blank. You can type the note into the blank window or paste in selected text from the reading window. To use a specific form when writing notes, you can specify a note template. If you have built and saved many note templates, you can designate one of them as the default. Then, when you use the **Note** option, the InfoExplorer program displays the default note template.

For procedural information, see Setting Defaults (InfoExplorer Help).

Changing the Default Search Information Base

By default, when you search with the InfoExplorer program, the search includes all information bases loaded with the program. However, it is not always necessary to include every information base in your search. To make your searches more efficient, you can specify which information bases to search during current and future sessions. You can also easily reset the selection to its original form (system default) so that the information bases loaded with the program are again included in a search.

For procedural information, see Setting Defaults (InfoExplorer Help).

Designating Default Printers

You might have printers that are better suited for artwork or pretty print. The **Pretty Print** option uses the **troff** program to convert a document to output for a phototypesetter. With the InfoExplorer program, you can designate a default printer for each of the different types of print: simple (text print), pretty (more elaborate print, retaining text font and style characteristics), or artwork. When you issue a print command for a screen containing one type of print or artwork, the printer you have designated automatically receives that particular command.

For example, when you choose the **Print Graphic** option of the info pull-down menu, the print job is automatically sent to the printer you designated for artwork.

Note: The **troff** document-formatting program must be installed on your system before you can use the pretty print feature.

For procedural information, see Setting Defaults (InfoExplorer Help).

Changing Preferences in the InfoExplorer Window Interface

In InfoExplorer, you can set many preferences. You use the **Preferences** option in the Customize pull-down menu to set defaults for:

- “Changing the Font Size” on page 146
- “Changing the Artwork Display” on page 146
- “Auto-Holding Articles” on page 146

- “Designating Print Article”
- “Changing the History Event Size”
- “Changing the Preferred Library”

Changing the Font Size

If the font size in the reading and navigation windows is too large or too small, you can change the default font size. The system default font size is medium. However, you can change it to X-small, small, large, or X-large. You can then apply the changes to the current session or both current and future sessions.

For procedural information, see Setting Preferences (InfoExplorer Help).

Changing the Artwork Display

Some hypertext articles have artwork. You determine whether to display this artwork in an artwork window or in the reading window. To do this, you select one of the **Inline**, **Separate Window**, or **Don't Care** options of the Customize pull-down menu. If you choose the **Don't Care** option, artwork appears in a separate artwork window unless specifically designed to appear in the reading window.

After determining how to display artwork, you can apply the changes to the current session only or to current and future sessions.

For procedural information, see Setting Preferences (InfoExplorer Help).

Auto-Holding Articles

The **Auto-Hold** option of the Customize pull-down menu determines whether the InfoExplorer program opens a new reading window for each new article. By system default, the InfoExplorer program replaces the contents of a reading window when you link to another article. To keep articles open as you move through the information base, you use the **Auto-Hold** option. When you set the **Auto-Hold** option to 0n, you can follow links without losing the articles from which you have linked. You can apply the changes to the current session only or to current and future sessions.

For procedural information, see Setting Preferences (InfoExplorer Help).

Designating Print Article

You can select between Simple Print and Pretty Print. **Simple Print** does not support graphics. The **Pretty Print** option uses the **troff** program to convert a document to output for a phototypesetter.

For procedural information, see Setting Preferences (InfoExplorer Help).

Changing the History Event Size

A history list can range in size from 0 (zero) to 500 events. For example, if the history list size is set at 10 events, the history list contains your last 10 links.

The system default for the history event size is 100 events. You can change the default size to fit your particular situation. You can then apply the changes to the current session only or to current and future sessions.

For procedural information, see Setting Preferences (InfoExplorer Help).

Changing the Preferred Library

You can designate one of the defined libraries as a “preferred library” to be used if InfoExplorer is started without a library specified at the command line.

For procedural information, see Setting Preferences (InfoExplorer Help).

Summary for User Environment Customization

System Startup Files

/etc/profile	System file that contains commands that the system executes when you log in.
/etc/environment	System file that contains variables specifying the basic environment for all processes.
\$HOME/.profile (“ .profile File” on page 135)	File in your home directory that contains commands that override the system /etc/profile when you log in.
\$HOME/.env (“ .env File” on page 136)	File in your home directory that overrides the system /etc/environment and contains variables specifying the basic environment for all processes.

AIXwindows Startup Files

\$HOME/.xinitrc (“ .xinitrc File” on page 137)	File in your home directory that controls the windows and applications that start up when you start AIXwindows.
\$HOME/.Xdefaults (“ .Xdefaults File” on page 138)	File in your home directory that controls the visual or behavioral aspect of AIXwindows resources.
\$HOME/.mwmrc (“ .mwmrc File” on page 139)	File in your home directory that defines key bindings, mouse button bindings, and menu definitions for your window manager.

Customization Procedures

PS1	Normal system prompt.
PS2	More input system prompt.
PS3	Root system prompt.
chfont	Changes the font used by a display at system restart.
stty	Sets, resets, and reports workstation operating parameters.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 9. File and System Security” on page 119

“Chapter 2. User Environment and System Information” on page 11

“System Startup Files Overview” on page 134

“Customization Procedures” on page 141

“Customizing the InfoExplorer ASCII Program” on page 260

“Customizing the InfoExplorer Windows Program” on page 144

“Chapter 11. Shells” on page 149

“Korn Shell or POSIX Shell Commands” on page 172

“Bourne Shell” on page 196

“C Shell” on page 212

Chapter 11. Shells

Your interface to the operating system is called a *shell*. The shell is the outermost layer of the operating system. Shells incorporate a programming language to control processes and files, as well as to start and control other programs. The shell manages the interaction between you and the operating system by prompting you for input, interpreting that input for the operating system, and then handling any resulting output from the operating system.

Shells provide a way for you to communicate with the operating system. This communication is carried out either interactively (input from the keyboard is acted upon immediately) or as a shell script. A *shell script* is a sequence of shell and operating system commands that is stored in a file.

When you log in to the system, the system locates the name of a shell program to execute. Once executed, the shell displays a command prompt. This prompt is usually a \$ (dollar sign). When you type a command at the prompt and press the Enter key, the shell evaluates the command and attempts to carry it out. Depending on your command instructions, the shell writes the command output to the screen or redirects the output. It then returns the command prompt and waits for you to type another command.

A *command line* is the line on which you type. It contains the shell prompt. The basic format for each line is:

```
$ Command Argument(s)
```

The shell considers the first word of a command line (up to the first blank space) as the command, and all words after that as arguments.

This section discusses:

- “Shell Features” on page 150
- “Korn Shell or POSIX Shell Commands” on page 172
- “Quoting in the Korn Shell or POSIX Shell” on page 158
- “Reserved Words in the Korn Shell or POSIX Shell” on page 159
- “Command Aliasing in the Korn Shell or POSIX Shell” on page 160
- “Parameter Substitution in the Korn Shell or POSIX Shell” on page 161
- “Command Substitution in the Korn Shell or POSIX Shell” on page 165
- “Arithmetic Evaluation in the Korn Shell or POSIX Shell” on page 166
- “Field Splitting in the Korn Shell or the POSIX Shell” on page 168
- “File Name Substitution in the Korn Shell or POSIX Shell” on page 168
- “Input and Output Redirection in the Korn Shell or POSIX Shell” on page 169
- “Exit Status in the Korn Shell or POSIX Shell” on page 172
- “Korn Shell or POSIX Shell Commands” on page 155
- “Korn Shell or POSIX Shell Built-In Commands” on page 174
- “Conditional Expressions for the Korn Shell or POSIX Shell” on page 185
- “Job Control in the Korn Shell or POSIX Shell” on page 186
- “Inline Editing in the Korn Shell or POSIX Shell” on page 187
- “List of Korn Shell or POSIX Shell Built-in Commands” on page 184
- “List of Bourne Shell Built-in Commands” on page 211
- “List of C Shell Built-in Commands” on page 232
- “Korn Shell Related Information” on page 195
- “Bourne Shell Related Information” on page 212
- “C Shell Related Information” on page 234

- “Bourne Shell” on page 196
- “Restricted Shell” on page 197
- “Bourne Shell Commands” on page 198
- “Variable and File Name Substitution in the Bourne Shell” on page 205
- “Input and Output Redirection in the Bourne Shell” on page 211
- “C Shell” on page 212
- “C Shell Commands” on page 214
- “History Substitution in the C Shell” on page 222
- “Alias Substitution in the C Shell” on page 225
- “Variable and File Name Substitution in the C Shell” on page 226
- “Environment Variables in the C Shell” on page 229
- “Input and Output Redirection in the C Shell” on page 231
- “Job Control in the C Shell” on page 232

Shell Features

The primary advantages of interfacing to the system through a shell are:

- **Wildcard substitution in file names (pattern matching)**

Carries out commands on a group of files by specifying a pattern to match, rather than an actual file name.

For more information, see:

- “File Name Substitution in the Korn Shell or POSIX Shell” on page 168
- “File Name Substitution in the Bourne Shell” on page 210
- “File Name Substitution in the C Shell” on page 227

- **Background processing**

Sets up lengthy tasks to run in the background, freeing the terminal for concurrent interactive processing.

For more information, see the **bg** command in:

- “Job Control in the Korn Shell or POSIX Shell” on page 186
- “C Shell Built-In Commands” on page 214

Note: The Bourne shell does not support job control.

- **Command aliasing**

Gives an alias name to a command or phrase. When the shell encounters an alias on the command line or in a shell script, it substitutes the text to which the alias refers.

For more information, see:

- “Command Aliasing in the Korn Shell or POSIX Shell” on page 160
- “Alias Substitution in the C Shell” on page 225

Note: The Bourne shell does not support command aliasing.

- **Command history**

Records the commands you enter in a history file. You can use this file to easily access, modify, and reissue any listed command.

For more information, see the **history** command in:

- “Korn Shell or POSIX Shell Command History” on page 174
- “C Shell Built-In Commands” on page 214
- “History Substitution in the C Shell” on page 222

Note: The Bourne shell does not support command history.

- **File name substitution**

Automatically produces a list of file names on a command line using pattern-matching characters.

For more information, see:

- “File Name Substitution in the Korn Shell or POSIX Shell” on page 168
- “File Name Substitution in the Bourne Shell” on page 210
- “File Name Substitution in the C Shell” on page 227

- **Input and output redirection**

Redirects input away from the keyboard and redirects output to a file or device other than the terminal. For example, input to a program can be provided from a file and redirected to the printer or to another file.

For more information, see:

- “Input and Output Redirection in the Korn Shell or POSIX Shell” on page 169
- “Input and Output Redirection in the Bourne Shell” on page 211
- “Input and Output Redirection in the C Shell” on page 231

- **Piping**

Links any number of commands together to form a complex program. The standard output of one program becomes the standard input of the next.

For more information, see the **pipeline** definition in the “Shells Terms” section.

- **Shell variable substitution**

Stores data in user-defined variables and predefined shell variables.

For more information, see:

- “Parameter Substitution in the Korn Shell or POSIX Shell” on page 161
- “Variable Substitution in the Bourne Shell” on page 205
- “Variable Substitution in the C Shell” on page 226

Available Shells

The following shells are provided with this version of the operating system:

- Korn shell (started with the **ksh** command)
- Bourne shell (started with the **bsh** command)
- Restricted shell (a limited version of the Bourne shell started with the **Rsh** command)
- POSIX shell (also known as the Korn Shell, and started with the **psh** command)
- Default shell (started with the **sh** command)
- C shell (started with the **cs** command)
- Trusted shell (a limited version of the Korn shell started with the **tsh** command)
- Remote shell (started with the **rsh** command).

The *login shell* refers to the shell loaded when you log in to the computer system. Your login shell is set in the **/etc/passwd** file. The Korn shell is the standard operating system login shell and is backwardly compatible with the “Bourne Shell” on page 196.

The *default or standard shell* refers to the shell linked to and started with the **/usr/bin/sh** command. The Bourne shell is set up as the default shell and is a subset of the Korn shell.

The *default or standard shell* refers to the shell linked to and started with the **/usr/bin/sh** command. The Korn shell, also known as the POSIX shell, is set up as the default shell. The POSIX shell is called the **/usr/bin/psh** and is linked to the **/usr/bin/ksh** command.

Shells Terms

The following definitions are helpful in understanding shells:

blank	A blank is one of the characters in the blank character class defined in the LC_CTYPE category. In the POSIX shell, a blank is either a tab or space.
built-in command	A command that the shell executes without searching for it and creating a separate process.
command	A sequence of characters in the syntax of the shell language. The shell reads each command and carries out the desired action either directly or by invoking separate utilities.
comment	Any word that begins with pound sign (#). The word and all characters that follow it, until the next new-line character, are ignored.
identifier	A sequence of letters, digits, or underscores from the portable character set, starting with a letter or underscore. The first character of an identifier must not be a digit. Identifiers are used as names for aliases, functions, and named parameters.
list	A sequence of one or more pipelines separated by one of these four symbols: semicolon (;), ampersand (&), double ampersand (&&), or double bar (). The list is optionally ended by one of the following symbols: semicolon (;), ampersand (&), or bar ampersand (&).

- ;** Sequentially processes the preceding pipeline. The shell carries out each command in turn and waits for the last command to complete.
- &** Asynchronously processes the preceding pipeline. The shell carries out each command in turn, processing the pipeline in the background without waiting for it to complete.
- |&** Asynchronously processes the preceding pipeline and establishes a two-way pipe to the parent shell. The shell carries out each command in turn, processing the pipeline in the background without waiting for it to complete. The parent shell can read from and write to the standard input and output of the spawned command by using the **read -p** and **print -p** commands. Only one such command can be active at any given time.
- &&** Processes the list that follows this symbol only if the preceding pipeline returns an exit value of zero (0).
- ||** Processes the list that follows this symbol only if the preceding pipeline returns a nonzero exit value.

The semicolon (;), ampersand (&), and bar ampersand (|&) have a lower priority than the double ampersand (&&) and double bar (||). The ;, &, and |& symbols have equal priority among themselves. The && and || symbols are equal in priority. One or more new-line characters can be used instead of a semicolon to delimit two commands in a list.

Note: The |& symbol is valid only in the Korn shell.

metacharacter	Each metacharacter has a special meaning to the shell and causes termination of a word unless it is quoted. Metacharacters are: pipe (), ampersand (&), semicolon (;), less-than sign (<), greater-than sign (>), left parenthesis ((), right parenthesis ()), dollar sign (\$), backquote (`), backslash (\), right quote ('), double quotation marks ("), new-line character, space character, and tab character. All characters enclosed between single quotation marks are considered quoted and are interpreted literally by the shell. The special meaning of metacharacters is retained if not quoted. (Metacharacters are also known as <i>parser metacharacters</i> in the C shell.)
parameter assignment list	Includes one or more words of the form <i>Identifier=Value</i> in which spaces surrounding the equal sign (=) must be balanced. That is, leading and trailing blanks, or no blanks, must be used.

Note: In the C shell, the parameter assignment list is of the form **set Identifier = Value**. The spaces surrounding the equal sign (=) are required.

pipeline	<p>A sequence of one or more commands separated by pipe (). Each command in the pipeline, except possibly the last command, is run as a separate process. However, the standard output of each command that is connected by a pipe becomes the standard input of the next command in the sequence. If a list is enclosed with parentheses, it is carried out as a simple command that operates in a separate subshell.</p> <p>If the reserved word ! does not precede the pipeline, the exit status will be the exit status of the last command specified in the pipeline. Otherwise, the exit status is the logical NOT of the exit status of the last command. In other words, if the last command returns zero, the exit status will be 1. If the last command returns greater than zero, the exit status will be zero.</p> <p>The format for a pipeline is:</p> <pre>[!] command1 [command2 ...]</pre>
shell variable	<p>Note: Early versions of the Bourne shell used the caret (^) to indicate a pipe.</p> <p>A name or parameter to which a value is assigned. Assign a variable by typing the variable name, an equal sign (=), and then the value. The variable name can be substituted for the assigned value by preceding the variable name with a dollar sign (\$). Variables are particularly useful for creating a short notation for a long path name, such as \$HOME for the home directory. A predefined variable is one whose value is assigned by the shell. A user-defined variable is one whose value is assigned by a user.</p>
simple command	<p>A sequence of optional parameter assignment lists and redirections, in any sequence. They are optionally followed by commands, words, and redirections. They are terminated by ;, , &, , &&, &, or a new-line character. The command name is passed as parameter 0 (as defined by the exec subroutine). The value of a simple command is its exit status of zero if it terminates normally or nonzero if it terminates abnormally. The sigaction, sigvec, or signal Subroutine in the <i>AIX 5L Version 5.1 Technical Reference: Base Operating System and Extensions Volume 2</i> includes a list of signal-exit status values.</p>
subshell	<p>A shell that is running as a child of the login shell or the current shell.</p>
wildcard character	<p>Also known as a pattern-matching character. The shell associates them with assigned values. The basic wildcards are ?, *, [set], and [!set]. Wildcard characters are particularly useful when performing file name substitution.</p>
word	<p>A sequence of characters that does not contain any blanks. Words are separated by one or more metacharacters.</p>

Creating and Running a Shell Script

Shell scripts provide an easy way to carry out tedious commands, large or complicated sequences of commands, and routine tasks. A shell script is a file that contains one or more commands. When you type the name of a shell script file, the system executes the command sequence contained by the file.

You can create a shell script using a text editor. Your script can contain both operating system commands and shell built-in commands.

The following steps are general guidelines for writing shell scripts:

1. Using a text editor, create and save a file. You can include any combination of shell and operating system commands in the shell script file.

By convention, shell scripts that are not set up for use by many users are stored in the **\$HOME/bin** directory.

Note: The operating system does not support the **setuid** or **setgid** subroutines within a shell script.

1. Use the **chmod** command to allow only the owner to run (or execute) the file. For example, if your file is named `script1`, type:

```
chmod u=rwx script1
```

Press Enter.

2. Enter the script name on the command line to run the shell script. To run the shell script, `script1`, type:

```
script1
```

Press Enter.

Note: You can run a shell script without making it executable if a shell command (**ksh**, **bsh**, or **csh**) precedes the shell script file name on the command line. For example, to run a nonexecutable file named `script1` under the control of the Korn shell, type:

```
ksh script1
```

Specifying a Shell for a Script File

When you run an executable shell script in either the Korn (the POSIX Shell) or Bourne shell, the commands in the script are carried out under the control of the current shell (the shell from which the script is started) unless you specify a different shell. When you run an executable shell script in the C shell, the commands in the script are carried out under the control of the Bourne shell (**/usr/bin/bsh**) unless you specify a different shell.

You can cause a shell script to run in a specific shell by including the shell within the shell script. To run an executable shell script under a specific shell, type `#!Path` on the first line of the shell script, and press Enter. The `#!` characters identify the file type. The *Path* variable specifies the path name of the shell from which to run the shell script. For example, if the first line in a shell script is `#!/usr/bin/bsh`, the script is run under control of the Bourne shell.

When you precede a shell script file name with a shell command, the shell specified on the command line overrides any shell specified within the script file itself. Therefore, typing `ksh myfile` and pressing Enter runs the file named **myfile** under the control of the Korn shell, even if the first line of **myfile** is `#!/usr/bin/csh`.

Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 9. File and System Security” on page 119

“Korn Shell or POSIX Shell Commands” on page 172

“Bourne Shell” on page 196

“C Shell” on page 212

Korn Shell or POSIX Shell Commands

A Korn shell command is one of the following:

- A simple command
- A pipeline
- A list
- A compound command
- A function

When you issue a command in the Korn shell or POSIX shell, the shell evaluates the command and acts as follows:

- Makes all indicated substitutions.
- Determines whether the command contains a /. If it does, the shell runs the program named by the specified path name.

If the command does not contain a /, the Korn shell or POSIX shell continues with the following actions:

- Determines whether the command is a special built-in command. If it is, the shell runs the command within the current shell process.
See ““Korn Shell or POSIX Shell Built-In Commands” on page 174” for information about special built-in commands.
- Compares the command to user-defined functions. If the command matches a user-defined function, the positional parameters are saved and then reset to the arguments of the **function** call. When the function completes or issues a return, the positional parameter list is restored, and any trap set on **EXIT** within the function is carried out. The value of a function is the value of the last command executed. A function is carried out in the current shell process.
- If the command name matches the name of a regular built-in command, that regular built-in command will be invoked.
See ““Korn Shell or POSIX Shell Built-In Commands” on page 174” for information about regular built-in commands.
- Creates a process and attempts to carry out the command by using the **exec** command (if the command is neither a built-in command nor a user-defined function).

The Korn shell, or POSIX shell, searches each directory in a specified path for an executable file. The **PATH** shell variable defines the search path for the directory containing the command. Alternative directory names are separated with a **:**. The default path is **/usr/bin:** (specifying the **/usr/bin** directory, and the current directory, in that order). The current directory is specified by two or more adjacent colons, or by a colon at the beginning or end of the path list.

If the file has execute permission but is not a directory or an **a.out** file, the shell assumes that it contains shell commands. The current shell process spawns a subshell to read the file. All nonexported aliases, functions, and named parameters are removed from the file. If the shell command file has read permission, or if the **setuid** or **setgid** bits are set on the file, then the shell runs an agent that sets up the permissions and carries out the shell with the shell command file passed down as an open file. A parenthesized command is run in a subshell without removing nonexported quantities.

This section discusses:

- “Korn Shell Compound Commands” on page 156
- “Functions” on page 157
- “Korn Shell or POSIX Shell Built-In Commands” on page 174
- “Conditional Expressions for the Korn Shell or POSIX Shell” on page 185
- “Korn Shell Related Information” on page 195

Korn Shell Compound Commands

A compound command is a list of simple commands, a pipeline, or it can begin with a reserved word. Most of the time you will use compound commands such as **if**, **while**, and **for** when you are writing shell scripts.

List of Korn Shell or POSIX Shell Compound Commands

for *Identifier* [**in** *Word ...*] ;**do** *List* ;**done**

Each time a **for** command is executed, the *Identifier* parameter is set to the next word taken from the **in** *Word ...* list. If the **in** *Word ...* command is omitted, then the **for** command executes the **do** *List* command once for each positional parameter that is set. Execution ends when there are no more words in the list. Refer to "Parameter Substitution in the Korn Shell or POSIX Shell" on page 161" for more information on positional parameters.

select *Identifier* [**in** *Word ...*] ;**do** *List* ;**done**

A **select** command prints on standard error (file descriptor 2) the set of words specified, each preceded by a number. If the **in** *Word ...* command is omitted, then the positional parameters are used instead. The **PS3** prompt is printed and a line is read from the standard input. If this line consists of the number of one of the listed words, then the value of the *Identifier* parameter is set to the word corresponding to this number.

If the line read from standard input is empty, the selection list is printed again. Otherwise, the value of the *Identifier* parameter is set to null. The contents of the line read from standard input is saved in the **REPLY** parameter. The *List* parameter is executed for each selection until a break or an end-of-file character is encountered. Refer to "Parameter Substitution in the Korn Shell or POSIX Shell" on page 161" for more information on positional parameters.

case *Word* **in** [(*Pattern* [*Pattern*] ...) *List* ;;] ... **esac**

A **case** command executes the *List* parameter associated with the first *Pattern* parameter that matches the *Word* parameter. The form of the patterns is the same as that used for file name substitution.

if *List* ;**then** *List* [**elif** *List* ;**then** *List*] ... [**else** *List*] ;**fi**

The *List* parameter specifies a list of commands to be run. The shell executes the **if** *List* command first. If a zero exit status is returned, it executes the **then** *List* command. Otherwise, the commands specified by the *List* parameter following the **elif** command are executed.

If the value returned by the last command in the **elif** *List* command is zero, the **then** *List* command is executed. If the value returned by the last command in the **then** *List* command is zero, the **else** *List* command is executed. If no commands specified by the *List* parameters are executed for the **else** or **then** command, the **if** command returns a zero exit status.

while *List* ;**do** *List* ;**done**
until *List* ;**do** *List* ;**done**

The *List* parameter specifies a list of commands to be run. The **while** command repeatedly executes the commands specified by the *List* parameter. If the exit status of the last command in the **while** *List* command is zero, the **do** *List* command is executed. If the exit status of the last command in the **while** *List* command is not zero, the loop terminates. If no commands in the **do** *List* command are executed, then the **while** command returns a zero exit status. The **until** command might be used in place of the **while** command to negate the loop termination test.

(*List*)

The *List* parameter specifies a list of commands to run. The shell executes the *List* parameter in a separate environment.

Note: If two adjacent open parentheses are needed for nesting, you must insert a space between them in order to differentiate between the command and arithmetic evaluation.

{ *List* ; }

The *List* parameter specifies a list of commands to run. The *List* parameter is simply executed.

Note: Unlike the metacharacters (), { } denote reserved words (used for special purposes, not as user-declared identifiers). To be recognized, these reserved words must appear at the beginning of a line or after a ;.

[[*Expression*]]

Evaluates the *Expression* parameter. If the expression is true, the command returns a zero exit status.

function <i>Identifier</i> { <i>List</i> ;} or function <i>Identifier</i> () { <i>List</i> ;}	Defines a function that is referenced by the <i>Identifier</i> parameter. The body of the function is the specified list of commands enclosed by { }. The () consists of two operators, so mixing blank characters with the <i>identifier</i> , (and) is permitted, but is not necessary.
time <i>Pipeline</i>	Executes the <i>Pipeline</i> parameter. The elapsed time, user time, and system time are printed to standard error.

Functions

The **function** reserved word defines shell functions. The shell reads and stores functions internally. Alias names are resolved when the function is read. The shell executes functions in the same manner as commands, with the arguments passed as positional parameters. Refer to “Parameter Substitution in the Korn Shell or POSIX Shell” on page 161 for more information on positional parameters.

The Korn shell or POSIX shell executes functions in the environment from which functions are invoked. All of the following are shared by the function and the invoking script, and side effects can be produced:

- Variable values and attributes (unless you use **typeset** within the function to declare a local variable)
- Working directory
- Aliases, function definitions, and attributes
- Special parameter \$
- Open files

The following are not shared between the function and the invoking script, and there are no side effects:

- Positional parameters.
- Special parameter #.
- Variables in a variable assignment list when the function is invoked.
- Variables declared using **typeset** within the function.
- Options.
- Traps. However, signals ignored by the invoking script will also be ignored by the function.

Note: In earlier versions of the Korn shell, traps other than **EXIT** and **ERR** were shared by the function as well as the invoking script.

If trap on **0** or **EXIT** is executed inside the body of a function, the action is executed after the function completes, in the environment that called the function. If the trap is executed outside the body of a function, the action is executed upon exit from the Korn shell. In earlier versions of the Korn shell, no trap on **0** or **EXIT** outside the body of a function was executed upon exit from the function.

When a function is executed, it has the same syntax-error and variable-assignment properties described in “Korn Shell or POSIX Shell Built-In Commands” on page 174.”

The compound command is executed whenever the function name is specified as the name of a simple command. The operands to the command temporarily will become the positional parameters during the execution of the compound command. The special parameter # will also change to reflect the number of operands. The special parameter 0 will not change.

The **return** special command is used to return from function calls. Errors within functions return control to the caller.

Function identifiers are listed with the **-f** or **+f** option of the **typeset** special command. The **-f** option also lists the text of functions. Functions are undefined with the **-f** option of the **unset** special command.

Ordinarily, functions are unset when the shell executes a shell script. The **-xf** option of the **typeset** special command allows a function to be exported to scripts that are executed without a separate invocation of the shell. Functions that must be defined across separate invocations of the shell should be specified in the **ENV** file with the **-xf** option of the **typeset** special command.

The exit status of a function definition is zero if the function was not successfully declared. Otherwise, it will be greater than zero. The exit status of a function invocation is the exit status of the last command executed by the function.

Quoting in the Korn Shell or POSIX Shell

When you want the Korn shell or POSIX shell to read a character as a regular character, rather than with any normally associated meaning, you must quote it. To negate the special meaning of a metacharacter, use one of the quoting mechanisms in the following list.

Each metacharacter has a special meaning to the shell and, unless quoted, causes termination of a word. The following characters are considered metacharacters by the Korn shell or POSIX shell and must be quoted if they are to represent themselves:

- pipe (|)
- ampersand (&)
- semicolon (;)
- less-than sign (<) and greater-than sign (>)
- left parenthesis (()) and right parenthesis ())
- dollar sign (\$)
- backquote (`) and single quotation mark (')
- backslash (\)
- double-quotation marks (")
- new-line character
- space character
- tab character.

The quoting mechanisms are the backslash (\), single quotation mark ('), and double quotation marks (").

Backslash (\)

A backslash (\) that is not quoted preserves the literal value of the following character, with the exception of a new-line character. If a new-line character follows the backslash, the shell interprets this as line continuation.

Single Quotation Marks

Enclosing characters in single quotation marks (' ') preserves the literal value of each character within the single quotation marks. A single quotation mark cannot occur within single quotation marks.

A backslash cannot be used to escape a single quotation mark in a string that is set in single-quotation marks. An embedded quotation mark can be created by writing, for example: 'a\'b', which yields a'b.

Double Quotation Marks

Enclosing characters in double quotation marks (" ") preserves the literal value of all characters within the double quotation marks, with the exception of the characters dollar sign, backquote, and backslash, as follows:

\$ The dollar sign retains its special meaning introducing parameter expansion, a form of command substitution, and arithmetic expansion.

The input characters within the quoted string that are also enclosed between \$(and the matching) will not be affected by the double quotation marks, but define that command whose output replaces the \$(...) when the word is expanded.

Within the string of characters from an enclosed \${ to the matching }, there must be an even number of unescaped double quotation marks or single quotation marks, if any. A preceding backslash character must be used to escape a literal { or }.

' The backquote retains its special meaning introducing the other form of command substitution. The portion of the quoted string, from the initial backquote and the characters up to the next backquote that is not preceded by a backslash, defines that command whose output replaces ' ... ' when the word is expanded.

**** The backslash retains its special meaning as an escape character only when followed by one of the following characters: \$, ', ", \, or a new-line character.

A double quotation mark must be preceded by a backslash to be included within double quotation marks. When you use double quotation marks, if a backslash is immediately followed by a character that would be interpreted as having a special meaning, the backslash is deleted, and the subsequent character is taken literally. If a backslash does not precede a character that would have a special meaning, it is left in place unchanged, and the character immediately following it is also left unchanged. For example:

```
"\$"   ->  $
"\a"   ->  \a
```

The following conditions apply to metacharacters and quoting characters in the Korn or POSIX shell:

- The meanings of dollar sign, asterisk (\$*) and dollar sign, at sign (\$@) are identical when not quoted, when used as a parameter assignment value, or when used as a file name.
- When used as a command argument, double quotation marks, dollar sign, asterisk, double quotation marks ("\$*") is equivalent to "\$1\$d\$2d...", where *d* is the first character of the IFS parameter.
- double quotation marks, at sign, asterisk, double quotation marks ("\$@") is equivalent to "\$1" "\$2"
- Inside backquotes (`), the backslash quotes the characters backslash (\), single quotation mark ('), and dollar sign (\$). If the backquotes occur within double quotation marks (" "), the backslash also quotes the double quotation marks character.
- Parameter and command substitution occurs inside double quotation marks (" ").
- The special meaning of reserved words or aliases is removed by quoting any character of the reserved word. You cannot quote function names or built-in command names.
- "Korn Shell Related Information" on page 195

Reserved Words in the Korn Shell or POSIX Shell

The following reserved words have special meaning to the shell:


```

!      case   do
done   elif   else
esac   fi     for
function if    in
select then   time
until  while  {
}      [[    ]]

```

The reserved words are recognized only when they appear without quotation marks and when the word is used as the:

- First word of a command
- First word following one of the reserved words other than **case**, **for**, or **in**
- Third word in a **case** or **for** command (only **in** is valid in this case).

Command Aliasing in the Korn Shell or POSIX Shell

The Korn shell, or POSIX shell, allows you to create aliases to customize commands. The **alias** command defines a word of the form `Name=String` as an alias. When you use an alias as the first word of a command line, **ksh** checks to see if it is already processing an alias with the same name. If it is, **ksh** does not replace the alias name. If an alias with the same name is not already being processed, **ksh** replaces the alias name by the value of the alias.

The first character of an alias name can be any printable character, except the metacharacters. The remaining characters must be the same as for a valid identifier. The replacement string can contain any valid shell text, including the metacharacters.

If the last character of the alias value is a blank, the shell also checks the word following the alias for alias substitution. You can use aliases to redefine special built-in commands, but not to redefine reserved words. Alias definitions are not inherited across invocations of **ksh**. However, if you specify **alias -x**, the alias stays in effect for scripts invoked by name, that do not invoke a separate shell. To export an alias definition and to cause child processes to have access to them, you must specify the **alias -x** as well as the alias definition in your environment file.

To create, list, and export aliases, use the **alias** command. Remove aliases with the **unalias** command.

The format for creating an alias is:

```
alias Name=String
```

in which the *Name* parameter specifies the name of the alias and the *String* parameter specifies the value of the alias.

The following exported aliases are predefined by the Korn shell, but can be unset or redefined. We recommend that you do not change them, because this might later confuse anyone who expects the alias to work as predefined by **ksh**.

```

autoload='typeset -fu'
false='let 0'
functions='typeset -f'
hash='alias -t'
history='fc -l'
integer='typeset -i'
nohup='nohup '
r='fc -e -'
true=':'
type='whence -v'

```

Aliases are not supported on noninteractive invocations of the Korn shell (**ksh**); for example, in a shell script, or with the **-c** option in **ksh**, as in:


```
ksh -c alias
```

For more information about aliasing, see *Creating a Command Alias* (“Creating a Command Alias (alias Shell Command)” on page 27) and the **alias** command in the *AIX 5L Version 5.1 Commands Reference*.

Tracked Aliases

Frequently, aliases are used as shorthand for full path names. One aliasing facility option allows you to automatically set the value of an alias to the full path name of a corresponding command. This special type of alias is a *tracked* alias. Tracked aliases speed execution by eliminating the need for the shell to search the **PATH** variable for a full path name.

The **set -h** command turns on command *tracking* so that each time a command is referenced, the shell defines the value of a tracked alias. This value is undefined each time you reset the **PATH** variable.

These aliases remain tracked so that the next subsequent reference will redefine the value. Several tracked aliases are compiled into the shell.

Tilde Substitution

After the shell performs alias substitution, it checks each word to see if it begins with an unquoted tilde (~). If it does, the shell checks the word, up to the first slash (/), to see if it matches a user name in the */etc/passwd* file. If the shell finds a match, it replaces the ~ character and the name with the login directory of the matched user. This process is called *tilde substitution*.

The shell does not change the original text if it does not find a match. The Korn shell also makes special replacements if the ~ character is the only character in the word or followed by plus sign (+) or hyphen (-):

- ~ Replaced by the value of the **HOME** variable.
- ~+ Replaced by the **\$PWD** variable (the full path name of the current directory).
- ~- Replaced by the **\$OLDPWD** variable (the full path name of the previous directory).

In addition, the shell attempts tilde substitution when the value of a variable assignment parameter begins with a tilde ~ character.

- “Korn Shell Related Information” on page 195

Parameter Substitution in the Korn Shell or POSIX Shell

The Korn Shell, or POSIX shell, enables you to do parameter substitutions.

This section discusses:

- “Parameters in the Korn Shell”
- “Parameter Substitution” on page 162
- “Predefined Special Parameters” on page 163
- “Variables Set by the Korn Shell or POSIX Shell” on page 164
- “Variables Used by the Korn Shell or POSIX Shell” on page 164

Parameters in the Korn Shell

A parameter is categorized as an:

- Identifier of any of the characters asterisk (*), at sign (@), pound sign (#), question mark (?), hyphen (-), dollar sign (\$), and exclamation point (!). These are called *special parameters*.
- Argument denoted by a number (*positional* parameter)

- Parameter denoted by an identifier, with a value and zero or more attributes (*named* parameter/variables).

The **typeset** special built-in command assigns values and attributes to named parameters. The attributes supported by the Korn shell are described with the **typeset** special built-in command. Exported parameters pass values and attributes to the environment.

The value of a named parameter is assigned by:

```
Name=Value [ Name=Value ] ...
```

If the **-i** integer attribute is set for the *Name* parameter, the *Value* parameter is subject to arithmetic evaluation. Refer to Arithmetic Evaluation in the Korn Shell or POSIX Shell (“Arithmetic Evaluation in the Korn Shell or POSIX Shell” on page 166) for more information about arithmetic expression evaluation.

The shell supports a one-dimensional array facility. An element of an array parameter is referenced by a subscript. A subscript is denoted by an arithmetic expression enclosed by brackets ([]). To assign values to an array, use `set -A Name Value ...`. The value of all subscripts must be in the range of 0 through 511. Arrays need not be declared. Any reference to a named parameter with a valid subscript is legal and an array will be created, if necessary. Referencing an array without a subscript is equivalent to referencing the element 0.

Positional parameters are assigned values with the **set** special command. The **\$0** parameter is set from argument 0 when the shell is invoked. The **\$** character is used to introduce substitutable parameters.

Parameter Substitution

The following are substitutable parameters:

`\${Parameter}`	The shell reads all the characters from the `\${ to the matching }` as part of the same word, even if that word contains braces or metacharacters. The value, if any, of the specified parameter is substituted. The braces are required when the <i>Parameter</i> parameter is followed by a letter, digit, or underscore that is not to be interpreted as part of its name, or when a named parameter is subscripted. If the specified parameter contains one or more digits, it is a <i>positional parameter</i> . A positional parameter of more than one digit must be enclosed in braces. If the value of the variable is an * or an @ , each positional parameter, starting with \$1 , is substituted (separated by a field separator character). If an array identifier with a subscript * or an @ is used, then the value for each of the elements (separated by a field separator character) is substituted.
`\${#Parameter}`	If the value of the <i>Parameter</i> parameter is an * or an @ , the number of positional parameters is substituted. Otherwise, the length specified by the <i>Parameter</i> parameter is substituted.
`\${#Identifier[*]}`	The number of elements in the array specified by the <i>Identifier</i> parameter is substituted.
`\${Parameter:-Word}`	If the <i>Parameter</i> parameter is set and is not null, then its value is substituted; otherwise, the value of the <i>Word</i> parameter is substituted.
`\${Parameter:=Word}`	If the <i>Parameter</i> parameter is not set or is null, then it is set to the value of the <i>Word</i> parameter. Positional parameters cannot be assigned in this way.
`\${Parameter:?Word}`	If the <i>Parameter</i> parameter is set and is not null, then substitute its value. Otherwise, print the value of the <i>Word</i> variable and exit from the shell. If the <i>Word</i> variable is omitted, then a standard message is printed.
`\${Parameter:+Word}`	If the <i>Parameter</i> parameter is set and is not null, then substitute the value of the <i>Word</i> variable. Otherwise, substitute nothing.

`${Parameter#Pattern}` | If the specified shell *Pattern* parameter matches the beginning of the value of the *Parameter* parameter, then the value of this substitution is the value of the *Parameter* parameter with the matched portion deleted. Otherwise, the value of the *Parameter* parameter is substituted. In the first form, the smallest matching pattern is deleted. In the second form, the largest matching pattern is deleted.

`${Parameter##Pattern}`

`${Parameter%Pattern}` | If the specified shell *Pattern* matches the end of the value of the *Parameter* variable, then the value of this substitution is the value of the *Parameter* variable with the matched part deleted; otherwise, substitute the value of the *Parameter* variable. In the first form, the smallest matching pattern is deleted; in the second form, the largest matching pattern is deleted.

`${Parameter%%Pattern}`

In the previous expressions, the *Word* variable is not evaluated unless it is to be used as the substituted string. Thus, in the following example the **pwd** command is executed only if the **-d** flag is not set or is null:

```
echo ${d:-$(pwd)}
```

Note: If the **:** is omitted from the previous expressions, the shell checks only whether the *Parameter* parameter is set.

Predefined Special Parameters

The following parameters are automatically set by the shell:

- @** Expands the positional parameters, beginning with **\$1**. Each parameter is separated by a space.
If you place " around **\$@**, the shell considers each positional parameter a separate string. If no positional parameters exist, the shell expands the statement to an unquoted null string.
- *** Expands the positional parameters, beginning with **\$1**. The shell separates each parameter with the first character of the **IFS** parameter value.
If you place " around **\$***, the shell includes the positional parameter values in double quotation marks. Each value is separated by the first character of the **IFS** parameter.
- #** Specifies the number (in decimals) of positional parameters passed to the shell, not counting the name of the shell procedure itself. The **\$#** parameter thus yields the number of the highest-numbered positional parameter that is set. One of the primary uses of this parameter is to check for the presence of the required number of arguments.
- Supplies flags to the shell on invocation or with the **set** command.
- ?** Specifies the exit value of the last command executed. Its value is a decimal string. Most commands return 0 to indicate successful completion. The shell itself returns the current value of the **\$?** parameter as its exit value.
- \$** Identifies the process number of this shell. Because process numbers are unique among all existing processes, this string of up to 5 digits is often used to generate unique names for temporary files.

The following example illustrates the recommended practice of creating temporary files in a directory used only for that purpose:

```
temp=$HOME/temp/$$
ls >$temp
.
.
.
rm $temp
```
- !** Specifies the process number of the last background command invoked.
- zero (0)** Expands to the name of the shell or shell script.

Variables Set by the Korn Shell or POSIX Shell

The following variables are set by the shell:

underscore (_)	Indicates initially the absolute path name of the shell or script being executed as passed in the environment. Subsequently, it is assigned the last argument of the previous command. This parameter is not set for commands that are asynchronous. This parameter is also used to hold the name of the matching MAIL file when checking for mail.
ERRNO	Specifies a value that is set by the most recently failed subroutine. This value is system-dependent and is intended for debugging purposes.
LINENO	Specifies the line number of the current line within the script or function being executed.
OLDPWD	Indicates the previous working directory set by the cd command.
OPTARG	Specifies the value of the last option argument processed by the getopts regular built-in command.
OPTIND	Specifies index of the last option argument processed by the getopts regular built-in command.
PPID	Identifies the process number of the parent of the shell.
PWD	Indicates the present working directory set by the cd command.
RANDOM	Generates a random integer, uniformly distributed between 0 and 32767. The sequence of random numbers can be initialized by assigning a numeric value to the RANDOM variable.
REPLY	Set by the select statement and by the read regular built-in command when no arguments are supplied.
SECONDS	Specifies the number of seconds since shell invocation is returned. If this variable is assigned a value, then the value returned upon reference will be the value that was assigned plus the number of seconds since the assignment.

Variables Used by the Korn Shell or POSIX Shell

The following variables are used by the shell:

CDPATH	Indicates the search path for the cd (change directory) command.
COLUMNS	Defines the width of the edit window for the shell edit modes and for printing select lists.
EDITOR	If the value of this parameter ends in emacs , gmacs , or vi , and the VISUAL variable is not set with the set special built-in command, then the corresponding option is turned on.
ENV	If this variable is set, then parameter substitution is performed on the value to generate the path name of the script that will be executed when the shell is invoked. This file is typically used for alias and function definitions.
FCEDIT	Specifies the default editor name for the fc regular built-in command.
FPATH	Specifies the search path for function definitions. This path is searched when a function with the -u flag is referenced and when a command is not found. If an executable file is found, then it is read and executed in the current environment.
HISTFILE	If this variable is set when the shell is invoked, then the value is the path name of the file that will be used to store the command history.
HISTSIZE	If this variable is set when the shell is invoked, then the number of previously entered commands that are accessible by this shell will be greater than or equal to this number. The default is 128.
HOME	Indicates the name of your login directory, which becomes the current directory upon completion of a login. The login program initializes this variable. The cd command uses the value of the \$HOME parameter as its default value. Using this variable rather than an explicit path name in a shell procedure allows the procedure to be run from a different directory without alterations.
IFS	Specifies internal field separators (normally space, tab, and new line) used to separate command words that result from command or parameter substitution and for separating words with the regular built-in command read . The first character of the IFS parameter is used to separate arguments for the \$* substitution.

LANG	Provides a default value for the LC_* variables.
LC_ALL	Overrides the value of the LANG and LC_* variables.
LC_COLLATE	Determines the behavior of range expression within pattern matching.
LC_CTYPE	Defines character classification, case conversion, and other character attributes.
LC_MESSAGES	Determines the language in which messages are written.
LINES	Determines the column length for printing select lists. Select lists print vertically until about two-thirds of lines specified by the LINES variable are filled.
MAIL	Specifies the file path name used by the mail system to detect the arrival of new mail. If this variable is set to the name of a mail file and the MAILPATH variable is not set, then the shell informs the user of new mail in the specified file.
MAILCHECK	Specifies how often (in seconds) the shell checks for changes in the modification time of any of the files specified by the MAILPATH or MAIL variables. The default value is 600 seconds. When the time has elapsed, the shell checks before issuing the next prompt.
MAILPATH	Specifies a list of file names separated by colons. If this variable is set, then the shell informs the user of any modifications to the specified files that have occurred during the period, in seconds, specified by the MAILCHECK variable. Each file name can be followed by a ? and a message that will be printed. The message will undergo variable substitution with the \$_ variable defined as the name of the file that has changed. The default message is you have mail in \$_ .
NLSPATH	Determines the location of message catalogs for the processing of LC_MESSAGES .
PATH	Indicates the search path for commands, which is an ordered list of directory path names separated by colons. The shell searches these directories in the specified order when it looks for commands. A null string anywhere in the list represents the current directory.
PS1	Specifies the string to be used as the primary system prompt. The value of this parameter is expanded for parameter substitution to define the primary prompt string, which is a \$ by default. The ! character in the primary prompt string is replaced by the command number.
PS2	Specifies the value of the secondary prompt string, which is a > by default.
PS3	Specifies the value of the selection prompt string used within a select loop, which is #!? by default.
PS4	The value of this variable is expanded for parameter substitution and precedes each line of an execution trace. If omitted, the execution trace prompt is a + .
SHELL	Specifies the path name of the shell, which is kept in the environment.
TMOUT	Specifies the number of seconds a shell waits inactive before exiting. If the TMOUT variable is set to a value greater than zero (0), the shell exits if a command is not entered within the prescribed number of seconds after issuing the PS1 prompt. (Note that the shell can be compiled with a maximum boundary that cannot be exceeded for this value.)
	Note: After the timeout period has expired, there is a 60-second pause before the shell exits.
VISUAL	If the value of this variable ends in emacs , gmacs , or vi , then the corresponding option is turned on.

The shell gives default values to the **PATH**, **PS1**, **PS2**, **MAILCHECK**, **TMOUT**, and **IFS** parameters, but the **HOME**, **SHELL**, **ENV**, and **MAIL** parameters are *not* set by the shell (although the **HOME** parameter is set by the **login** command).

Command Substitution in the Korn Shell or POSIX Shell

The Korn Shell, or POSIX Shell, enables you to do command substitution.

In command substitution, the shell executes a specified command in a subshell environment and replaces that command with its output. To execute command substitution in the Korn shell or POSIX shell, perform the following:

```
$(command)
```

or, for the backquoted version, use:

'command'

Note: Although the backquote syntax is accepted by **ksh**, it is considered obsolete by the XPG4 and POSIX standards. These standards recommend that portable applications use the `$(command)` syntax.

The shell expands the command substitution by executing *command* in a subshell environment and replacing the command substitution (the text of *command* plus the enclosing `$()` or backquotes) with the standard output of the command, removing sequences of one or more new-line characters at the end of the substitution.

In the following example, the `$()` surrounding the command indicates that the output of the **whoami** command is substituted:

```
echo My name is: $(whoami)
```

You can perform the same command substitution with:

```
echo My name is: 'whoami'
```

The output from both examples for user dee is:

```
My name is: dee
```

You can also substitute arithmetic expressions by enclosing them in `()`. For example, the command:

```
echo Each hour contains=$((60 * 60)) seconds
```

produces the following result:

```
Each hour contains 3600 seconds
```

The Korn shell or POSIX shell removes all trailing new-line characters when performing command substitution. For example, if your current directory contains the `file1`, `file2`, and `file3` files, the command:

```
echo $(ls)
```

removes the new-line characters and produces the following output:

```
file1 file2 file3
```

To preserve new-line characters, insert the substituted command in `" "`:

```
echo "$(ls)"
```

Arithmetic Evaluation in the Korn Shell or POSIX Shell

The Korn shell or POSIX shell regular built-in command **let** enables you to perform integer arithmetic. Constants are of the form `[Base]Number`. The *Base* parameter is a decimal number between 2 and 36 inclusive, representing the arithmetic base. The *Number* parameter is a number in that base. If you omit the *Base* parameter, the shell uses a base of 10.

Arithmetic expressions use the same syntax, precedence, and associativity of expression as the C language. All of the integral operators, other than double plus (`++`), double hyphen (`--`), question mark, colon (`?:`), and comma (`,`), are supported. The following Korn Shell Arithmetic Operators table lists valid Korn shell or POSIX shell operators in decreasing order of precedence:

Korn Shell Arithmetic Operators	
Operator	Definition
-	Unary minus
!	Logical negation

-	Bitwise negation
*	Multiplication
/	Division
%	Remainder
+	Addition
-	Subtraction
<<, >>	Left shift, right shift
<=, >=, <>, ==, !=	Comparison
&	Bitwise AND
^	Bitwise exclusive OR
	Bitwise OR
&&	Logical AND
	Logical OR
= *=, /=, &= +=, -=, <<=, >>=, &=, ^=, =	Assignment

Many arithmetic operators, such as *, &, <, and >, have special meaning to the Korn shell or POSIX shell. These characters must be quoted. For example, to multiply the current value of y by 5 and reassign the new value to y, use the expression:

```
let "y = y * 5"
```

Enclosing the expression in quotation marks removes the special meaning of the * character.

You can group operations inside **let** command expressions to force grouping. For example, in the expression:

```
let "z = q * (z - 10)"
```

the command multiplies q by the reduced value of z.

The Korn shell or POSIX shell includes an alternative form of the **let** command if only a single expression is to be evaluated. The shell treats commands enclosed in **(())** as quoted expressions. Therefore, the expression:

```
((x = x / 3))
```

is equivalent to:

```
let "x = x / 3"
```

Named parameters are referenced by name within an arithmetic expression without using the parameter substitution syntax. When a named parameter is referenced, its value is evaluated as an arithmetic expression.

Specify an internal integer representation of a named parameter with the **-i** flag of the **typeset** special built-in command. Using the **-i** flag, arithmetic evaluation is performed on the value of each assignment to a named parameter. If you do not specify an arithmetic base, the first assignment to the parameter determines the arithmetic base. This base is used when parameter substitution occurs.

Field Splitting in the Korn Shell or the POSIX Shell

After performing command substitution, the Korn shell scans the results of substitutions for those field separator characters found in the **IFS** (Internal Field Separator) variable. Where such characters are found, the shell splits the substitutions into distinct arguments. The shell retains explicit null arguments ("") and removes implicit null arguments (those resulting from parameters that have no values).

- If the value of **IFS** is a space, tab and new-line character, or if it is not set, any sequence of space, tab and new-line characters at the beginning or end of the input will be ignored and any sequence of those characters within the input will delimit a field. For example, the following input yields two fields, **school** and **days**:

```
<newline><space><tab>school<tab><tab>days<space>
```

- Otherwise, and if the value of **IFS** is not null, the following rules apply in sequence. "**IFS** white space" is used to mean any sequence (zero or more instances) of white-space characters that are in the **IFS** value (for example, if **IFS** contains space/comma/tab, any sequence of space and tab characters is considered **IFS** white space).
 1. **IFS** white space is ignored at the beginning and end of the input.
 2. Each occurrence in the input of an **IFS** character that is not **IFS** white space, along with any adjacent **IFS** white space, delimits a field.
 3. Non-zero length **IFS** white space delimits a field.

File Name Substitution in the Korn Shell or POSIX Shell

The Korn shell, or POSIX shell, performs file name substitution by scanning each command word specified by the *Word* variable for certain characters. If a command word includes the *****, **?** or **[** characters, and the **-f** flag has not been set, the shell regards the word as a pattern. The shell replaces the word with file names, sorted according to the collating sequence in effect in the current locale, that match that pattern. If the shell does not find a file name to match the pattern, it does not change the word.

When the shell uses a pattern for file name substitution, the **.** and **/** characters must be matched explicitly.

Note: The Korn shell does not treat these characters specially in other instances of pattern matching.

These pattern-matching characters indicate the following substitutions:

- * Matches any string, including the null string.
- ? Matches any single character.
- [...] Matches any one of the enclosed characters. A pair of characters separated by a - matches any character lexically within the inclusive range of that pair, according to the collating sequence in effect in the current locale. If the first character following the opening [is an !, then any character not enclosed is matched. A - can be included in the character set by putting it as the first or last character.

You can also use the `[:charclass:]` notation to match file names within a range indication. This format instructs the system to match any single character belonging to `class`. The definition of which characters constitute a specific character class is present through the **LC_CTYPE** category of the **setlocale** subroutine. All character classes specified in the current locale are recognized.

The names of some of the character classes are:

- **alnum**
- **alpha**
- **cntrl**
- **digit**
- **graph**

- **lower**
- **print**
- **punct**
- **space**
- **upper**
- **xdigit**.

For example, `[:upper:]` matches any uppercase letter.

The Korn shell supports file name expansion based on collating elements or symbols, or equivalence classes.

A *PatternList* is a list of one or more patterns separated from each other with a |. Composite patterns are formed with one or more of the following:

<code>?(PatternList)</code>	Optionally matches any one of the given patterns.
<code>*(PatternList)</code>	Matches zero or more occurrences of the given patterns.
<code>+(PatternList)</code>	Matches one or more occurrences of the given patterns.
<code>@(PatternList)</code>	Matches exactly one of the given patterns.
<code>!(PatternList)</code>	Matches anything, except one of the given patterns.

Pattern matching has some restrictions. If the first character of a file name is a dot (.), it can be matched only by a pattern that also begins with a dot. For example, `*` matches the file names `myfile` and `yourfile` but not the file names `.myfile` and `.yourfile`. To match these files, use a pattern such as the following:

```
.*file
```

If a pattern does not match any file names, then the pattern itself is returned as the result of the attempted match.

File and directory names should not contain the characters `*`, `?`, `[`, or `]` because they can cause infinite recursion (that is, infinite loops) during pattern-matching attempts.

Quote Removal

The quote characters, backslash (`\`), single quote (`'`), and double quote (`"`) that were present in the original word will be removed unless they have themselves been quoted.

- “Korn Shell Related Information” on page 195

Input and Output Redirection in the Korn Shell or POSIX Shell

Before the Korn shell executes a command, it scans the command line for redirection characters. These special notations direct the shell to redirect input and output. Redirection characters can appear anywhere in a simple command or can precede or follow a command. They are not passed on to the invoked command.

The shell performs command and parameter substitution before using the *Word* or *Digit* parameter except as noted. File name substitution occurs only if the pattern matches a single file and blank interpretation is not performed.

<code><Word</code>	Uses the file specified by the <i>Word</i> parameter as standard input (file descriptor 0).
<code>>Word</code>	Uses the file specified by the <i>Word</i> parameter as standard output (file descriptor 1). If the file does not exist, the shell creates it. If the file exists and the noclobber option is on, an error results; otherwise, the file is truncated to zero length.

<code>> Word</code>	Same as the <code>>Word</code> command, except that this redirection statement overrides the noclobber option.
<code>> >Word</code>	Uses the file specified by the <i>Word</i> parameter as standard output. If the file currently exists, the shell appends the output to it (by first seeking the end-of-file character). If the file does not exist, the shell creates it.
<code><>Word</code>	Opens the file specified by the <i>Word</i> parameter for reading and writing as standard input.
<code><<[-]Word</code>	Reads each line of shell input until it locates a line containing only the value of the <i>Word</i> parameter or an end-of-file character. The shell does not perform parameter substitution, command substitution, or file name substitution on the file specified. The resulting document, called a <i>here document</i> , becomes the standard input. For more information on a here document, see ““Inline Input (Here) Documents” on page 45”. If any character of the <i>Word</i> parameter is quoted, no interpretation is placed upon the characters of the document.

The here document is treated as a single word that begins after the next new-line character and continues until there is a line containing only the delimiter, with no trailing blank characters. Then the next here document, if any, starts. The format is:

```
[n]<<word
  here document
delimiter
```

If any character in *word* is quoted, the delimiter is formed by removing the quote on *word*. The here document lines will not be expanded. Otherwise, the delimiter is the *word* itself. If no characters in *word* are quoted, all lines of the here document will be expanded for parameter expansion, command substitution, and arithmetic expansion.

The shell performs parameter substitution for the redirected data. To prevent the shell from interpreting the `\`, `$`, and single quotation mark (`'`) characters and the first character of the *Word* parameter, precede the characters with a `\` character.

If a `-` is appended to `<<`, the shell strips all leading tabs from the *Word* parameter and the document.

<code><&Digit</code>	Duplicates standard input from the file descriptor specified by the <i>Digit</i> parameter.
<code>>& Digit</code>	Duplicates standard output in the file descriptor specified by the <i>Digit</i> parameter.
<code><&-</code>	Closes standard input.
<code>>&-</code>	Closes standard output.
<code><&p</code>	Moves input from the coprocess to standard input.
<code>>&p</code>	Moves output to the coprocess to standard output.

If one of these redirection options is preceded by a digit, then the file descriptor number referred to is specified by the digit (instead of the default 0 or 1). In the following example, the shell opens file descriptor 2 for writing as a duplicate of file descriptor 1:

```
... 2>&1
```

The order in which redirections are specified is significant. The shell evaluates each redirection in terms of the (*FileDescriptor*, *File*) association at the time of evaluation. For example, in the statement:

```
... 1>File 2>&1
```

the file descriptor 1 is associated with the file specified by the *File* parameter. The shell associates file descriptor 2 with the file associated with file descriptor 1 (*File*). If the order of redirections were reversed, file descriptor 2 would be associated with the terminal (assuming file descriptor 1 had previously been) and file descriptor 1 would be associated with the file specified by the *File* parameter.

If a command is followed by an `&` and job control is not active, the default standard input for the command is the empty file, **/dev/null**. Otherwise, the environment for the execution of a command contains the file descriptors of the invoking shell as modified by input and output specifications.

For more information about redirection, see “Chapter 4. Input and Output Redirection” on page 41”

Coprocess Facility

The Korn shell, or POSIX shell, allows you to run one or more commands as background processes. These commands, run from within a shell script, are called *coprocesses*. Coprocesses are useful when you want to communicate with a program.

Designate a coprocess by placing the **I&** operator after a command. Both standard input and output of the command are piped to your script.

A coprocess must meet the following restrictions:

- Include a new-line character at the end of each message
- Send each output message to standard output
- Clear its standard output after each message.

The following example demonstrates how input is passed to and returned from a coprocess:

```
echo "Initial process"
./FileB.sh |&
read -p a b c d
echo "Read from coprocess: $a $b $c $d"
print -p "Passed to the coprocess"
read -p a b c d
echo "Passed back from coprocess: $a $b $c $d"
FileB.sh
  echo "The coprocess is running"
  read a b c d
  echo $a $b $c $d
```

The resulting standard output is:

```
Initial process
Read from coprocess: The coprocess is running
Passed back from coprocess: Passed to the coprocess
```

The **print -p** command lets you write to the coprocess. To read from the coprocess, issue the **read -p** command.

Redirecting Coprocess Input and Output

The standard input and output of a coprocess is reassigned to a numbered file descriptor by using I/O redirection. For example, the command:

```
exec 5>&p
```

moves the input of the coprocess to file descriptor 5.

Once this is done, you can use standard redirection syntax to redirect command output to the coprocess. You can also start another coprocess. Output from both coprocesses is connected to the same pipe and is read with the **read -p** command. To stop the coprocess, type:

```
read -u5
```

Exit Status in the Korn Shell or POSIX Shell

Errors detected by the shell, such as syntax errors, cause the shell to return a nonzero exit status. Otherwise, the shell returns the exit status of the last command carried out. The shell reports detected run-time errors by printing the command or function name and the error condition. If the number of the line on which an error occurred is greater than 1, then the line number is also printed in [] (brackets) after the command or function name.

For a non-interactive shell, an error encountered by a special built-in or other type of command will cause the shell to write a diagnostic message as shown in the following table:

Error	Special Built-In	Other Utilities
Shell language syntax error	will exit	will exit
Utility syntax error (option or operand error)	will exit	will not exit
Redirection error	will exit	will not exit
Variable assignment error	will exit	will not exit
Expansion error	will exit	will exit
Command not found	not applicable	may exit
Dot script not found	will exit	not applicable

If any of the errors shown as "will (may) exit" occur in a subshell, the subshell will (may) exit with a nonzero status, but the script containing the subshell will not exit because of the error.

In all cases shown in the table, an interactive shell will write a diagnostic message to standard error, without exiting.

For more information about redirection see "Input and Output Redirection in the Korn Shell or POSIX Shell" on page 169."

- "Korn Shell Related Information" on page 195

Korn Shell or POSIX Shell Commands

The Korn shell is an interactive command interpreter and command programming language. It conforms to the Portable Operating System Interface for Computer Environments (POSIX), an international standard for operating systems. POSIX is not an operating system, but is a *standard* aimed at portability of applications, at the source level, across many systems. POSIX features are built on top of the Korn shell. The Korn shell (also known as the POSIX shell) offers many of the same features as the Bourne and C shells, such as I/O redirection capabilities, variable substitution, and file name substitution. It also includes several additional command and programming language features:

- Arithmetic evaluation** The Korn shell, or POSIX shell, can perform integer arithmetic using the built-in **let** command, using any base from 2 to 36. "Arithmetic Evaluation in the Korn Shell or POSIX Shell" on page 166 further describes this feature.
- Command history** The Korn shell, or POSIX shell, stores a file that records all of the commands you enter. You can use a text editor to alter a command in this history file and then reissue the command. For more information about the command history feature, see "Korn Shell or POSIX Shell Command History" on page 174.
- Coprocess facility** The "Coprocess Facility" on page 171 enables you to run programs in the background and send and receive information to these background processes.
- Editing** The Korn shell, or POSIX shell, offers inline editing options that enable you to edit the command line. Editors similar to emacs, gmacs, and vi are available. "Inline Editing in the Korn Shell or POSIX Shell" on page 187 further describes this feature.

This section discusses the following:

- “Korn Shell Environment”
- “Shell Startup”
- “Korn Shell or POSIX Shell Command History” on page 174

Korn Shell Environment

All variables (with their associated values) known to a command at the beginning of its execution constitute its *environment*. This environment includes variables that a command inherits from its parent process and variables specified as keyword parameters on the command line that calls the command. The shell interacts with the environment in several ways. When it is started, the shell scans the environment and creates a parameter for each name found, giving the parameter the corresponding value and marking it for export. Executed commands inherit the environment.

If you modify the values of the shell parameters or create new ones using the **export** or **typeset -x** commands, the parameters become part of the environment. The environment seen by any executed command is therefore composed of any name-value pairs originally inherited by the shell, whose values might be modified by the current shell, plus any additions that resulted from using the **export** or **typeset -x** commands. The executed command (subshell) will see any modifications it makes to the environment variables it has inherited, but it needs to export these variables for its child shells or processes to see the modified values.

The environment for any simple command or function is changed by prefixing with one or more parameter assignments. A parameter assignment argument is a word of the form *Identifier=Value*. Thus, the two following expressions are equivalent (as far as the execution of the command is concerned).

```
TERM=450 Command arguments
(export TERM; TERM=450; Command arguments)
```

If the **-k** flag is set, *all* parameter assignment arguments are placed in the environment, even if they occur after the command name. The following first prints **a=b c** and then **c**:

```
echo a=b c
set -k
echo a=b c
```

Note: This feature is intended for use with scripts written for early versions of the shell. Its use in new scripts is strongly discouraged.

Shell Startup

You can start the Korn shell with either the **ksh** command or the **psh** command (POSIX shell).

If the shell is started by the **exec** command, and the first character of zero argument (**\$0**) is the hyphen (-), then the shell is assumed to be a login shell. The shell first reads commands from the **/etc/profile** file, and then from either the **.profile** file in the current directory or from the **\$HOME/.profile** file, if either file exists. Next, the shell reads commands from the file named by performing parameter substitution on the value of the **ENV** environment variable, if the file exists.

If you specify the *File [Parameter]* parameter when invoking the Korn shell or POSIX shell, the shell runs the script file identified by the *File* parameter, including any parameters specified. The script file specified must have read permission; any **setuid** and **setgid** settings are ignored. The shell then reads the commands.

Note: Do not specify a script file with the **-c** or **-s** flags.

Refer to “Parameter Substitution in the Korn Shell or POSIX Shell” on page 161 for more information on positional parameters.

Shell Prompt

When used interactively, the shell prompts with the value of the **PS1** parameter before reading a command. If at any time a new line is entered and the shell requires further input to complete a command, the shell issues the secondary prompt (the value of the **PS2** parameter).

Korn Shell or POSIX Shell Command History

The Korn shell or POSIX shell saves commands entered from your terminal device to a history file. If set, the **HISTFILE** variable value is the name of the history file. If the **HISTFILE** variable is not set or cannot be written, the history file used is **\$HOME/.sh_history**. If the history file does not exist and the Korn shell cannot create it, or if it does exist and the Korn shell does not have permission to append to it, then the Korn shell uses a temporary file as the history file. The shell accesses the commands of all interactive shells using the same named history file with appropriate permissions.

By default, the Korn shell or POSIX shell saves the text of the last 128 commands entered from a terminal device. The history file size (specified by the **HISTSIZE** variable) is not limited, although a very large history file can cause the Korn shell to start up slowly.

Command History Substitution

Use the **fc** built-in command to list or edit portions of the history file. To select a portion of the file to edit or list, specify the number or the first character or characters of the command. You can specify a single command or range of commands.

If you do not specify an editor program as an argument to the **fc** regular built-in command, the editor specified by the **FCEDIT** variable is used. If the **FCEDIT** variable is not defined, then the **/usr/bin/ed** file is used. The edited command or commands are printed and run when you exit the editor.

The editor name hyphen (-) is used to skip the editing phase and run the command again. In this case, a substitution parameter of the form *Old=New* can be used to modify the command before it is run. For example, if **r** is aliased to **fc -e -**, then typing **r bad=good c** runs the most recent command that starts with the letter **c**, and replaces the first occurrence of the **bad** string with the **good** string.

For more information about using the history shell command, see “Listing Previously Entered Commands (history Shell Command)” on page 24 and the **fc** command in the *AIX 5L Version 5.1 Commands Reference*.

Korn Shell or POSIX Shell Built-In Commands

Special commands are built in to the Korn shell and POSIX shell and executed in the shell process. Unless otherwise indicated, the output is written to file descriptor 1 and the exit status is zero (0) if the command does not contain any syntax errors. Input and output redirection is permitted. There are two types of built-in commands, *special built-in commands* and *regular built-in commands*.

Refer to the “List of Korn Shell or POSIX Shell Built-in Commands” on page 184 for an alphabetical listing of these commands.

Special built-in commands differ from regular built-in commands in the following ways:

- A syntax error in a special built-in command might cause the shell executing the command to end. This does not happen if you have a syntax error in a regular built-in command. If a syntax error in a special built-in command does not end the shell program, the exit value is non-zero.

- Variable assignments specified with special built-in commands remain in effect after the command completes. This is not the situation with regular built-in commands.
- I/O redirections are processed after parameter assignments.

In addition, words that are in the form of a parameter assignment following the **export**, **readonly**, and **typeset** special commands are expanded with the same rules as a parameter assignment. This means that tilde substitution is performed after the =, and word splitting and file name substitution are not performed.

Special Built-in Command Descriptions

The Korn Shell provides the following special built-in commands:

:	eval	newgrp	shift
.	exec	readonly	times
break	exit	return	trap
continue	export	set	typeset
			unset

: <i>[Argument ...]</i>	Expands only arguments. It is used when a command is necessary, as in the <i>then</i> condition of an if command, but nothing is to be done by the command.
. <i>File [Argument ...]</i>	Reads the complete specified file and then executes the commands. The commands are executed in the current shell environment. The search path specified by the PATH variable is used to find the directory containing the specified file. If any arguments are specified, they become the positional parameters. Otherwise, the positional parameters are unchanged. The exit status is the exit status of the last command executed. Refer to “Parameter Substitution in the Korn Shell or POSIX Shell” on page 161 for more information on positional parameters. <p style="text-align: center;">Note: The <i>.File [Argument ...]</i> command reads the entire file before any commands are carried out. Therefore, the alias and unalias commands in the file do not apply to any functions defined in the file.</p>
break [<i>n</i>]	Exits from the enclosing for , while , until , or select loop, if one exists. If you specify the <i>n</i> parameter, the command breaks the number of levels specified by the <i>n</i> parameter. The value of <i>n</i> is any integer equal to or greater than 1.
continue [<i>n</i>]	Resumes the next iteration of the enclosing for , while , until , or select loop. If you specify the <i>n</i> variable, the command resumes at the <i>n</i> th enclosing loop. The value of <i>n</i> is any integer equal to or greater than 1.
eval <i>[Argument ...]</i>	Reads the specified arguments as input to the shell and executes the resulting command or commands.
exec <i>[Argument ...]</i>	Executes the command specified by the argument in place of this shell (without creating a new process). Input and output arguments can appear and affect the current process. If you do not specify an argument, the exec command modifies file descriptors as prescribed by the input and output redirection list. In this case, any file descriptor numbers greater than 2 that are opened with this mechanism are closed when invoking another program.
exit [<i>n</i>]	Exits the shell with the exit status specified by the <i>n</i> parameter. The <i>n</i> parameter must be an unsigned decimal integer with range 0-255. If you omit the <i>n</i> parameter, the exit status is that of the last command executed. An end-of-file character also exits the shell, unless the ignoreeof option of the set special command is turned on.
export -p [<i>Name</i> [= <i>Value</i>]] ...	Marks the specified names for automatic export to the environment of subsequently executed commands. <p>-p writes to standard output the names and values of all exported variables, in the following format:</p> <pre>"export %s= %s\n", <name> <value></pre>
newgrp [<i>Group</i>]	Equivalent to the exec/usr/bin/newgrp [<i>Group</i>] command.

Note: This command does not return.

readonly -p [*Name*[=*Value*]] ... Marks the names specified by the *Name* parameter as read-only. These names cannot be changed by subsequent assignment.

-p writes to standard output the names and values of all exported variables, in the following format:

```
"export %s= %s\n", <name> <value>
```

return [*n*] Causes a shell function to return to the invoking script. The return status is specified by the *n* variable. If you omit the *n* variable, the return status is that of the last command executed. If you invoke the **return** command outside of a function or a script, then it is the same as an **exit** command.

set [+
l-abCefhkmnostuvx]
 [+ **l-o** *Option*]... [+ **l-A**
Name] [*Argument* ...]

If no options or arguments are specified, the **set** command writes the names and values of all shell variables in the collation sequence of the current locale. When options are specified, they will set or unset attributes of the shell, as described below. When arguments are specified, they will cause positional parameters to be set or unset, as described below. The flags for this command are interpreted as follows:

- A** Array assignment. Unsets the *Name* parameter and assigns values sequentially from the specified *Argument* parameter list. If the **+A** flag is used, the *Name* parameter is not unset first.
- a** Exports automatically all subsequent parameters that are defined.
- b** Notifies the user asynchronously of background job completions.
- C** Equivalent to `set -o noclobber`.
- e** Executes the **ERR** trap, if set, and exits if a command has a nonzero exit status. This mode is disabled while reading profiles.
- f** Disables file name substitution.
- h** Designates each command as a tracked alias when first encountered.
- k** Places all parameter assignment arguments in the environment for a command, not just those arguments that precede the command name.
- m** Runs background jobs in a separate process and prints a line upon completion. The exit status of background jobs is reported in a completion message. On systems with job control, this flag is turned on automatically for interactive shells (refer to "Job Control in the Korn Shell or POSIX Shell" ("Job Control in the Korn Shell or POSIX Shell" on page 186) .)
- n** Reads commands and checks them for syntax errors, but does not execute them. This flag is ignored for interactive shells.

-o *Option*

Prints current option settings and an error message if you do not specify an argument. You can set more than one option on a single **ksh** command line. If the **+o** flag is used, the specified option is unset. Arguments, as specified by the *Option* variable, can be one of the following:

allexport

Same as the **-a** flag.

errexit Same as the **-e** flag.

bgnice

Runs all background jobs at a lower priority. This is the default mode.

emacs

Enters an emacs-style inline editor for command entry.

gmacs

Enters a gmacs-style inline editor for command entry.

ignoreeof

Does not exit the shell when it encounters an end-of-file character. To exit the shell, you must use the **exit** command, or press the Ctrl-D key sequence more than 11 times.

keyword

Same as the **-k** flag.

Note: This flag is for backward compatibility with the Bourne shell only. Its use is strongly discouraged.

markdirs

Appends a / to all directory names that are a result of file name substitution.

monitor

Same as the **-m** flag.

noclobber

Prevents redirection from truncating existing files. When you specify this option, a vertical bar must follow the redirection symbol (>|) to truncate a file.

noexec

Same as the **-n** flag.

noglob

Same as the **-f** flag.

nolog Prevents function definitions from being saved in the history file.

nounset

Same as the **-u** flag.

privileged

Same as the **-p** flag.

verbose

Same as the **-v** flag.

trackall

Same as the **-h** flag.

vi

Enters the insert mode of a vi-style inline editor for command entry. Entering escape character 033 puts the editor into the move mode. A return sends the line.

viraw

Processes each character as it is typed in vi mode.

xtrace

Same as the **-x** flag.

-p

Disables processing of the **\$HOME/.profile** file and uses the **/etc/suid _profile** file instead of the **ENV** file. This mode is enabled whenever the effective user ID (UID) or group ID (GID) is not equal to the real UID or GID. Turning off this option sets the effective UID or GID to the real UID and GID.

Note: The system does not support the **-p** option since the operating system does not support **setuid** shell scripts.

-s

Sorts the positional parameters lexicographically.

-t

Exits after reading and executing one command.

Note: This flag is for backward compatibility with the Bourne shell only. Its use is strongly discouraged.

-u

Treats unset parameters as errors when substituting.

-v

Prints shell input lines as they are read.

-x

Prints commands and their arguments as they are executed.

-

Turns off the **-x** and **-v** flags and stops examining arguments for flags.

—

Prevents any flags from being changed. This option is useful in setting the **\$1** parameter to a value beginning with a **-**. If no arguments follow this flag, the positional parameters are not set.

Preceding any of the **set** command flags with a **+** rather than a **-** turns off the flag. You can use these flags when you invoke the shell. The current set of flags is found in the **\$-** parameter. Unless you specify the **-A** flag, the remaining arguments are positional parameters and are assigned, in order, to **\$1**, **\$2**, ..., and so forth. If no arguments are given, the names and values of all named parameters are printed to standard output.

shift [*n*]

Renames the positional parameters, beginning with **\$n+1** ... through **\$1** The default value of the *n* parameter is 1. The *n* parameter is any arithmetic expression that evaluates to a nonnegative number less than or equal to the **\$#** parameter.

times

Prints the accumulated user and system times for the shell and for processes run from the shell.

trap [*Command*]
[*Signal*] ...

Runs the specified command when the shell receives the specified signal or signals. The *Command* parameter is read once when the trap is set and once when the trap is taken. The *Signal* parameter can be given as a number or as the name of the signal. Trap commands are executed in order of signal number. Any attempt to set a trap on a signal that was ignored on entry to the current shell is ineffective.

If the command is a -, all traps are reset to their original values. If you omit the command and the first signal is a numeric signal number, then the **ksh** command resets the value of the *Signal* parameter or parameters to the original values.

Note: If you omit the command and the first signal is a symbolic name, the signal is interpreted as a command.

If the value of the *Signal* parameter is the **ERR** signal, the specified command is carried out whenever a command has a nonzero exit status. If the signal is **DEBUG**, then the specified command is carried out after each command. If the value of the *Signal* parameter is the **0** or **EXIT** signal and the **trap** command is executed inside the body of a function, the specified command is carried out after the function completes. If the *Signal* parameter is **0** or **EXIT** for a **trap** command set outside any function, the specified command is carried out on exit from the shell. The **trap** command with no arguments prints a list of commands associated with each signal number.

For a complete list of *Signal* parameter values, used in the **trap** command without the **SIG** prefix, refer to the **sigaction**, **sigvec**, or **signal** subroutine in the *AIX 5L Version 5.1 Technical Reference: Base Operating System and Extensions Volume 2*.

typeset [+HLRZfirtux
[*n*]] [*Name*[= *Value*]] ...

Sets attributes and values for shell parameters. When invoked inside a function, a new instance of the *Name* parameter is created. The parameter value and type are restored when the function completes. You can specify the following flags with the **typeset** command:

- H** Provides AIX-to-host-file mapping on non-AIX machines.
- L** Left-justifies and removes leading blanks from the *Value* parameter. If the *n* parameter has a nonzero value, it defines the width of the field; otherwise, it is determined by the width of the value of its first assignment. When the parameter is assigned, it is filled on the right with blanks or truncated, if necessary, to fit into the field. Leading zeros are removed if the **-Z** flag is also set. The **-R** flag is turned off.
- R** Right-justifies and fills with leading blanks. If the *n* parameter has a nonzero value, it defines the width of the field; otherwise, it is determined by the width of the value of its first assignment. The field remains filled with blanks or is truncated from the end if the parameter is reassigned. The **L** flag is turned off.
- Z** Right-justifies and fills with leading zeros if the first nonblank character is a digit and the **-L** flag has not been set. If the *n* parameter has a nonzero value, it defines the width of the field; otherwise, it is determined by the width of the value of its first assignment.
- f** Indicates that the names refer to function, rather than parameter, names. No assignments can be made and the only other valid flags are **-t**, **-u**, and **-x**. The **-t** flag turns on execution tracing for this function. The **-u** flag causes this function to be marked undefined. The **FPATH** variable is searched to find the function definition when the function is referenced. The **-x** flag allows the function definition to remain in effect across shell scripts that are not a separate invocation of the **ksh** command.
- i** Identifies the parameter as an integer, making arithmetic faster. If the *n* parameter has a nonzero value, it defines the output arithmetic base; otherwise, the first assignment determines the output base.
- l** Converts all uppercase characters to lowercase. The **-u** uppercase conversion flag is turned off.
- r** Marks the names specified by the *Name* parameter as read-only. These names cannot be changed by subsequent assignment.

- t** Tags the named parameters. Tags can be defined by the user and have no special meaning to the shell.
- u** Converts all lowercase characters to uppercase characters. The **-l** lowercase flag is turned off.
- x** Marks the name specified by the *Name* parameter for automatic export to the environment of subsequently executed commands.

Using a **+** rather than a **-** turns off the **typeset** command flags. If you do not specify *Name* parameters but do specify flags, a list of names (and optionally the values) of the parameters that have these flags set is printed. (Using a **+** rather than a **-** keeps the values from being printed.) If you do not specify any names or flags, the names and attributes of all parameters are printed.

unset [-fv] Name ... Unsets the values and attributes of the parameters given by the list of names. If **-v** is specified, *Name* refers to a variable name, and the shell will unset it and remove it from the environment. Read-only variables cannot be unset. Unsetting the **ERRNO**, **LINENO**, **MAILCHECK**, **OPTARG**, **OPTIND**, **RANDOM**, **SECONDS**, **TMOUT**, and underscore (**_**) variables removes their special meanings even if they are subsequently assigned.

If the **-f** flag is set, then *Name* refers to a function name, and the shell will unset the function definition.

Regular Built-in Command Descriptions

The Korn Shell provides the following regular built-in commands:

alias	fg	print	ulimit
bg	getopts	pwd	umask
cd	jobs	read	unalias
command	kill	setgroups	wait
echo	let	test	whence
fc			

alias [-t] [-x] Creates or redefines alias definitions or writes existing alias definitions to standard output.

[*AliasName*[= *String*]]

...

For more information, refer to the **alias** command in the *AIX 5L Version 5.1 Commands Reference*.

bg [*JobID*...]

Puts each specified job into the background. The current job is put in the background if a *JobID* parameter is not specified. Refer to "Job Control in the Korn Shell or POSIX Shell" on page 186" for more information about job control.

For more information about running jobs in the background, refer to the **bg** command in the *AIX 5L Version 5.1 Commands Reference*.

cd [*Argument*]

cd *Old New*

This command can be in either of two forms. In the first form, it changes the current directory to the one specified by the *Argument* parameter. If the value of the *Argument* parameter is **-**, the directory is changed to the previous directory. The **HOME** shell variable is the default value of the *Argument* parameter. The **PWD** variable is set to the current directory.

The **CDPATH** shell variable defines the search path for the directory containing the value of the *Argument* parameter. Alternative directory names are separated by a **:**. The default path is null, specifying the current directory. The current directory is specified by a null path name, which appears immediately after the equal sign or between the colon delimiters anywhere in the path list. If the specified argument begins with a **/**, the search path is not used. Otherwise, each directory in the path is searched for the argument.

The second form of the **cd** command substitutes the string specified by the *New* variable for the string specified by the *Old* variable in the current directory name, **PWD**, and tries to change to this new directory.

command [-p]
CommandName
[Argument ...]

command [-v | -V]
CommandName

Command causes the shell to treat the specified command and arguments as a simple command, suppressing shell function lookup.

For more information, refer to the **command** command in the *AIX 5L Version 5.1 Commands Reference*.

echo [*String ...*]

Writes character strings to standard output. Refer to the **echo** command for usage and description. The **-n** flag is not supported.

fc [-r] [-e *Editor*] [*First [Last]*]

fc -l [-n] [-r] [*First [Last]*]

fc -s [*Old= New*] [*First*]

Displays the contents of your command history file or invokes an editor to modify and re-executes commands previously entered in the shell.

For more information, refer to the **fc** command in the *AIX 5L Version 5.1 Commands Reference*.

fg [*JobID*]

Brings each job specified into the foreground. If you do not specify any jobs, the command brings the current job into the foreground.

For more information about running jobs in the foreground, refer to the **fg** command in the *AIX 5L Version 5.1 Commands Reference*.

getopts *OptionString Name* [*Argument ...*]

Checks the *Argument* parameter for legal options.

For more information, refer to the **getopts** command in the *AIX 5L Version 5.1 Commands Reference*.

jobs [-l | -n | -p]
[JobID ...]

Displays the status of jobs started in the current shell environment. If no specific job is specified with the *JobID* parameter, status information for all active jobs is displayed. If a job termination is reported, the shell removes that job's process ID from the list of those known by the current shell environment.

For more information, refer to the **jobs** command in the *AIX 5L Version 5.1 Commands Reference*.

kill [-s { *SignalName* | *SignalNumber* }]
ProcessID...

kill [-*SignalName* | -*SignalNumber*]
ProcessID...

kill -l [*ExitStatus*]

Sends a signal (by default, the **SIGTERM** signal) to a running process. This default action normally stops processes. If you want to stop a process, specify the process ID (PID) in the *ProcessID* variable. The shell reports the PID of each process that is running in the background (unless you start more than one process in a pipeline, in which case the shell reports the number of the last process). You can also use the **ps** command to find the process ID number of commands.

Lists signal names.

For more information, refer to the **kill** command in the *AIX 5L Version 5.1 Commands Reference*.

let *Expression ...*

Evaluates specified arithmetic expressions. The exit status is 0 if the value of the last expression is nonzero, and 1 otherwise. Refer to "Arithmetic Evaluation in the Korn Shell or POSIX Shell" on page 166 for more information.

<p>print [-Rnprsu [n]] [Argument ...]</p>	<p>Prints shell output. If you do not specify any flags, or if the hyphen (-) or double hyphen (—) flags are specified, the arguments are printed to standard output as described by the echo command. The flags do the following:</p> <ul style="list-style-type: none"> -R Prints in raw mode (the escape conventions of the echo command are ignored). The -R flag prints all subsequent arguments and flags other than -n. -n Prevents a new-line character from being added to the output. -p Writes the arguments to the pipe of the process run with I& instead of to standard output. -r Prints in raw mode. The escape conventions of the echo command are ignored. -s Writes the arguments to the history file instead of to standard output. -u Specifies a one-digit file descriptor unit number, <i>n</i>, on which the output is placed. The default is 1. <p>Note: The internal Korn shell pwd command does not support symbolic links.</p>
<p>pwd Equivalent to print -r - \$PWD.</p> <p>read [-prsu [n]] [Name?Prompt] [Name...]</p>	<p>Takes shell input. One line is read and broken up into fields, using the characters in the IFS variable as separators.</p> <p>For more information, refer to the read command in the <i>AIX 5L Version 5.1 Commands Reference</i>.</p>
<p>setgroups</p>	<p>Executes the /usr/bin/setgroups command, which runs as a separate shell. See the setgroups command for information on how this command works. There is one difference, however. The setgroups built-in command invokes a subshell, but the setgroups command replaces the currently executing shell. Since the built-in command is supported only for compatibility, it is recommended that scripts use the absolute path name /usr/bin/setgroups rather than the shell built-in command.</p>
<p>test</p>	<p>Same as [expression]. See "Conditional Expressions for the Korn Shell or POSIX Shell" on page 185" for usage and description.</p>

ulimit [-HSacdfmst]
[Limit]

Sets or displays user-process resource limits as defined in the `/etc/security/limits` file. This file contains six default limits:

```
fsize = 2097151
core = 2048
cpu = 3600
data = 131072
rss = 65536
stack = 8192
```

These values are used as default settings when a new user is added to the system. The values are set with the **mkuser** command when the user is added to the system, or changed with the **chuser** command.

Limits are categorized as either soft or hard. Users might change their soft limits, up to the maximum set by the hard limits, with the **ulimit** command. You must have root user authority to change resource hard limits.

Many systems do not contain one or more of these limits. The limit for a specified resource is set when the *Limit* parameter is specified. The value of the *Limit* parameter can be a number in the unit specified with each resource, or the value `unlimited`. You can specify the following **ulimit** command flags:

- H** Specifies that the hard limit for the given resource is set. If you have root user authority, you can increase the hard limit. Anyone can decrease it.
- S** Specifies that the soft limit for the given resource is set. A soft limit can be increased up to the value of the hard limit. If neither the **-H** or **-S** options are specified, the limit applies to both.
- a** Lists all of the current resource limits.
- c** Specifies the number of 512-byte blocks on the size of core dumps.
- d** Specifies the size, in KB, of the data area.
- f** Specifies the number of 512-byte blocks for files written by child processes (files of any size can be read).
- m** Specifies the number of KB for the size of physical memory.
- n** Specifies the limit on the number of file descriptors a process might have open.
- s** Specifies the number of KB for the size of the stack area.
- t** Specifies the number of seconds to be used by each process.

The current resource limit is printed when you omit the *Limit* variable. The soft limit is printed unless you specify the **-H** flag. When you specify more than one resource, the limit name and unit is printed before the value. If no option is given, the **-f** flag is assumed. When you change the value, set both hard and soft limits to *Limit* unless you specify **-H** or **-S**.

For more information about user and system resource limits, refer to the **getrlimit**, **setrlimit**, or **vlimit** subroutine in the *AIX 5L Version 5.1 Technical Reference: Base Operating System and Extensions Volume 1*.

umask [-S] [Mask]

Determines file permissions. This value, along with the permissions of the creating process, determines a file's permissions when the file is created. The default is 022. If the *Mask* parameter is not specified, the **umask** command displays to standard output the file mode creation mask of the current shell environment.

For more information about file permissions, refer to the **umask** command in the *AIX 5L Version 5.1 Commands Reference*.

unalias { -a |
AliasName... }

Removes the definition for each alias name specified, or removes all alias definitions if the **-a** flag is used. Alias definitions are removed from the current shell environment.

For more information, refer to the **unalias** command in the *AIX 5L Version 5.1 Commands Reference*.

wait [<i>ProcessID...</i>]	Waits for the specified job and terminates. If you do not specify a job, the command waits for all currently active child processes. The exit status from this command is that of the process for which it waits.
	For more information, refer to the wait command in the <i>AIX 5L Version 5.1 Commands Reference</i> .
whence [-pv] <i>Name</i> ...	Indicates, for each name specified, how it would be interpreted if used as a command name. When used without either flag, whence will display the absolute pathname, if any, that corresponds to each name.
-p	Does a path search for the specified name or names even if these are aliases, functions, or reserved words.
-v	Produces a more verbose report that specifies which type each name is.

List of Korn Shell or POSIX Shell Built-in Commands

Special Built-in Commands

: (colon)	Expands only arguments.
. (dot)	Reads a specified file and then executes the commands.
break	Exits from the enclosing for , while , until , or select loop, if one exists.
continue	Resumes the next iteration of the enclosing for , while , until , or select loop.
eval	Reads the arguments as input to the shell and executes the resulting command or commands.
exec	Executes the command specified by the <i>Argument</i> parameter, instead of this shell, without creating a new process.
exit	Exits the shell whose exit status is specified by the <i>n</i> parameter.
export	Marks names for automatic export to the environment of subsequently executed commands.
newgrp	Equivalent to the exec /usr/bin/newgrp [<i>Group ...</i>] command.
readonly	Marks the specified names read-only.
return	Causes a shell to return to the invoking script.
set	Unless options or arguments are specified, writes the names and values of all shell variables in the collation sequence of the current locale.
shift	Renames positional parameters.
times	Prints the accumulated user and system times for both the shell and the processes run from the shell.
trap	Runs a specified command when the shell receives a specified signal or signals.
typeset	Sets attributes and values for shell parameters.
unset	Unsets the values and attributes of the specified parameters.

Regular Built-in Commands

alias	Prints a list of aliases to standard output.
bg	Puts specified jobs in the background.
cd	Changes the current directory to the specified directory or substitutes the current string with the specified string.
echo	Writes character strings to standard output.
fc	Selects a range of commands from the last HISTSIZE variable command typed at the terminal. Re-executes the specified command after old-to-new substitution is performed.
fg	Brings the specified job to the foreground.
getopts	Checks the <i>Argument</i> parameter for legal options.
jobs	Lists information for the specified jobs.
kill	Sends the TERM (terminate) signal to specified jobs or processes.
let	Evaluates specified arithmetic expressions.
print	Prints shell output.

pwd	Equivalent to the print -r -\$PWD command.
read	Takes shell input.
ulimit	Sets or displays user process resource limits as defined in the /etc/security/limits file.
umask	Determines file permissions.
unalias	Removes the parameters in the list of names from the alias list.
wait	Waits for the specified job and terminates.
whence	Indicates how each specified name would be interpreted if used as a command name.

See “Korn Shell or POSIX Shell Built-In Commands” on page 174 for more information.

Conditional Expressions for the Korn Shell or POSIX Shell

A conditional expression is used with the **[[** compound command to test attributes of files and to compare strings. Word splitting and file name substitution are not performed on words appearing between **[[** and **]]**. Each expression is constructed from one or more of the following unary or binary expressions:

-a File	True, if the specified file is a symbolic link that points to another file that does exist.
-b File	True, if the specified file exists and is a block special file.
-c File	True, if the specified file exists and is a character special file.
-d File	True, if the specified file exists and is a directory.
-e File	True, if the specified file exists.
-f File	True, if the specified file exists and is an ordinary file.
-g File	True, if the specified file exists and its setgid bit is set.
-h File	True, if the specified file exists and is a symbolic link.
-k File	True, if the specified file exists and its sticky bit is set.
-n String	True, if the length of the specified string is nonzero.
-o Option	True, if the specified option is on.
-p File	True, if the specified file exists and is a FIFO special file or a pipe.
-r File	True, if the specified file exists and is readable by the current process.
-s File	True, if the specified file exists and has a size greater than 0.
-t FileDescriptor	True, if specified file descriptor number is open and associated with a terminal device.
-u File	True, if the specified file exists and its setuid bit is set.
-w File	True, if the specified file exists and the write bit is on. However, the file will not be writable on a read-only file system even if this test indicates true.
-x File	True, if the specified file exists and the execute flag is on. If the specified file exists and is a directory, then the current process has permission to search in the directory.
-z String	True, if length of the specified string is 0.
-L File	True, if the specified file exists and is a symbolic link.
-O File	True, if the specified file exists and is owned by the effective user ID of this process.
-G File	True, if the specified file exists and its group matches the effective group ID of this process.
-S File	True, if the specified file exists and is a socket.
File1 -nt File2	True, if <i>File1</i> exists and is newer than <i>File2</i> .
File1 -ot File2	True, if <i>File1</i> exists and is older than <i>File2</i> .
File1 -ef File2	True, if <i>File1</i> and <i>File2</i> exist and refer to the same file.
String1 = String2	True, if <i>String1</i> is equal to <i>String2</i> .
String1 != String2	True, if <i>String1</i> is not equal to <i>String2</i> .
String = Pattern	True, if the specified string matches the specified pattern.
String != Pattern	True, if the specified string does not match the specified pattern.
String1 < String2	True, if <i>String1</i> comes before <i>String2</i> based on the ASCII value of their characters.
String1 > String2	True, if <i>String1</i> comes after <i>String2</i> based on the ASCII value of their characters.
Expression1 -eq Expression2	True, if <i>Expression1</i> is equal to <i>Expression2</i> .
Expression1 -ne Expression2	True, if <i>Expression1</i> is not equal to <i>Expression2</i> .

<i>Expression1</i> -lt <i>Expression2</i>	True, if <i>Expression1</i> is less than <i>Expression2</i> .
<i>Expression1</i> -gt <i>Expression2</i>	True, if <i>Expression1</i> is greater than <i>Expression2</i> .
<i>Expression1</i> -le <i>Expression2</i>	True, if <i>Expression1</i> is less than or equal to <i>Expression2</i> .
<i>Expression1</i> -ge <i>Expression2</i>	True, if <i>Expression1</i> is greater than or equal to <i>Expression2</i> .

Note: In each of the previous expressions, if the *File* variable is similar to */dev/fd/n*, where *n* is an integer, then the test is applied to the open file whose descriptor number is *n*.

You can construct a compound expression from these primitives by using any of the following expressions, listed in decreasing order of precedence:

(<i>Expression</i>)	True, if the specified expression is true. Used to group expressions.
! <i>Expression</i>	True, if the specified expression is false.
<i>Expression1</i> && <i>Expression2</i>	True, if <i>Expression1</i> and <i>Expression2</i> are both true.
<i>Expression1</i> <i>Expression2</i>	True, if either <i>Expression1</i> or <i>Expression2</i> is true.

Job Control in the Korn Shell or POSIX Shell

The Korn shell, or POSIX shell, provides a facility to control command sequences, or *jobs*. When you execute the **set -m** special command, the Korn shell associates a job with each pipeline. It keeps a table of current jobs, printed by the **jobs** command, and assigns them small integer numbers.

When a job is started in the background with an **&**, the shell prints a line that looks like:

```
[1] 1234
```

This indicates that the job, which was started in the background, was job number 1. It also shows that the job had one (top-level) process with a process ID of 1234.

If you are running a job and want to do something else, use the Ctrl-Z key sequence. This key sequence sends a **STOP** signal to the current job. The shell normally indicates that the job has been stopped, and then displays a shell prompt. You can then manipulate the state of this job (putting it in the background with the **bg** command), run other commands, and then eventually bring the job back into the foreground with the **fg** command. The Ctrl-Z key sequence takes effect immediately, and is like an interrupt in that the shell discards pending output and unread input when you type the sequence.

A job being run in the background stops if it tries to read from the terminal. Background jobs are normally allowed to produce output. You can disable this option by issuing the **stty tostop** command. If you set this terminal option, then background jobs stop when they try to produce output or read input.

You can refer to jobs in the Korn shell in several ways. A job is referenced by the process ID of any of its processes, or in one of the following ways:

% <i>Number</i>	Specifies the job with the given number.
% <i>String</i>	Specifies any job whose command line begins with the <i>String</i> variable.
%? <i>String</i>	Specifies any job whose command line contains the <i>String</i> variable.
%%	Specifies the current job.
%+	Equivalent to %%.
%-	Specifies the previous job.

This shell learns immediately whenever a process changes state. It normally informs you whenever a job becomes blocked so that no further progress is possible. The shell does this just before it prints a prompt so that it does not otherwise disturb your work.

When the monitor mode is on, each completed background job triggers traps set for the **CHLD** signal.

If you try to leave the shell (either by typing `exit` or using the Ctrl-D key sequence) while jobs are stopped or running, the system warns you with the message `There are stopped (running) jobs`. Use the **jobs** command to see which jobs are affected. If you immediately try to exit again, the shell terminates the stopped and running jobs without warning.

Signal Handling

The **SIGINT** and **SIGQUIT** signals for an invoked command are ignored if the command is followed by **&** and the job **monitor** option is not active. Otherwise, signals have the values that the shell inherits from its parent.

When a signal for which a trap has been set is received while the shell is waiting for the completion of a foreground command, the trap associated with that signal will not be executed until after the foreground command has completed. Therefore, a trap on a **CHILD** signal is not performed until the foreground job terminates.

- “Korn Shell Related Information” on page 195

Inline Editing in the Korn Shell or POSIX Shell

Normally, you type each command line from a terminal device and follow it by a new-line character (RETURN or LINE FEED). When you activate the `emacs`, `gmacs`, or `vi` inline editing option, you can edit the command line.

The following commands enter edit modes:

set -o emacs	Enters “emacs Editing Mode” on page 188 and initiates an emacs-style inline editor.
set -o gmacs	Enters “emacs Editing Mode” on page 188 and initiates a gmacs-style inline editor.
set -o vi	Enters “vi Editing Mode” on page 189 and initiates a vi-style inline editor.

An editing option is automatically selected each time the **VISUAL** or **EDITOR** variable is assigned a value ending in any of these option names.

Note: To use the editing features, your terminal must accept RETURN as a carriage return without line feed. A space must overwrite the current character on the screen.

Each editing mode opens a window at the current line. The window width is the value of the **COLUMNS** variable if it is defined; otherwise, the width is 80 character spaces. If the line is longer than the window width minus two, the system notifies you by displaying a mark at the end of the window. As the cursor moves and reaches the window boundaries, the window is centered about the cursor. The marks displayed are:

>	Indicates that the line extends on the right side of the window.
<	Indicates that the line extends on the left side of the window.
*	Indicates that the line extends on both sides of the window.

The search commands in each edit mode provide access to the Korn shell history file. Only strings are matched. If the leading character in the string is a `^`, the match must begin at the first character in the line.

This section discusses:

- “emacs Editing Mode”
- “vi Editing Mode” on page 189

emacs Editing Mode

The emacs mode is entered when you enable either the **emacs** or **gmacs** option. The only difference between these two modes is the way each handles the Ctrl-T edit command. To edit, move the cursor to the point needing correction and insert or delete characters or words, as needed. All of the editing commands are control characters or escape sequences.

Edit commands operate from any place on a line (not just at the beginning). Do not press the Enter key or line-feed (Down Arrow) key after edit commands, except as noted.

Ctrl-F	Moves the cursor forward (right) one character.
Esc-F	Moves the cursor forward one word (a string of characters consisting of only letters, digits, and underscores).
Ctrl-B	Moves the cursor backward (left) one character.
Esc-B	Moves the cursor backward one word.
Ctrl-A	Moves the cursor to the beginning of the line.
Ctrl-E	Moves the cursor to the end of the line.
Ctrl-] c	Moves the cursor forward on the current line to the indicated character.
Esc-Ctrl-] c	Moves the cursor backward on the current line to the indicated character.
Ctrl-X Ctrl-X	Interchanges the cursor and the mark.
ERASE	Deletes the previous character. (User-defined erase character as defined by the stty command, usually the Ctrl-H key sequence.)
Ctrl-D	Deletes the current character.
Esc-D	Deletes the current word.
Esc-Backspace	Deletes the previous word.
Esc-H	Deletes the previous word.
Esc-Delete	Deletes the previous word. If your interrupt character is the Delete key, then this command does not work.
Ctrl-T	Transposes the current character with the next character in emacs mode. Transposes the two previous characters in gmacs mode.
Ctrl-C	Capitalizes the current character.
Esc-C	Capitalizes the current word.
Esc-L	Changes the current word to lowercase.
Ctrl-K	Deletes from the cursor to the end of the line. If preceded by a numerical parameter whose value is less than the current cursor position, this editing command deletes from the given position up to the cursor. If preceded by a numerical parameter whose value is greater than the current cursor position, this editing command deletes from the cursor up to the given cursor position.
Ctrl-W	Deletes from the cursor to the mark.
Esc-P	Pushes the region from the cursor to the mark on the stack.
KILL	User-defined kill character as defined by the stty command, usually the Ctrl-G key sequence or an @. Kills the entire current line. If two kill characters are entered in succession, all subsequent kill characters cause a line feed (useful when using paper terminals).
Ctrl-Y	Restores the last item removed from the line. (Yanks the item back to the line.)
Ctrl-L	Line feeds and prints the current line.
Ctrl-@	(Null character) Sets a mark.
Esc-space	Sets a mark.
Ctrl-J	(New line) Executes the current line.
Ctrl-M	(Return) Executes the current line.
EOF	Processes the end-of-file character, normally the Ctrl-D key sequence, as an end-of-file only if the current line is null.

Ctrl-P	Fetches the previous command. Each time the Ctrl-P key sequence is entered, the previous command back in time is accessed. Moves back one line when not on the first line of a multiple-line command.
Esc-<	Fetches the least recent (oldest) history line.
Esc->	Fetches the most recent (youngest) history line.
Ctrl-N	Fetches the next command line. Each time the Ctrl-N key sequence is entered, the next command line forward in time is accessed.
Ctrl-R <i>String</i>	Reverses search history for a previous command line containing the string specified by the <i>String</i> parameter. If a value of 0 is given, the search is forward. The specified string is terminated by an Enter or new-line character. If the string is preceded by a <code>^</code> , the matched line must begin with the <i>String</i> parameter. If the <i>String</i> parameter is omitted, then the next command line containing the most recent <i>String</i> parameter is accessed. In this case, a value of 0 reverses the direction of the search.
Ctrl-O	(Operate) Executes the current line and fetches the next line relative to the current line from the history file.
Esc <i>Digits</i>	(Escape) Defines the numeric parameter. The digits are taken as a parameter to the next command. The commands that accept a parameter are Ctrl-F , Ctrl-B , ERASE , Ctrl-C , Ctrl-D , Ctrl-K , Ctrl-R , Ctrl-P , Ctrl-N , Ctrl-] , Esc-. , Esc-Ctrl-] , Esc-__ , Esc-B , Esc-C , Esc-D , Esc-F , Esc-H , Esc-L , and Esc-Ctrl-H .
Esc <i>Letter</i>	(Soft-key) Searches the alias list for an alias named <i>_Letter</i> . If an alias of this name is defined, its value is placed into the input queue. The <i>Letter</i> parameter must not specify one of the escape functions.
Esc-[<i>Letter</i>	(Soft-key) Searches the alias list for an alias named double underscore <i>Letter</i> (<i>__Letter</i>). If an alias of this name is defined, its value is placed into the input queue. This command can be used to program function keys on many terminals.
Esc-.	Inserts on the line the last word of the previous command. If preceded by a numeric parameter, the value of this parameter determines which word to insert rather than the last word.
Esc-__	Same as the Esc-. key sequence.
Esc-*	Attempts file name substitution on the current word. An asterisk is appended if the word does not match any file or contain any special pattern characters.
Esc-Esc	File name completion. Replaces the current word with the longest common prefix of all file names that match the current word with an asterisk appended. If the match is unique, a <i>/</i> is appended if the file is a directory and a space is appended if the file is not a directory.
Esc==	Lists the files that match the current word pattern as if an asterisk were appended.
Ctrl-U	Multiplies the parameter of the next command by 4.
\	Escapes the next character. Editing characters and the ERASE, KILL and INTERRUPT (normally the Delete key) characters can be entered in a command line or in a search string if preceded by a <code>\</code> . The backslash removes the next character's editing features, if any.
Ctrl-V	Displays the version of the shell.
Esc-#	Inserts a <code>#</code> at the beginning of the line and then executes the line. This causes a comment to be inserted in the history file.

vi Editing Mode

The vi editing mode has two typing modes. When you enter a command, you are in Input mode. To edit, you must enter the Control mode by pressing the Esc key.

Most control commands accept an optional repeat *Count* parameter prior to the command. When in vi mode on most systems, canonical processing is initially enabled. The command is echoed again if:

- The speed is 1200 baud or greater.
- The command contains any control characters.
- Less than one second has elapsed since the prompt was printed.

The Esc character terminates canonical processing for the remainder of the command, and you can then modify the command line. This scheme has the advantages of canonical processing with the type-ahead echoing of raw mode. If the **viraw** option is also set, canonical processing is always disabled. This mode is implicit for systems that do not support two alternate end-of-line delimiters and might be helpful for certain terminals.

Available vi edit commands are grouped in the following categories:

- “Input Edit Commands”
- “Motion Edit Commands”
- “Search Edit Commands”
- “Text-Modification Edit Commands” on page 191
- “Miscellaneous Edit Commands” on page 192

Input Edit Commands

Note: By default, the editor is in input mode.

ERASE	(User-defined erase character as defined by the stty command, usually Ctrl-H or #.) Deletes the previous character.
Ctrl-W	Deletes the previous blank separated word.
Ctrl-D	Terminates the shell.
Ctrl-V	Escapes the next character. Editing characters, such as the ERASE or KILL characters, can be entered in a command line or in a search string if preceded by a Ctrl-V key sequence. The Ctrl-V key sequence removes the next character’s editing features (if any).
\	Escapes the next ERASE or KILL character.

Motion Edit Commands

Motion edit commands move the cursor:

[Count]l	Moves the cursor forward (right) one character.
[Count]w	Moves the cursor forward one alphanumeric word.
[Count]W	Moves the cursor to the beginning of the next word that follows a blank.
[Count]e	Moves the cursor to the end of the current word.
[Count]E	Moves the cursor to the end of the current blank-separated word.
[Count]h	Moves the cursor backward (left) one character.
[Count]b	Moves the cursor backward one word.
[Count]B	Moves the cursor to the previous blank-separated word.
[Count]l	Moves the cursor to the column specified by the <i>Count</i> parameter.
[Count]fc	Finds the next character <i>c</i> in the current line.
[Count]Fc	Finds the previous character <i>c</i> in the current line.
[Count]tc	Equivalent to f followed by h .
[Count]Tc	Equivalent to F followed by l .
[Count];	Repeats for the number of times specified by the <i>Count</i> parameter the last single-character find command: f , F , t , or T .
[Count],	Reverses the last single-character find command the number of times specified by the <i>Count</i> parameter.
0	Moves the cursor to the start of a line.
^	Moves the cursor to the first nonblank character in a line.
\$	Moves the cursor to the end of a line.

Search Edit Commands

Search edit commands access your command history:

[Count]k	Fetches the previous command.
[Count]-	Equivalent to the k command.

[<i>Count</i>]j	Fetches the next command. Each time the j command is entered, the next command is accessed.
[<i>Count</i>]+	Equivalent to the j command.
[<i>Count</i>]G	Fetches the command whose number is specified by the <i>Count</i> parameter. The default is the least recent history command.
<i>IString</i>	Searches backward through history for a previous command containing the specified string. The string is terminated by a RETURN or new-line character. If the specified string is preceded by a ^ , the matched line must begin with the <i>String</i> parameter. If the value of the <i>String</i> parameter is null, the previous string is used.
? <i>String</i>	Same as <i>IString</i> except that the search is in the forward direction.
n	Searches for the next match of the last pattern to <i>IString</i> or ? commands.
N	Searches for the next match of the last pattern to <i>IString</i> or ? commands, but in the opposite direction. Searches history for the string entered by the previous <i>IString</i> command.

Text-Modification Edit Commands

Text-modification edit commands modify the line:

a	Enters the input mode and enters text after the current character.
A	Appends text to the end of the line. Equivalent to the \$a command.
[<i>Count</i>]c <i>Motion</i>	Deletes the current character through the character to which the <i>Motion</i> parameter specifies to move the cursor, and enters input mode. If the value of the <i>Motion</i> parameter is c , the entire line is deleted and the input mode is entered.
c[<i>Count</i>]i <i>Motion</i>	
C	Deletes the current character through the end of the line and enters input mode. Equivalent to the c\$ command.
S	Equivalent to the cc command.
D	Deletes the current character through the end of line. Equivalent to the d\$ command.
[<i>Count</i>]d <i>Motion</i>	Deletes the current character up to and including the character specified by the <i>Motion</i> parameter. If <i>Motion</i> is d , the entire line is deleted.
d[<i>Count</i>]i <i>Motion</i>	
i	Enters the input mode and inserts text before the current character.
I	Inserts text before the beginning of the line. Equivalent to the 0i command.
[<i>Count</i>]P	Places the previous text modification before the cursor.
[<i>Count</i>]p	Places the previous text modification after the cursor.
R	Enters the input mode and types over the characters on the screen.
[<i>Count</i>]rc	Replaces the number of characters specified by the <i>Count</i> parameter, starting at the current cursor position, with the characters specified by the <i>c</i> parameter. This command also advances the cursor after the characters are replaced.
[<i>Count</i>]x	Deletes the current character.
[<i>Count</i>]X	Deletes the preceding character.
[<i>Count</i>].	Repeats the previous text-modification command.
[<i>Count</i>]~	Inverts the case of the number of characters specified by the <i>Count</i> parameter, starting at the current cursor position, and advances the cursor.
[<i>Count</i>]_	Appends the word specified by the <i>Count</i> parameter of the previous command and enters input mode. The last word is used if the <i>Count</i> parameter is omitted.
*	Appends an * to the current word and attempts file name substitution. If no match is found, it rings the bell. Otherwise, the word is replaced by the matching pattern and input mode is entered.
\	File name completion. Replaces the current word with the longest common prefix of all file names matching the current word with an asterisk appended. If the match is unique, a / is appended if the file is a directory. A space is appended if the file is not a directory.

Miscellaneous Edit Commands

Miscellaneous edit commands include:

<code>[Count]yMotion</code>	
<code>y[Count]Motion</code>	Yanks the current character up to and including the character marked by the cursor position specified by the <i>Motion</i> parameter and puts all of these characters into the delete buffer. The text and cursor are unchanged.
Y	Yanks from the current position to the end of the line. Equivalent to the y\$ command.
u	Undoes the last text-modifying command.
U	Undoes all the text-modifying commands performed on the line.
<code>[Count]v</code>	Returns the command <code>fc -e \${VISUAL:-\${EDITOR:-vi}}</code> Count in the input buffer. If the <i>Count</i> parameter is omitted, then the current line is used.
Ctrl-L	Line feeds and prints the current line. This command is effective only in control mode.
Ctrl-J	(New line) Executes the current line, regardless of the mode.
Ctrl-M	(Return) Executes the current line, regardless of the mode.
#	Sends the line after inserting a # in front of the line. Useful if you want to insert the current line in the history without executing it.
	If the command line contains a pipe or semicolon or new-line character, then additional # s will be inserted in front of each of these symbols. To delete all pound signs, retrieve the command line from history and enter another # .
=	Lists the file names that match the current word as if an asterisk were appended to it.
@Letter	Searches the alias list for an alias named <i>_Letter</i> . If an alias of this name is defined, its value is placed into the input queue for processing.

Enhanced Korn Shell (ksh93)

In addition to the default system Korn shell (`/usr/bin/ksh`), AIX provides an enhanced version available as `/usr/bin/ksh93`. This enhanced version is upwardly compatible with the current default version, and includes a few additional features that are not available in `/usr/bin/ksh`. The following table contains an overview of these additional features.

Features of ksh93

The following features are available in `/usr/bin/ksh93`:

Arithmetic Enhancements	You can use libm functions (math functions typically found in the C programming language), within arithmetic expressions, such as <code>\$ value=\$((sqrt(9)))</code> . More arithmetic operators are available, including the unary <code>+</code> , <code>++</code> , <code>--</code> , and the <code>?:</code> construct (for example, <code>"x ? y : z"</code>), as well as the <code>,</code> (comma) operator. Arithmetic bases are supported up to base 64. Floating point arithmetic is also supported. <code>"typeset -E"</code> (exponential) can be used to specify the number of significant digits and <code>"typeset -F"</code> (float) can be used to specify the number of decimal places for an arithmetic variable. The <code>SECONDS</code> variable now displays to the nearest hundredth of a second, rather than to the nearest second.
Compound Variables	Compound variables are supported in ksh93. A compound variable allows a user to specify multiple values within a single variable name. The values are each assigned with a subscript variable, separated from the parent variable with a <code>.</code> (period). For example: <pre>\$ myvar=(x=1 y=2) \$ print "\${myvar.x}" 1</pre>
Compound Assignments	Compound assignments are supported when initializing arrays, both for indexed arrays and associative arrays. The assignment values are placed in parentheses as shown in the following example: <pre>\$ numbers=(zero one two three) \$ print \${numbers[0]} \${numbers[3]} zero three</pre>

Associative Arrays	<p>An associative array is an array with a string as an index.</p> <p>The typeset command used with the -A flag allows you to specify associative arrays within ksh93. For example:</p> <pre>\$ typeset -A teammates \$ teammates=([john]=smith [mary]=jones) \$ print \${teammates[mary]} jones</pre>
Variable Name References	<p>The typeset command used with the -n flag allows you to assign one variable name as a reference to another. In this way, modifying the value of a variable will in turn modify the value of the variable that is referenced. For example:</p> <pre>\$ greeting="hello" \$ typeset -n welcome=greeting # establishes the reference \$ welcome="hi there" # overrides previous value \$ print \$greeting hi there</pre>
Parameter Expansions	<p>The following parameter-expansion constructs are available in ksh93:</p> <ul style="list-style-type: none"> • <code>\${!varname}</code> is the name of the variable itself. • <code>\${!varname[@]}</code> names the indexes for the <i>varname</i> array. • <code>\${param:offset}</code> is a substring of <i>param</i>, starting at <i>offset</i>. • <code>\${param:offset:num}</code> is a substring of <i>param</i>, starting at <i>offset</i>, for <i>num</i> number of characters. • <code>\${@:offset}</code> indicates all positional parameters starting at <i>offset</i>. • <code>\${@:offset:num}</code> indicates <i>num</i> positional parameters starting at <i>offset</i>. • <code>\${param/pattern/repl}</code> evaluates to <i>param</i>, with the first occurrence of <i>pattern</i> replaced by <i>repl</i>. • <code>\${param//pattern/repl}</code> evaluates to <i>param</i>, with every occurrence of <i>pattern</i> replaced by <i>repl</i>. • <code>\${param/#pattern/repl}</code> if <i>param</i> begins with <i>pattern</i>, then <i>param</i> is replaced by <i>repl</i>. • <code>\${param/%pattern/repl}</code> if <i>param</i> ends with <i>pattern</i>, then <i>param</i> is replaced by <i>repl</i>.

Discipline Functions	<p>A discipline function is a function that is associated with a specific variable. This allows you to define and call a function every time that variable is referenced, set, or unset. These functions take the form of <i>varname.function</i>, where <i>varname</i> is the name of the variable and <i>function</i> is the discipline function. There are three predefined discipline functions: get, set, and unset.</p> <ul style="list-style-type: none"> The <i>varname.get</i> function is invoked every time <i>varname</i> is referenced. If the special variable .sh.value is set within this function, then the value of <i>varname</i> is changed to this value. A simple example is the time of day: <pre> \$ function time.get > { > .sh.value=\$(date +%r) > } \$ print \$time 09:15:58 AM \$ print \$time # it will change in a few seconds 09:16:04 AM </pre> The <i>varname.set</i> function is invoked every time <i>varname</i> is set. The .sh.value variable is given the value that was assigned. The value assigned to <i>varname</i> is the value of .sh.value when the function completes. For example: <pre> \$ function adder.set > { > let .sh.value=" \$ { .sh.value} + 1" > } \$ adder=0 \$ echo \$adder 1 \$ adder=\$adder \$ echo \$adder 2 </pre> The <i>varname.unset</i> function is executed every time <i>varname</i> is unset. The variable does not actually get unset unless it is unset within the function itself; otherwise it retains its value. <p>Within all discipline functions, the special variable .sh.name is set to the name of the variable, while .sh.subscript is set to the value of the variables subscript, if applicable.</p>
Function Environments	<p>Functions declared with the <i>function myfunc</i> format are executed in a separate function environment. Functions declared as <i>myfunc ()</i> execute with the same environment as the parent shell.</p>
Variables	<p>Variables beginning with .sh. are reserved by the shell and have special meaning. See the description of Discipline Functions above for an explanation of .sh.name, .sh.value, and .sh.subscript. Also available is .sh.version, which represents the version of the shell.</p> <p>Note: The variable ERRNO is no longer available.</p>
Command Return Values	<p>Return values of commands in ksh93 are as follows:</p> <ul style="list-style-type: none"> If the command to be executed is not found, the return value is set to 127. If the command to be executed is found, but not executable, the return value is 126. If the command is executed, but is terminated by a signal, the return value is 256 plus the signal number.
PATH Search Rules	<p>Special built-in commands are searched for first, followed by all functions (including those in FPATH directories), followed by other built-ins. Previously, all built-ins were searched before all functions, and FPATH functions were not searched until after everything in PATH.</p>
Shell History	<p>The hist command allows you to display and edit the shells command history. In the ksh shell, the fc command was used. The fc command is now an alias to hist. Variables are HISTCMD, which increments once for each command executed in the shells current history, and HISTEDIT, which specifies which editor to use when using the hist command.</p>

Built-In Commands	<ul style="list-style-type: none"> • The built-in command builtin has been added. The builtin command lists all available built-in commands. • The printf command has been added as a built-in. This functions much as the printf() C library routine does. Refer to the printf command manual page. • The disown built-in command has been added. disown blocks the shell from sending a SIGHUP to the specified command. • The getconf command has been added as a built-in. It functions in the same way as the stand-alone command /usr/bin/getconf. Refer to the getconf command manual page. • The read built-in command has two flags: <ul style="list-style-type: none"> – read -d {char} allows you to specify a character delimiter instead of the default newline. – read -t {seconds} allows you to specify a time limit in seconds after which the read command will time out. If read times out, it will return FALSE. • The exec built-in command has two flags: <ul style="list-style-type: none"> – exec -a {name} {cmd} specifies that argument 0 of <i>cmd</i> be replaced with <i>name</i>. – exec -c {cmd} tells exec to clear the environment before executing <i>cmd</i>. • The kill built-in command has two flags: <ul style="list-style-type: none"> – kill -n {signal} is used for specifying a signal number to send to a process, while kill -s {signame} is used to specify a signal name. – kill -l, with no arguments, lists all signal names but not their numbers. • The whence built-in command has two flags. <ul style="list-style-type: none"> – The -a flag displays all matches, not just the first one found. – The -f flag tells whence not to search for any functions. • An escape character sequence has been added for use by the print and echo commands. The Esc (Escape) key can be represented by the sequence \E. • All regular built-in commands recognize the -? flag, which shows the syntax for the specified command.
--------------------------	---

Korn Shell Related Information

“Chapter 11. Shells” on page 149

“Korn Shell or POSIX Shell Commands” on page 172

“Korn Shell or POSIX Shell Commands” on page 155

“Command Aliasing in the Korn Shell or POSIX Shell” on page 160

“Parameter Substitution in the Korn Shell or POSIX Shell” on page 161

“Command Substitution in the Korn Shell or POSIX Shell” on page 165

“Arithmetic Evaluation in the Korn Shell or POSIX Shell” on page 166

“Field Splitting in the Korn Shell or the POSIX Shell” on page 168

“File Name Substitution in the Korn Shell or POSIX Shell” on page 168

“Quote Removal” on page 169

“Input and Output Redirection in the Korn Shell or POSIX Shell” on page 169

“Job Control in the Korn Shell or POSIX Shell” on page 186

“Inline Editing in the Korn Shell or POSIX Shell” on page 187

The **ksh** and **stty** commands.

The **alias**, **cd**, **export**, **fc**, **getopts**, **read**, **set**, and **typeset** Korn shell commands.

The **/etc/passwd** file.

“Bourne Shell”

“C Shell” on page 212

Bourne Shell

The Bourne shell is an interactive command interpreter and command programming language. The **bsh** command runs the Bourne shell.

The Bourne shell can be run either as a login shell or as a subshell under the login shell. Only the **login** command can call the Bourne shell as a login shell. It does this by using a special form of the **bsh** command name: **-bsh**. When called with an initial hyphen (-), the shell first reads and runs commands found in the system **/etc/profile** file and your **\$HOME/.profile**, if one exists. The **/etc/profile** file sets variables needed by all users. Finally, the shell is ready to read commands from your standard input.

If the *File* [*Parameter*] parameter is specified when the Bourne shell is started, the shell runs the script file identified by the *File* parameter, including any parameters specified. The script file specified must have read permission; any **setuid** and **setgid** settings are ignored. The commands are then read. A script file should not be specified if either the **-c** or **-s** flag is used.

Bourne Shell Environment

All variables (with their associated values) known to a command at the beginning of its execution constitute its *environment*. This environment includes variables that a command inherits from its parent process and variables specified as keyword parameters on the command line that calls the command.

The shell passes to its child processes the variables named as arguments to the built-in **export** command. This command places the named variables in the environments of both the shell and all its future child processes.

Keyword parameters are variable-value pairs that appear in the form of assignments, normally before the procedure name on a command line (but see also the flag for the **set** command). Such variables are placed in the environment of the procedure being called.

For example, consider the following simple procedure, which displays the values of two variables (saved in a command file named `key_command`):

```
# key_command
echo $a $b
```

The following command lines produce the output shown:

Input	Output
a=key1 b=key2 key_command	key1 key2
a=tom b=john key_command	tom john

A procedure’s keyword parameters are not included in the parameter count stored in `$#`.

A procedure can access the values of any variables in its environment. If it changes any of these values, however, the changes are not reflected in the shell environment. They are local to the procedure in question. To place the changes in the environment that the procedure passes to its child processes, you must export the new values within that procedure.

To obtain a list of variables that are exportable from the current shell, type:

```
export
```

Press Enter.

To obtain a list of read-only variables from the current shell, type:

```
readonly
```

Press Enter.

To obtain a list of variable-value pairs in the current environment, type:

```
env
```

Press Enter.

For more information about user environments, see “/etc/environment File” on page 135

Restricted Shell

The restricted shell is used to set up login names and execution environments whose capabilities are more controlled than those of the regular Bourne shell. The **Rsh** or **bsh -r** command opens the restricted shell. The behavior of these commands is identical to those of the **bsh** command, except that the following actions are not allowed:

- Changing the directory (with the **cd** command)
- Setting the value of **PATH** or **SHELL** variables
- Specifying path or command names containing a slash (/)
- Redirecting output

If the restricted shell determines that a command to be run is a shell procedure, it uses the Bourne shell to run the command. In this way, it is possible to provide an end user with shell procedures that access the full power of the Bourne shell while imposing a limited menu of commands. This scheme assumes that the end user does not have write and execute permissions in the same directory.

If the *File* [*Parameter*] parameter is specified when the Bourne shell is started, the shell runs the script file identified by the *File* parameter, including any parameters specified. The script file specified must have read permission. Any **setuid** and **setgid** settings for script files are ignored. The shell then reads the commands.

Note: You should not specify a script file if using either the **-c** or **-s** flag.

When started with the **Rsh** command, the shell enforces restrictions after interpreting the **.profile** and **/etc/environment** files. Therefore, the writer of the **.profile** file has complete control over user actions by performing setup actions and leaving the user in an appropriate directory (probably not the login directory). An administrator can create a directory of commands in the **/usr/rbin** directory that the **Rsh** command can use by changing the **PATH** variable to contain the directory. If started with the **bsh -r** command, the shell applies restrictions when interpreting the **.profile** files.

When called with the name **Rsh**, the restricted shell reads the user's **.profile** file (**\$HOME/.profile**). It acts as the regular Bourne shell while doing this, except that an interrupt causes an immediate exit instead of a return to command level.

- "Bourne Shell Related Information" on page 212

Bourne Shell Commands

When you issue a command in the Bourne shell, it first evaluates the command and makes all indicated substitutions. It then runs the command provided that:

- The command name is a Bourne shell special built-in command
OR
- The command name matches the name of a defined function. If this is the case, the shell sets the positional parameters to the parameters of the function.

If the command name matches neither a built-in command nor the name of a defined function and the command names an executable file that is a compiled (binary) program, the shell (as *parent*) spawns a new (*child*) process that immediately runs the program. If the file is marked executable but is not a compiled program, the shell assumes that it is a shell procedure. In this case, the shell spawns another instance of itself (a *subshell*), to read the file and execute the commands included in it. The shell also runs a parenthesized command in a subshell. To the end user, a compiled program is run in exactly the same way as a shell procedure. The shell normally searches for commands in file system directories, in this order:

1. **/usr/bin**
2. **/etc**
3. **/usr/sbin**
4. **/usr/ucb**
5. **\$HOME/bin**
6. **/usr/bin/X11**
7. **/sbin**
8. Current directory

The shell searches each directory, in turn, continuing with the next directory if it fails to find the command.

Note: The order in which the shell searches directories is determined by the **PATH** variable. You can change the particular sequence of directories searched by resetting the **PATH** variable.

If you give a specific path name when you run a command (for example, `/usr/bin/sort`), the shell does not search any directories other than the one you specify. If the command name contains a slash (/), the shell does not use the search path.

You can give a full path name that begins with the root directory (such as `/usr/bin/sort`). You can also specify a path name relative to the current directory. If you specify, for example:

```
bin/myfile
```

the shell looks in the current directory for a directory named `bin` and in that directory for the file `myfile`.

Note: The restricted shell does not run commands containing a / (slash).

The shell remembers the location in the search path of each executed command (to avoid unnecessary **exec** commands later). If it finds the command in a relative directory (one whose name does not begin

with /), the shell must redetermine the command's location whenever the current directory changes. The shell forgets all remembered locations each time you change the **PATH** variable or run the **hash -r** command.

This section discusses:

- “Quoting Characters”
- “Signal Handling”
- “Bourne Shell Built-In Commands” on page 201
- “Command Substitution in the Bourne Shell” on page 204
- “Bourne Shell Related Information” on page 212

Quoting Characters

Many characters have a special meaning to the shell. Sometimes you want to conceal that meaning. Single (') and double (") quotation marks surrounding a string, or a backslash (\) before a single character allow you to conceal the character's meaning.

All characters, except the enclosing single quotation marks, are taken literally, with any special meaning removed. Thus, the command:

```
stuff='echo $? $*; ls * | wc'
```

assigns the literal string `echo $? $*; ls * | wc` to the variable `stuff`. The shell does not execute the **echo**, **ls**, and **wc** commands or expand the `?` and `$*` variables and the `*` (asterisk) special character.

Within double quotation marks, the special meaning of the `$` (dollar sign), `'` (backquote), and `"` (double quotation) characters remains in effect, while all other characters are taken literally. Thus, within double quotation marks, command and variable substitution takes place. In addition, the quotation marks do not affect the commands within a command substitution that is part of the quoted string, so characters there retain their special meanings.

Consider the following sequence:

```
ls *
file1 file2 file3
message="This directory contains 'ls * ' "
echo $message
This directory contains file1 file2 file3
```

This shows that the `*` (asterisk) special character inside the command substitution was expanded.

To hide the special meaning of the `$` (dollar sign), `'` (backquote), and `"` (double quotation) characters within double quotation marks, precede these characters with a `\` (backslash). When you do not use double quotation marks, preceding a character with a backslash is equivalent to placing it within single quotation marks. Hence, a backslash immediately preceding a new-line character (that is, a backslash at the end of the line) hides the new-line character and allows you to continue the command line on the next physical line.

Signal Handling

The shell ignores **INTERRUPT** and **QUIT** signals for an invoked command if the command is terminated with an `&` (ampersand); that is, if it is running in the background. Otherwise, signals have the values inherited by the shell from its parent, with the exception of the **SEGMENTATION VIOLATION** signal. For more information, refer to the Bourne shell built-in **trap** command.

Bourne Shell Compound Commands

A compound command is one of the following:

- Pipeline (one or more simple commands separated by the | (pipe) symbol)
- List of simple commands
- Command beginning with a reserved word
- Command beginning with the control operator ((left parenthesis).

Unless otherwise stated, the value returned by a compound command is that of the last simple command executed.

Reserved Words

The following reserved words are recognized only when they appear without quotation marks as the first word of a command:

for	do	done
case	esac	
if	then	fi
elif	else	
while	until	
{	}	
()	

for *Identifier* [**in** *Word* . . .] **do** *List* **done** Sets the *Identifier* parameter to the word or words specified by the *Word* parameter (one at a time) and runs the commands specified in the *List* parameter. If you omit *Word* . . . , then the **for** command runs the *List* parameter for each positional parameter that is set, and processing ends when all positional parameters have been used.

case *Word* **in** *Pattern* [*Pattern* . . .) *List*; [*Pattern* [*Pattern* . . .) *List*;] . . . **esac** Runs the commands specified in the *List* parameter that are associated with the first *Pattern* parameter that matches the value of the *Word* parameter. Uses the same character-matching notation in patterns that are used for file name substitution, except that a / (slash), leading . (dot), or a dot immediately following a slash do not need to match explicitly.

if *List* **then** *List* [**elif** *List* **then** *List*] . . . [**else** *List*] **fi** Runs the commands specified in the *List* parameter following the **if** command. If the command returns a zero exit value, the shell runs the *List* parameter following the first **then** command. Otherwise, it runs the *List* parameter following the **elif** command (if it exists). If this exit value is zero, the shell runs the *List* parameter following the next **then** command. If the command returns a non-zero exit value, the shell runs the *List* parameter following the **else** command (if it exists). If no **else** *List* or **then** *List* is performed, the **if** command returns a zero exit value.

while *List* **do** *List* **done** Runs the commands specified in the *List* parameter following the **while** command. If the exit value of the last command in the **while** *List* is zero, the shell runs the *List* parameter following the **do** command. It continues looping through the lists until the exit value of the last command in the **while** *List* is non-zero. If no commands in the **do** *List* are performed, the **while** command returns a zero exit value.

until *List* **do** *List* **done** Runs the commands specified in the *List* parameter following the **until** command. If the exit value of the last command in the **until** *List* is non-zero, runs the *List* following the **do** command. Continues looping through the lists until the exit value of the last command in the **until** *List* is zero. If no commands in the **do** *List* are performed, the **until** command returns a zero exit value.

(*List*) Runs the commands in the *List* parameter in a subshell.

{ *List*; } Runs the commands in the *List* parameter in the current shell process and does not start a subshell.

Name () { *List* } Defines a function that is referenced by the *Name* parameter. The body of the function is the list of commands between the braces specified by the *List* parameter.

Bourne Shell Built-In Commands

Special commands are built in to the Bourne shell and run in the shell process. Unless otherwise indicated, output is written to file descriptor 1 (stdout) and the exit status is 0 (zero) if the command does not contain any syntax errors. Input and output redirection is permitted.

Refer to the “List of Bourne Shell Built-in Commands” on page 211 for an alphabetical listing of these commands.

The following special commands are treated somewhat differently from other special built-in commands:

<code>:</code> (colon)	<code>exec</code>	<code>shift</code>
<code>.</code> (dot)	<code>exit</code>	<code>times</code>
<code>break</code>	<code>export</code>	<code>trap</code>
<code>continue</code>	<code>readonly</code>	<code>wait</code>
<code>eval</code>	<code>return</code>	

The Bourne shell processes these commands as follows:

- Keyword parameter assignment lists preceding the command remain in effect when the command completes.
- I/O redirections are processed after parameter assignments.
- Errors in a shell script cause the script to stop processing.

Special Command Descriptions

The Bourne shell provides the following special built-in commands:

Built-In Commands

<code>:</code>	Returns a zero exit value.
<code>. <i>File</i></code>	Reads and runs commands from the <i>File</i> parameter, and returns. Does not start a subshell. The shell uses the search path specified by the PATH variable to find the directory containing the specified file.
<code>break [<i>n</i>]</code>	Exits from the enclosing for , while , or until command loops, if any. If you specify the <i>n</i> variable, the break command breaks the number of levels specified by the <i>n</i> variable.
<code>continue [<i>n</i>]</code>	Resumes the next iteration of the enclosing for , while , or until command loops. If you specify the <i>n</i> variable, the command resumes at the <i>n</i> th enclosing loop.
<code>cd <i>Directory</i>]</code>	Changes the current directory to <i>Directory</i> . If you do not specify <i>Directory</i> , the value of the HOME shell variable is used. The CDPATH shell variable defines the search path for <i>Directory</i> . CDPATH is a colon-separated list of alternative directory names. A null path name specifies the current directory (which is the default path). This null path name appears immediately after the equal sign in the assignment or between the colon delimiters anywhere else in the path list. If <i>Directory</i> begins with a / (slash), the shell does not use the search path. Otherwise, the shell searches each directory in the CDPATH shell variable. Note: The restricted shell cannot run the cd shell command.
<code>echo <i>String</i> . . .]</code>	Writes character strings to standard output. Refer to the echo command for usage and parameter information. The -n flag is not supported.
<code>eval [<i>Argument</i> . . .]</code>	Reads arguments as input to the shell and runs the resulting command or commands.
<code>exec [<i>Argument</i> . . .]</code>	Runs the command specified by the <i>Argument</i> parameter in place of this shell without creating a new process. Input and output arguments can appear and, if no other arguments appear, cause the shell input or output to be modified. This is not recommended for your login shell.
<code>exit [<i>n</i>]</code>	Causes a shell to exit with the exit value specified by the <i>n</i> parameter. If you omit this parameter, the exit value is that of the last command executed (the Ctrl-D key sequence also causes a shell to exit). The value of the <i>n</i> parameter can be from 0 to 255, inclusive.

Built-In Commands

- export** [*Name* . . .] Marks the specified names for automatic export to the environments of subsequently executed commands. If you do not specify the *Name* parameter, the **export** command displays a list of all names that are exported in this shell. You cannot export function names.
- hash** [-r] [*Command* . . .] Finds and remembers the location in the search path of each *Command* specified. The -r flag causes the shell to forget all locations. If you do not specify the flag or any commands, the shell displays information about the remembered commands in the following format:
- ```
Hits Cost Command
```
- Hits indicates the number of times a command has been run by the shell process. Cost is a measure of the work required to locate a command in the search path. Command shows the path names of each specified command. Certain situations require that the stored location of a command be recalculated; for example, the location of a relative path name when the current directory changes. Commands for which that might be done are indicated by an \* (asterisk) next to the Hits information. Cost is incremented when the recalculation is done.
- pwd** Displays the current directory. Refer to the **pwd** command for a discussion of command options.
- read** [ *Name* . . . ] Reads one line from standard input. Assigns the first word in the line to the first *Name* parameter, the second word to the second *Name* parameter, and so on, with leftover words assigned to the last *Name* parameter. This command returns a value of 0 unless it encounters an end-of-file character.
- readonly** [ *Name* . . . ] Marks the name specified by the *Name* parameter as read-only. The value of the name cannot be reset. If you do not specify any *Name*, the **readonly** command displays a list of all read-only names.
- return** [ *n* ] Causes a function to exit with a return value of *n*. If you do not specify the *n* variable, the function returns the status of the last command performed in that function. This command is valid only when run within a shell function.

## Built-In Commands

**set** [ *Flag* [ *Argument*  
] . . . ]

Sets one or more of the following flags:

- a** Marks for export all variables to which an assignment is performed. If the assignment precedes a command name, the export attribute is effective only for that command execution environment, except when the assignment precedes one of the special built-in commands. In this case, the export attribute persists after the built-in command has completed. If the assignment does not precede a command name, or if the assignment is a result of the operation of the **getopts** or **read** commands, the export attribute persists until the variable is unset.
- e** Exits immediately if all of the following conditions exist for a command:
  - It exits with a return value greater than 0 (zero).
  - It is not part of the compound list of a **while**, **until**, or **if** command.
  - It is not being tested using AND or OR lists.
  - It is not a pipeline preceded by the ! (exclamation point) reserved word.
- f** Disables file name substitution.
- h** Locates and remembers the commands called within functions as the functions are defined. (Normally these commands are located when the function is performed; see the **hash** command.)
- k** Places all keyword parameters in the environment for a command, not just those preceding the command name.
- n** Reads commands but does not run them. The **-n** flag can be used to check for shell script syntax errors.
- t** Exits after reading and executing one command.
- u** Treats an unset variable as an error and immediately exits when performing variable substitution. An interactive shell does not exit.
- v** Displays shell input lines as they are read.
- x** Displays commands and their arguments before they are run.
- Does not change any of the flags. This is useful in setting the **\$1** positional parameter to a string beginning with a hyphen (-).

Using a plus sign (+) rather than a hyphen (-) unsets flags. You can also specify these flags on the shell command line. The **\$-** special variable contains the current set of flags.

Any *Argument* to the **set** command becomes a positional parameter and is assigned, in order, to **\$1**, **\$2**, and so on. If you do not specify a *flag* or *Argument*, the **set** command displays all the names and values of the current shell variables.

**shift** [*n*]

Shifts command line arguments to the left; that is, reassigns the value of the positional parameters by discarding the current value of **\$1** and assigning the value of **\$2** to **\$1**, of **\$3** to **\$2**, and so on. If there are more than 9 command line arguments, the 10th is assigned to **\$9** and any that remain are still unassigned (until after another **shift**). If there are 9 or fewer arguments, the **shift** command unsets the highest-numbered positional parameter that has a value.

The **\$0** positional parameter is never shifted. The **shift** *n* command is a shorthand notation specifying *n* number of consecutive shifts. The default value of the *n* parameter is 1.

**test** *Expression* | [  
*Expression* ]

Evaluates conditional expressions. Refer to the **test** command for a discussion of command flags and parameters. The **-h** flag is not supported by the built-in test command in **bash**.

**times**

Displays the accumulated user and system times for processes run from the shell.

## Built-In Commands

**trap** [ *Command* ] [ *n* ] . . .

Runs the command specified by the *Command* parameter when the shell receives the signal or signals specified by the *n* parameter. The **trap** commands are run in order of signal number. Any attempt to set a trap on a signal that was ignored on entry to the current shell is ineffective.

**Note:** The shell scans the *Command* parameter once when the trap is set and again when the trap is taken.

If you do not specify a command, then all traps specified by the *n* parameter are reset to their current values. If you specify a null string, this signal is ignored by the shell and by the commands it invokes. If the *n* parameter is zero (0), the specified command is run when you exit from the shell. If you do not specify either a command or a signal, the **trap** command displays a list of commands associated with each signal number.

**type** [*Name* . . . ]

For each *Name* specified, indicates how the shell would interpret it as a command name.

**ulimit** [-HS] [ -c | -d | -f | -m | -s | -t ] [*limit*]

Displays or adjusts allocated shell resources. There are two modes for displaying the shell resource settings, which can either be displayed individually or as a group. The default mode is to display resources set to the soft setting, or the lower bound, as a group.

The setting of shell resources depends on the effective user ID of the current shell. The hard level of a resource can be set only if the effective user ID of the current shell is root. You will get an error if you are not root and you are attempting to set the hard level of a resource. By default, the root user sets both the hard and soft limits of a particular resource. The root user should therefore be careful in using the **-S**, **-H**, or default flag usage of limit settings. Unless you are a root user, you can set only the soft limit of a resource. Once a limit has been decreased by a non-root user, it cannot be increased, even back to the original system limit.

To set a resource limit, select the appropriate flag and the limit value of the new resource, which should be an integer. You can set only one resource limit at a time. If more than one resource flag is specified, you receive undefined results. By default, **ulimit** with only a new value on the command line sets the file size of the shell. Use of the **-f** flag is optional.

You can specify the following **ulimit** command flags:

- c** Sets or displays core segment for shell.
- d** Sets or displays data segment for shell.
- f** Sets or displays file size for shell.
- H** Sets or displays hard resource limit (root user only)
- m** Sets or displays memory for shell.
- s** Sets or displays stack segment for shell.
- S** Sets or displays soft resource limit.
- t** Sets or displays CPU time maximum for shell.

**umask** [*nnn*]

Determines file permissions. This value, along with the permissions of the creating process, determines a file's permissions when the file is created. The default is 022. When no value is entered, umask displays the current value.

**unset** [*Name* . . . ]

Removes the corresponding variable or function for each name specified by the *Name* parameter. The **PATH**, **PS1**, **PS2**, **MAILCHECK**, and **IFS** shell variables cannot be unset.

**wait** [*n*]

Waits for the child process whose process number is specified by the *n* parameter to exit and then returns the exit status of that process. If you do not specify the *n* parameter, the shell waits for all currently active child processes and the return value is 0.

## Command Substitution in the Bourne Shell

Command substitution allows you to capture the output of any command as an argument to another command. When you place a command line within backquotes ("`"), the shell first runs the command or

commands, and then replaces the entire expression, including the backquotes, with the output. This feature is often used to give values to shell variables. For example, the statement:

```
today='date'
```

assigns the string representing the current date to the `today` variable. The following assignment saves, in the `files` variable, the number of files in the current directory:

```
files='ls | wc -l'
```

You can perform command substitution on any command that writes to standard output.

To nest command substitutions, precede each of the nested backquotes with a backslash (`\`), as in:

```
logmsg='echo Your login directory is `pwd`'
```

You can also give values to shell variables indirectly by using the **read** special command. This command takes a line from standard input (usually your keyboard) and assigns consecutive words on that line to any variables named. For example:

```
read first init last
```

takes an input line of the form:

```
J. Q. Public
```

and has the same effect as if you had typed:

```
first=J. init=Q. last=Public
```

The **read** special command assigns any excess words to the last variable.

---

## Variable and File Name Substitution in the Bourne Shell

The Bourne shell permits you to do variable and file name substitutions.

The following sections offer information about creating and substituting variables in the Bourne shell:

- “Variable Substitution in the Bourne Shell”
- “User-Defined Variables”
- “Conditional Substitution” on page 209
- “Positional Parameters” on page 210
- “File Name Substitution in the Bourne Shell” on page 210
- “Character Classes” on page 210

## Variable Substitution in the Bourne Shell

The Bourne shell has several mechanisms for creating variables (assigning a string value to a name). Certain variables, positional parameters and keyword parameters, are normally set only on a command line. Other variables are simply names to which you or the shell can assign string values.

## User-Defined Variables

The shell recognizes alphanumeric variables to which string values can be assigned. To assign a string value to a name, type:

```
Name=String
```

Press Enter.

A name is a sequence of letters, digits, and underscores that begins with an underscore or a letter. To use the value that you have assigned to a variable, add a dollar sign (\$) to the beginning of its name. Thus, the *\$Name* variable yields the value specified by the *String* variable. Note that no spaces are on either side of the equal sign (=) in an assignment statement. (Positional parameters cannot appear in an assignment statement. They can be set only as described in “Positional Parameters” on page 210.) You can put more than one assignment on a command line, but remember that the shell performs the assignments from right to left.

If you enclose the *String* variable with double or single quotation marks (" or '), the shell does not treat blanks, tabs, semicolons, and new-line characters within the string as word delimiters, but imbeds them literally in the string.

If you enclose the *String* variable with double quotation marks ("), the shell still recognizes variable names in the string and performs variable substitution; that is, it replaces references to positional parameters and other variable names that are prefaced by dollar sign (\$) with their corresponding values, if any. The shell also performs command substitution within strings that are enclosed in double quotation marks.

If you enclose the *String* variable with single quotation marks ('), the shell does not substitute variables or commands within the string. The following sequence illustrates this difference:

```
You: num=875
 number1="Add $num"
 number2='Add $num'
 echo $number1
System: Add 875
You: echo $number2
System: Add $num
```

The shell does not reinterpret blanks in assignments after variable substitution. Thus, the following assignments result in *\$first* and *\$second* having the same value:

```
first='a string with embedded blanks'
second=$first
```

When you reference a variable, you can enclose the variable name (or the digit designating a positional parameter) in { } to delimit the variable name from any string following. In particular, if the character immediately following the name is a letter, digit, or underscore, and the variable is not a positional parameter, then the braces are required:

```
You: a='This is a'
 echo "${a}n example"
System: This is an example
You: echo "$a test"
System: This is a test
```

Refer to “Conditional Substitution” on page 209 for a different use of braces in variable substitutions.

## Variables Used by the Shell

The shell uses the following variables. Although the shell sets some of them, you can set or reset all of them:

|               |                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>CDPATH</b> | Specifies the search path for the <b>cd</b> (change directory) command.                                                                                                                                                                                                                                                                                                                                                                 |
| <b>HOME</b>   | Indicates the name of your <i>login directory</i> , the directory that becomes the current directory upon completion of a login. The <b>login</b> program initializes this variable. The <b>cd</b> command uses the value of the <b>\$HOME</b> variable as its default value. Using this variable rather than an explicit path name in a shell procedure allows the procedure to be run from a different directory without alterations. |
| <b>IFS</b>    | The characters that are internal field separators (the characters that the shell uses during blank interpretation; see “Blank Interpretation” on page 208 ). The shell initially sets the <b>IFS</b> variable to include the blank, tab, and new-line characters.                                                                                                                                                                       |

|                    |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|--------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>LANG</b>        | Determines the locale to use for the locale categories when both the <b>LC_ALL</b> variable and the corresponding environment variable (beginning with <b>LC_</b> ) do not specify a locale. For more information about locales, see "Locale Overview" in <i>AIX 5L Version 5.1 System Management Concepts: Operating System and Devices</i> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| <b>LC_ALL</b>      | Determines the locale to be used to override any values for locale categories specified by the settings of the <b>LANG</b> environment variable or any environment variables beginning with <b>LC_</b> . For more information about locales and the <b>LANG</b> environment variable, see "Locale Overview" in <i>AIX 5L Version 5.1 System Management Concepts: Operating System and Devices</i> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| <b>LC_COLLATE</b>  | Defines the collating sequence to use when sorting names and when character ranges occur in patterns. For information about locales and the <b>LANG</b> environment variable, see "Locale Overview" in <i>AIX 5L Version 5.1 System Management Concepts: Operating System and Devices</i> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| <b>LC_CTYPE</b>    | Determines the locale for the interpretation of sequences of bytes of text data as characters (that is, single- versus multibyte characters in arguments and input files), which characters are defined as letters ( <b>alpha</b> character class), and the behavior of character classes within pattern matching. For more information about locales, see "Locale Overview" in <i>AIX 5L Version 5.1 System Management Concepts: Operating System and Devices</i> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| <b>LC_MESSAGES</b> | Determines the language in which messages should be written. For information about locales and the <b>LANG</b> environment variable, see "Locale Overview" in <i>AIX 5L Version 5.1 System Management Concepts: Operating System and Devices</i> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| <b>LIBPATH</b>     | Specifies the search path for shared libraries.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| <b>LOGNAME</b>     | Specifies your login name, marked <b>readonly</b> in the <b>/etc/profile</b> file.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| <b>MAIL</b>        | Indicates the path name of the file used by the mail system to detect the arrival of new mail. If this variable is set, the shell periodically checks the modification time of this file and displays the value of <b>\$MAILMSG</b> if the time changes and the length of the file is greater than 0. Set the <b>MAIL</b> variable in the <b>.profile</b> file. The value normally assigned to it by users of the <b>mail</b> command is <b>/usr/spool/mail/\$LOGNAME</b> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| <b>MAILCHECK</b>   | The number of seconds that the shell lets elapse before checking again for the arrival of mail in the files specified by the <b>MAILPATH</b> or <b>MAIL</b> variables. The default value is 600 seconds (10 minutes). If you set the <b>MAILCHECK</b> variable to 0, the shell checks before each prompt.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| <b>MAILMSG</b>     | The mail notification message. If you explicitly set the <b>MAILMSG</b> variable to a null string ( <b>MAILMSG=""</b> ), no message is displayed.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| <b>MAILPATH</b>    | A list of file names separated by colons. If this variable is set, the shell informs you of the arrival of mail in any of the files specified in the list. You can follow each file name by a <b>%</b> and a message to be displayed when mail arrives. Otherwise, the shell uses the value of the <b>MAILMSG</b> variable or, by default, the message <b>[YOU HAVE NEW MAIL]</b> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|                    | <b>Note:</b> When the <b>MAILPATH</b> variable is set, these files are checked instead of the file set by the <b>MAIL</b> variable. To check the files set by the <b>MAILPATH</b> variable and the file set by the <b>MAIL</b> variable, specify the <b>MAIL</b> file in your list of <b>MAILPATH</b> files.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| <b>PATH</b>        | The search path for commands, which is an ordered list of directory path names separated by colons. The shell searches these directories in the specified order when it looks for commands. A null string anywhere in the list represents the current directory.<br><br>The <b>PATH</b> variable is normally initialized in the <b>/etc/environment</b> file, usually to <b>/usr/bin:/etc:/usr/sbin:/usr/ucb:/usr/bin/X11:/sbin</b> . You can reset this variable to suit your own needs. The <b>PATH</b> variable provided in your <b>.profile</b> file also includes <b>\$HOME/bin</b> and your current directory.<br><br>If you have a project-specific directory of commands, for example, <b>/project/bin</b> , that you want searched before the standard system directories, set your <b>PATH</b> variable as follows:<br><pre>PATH=/project/bin:\$PATH</pre><br>The best place to set your <b>PATH</b> variable to a value other than the default value is in your <b>\$HOME/.profile</b> file. You cannot reset the <b>PATH</b> variable if you are executing commands under the restricted shell. |



|                |                                                                                                                                                                                                                                                                                                                                                                                                   |
|----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>PS1</b>     | The string to be used as the primary system prompt. An interactive shell displays this prompt string when it expects input. The default value of the <b>PS1</b> variable is \$ followed by a blank space, for nonroot users.                                                                                                                                                                      |
| <b>PS2</b>     | The value of the secondary prompt string. If the shell expects more input when it encounters a new-line character in its input, it prompts with the value of the <b>PS2</b> variable. The default value of the <b>PS2</b> variable is > , followed by a blank space.                                                                                                                              |
| <b>SHACCT</b>  | The name of a file that you own. If this variable is set, the shell writes an accounting record in the file for each shell script executed. You can use accounting programs such as <b>acctcom</b> and <b>acctcms</b> to analyze the data collected.                                                                                                                                              |
| <b>SHELL</b>   | The path name of the shell, which is kept in the environment. This variable should be set and exported by the <b>\$HOME/.profile</b> file of each restricted login.                                                                                                                                                                                                                               |
| <b>TIMEOUT</b> | The number of minutes a shell remains inactive before it exits. If this variable is set to a value greater than zero (0), the shell exits if a command is not entered within the prescribed number of seconds after issuing the <b>PS1</b> prompt. (Note that the shell can be compiled with a maximum boundary that cannot be exceeded for this value.) A value of zero indicates no time limit. |

## Predefined Special Variables

Several variables have special meanings. The following variables are set only by the shell.

- \$@** Expands the positional parameters, beginning with **\$1**. Each parameter is separated by a space.
- If you place " " around **\$@**, the shell considers each positional parameter a separate string. If no positional parameters exist, the Bourne shell expands the statement to an unquoted null string.
- \$\*** Expands the positional parameters, beginning with **\$1**. The shell separates each parameter with the first character of the **IFS** variable value.
- If you place " " around **\$\***, the shell includes the positional parameter values, in double quotation marks. Each value is separated by the first character of the **IFS** variable.
- \$#** Specifies the number of positional parameters passed to the shell, not counting the name of the shell procedure itself. The  **\$#** variable thus yields the number of the highest-numbered positional parameter that is set. One of the primary uses of this variable is to check for the presence of the required number of arguments. Only positional parameters **\$0** through **\$9** are accessible through the shell. See "Positional Parameters" on page 210" for more information.
- \$?** Specifies the exit value of the last command executed. Its value is a decimal string. Most commands return a value of 0 to indicate successful completion. The shell itself returns the current value of the  **\$?** variable as its exit value.
- \$\$** Identifies the process number of the current process. Because process numbers are unique among all existing processes, this string is often used to generate unique names for temporary files.
- The following example illustrates the recommended practice of creating temporary files in a directory used only for that purpose:
- ```
temp=/tmp/$$
ls >$temp
.
.
.
rm $temp
```
- \$!** Specifies the process number of the last process run in the background using the **&** terminator.
- \$-** A string consisting of the names of the execution flags currently set in the shell.

Blank Interpretation

After the shell performs variable and command substitution, it scans the results for internal field separators (those defined in the **IFS** shell variable). The shell splits the line into distinct words at each place it finds one or more of these characters separating each distinct word with a single space. It then retains explicit null arguments (" " or ") and discards implicit null arguments (those resulting from parameters that have no values).

Conditional Substitution

Normally, the shell replaces the expression `$Variable` with the string value assigned to the *Variable* variable, if there is one. However, there is a special notation that allows *conditional substitution*, depending on whether the variable is set or not null, or both. By definition, a variable is set if it has ever been assigned a value. The value of a variable can be the null string, which you can assign to a variable in any one of the following ways:

```
A=
```

```
bcd=""
```

```
Efg=""           Assigns the null string to the A, bcd, and Efg.
```

```
set "" ""       Sets the first and second positional parameters to the null string and unsets all other positional parameters.
```

The following is a list of the available expressions you can use to perform conditional substitution:

<code>\${Variable-String}</code>	If the variable is set, substitute the <i>Variable</i> value in place of this expression. Otherwise, replace this expression with the <i>String</i> value.
<code>\${Variable:-String}</code>	If the variable is set and not null, substitute the <i>Variable</i> value in place of this expression. Otherwise, replace this expression with the <i>String</i> value.
<code>\${Variable=String}</code>	If the variable is set, substitute the <i>Variable</i> value in place of this expression. Otherwise, set the <i>Variable</i> value to the <i>String</i> value and then substitute the <i>Variable</i> value in place of this expression. You cannot assign values to positional parameters in this fashion.
<code>\${Variable:=String}</code>	If the variable is set and not null, substitute the <i>Variable</i> value in place of this expression. Otherwise, set the <i>Variable</i> value to the <i>String</i> value and then substitute the <i>Variable</i> value in place of this expression. You cannot assign values to positional parameters in this fashion.
<code>\${Variable?String}</code>	If the variable is set, substitute the <i>Variable</i> value in place of this expression. Otherwise, display a message of the form: Variable: String and exit from the current shell (unless the shell is the login shell). If you do not specify a value for the <i>String</i> variable, the shell displays the following message: Variable: parameter null or not set
<code>\${Variable:?String}</code>	If the variable is set and not null, substitute the <i>Variable</i> value in place of this expression. Otherwise, display a message of the form: Variable: String and exit from the current shell (unless the shell is the login shell). If you do not specify the <i>String</i> value, the shell displays the following message: Variable: parameter null or not set
<code>\${Variable+String}</code>	If the variable is set, substitute the <i>String</i> value in place of this expression. Otherwise, substitute the null string.
<code>\${Variable:+String}</code>	If the variable is set and not null, substitute the <i>String</i> value in place of this expression. Otherwise, substitute the null string.

In conditional substitution, the shell does not evaluate the *String* variable until the shell uses this variable as a substituted string. Thus, in the following example, the shell executes the **pwd** command only if *d* is not set or is null:

```
echo ${d:-'pwd'}
```

Positional Parameters

When you run a shell procedure, the shell implicitly creates positional parameters that reference each word on the command line by its position on the command line. The word in position 0 (the procedure name) is called **\$0**, the next word (the first parameter) is called **\$1**, and so on, up to **\$9**. To refer to command line parameters numbered higher than 9, use the built-in **shift** command.

You can reset the values of the positional parameters explicitly by using the built-in **set** command.

Note: When an argument for a position is not specified, its positional parameter is set to null. Positional parameters are global and can be passed to nested shell procedures.

File Name Substitution in the Bourne Shell

Command parameters are often file names. You can automatically produce a list of file names as parameters on a command line. To do this, specify a character that the shell recognizes as a pattern-matching character. When a command includes such a character, the shell replaces it with the file names in a directory.

Note: The Bourne shell does not support file name expansion based on equivalence classification of characters.

Most characters in such a pattern match themselves, but you can also use some special pattern-matching characters in your pattern. These special characters are:

*	Matches any string, including the null string.
?	Matches any one character.
[. . .]	Matches any one of the characters enclosed in square brackets.
[! . . .]	Matches any character within square brackets <i>other than</i> one of the characters that follow the exclamation mark.

Within square brackets, a pair of characters separated by a - specifies the set of all characters lexically within the inclusive range of that pair, according to the binary ordering of character values.

Pattern matching has some restrictions. If the first character of a file name is a dot (.), it can be matched only by a pattern that also begins with a dot. For example, ***** matches the file names `myfile` and `yourfile` but not the file names `.myfile` and `.yourfile`. To match these files, use a pattern such as the following:

```
.*file
```

If a pattern does not match any file names, then the pattern itself is returned as the result of the attempted match.

File and directory names should not contain the characters *****, **?**, **[**, or **]** because they can cause infinite recursion (that is, infinite loops) during pattern-matching attempts.

Character Classes

You can also use character classes to match file names:

```
[[:charclass:]]
```

This format instructs the system to match any single character belonging to the specified class. The defined classes correspond to **c_{type}** subroutines. They are:

Character Class	Definition
alnum	Alphanumeric characters

Character Class	Definition
alpha	Uppercase and lowercase letters
blank	Space or horizontal tab
cntrl	Control characters
digit	Digits
graph	Graphic characters
lower	Lowercase letters
print	Printable characters
punct	Punctuation characters
space	Space, horizontal tab, carriage return, new-line, vertical tab or form-feed character
upper	Uppercase characters
xdigit	Hexadecimal digits.

Input and Output Redirection in the Bourne Shell

In general, most commands do not know or care whether their input or output is associated with the keyboard, the display screen, or a file. Thus, a command can be used conveniently either at the keyboard or in a pipeline.

The following redirection options can appear anywhere in a simple command. They can also precede or follow a command, but are not passed to the command.

<code><File</code>	Uses the specified file as standard input.
<code>>File</code>	Uses the specified file as standard output. Creates the file if it does not exist; otherwise, truncates it to zero length.
<code>>>File</code>	Uses the specified file as standard output. Creates the file if it does not exist; otherwise, adds the output to the end of the file.
<code><<[-]eofstr</code>	Reads as standard input all lines from the <i>eofstr</i> variable up to a line containing only <i>eofstr</i> or up to an end-of-file character. If any character in the <i>eofstr</i> variable is quoted, the shell does not expand or interpret any characters in the input lines. Otherwise, it performs variable and command substitution and ignores a quoted new-line character (\new-line). Use a <code>\</code> to quote characters within the <i>eofstr</i> variable or within the input lines.
	If you add a <code>-</code> to the <code><<</code> redirection option, then all leading tabs are stripped from the <i>eofstr</i> variable and from the input lines.
<code><&Digit</code>	Associates standard input with the file descriptor specified by the <i>Digit</i> variable.
<code>>&Digit</code>	Associates standard output with the file descriptor specified by the <i>Digit</i> variable.
<code><&-</code>	Closes standard input.
<code>>&-</code>	Closes standard output.

Note: The restricted shell does not allow output redirection.

For more information about redirection, see “Chapter 4. Input and Output Redirection” on page 41 and “Bourne Shell Related Information” on page 212.

List of Bourne Shell Built-in Commands

<code>:</code>	Returns a zero exit value
<code>.</code>	Reads and executes commands from a file parameter and then returns.
break	Exists from the enclosing for , while , or until command loops, if any.
cd	Changes the current directory to the specified directory.
continue	Resumes the next iteration of the enclosing for , while , or until command loops.
echo	Writes character strings to standard output.
eval	Reads the arguments as input to the shell and executes the resulting command or commands.

exec	Executes the command specified by the <i>Argument</i> parameter, instead of this shell, without creating a new process.
exit	Exits the shell whose exit status is specified by the <i>n</i> parameter.
export	Marks names for automatic export to the environment of subsequently executed commands.
hash	Finds and remembers the location in the search path of specified commands.
pwd	Displays the current directory.
read	Reads one line from standard input.
readonly	Marks name specified by <i>Name</i> parameter as read-only.
return	Causes a function to exit with a specified return value.
set	Controls the display of various parameters to standard output.
shift	Shifts command-line arguments to the left.
test	Evaluates conditional expressions.
times	Displays the accumulated user and system times for processes run from the shell.
trap	Runs a specified command when the shell receives a specified signal or signals.
type	Interprets how the shell would interpret a specified name as a command name.
ulimit	Displays or adjusts allocated shell resources.
umask	Determines file permissions.
unset	Removes the variable or function corresponding to a specified name.
wait	Waits for the specified child process to end and reports its termination status.

See “Bourne Shell Built-In Commands” on page 201 for more information.

Bourne Shell Related Information

“Chapter 11. Shells” on page 149

“Bourne Shell” on page 196

“Restricted Shell” on page 197

“Bourne Shell Commands” on page 198

“Variable and File Name Substitution in the Bourne Shell” on page 205

“Input and Output Redirection in the Bourne Shell” on page 211

The **bash** or **Rsh** command, **login** command.

The Bourne shell **read** special command.

The **setuid** subroutine, **setgid** subroutine.

The **null** special file.

The **environment** file, **profile** file format.

“Korn Shell or POSIX Shell Commands” on page 172

“C Shell”

C Shell

The C shell is an interactive command interpreter and a command programming language. It uses syntax that is similar to the C programming language. The **cs** command starts the C shell.

When you log in, it first searches the systemwide setup file **/etc/csh.cshrc**. If it is there, the C shell executes the commands stored in that file. Next, the C shell executes the systemwide setup file **/etc/csh.login** if it is available. Then, it searches your home directory for the **.cshrc** and **.login** files. If they exist, they contain any customized user information pertinent to running the C shell. All variables set in the **/etc/csh.cshrc** and **/etc/csh.login** files might be overridden by your **.cshrc** and **.login** files in your **\$HOME** directory. Only the root user can modify the **/etc/csh.cshrc** and **/etc/csh.login** files.

The **/etc/csh.login** and **\$HOME/.login** files are executed only once at login time. They are generally used to hold environment variable definitions, commands that you want executed once at login, or commands that set up terminal characteristics.

The **/etc/csh.cshrc** and **\$HOME/.cshrc** files are executed at login time, and every time the **csh** command or a C shell script is invoked. They are generally used to define C shell characteristics like aliases and C shell variables (for example, history, noclobber, or ignoreeof). It is recommended that you only use the “C Shell Built-In Commands” on page 214 in the **/etc/csh.cshrc** and **\$HOME/.cshrc** files because using other commands increases the startup time for shell scripts.

This section discusses the following:

- “C Shell Limitations”
- “Signal Handling” on page 214
- “C Shell Commands” on page 214
 - “C Shell Built-In Commands” on page 214
 - “C Shell Expressions and Operators” on page 220
 - “Command Substitution in the C Shell” on page 221
 - “Nonbuilt-in C Shell Command Execution” on page 222
- “History Substitution in the C Shell” on page 222
 - “History Lists” on page 222
 - “Event Specification” on page 223
 - “Quoting with Single and Double Quotes” on page 224
- “Alias Substitution in the C Shell” on page 225
- “Variable and File Name Substitution in the C Shell” on page 226
 - “Variable Substitution in the C Shell” on page 226
 - “File Name Substitution in the C Shell” on page 227
 - “File Name Expansion” on page 227
 - “File Name Abbreviation” on page 228
 - “Character Classes” on page 229
- “Environment Variables in the C Shell” on page 229
- “Input and Output Redirection in the C Shell” on page 231
- “Job Control in the C Shell” on page 232
- “C Shell Related Information” on page 234

C Shell Limitations

The following are limitations of the C shell:

- Words can be no longer than 1024 bytes.
- Argument lists are limited to ARG_MAX bytes. Values for the ARG_MAX variable are found in the **/usr/include/sys/limits.h** file.
- The number of arguments to a command that involves file name expansion is limited to 1/6th the number of bytes allowed in an argument list.

- Command substitutions can substitute no more bytes than are allowed in an argument list.
- To detect looping, the shell restricts the number of alias substitutions on a single line to 20.
- The **cs**h command does not support file name expansion based on equivalence classification of characters.

Signal Handling

The C shell normally ignores quit signals. Jobs running detached are immune to signals generated from the keyboard (**INTERRUPT**, **QUIT**, and **HANGUP**). Other signals have the values the shell inherits from its parent. You can control the shell's handling of **INTERRUPT** and **TERMINATE** signals in shell procedures with **onintr**. Login shells catch or ignore **TERMINATE** signals depending on how they are set up. Shells other than login shells pass **TERMINATE** signals on to the child processes. In no cases are **INTERRUPT** signals allowed when a login shell is reading the **.logout** file.

C Shell Commands

A simple command is a sequence of words separated by blanks or tabs.

A *word* is a sequence of characters or numerals, or both, that does not contain blanks without quotation marks. In addition, the following characters and doubled characters also form single words when used as command separators or terminators:

```
&      |      ;
&&     ||     <<     >>
<      >     (      )
```

These special characters can be parts of other words. Preceding them with a ****, however, prevents the shell from interpreting them as special characters. Strings enclosed in **' '** or **" "** (matched pairs of quotation characters) or backquotes can also form parts of words. Blanks, tab characters, and special characters do not form separate words when they are enclosed in these marks. In addition, you can enclose a new-line character within these marks by preceding it with a ****.

The first word in the simple command sequence (numbered 0) usually specifies the name of a command. Any remaining words, with a few exceptions, are passed to that command. If the command specifies an executable file that is a compiled program, the shell immediately runs that program. If the file is marked executable but is not a compiled program, the shell assumes that it is a shell script. In this case, the shell starts another instance of itself (a subshell) to read the file and execute the commands included in it.

This section discusses:

- "C Shell Built-In Commands"
- "C Shell Expressions and Operators" on page 220
- "Command Substitution in the C Shell" on page 221
- "Nonbuilt-in C Shell Command Execution" on page 222
- "C Shell Related Information" on page 234

C Shell Built-In Commands

Built-in commands are run within the shell. If a built-in command occurs as any component of a pipeline, except the last, the command runs in a subshell.

Note: If you enter a command from the C shell prompt, the system searches for a built-in command first. If a built-in command does not exist, the system searches the directories specified by the **path** shell variable for a system-level command. Some C shell built-in commands and operating system

commands have the same name. However, these commands do not necessarily work the same way. Check the appropriate command description for information on how the command works.

If you run a shell script from the shell and the first line of the shell script begins with `#!/ShellPathname`, the C shell runs the shell specified in the comment to process the script. Otherwise, it runs the default shell (the shell linked to `/usr/bin/sh`). If run by the default shell, C shell built-in commands might not be recognized. To get the system to run C shell commands, make the first line of the script `#!/usr/bin/csh`.

Refer to the “List of C Shell Built-in Commands” on page 232 for an alphabetic listing of the built-in commands.

C Shell Command Descriptions

The C shell provides the following built-in commands:

alias [<i>Name</i> [<i>WordList</i>]]	Displays all aliases if you do not specify any parameters. Otherwise, the command displays the alias for the specified <i>Name</i> . If <i>WordList</i> is specified, this command assigns the value of <i>WordList</i> to the alias <i>Name</i> . The specified alias <i>Name</i> cannot be alias or unalias .
bg [% <i>Job</i> ...]	Puts the current job or job specified by <i>Job</i> into the background, continuing the job if it was stopped.
break	Resumes running after the end of the nearest enclosing foreach or while command.
breaksw	Breaks from a switch command; resumes after the endsw command.
case <i>Label</i> :	Defines a <i>Label</i> in a switch command.
cd [<i>Name</i>]	Equivalent to the chdir command (see following description).
chdir [<i>Name</i>]	Changes the current directory to that specified by the <i>Name</i> variable. If you do not specify <i>Name</i> , the command changes to your home directory. If the value of the <i>Name</i> variable is not a subdirectory of the current directory and does not begin with <code>/</code> , <code>./</code> , or <code>../</code> , the shell checks each component of the cdpath shell variable to see if it has a subdirectory matching the <i>Name</i> variable. If the <i>Name</i> variable is a shell variable with a value that begins with <code>/</code> , the shell tries this to see if it is a directory. The chdir command is equivalent to the cd command.
continue	Continues execution at the end of the nearest enclosing while or foreach command.
default :	Labels the default case in a switch statement. The default should come after all other case labels.
dirs	Displays the directory stack.
echo	Writes character strings to the standard output of the shell.
else	Runs the commands that follow the second else in an if (Expression) then ...else if (Expression2) then ... else ... endif command sequence.
end	Successively sets the <i>Name</i> variable to each member specified by the <i>List</i> variable and runs the sequence of <i>Commands</i> between the foreach and the matching end statements. The foreach and end statements must appear alone on separate lines.
endif	Uses the continue statement to continue the loop and the break statement to end the loop prematurely. When the foreach command is read from the terminal, the C shell prompts with a <code>?</code> to allow <i>Commands</i> to be entered. Commands within loops, prompted for by <code>?</code> , are not placed in the history list. If the <i>Expression</i> variable is true, runs the <i>Commands</i> that follow the first then statement. If the else if Expression2 is true, runs the <i>Commands</i> that follow the second then statement. If the else if Expression2 is false, runs the <i>Commands</i> that follow the else . Any number of else if pairs are possible. Only one endif statement is needed. The else segment is optional. The words else and endif can be used only at the beginning of input lines. The if segment must appear alone on its input line or after an else command.

endsw	Successively matches each case label against the value of the <i>string</i> variable. The <i>string</i> is command and file name expanded first. Use the pattern-matching characters *, ?, and [. . .] in the case labels, which are variable-expanded. If none of the labels match before a default label is found, the execution begins after the default label. The case label and the default label must appear at the beginning of the line. The breaksw command causes execution to continue after the endsw command. Otherwise, control might fall through the case and default labels, as in the C programming language. If no label matches and there is no default , execution continues after the endsw command.
eval <i>Parameter</i> . . .	Reads the value of the <i>Parameter</i> variable as input to the shell and runs the resulting command or commands in the context of the current shell. Use this command to run commands generated as the result of command or variable substitution, since parsing occurs before these substitutions.
exec <i>Command</i>	Runs the specified <i>Command</i> in place of the current shell.
exit [(<i>Expression</i>)]	Exits the shell with either the value of the status shell variable (if no <i>Expression</i> is specified) or with the value of the specified <i>Expression</i> .
fg [% <i>Job</i> ...]	Brings the current job or job specified by <i>Job</i> into the foreground, continuing the job if it was stopped.
foreach <i>Name</i> (<i>List</i>) <i>Command</i> . . .	Successively sets a <i>Name</i> variable for each member specified by the <i>List</i> variable and a sequence of commands, until reaching an end command.
glob <i>List</i>	Displays <i>List</i> using history, variable, and file name expansion. Puts a null character between words and does not include a carriage return at the end.
goto <i>Word</i>	Continues to run after the line specified by the <i>Word</i> variable. The specified <i>Word</i> is file name and command expanded to yield a string of the form specified by the <i>Label:</i> variable. The shell rewinds its input as much as possible and searches for a line of the form <i>Label:</i> , possibly preceded by blanks or tabs.
hashstat	Displays statistics indicating how successful the hash table has been at locating commands.
history [-r -h] [<i>n</i>]	Displays the history event list. The oldest events are displayed first. If you specify a number <i>n</i> , only the specified number of the most recent events are displayed. The -r flag reverses the order in which the events are displayed so the most recent is displayed first. The -h flag displays the history list without leading numbers. Use this flag to produce files suitable for use with the -h flag of the source command.
if (<i>Expression</i>) <i>Command</i>	Runs the specified <i>Command</i> (including its arguments) if the specified <i>Expression</i> is true. Variable substitution on the <i>Command</i> variable happens early, at the same time as the rest of the if statement. The specified <i>Command</i> must be a simple command (rather than a pipeline, command list, or parenthesized command list).
	Note: Input and output redirection occurs even if the <i>Expression</i> variable is false and the <i>Command</i> is not executed.
jobs [-l]	Lists the active jobs. With the -l (lowercase L) flag, the jobs command lists process IDs in addition to the job number and name.
kill -l [[- <i>Signal</i>] % <i>Job</i> ...! <i>PID</i> ...]	Sends either the TERM (terminate) signal or the signal specified by <i>Signal</i> to the specified <i>Job</i> or <i>PID</i> (process). Specify signals either by number or by name (as given in the /usr/include/sys/signal.h file, stripped of the SIG prefix). The -l (lowercase L) flag lists the signal names.

limit [-h] [Resource [Max-Use]]

Limits the usage of the specified resource by the current process and each process it creates. Process resource limits are defined in the **/etc/security/limits** file. Controllable resources are the central processing unit (CPU) time, file size, data size, core dump size, and memory use. Maximum allowable values for these resources are set with the **mkuser** command when the user is added to the system. They are changed with the **chuser** command.

Limits are categorized as either soft or hard. Users may increase their soft limits up to the ceiling imposed by the hard limits. You must have root user authority to increase a soft limit above the hard limit, or to change hard limits. The **-h** flag displays hard limits instead of the soft limits.

If a *Max-Use* parameter is not specified, the **limit** command displays the current limit of the specified resource. If the *Resource* parameter is not specified, the **limit** command displays the current limits of all resources. For more information about the resources controlled by the **limit** subcommand, see the **getrlimit**, **setrlimit**, or **vlimit** subroutine in the *AIX 5L Version 5.1 Technical Reference: Base Operating System and Extensions Volume 1*.

The *Max-Use* parameter for CPU time is specified in the hh:mm:ss format. The *Max-Use* parameter for other resources is specified as a floating-point number or an integer optionally followed by a scale factor. The scale factor is: k or kilobytes (1024 bytes), m or megabytes, or b or blocks (the units used by the **ulimit** subroutine as explained in the *AIX 5L Version 5.1 Technical Reference: Base Operating System and Extensions Volume 2*). If you do not specify a scale factor, k is assumed for all resources. For both resource names and scale factors, unambiguous prefixes of the names suffice.

Note: This command limits the physical memory (memory use) available for a process only if there is contention for system memory by other active processes.

login

Ends a login shell and replaces it with an instance of the **/usr/bin/login** command. This is one way to log out (included for compatibility with the **ksh** and **bsh** commands).

logout

nice [+n] [Command]

Ends a login shell. This command must be used if the **ignoreeof** option is set. If no values are specified, sets the priority of commands run in this shell to 24. If the **+n** flag is specified, sets the priority plus the specified number. If the **+n** flag and *Command* are specified, runs *Command* at priority 24 plus the specified number. If you have root user authority, you can run the **nice** statement with a negative number. The *Command* always runs in a subshell, and the restrictions placed on commands in simple **if** statements apply.

nohup [Command]

Causes **hangups** to be ignored for the remainder of the script when no *Command* is specified. If *Command* is specified, causes the specified *Command* to be run with **hangups** ignored. To run a pipeline or list of commands, put the pipeline or list in a shell script, give the script execute permission, and use the shell script as the value of the *Command* variable. All processes run in the background with **&** are effectively protected from being sent a **hangup** signal when you log out. However, these processes are still subject to explicitly sent **hangups** unless the **nohup** statement is used.

notify [%Job...]

Causes the shell to notify you asynchronously when the status of the current job or specified *Job* changes. Normally, the shell provides notification just before it presents the shell prompt. This feature is automatic if the **notify** shell variable is set.

onintr [- <i>Label</i>]	Controls the action of the shell on interrupts. If no arguments are specified, restores the default action of the shell on interrupts, which ends shell scripts or returns to the command input level. If a - flag is specified, causes all interrupts to be ignored. If <i>Label</i> is specified, causes the shell to run a goto <i>Label</i> statement when the shell receives an interrupt or when a child process ends due to an interruption. In any case, if the shell is running detached and interrupts are being ignored, all forms of the onintr statement have no meaning. Interrupts continue to be ignored by the shell and all invoked commands.
popd [+ <i>n</i>]	Pops the directory stack and changes to the new top directory. If you specify a + <i>n</i> variable, the command discards the <i>n</i> th entry in the stack. The elements of the directory stack are numbered from the top, starting at 0.
pushd [+ <i>n</i> <i>Name</i>]	With no arguments, exchanges the top two elements of the directory stack. With the <i>Name</i> variable, the command changes to the new directory and pushes the old current directory (as given in the cwd shell variable) onto the directory stack. If you specify a + <i>n</i> variable, the command rotates the <i>n</i> th component of the directory stack around to be the top element and changes to it. The members of the directory stack are numbered from the top, starting at 0.
rehash	Causes recomputation of the internal hash table of the contents of the directories in the path shell variable. This action is needed if new commands are added to directories in the path shell variable while you are logged in. The rehash command is necessary only if commands are added to one of the user's own directories or if someone changes the contents of one of the system directories.
repeat <i>Count Command</i>	Runs the specified <i>Command</i> , subject to the same restrictions as commands in simple if statements, the number of times specified by <i>Count</i> .
	Note: I/O redirections occur exactly once, even if the <i>Count</i> variable equals 0.
set [[<i>Name</i> [<i>n</i>]] [= <i>Word</i>]] [<i>Name</i> = (<i>List</i>)	Shows the value of all shell variables when used with no arguments. Variables that have more than a single word as their value are displayed as a parenthesized word list. If only <i>Name</i> is specified, the C shell sets the <i>Name</i> variable to the null string. Otherwise, sets <i>Name</i> to the value of the <i>Word</i> variable, or sets the <i>Name</i> variable to the list of words specified by the <i>List</i> variable. When <i>n</i> is specified, the <i>n</i> th component of the <i>Name</i> variable is set to the value of the <i>Word</i> variable; the <i>n</i> th component must already exist. In all cases, the value is command and file name expanded. These arguments may be repeated to set multiple values in a single set command. However, variable expansion happens for all arguments before any setting occurs.
setenv <i>Name Value</i>	Sets the value of the environment variable specified by the <i>Name</i> variable to <i>Value</i> , a single string. The most commonly used environment variables, USER , TERM , HOME , and PATH , are automatically imported to and exported from the C shell variables user , term , home , and path . There is no need to use the setenv statement for these.
shift [<i>Variable</i>]	Shifts the members of the argv shell variable or the specified <i>Variable</i> to the left. An error occurs if the argv shell variable or specified <i>Variable</i> is not set or has less than one word as its value.
source [- h] <i>Name</i>	Reads commands specified by the <i>Name</i> variable. You can nest the source commands. However, if they are nested too deeply, the shell might run out of file descriptors. An error in a source command at any level ends all nested source commands. Normally, input during source commands is not placed on the history list. The -h flag causes the commands to be placed in the history list without executing them.
stop [% <i>Job</i> ...]	Stops the current job or specified <i>Job</i> running in the background.
suspend	Stops the shell as if a STOP signal had been received.

switch (<i>string</i>)	Starts a switch (<i>String</i>) case <i>String</i> : ... breaksw default: ... breaksw endsw command sequence. This command sequence successively matches each case label against the value of the <i>String</i> variable. If none of the labels match before a default label is found, the execution begins after the default label.																
time [<i>Command</i>]	<p>The time command controls automatic timing of commands. If you do not specify the <i>Command</i> variable, the time command displays a summary of time used by this shell and its children. If you specify a command with the <i>Command</i> variable, it is timed. The shell then displays a time summary, as described under the time shell variable. If necessary, an extra shell is created to display the time statistic when the command completes.</p> <p>Here is an example using time with the sleep command:</p> <pre>time sleep</pre> <p>The output from this command might look like:</p> <pre>0.0u 0.0s 0:00 100% 44+4k 0+0io 0pf+0w</pre> <p>The seven fields in the output are described below:</p> <table border="0"> <tr> <td style="padding-right: 20px;">Field</td> <td>Description</td> </tr> <tr> <td>First</td> <td>Number of seconds of CPU time devoted to the user process</td> </tr> <tr> <td>Second</td> <td>Number of seconds of CPU time consumed by the kernel on behalf of the user process</td> </tr> <tr> <td>Third</td> <td>Elapsed (wall clock) time for the command</td> </tr> <tr> <td>Fourth</td> <td>Total user CPU Time plus system time, as a percentage of elapsed time</td> </tr> <tr> <td>Fifth</td> <td>Average amount of shared memory used, plus average amount of unshared data space used, in kilobytes</td> </tr> <tr> <td>Sixth</td> <td>Number of block input and output operations</td> </tr> <tr> <td>Seventh</td> <td>Page faults plus number of swaps</td> </tr> </table>	Field	Description	First	Number of seconds of CPU time devoted to the user process	Second	Number of seconds of CPU time consumed by the kernel on behalf of the user process	Third	Elapsed (wall clock) time for the command	Fourth	Total user CPU Time plus system time, as a percentage of elapsed time	Fifth	Average amount of shared memory used, plus average amount of unshared data space used, in kilobytes	Sixth	Number of block input and output operations	Seventh	Page faults plus number of swaps
Field	Description																
First	Number of seconds of CPU time devoted to the user process																
Second	Number of seconds of CPU time consumed by the kernel on behalf of the user process																
Third	Elapsed (wall clock) time for the command																
Fourth	Total user CPU Time plus system time, as a percentage of elapsed time																
Fifth	Average amount of shared memory used, plus average amount of unshared data space used, in kilobytes																
Sixth	Number of block input and output operations																
Seventh	Page faults plus number of swaps																
umask [<i>Value</i>]	Determines file permissions. This <i>Value</i> , along with the permissions of the creating process, determines a file's permissions when the file is created. The default is 022. The current setting will be displayed if no <i>Value</i> is specified.																
unalias * <i>Pattern</i>	Discards all aliases with names that match the <i>Pattern</i> variable. All aliases are removed by the unalias * command. The absence of aliases does not cause an error.																
unhash	Disables the use of the internal hash table to locate running programs.																
unlimit [-h][<i>Resource</i>]	Removes the limitation on the <i>Resource</i> variable. If no <i>Resource</i> variable is specified, all resource limitations are removed. See the description of the limit command for the list of <i>Resource</i> names.																
	The -h flag removes corresponding hard limits. Only a user with root user authority can change hard limits.																
unset * <i>Pattern</i>	Removes all variables with names that match the <i>Pattern</i> variable. Use unset * to remove all variables. If no variables are set, it does not cause an error.																
unsetenv <i>Pattern</i>	Removes all variables from the environment whose name matches the specified <i>Pattern</i> . (See the setenv built-in command.)																
wait	Waits for all background jobs. If the shell is interactive, an INTERRUPT (usually the Ctrl-C key sequence) disrupts the wait. The shell then displays the names and job numbers of all jobs known to be outstanding.																

while (*Expression*) *Command* . . .
end

Evaluates the *Commands* between the **while** and the matching **end** statements while the expression specified by the *Expression* variable evaluates nonzero. You can use the **break** statement to end and the **continue** statement to continue the loop prematurely. The **while** and **end** statements must appear alone on their input lines. If the input is from a terminal, prompts occur after the *while* (*Expression*) similar to the **foreach** statement.

@ [*Name*[*n*] = *Expression*]

Displays the values of all the shell variables when used with no arguments. Otherwise, sets the name specified by the *Name* variable to the value of the *Expression* variable. If the expression contains <, >, &, or | characters, this part of the expression must be placed within parentheses. When *n* is specified, the *n*th component of the *Name* variable is set to the *Expression* variable. Both the *Name* variable and its *n*th component must already exist.

C language operators, such as *= and +=, are available. The space separating the *Name* variable from the assignment operator is optional. Spaces are, however, required in separating components of the *Expression* variable, which would otherwise be read as a single word. Special suffix operators, double plus sign (++) and double hyphen (- -) increase and decrease, respectively, the value of the *Name* variable.

C Shell Expressions and Operators

The @ built-in command and the **exit**, **if**, and **while** statements accept expressions that include operators similar to those of C language, with the same precedence. The following operators are available:

Operator	What it Means
()	change precedence
~	complement
!	negation
*/ %	multiply, divide, modulo
+ -	add, subtract
<< > >	left shift, right shift
<= >= < >	relational operators
== != = ~ ! ~	string comparison/pattern matching
&	bitwise "and"
^	bitwise "exclusive or"
	bitwise "inclusive or"
&&	logical "and"
	logical "or"

In the above list, precedence of the operators decreases down the list - left to right, top to bottom.

Note: The operators + and - are right associative. For example, evaluation of a + b - c is performed as follows:

a + (b - c)

and not:

(a + b) - c

The ==, !=, = ~, and ! ~ operators compare their arguments as strings; all others operate on numbers. The = ~ and ! ~ operators are similar to == and !=, except that the rightmost side is a *pattern* against which the leftmost operand is matched. This reduces the need for use of the **switch** statement in shell procedures when all that is really needed is pattern matching.

The logical operators or (||) and and (&&) are available as well. They can be used, for example, to check for a range of numbers:

```
if ($#argv > 2 && $#argv < 7) then
```

In the preceding example, the number of arguments must be greater than 2 and less than 7.

Strings beginning with zero (0) are considered octal numbers. Null or missing arguments are considered 0. All expressions result in strings representing decimal numbers. Note that two components of an expression can appear in the same word. Except when next to components of expressions that are syntactically significant to the parser (& | < > ()), expression components should be surrounded by spaces.

Also available in expressions as primitive operands are command executions enclosed in () and file inquiries of the form (**-operator** *Filename*), where **operator** is one of the following:

r	Read access
w	Write access
x	Execute access
e	Existence
o	Ownership
z	Zero size
f	Plain file
d	Directory

The specified *Filename* is command and file name expanded and then tested to see if it has the specified relationship to the real user. If *Filename* does not exist or is inaccessible, then all inquiries return false(0). If the command runs successfully, the inquiry returns a value of true(1). Otherwise, if the command fails, the inquiry returns a value of false(0). If more detailed status information is required, run the command outside an expression and then examine the **status** shell variable.

Command Substitution in the C Shell

In *command substitution*, the shell executes a specified command and replaces that command with its output. To perform command substitution in the C shell, enclose the command or command string in backquotes (` `). The shell normally breaks the output from the command into separate words at blanks, tabs, and new-line characters. It then replaces the original command with this output.

In the following example, the backquotes (` `) around the **date** command indicate that the output of the command will be substituted:

```
echo The current date and time is: `date`
```

The output from this command might look like:

```
The current date and time is: Wed Apr 8 13:52:14 CDT 1992
```

The C shell performs command substitution selectively on the arguments of built-in shell commands. This means that it does not expand those parts of expressions that are not evaluated. For commands that are not built-in, the shell substitutes the command name separately from the argument list. The substitution occurs in a child of the main shell, only after the shell performs input or output redirection.

If a command string is surrounded by " ", the shell treats only new-line characters as word separators, thus preserving blanks and tabs within the word. In all cases, the single final new-line character does not force a new word.

Nonbuilt-in C Shell Command Execution

When the C shell determines that a command is not a built-in shell command, it attempts to run the command with the **execv** system call. Each word in the **path** shell variable names a directory from which the shell attempts to run the command. If given neither the **-c** nor **-t** flag, the shell hashes the names in these directories into an internal table. The shell tries to call the **exec** system call on a directory only if there is a possibility that the command resides there. If you turn off this mechanism with the **unhash** command or give the shell the **-c** or **-t** flag, the shell concatenates with the given command name to form a path name of a file. The shell also does this in any case for each directory component of the **path** variable that does not begin with a **/**. The shell then attempts to run the command.

Parenthesized commands always run in a subshell. For example:

```
(cd ; pwd) ; pwd
```

displays the home directory without changing the current directory location. However, the command:

```
cd ; pwd
```

changes the current directory location to the home directory. Parenthesized commands are most often used to prevent the **chdir** command from affecting the current shell.

If the file has execute permission, but is not an executable binary to the system, then the shell assumes it is a file containing shell commands and runs a new shell to read it.

If there is an alias for the shell, then the words of the alias are prefixed to the argument list to form the shell command. The first word of the alias should be the full path name of the shell.

History Substitution in the C Shell

History substitution lets you modify individual words from previous commands to create new commands. History substitution makes it easy to repeat commands, repeat the arguments of a previous command in the current command, or fix spelling mistakes in the previous command with little typing.

History substitutions begin with the **!** character and can appear anywhere on the command line, provided they do not nest (in other words, a history substitution cannot contain another history substitution). You can precede the **!** with a **** to cancel the exclamation point's special meaning. In addition, if you place the **!** before a blank, tab, new-line character, **=**, or **(**, history substitution does not occur.

History substitutions also occur when you begin an input line with a **^**. The shell echoes any input line containing history substitutions at the workstation before it executes that line.

This section discusses:

- “History Lists”
- “Event Specification” on page 223
- “Quoting with Single and Double Quotes” on page 224
- “C Shell Related Information” on page 234

History Lists

The history list saves commands that the shell reads from the command line that consist of one or more words. History substitution reintroduces sequences of words from these saved commands into the input stream.

The **history** shell variable controls the size of the history list. You must set the **history** shell variable either in the **.cshrc** file or on the command line with the built-in **set** command. The previous command is always

retained regardless of the value of the **history** variable. Commands in the history list are numbered sequentially starting from 1. The built-in **history** command produces output of the type:

```
9 write michael
10 ed write.c
11 cat oldwrite.c
12 diff *write.c
```

The shell displays the command strings with their event numbers. It is not usually necessary to use event numbers to refer to events, but you can have the current event number displayed as part of your system prompt by placing an **!** in the prompt string assigned to the **prompt** environment variable.

A full history reference contains an event specification, a word designator, and one or more modifiers in the following general format:

```
Event[.]Word:Modifier[:Modifier] . . .
```

Note: Only one word can be modified. A string that contains blanks is not allowed.

In the previous sample of **history** command output, the current event number is 13. Using this example, the following refer to previous events:

```
!10      Event number 10.
!-2      Event number 11 (the current event minus 2).
!d       Command word beginning with d (event number 12).
!?mic?   Command word containing the string mic (event number 9).
```

These forms, without further modification, simply reintroduce the words of the specified events, each separated by a single blank. As a special case, **!!** refers to the previous command; the command **!!** alone on an input line reruns the previous command.

Event Specification

To select words from an event, follow the event specification with a **:** and one of the following word designators (the words of an input line are numbered sequentially starting from 0):

```
0      First word (the command name).
n      nth argument.
^      First argument.
$      Last argument.
%      Word matched by an immediately preceding ?string? search.
x-y    Range of words from the xth word to the yth word.
-y     Range of words from the first word (0) to the yth word.
*      First through the last argument, or nothing if there is only one word (the command name) in the event.
x*    xth argument through the last argument.
x-    Like x* but omitting the last argument.
```

You can omit the colon that separates the event specification from the word designator if the word designator begins with a ^{**^**}, ^{**\$**}, ^{**%**}, *****, **-**, or **%**. You can also place a sequence of the following modifiers after the optional word designator, each preceded by a colon:

```
h      Removes a trailing path name extension, leaving the head.
r      Removes a trailing .xxx component, leaving the root name.
e      Removes all but the .xxx trailing extension.
s/OldWord/NewWord/ Substitutes the value of the NewWord variable for the value of the OldWord variable.
```


The left side of a substitution is not a pattern in the sense of a string recognized by an editor; rather, it is a word, a single unit without blanks. Normally, a / delimits the original word (*OldWord*) and its replacement (*NewWord*). However, you can use any character as the delimiter. In the following example, using the % as a delimiter allows a / to be included in the words:

```
s%/home/myfile%/home/yourfile%
```

The shell replaces an & with the *OldWord* text in the *NewWord* variable. In the following example, /home/myfile becomes /temp/home/myfile.

```
s%/home/myfile%/temp&%
```

The shell replaces a null word in a substitution with either the last substitution or with the last string used in the contextual scan `!?String?`. You can omit the trailing delimiter (/) if a new-line character follows immediately. Use the following modifiers to delimit the history list:

t	Removes all leading path name components, leaving the tail.
&	Repeats the previous substitution.
g	Applies the change globally; that is, all occurrences for each line.
p	Displays the new command, but does not run it.
q	Quotes the substituted words, thus preventing further substitutions.
x	Acts like the q modifier, but breaks into words at blanks, tabs, and new-line characters.

Unless the **g** modifier precedes the above modifiers, the change applies only to the first modifiable word.

If you give a history reference without an event specification (for example, !\$), the shell uses the previous command as the event. If a previous history reference occurs on the same line, the shell repeats the previous reference. Thus, the following sequence gives the first and last arguments of the command that matches `?foo?`.

```
!?foo? ^ !$
```

A special abbreviation of a history reference occurs when the first nonblank character of an input line is a ^ . This is equivalent to `!:s ^`, thus providing a convenient shorthand for substitutions on the text of the previous line. The command `^ lb ^ lib` corrects the spelling of lib in the previous command.

If necessary, you can enclose a history substitution in { } to insulate it from the characters that follow. For example, if you want to use a reference to the command:

```
ls -ld ~paul
```

to perform the command:

```
ls -ld ~paula
```

use the following construction:

```
!{1}a
```

In this example, `!{1}a` looks for a command starting with 1 and appends a to the end.

Quoting with Single and Double Quotes

Enclose strings in single and double quotation marks in order to prevent all or some of the substitutions that remain. Enclosing strings in ' ' prevents further interpretation, while enclosing strings in " " allows further expansion. In both cases, the text that results becomes (all or part of) a single word.

Alias Substitution in the C Shell

An *alias* is a name assigned to a command or command string. The C shell allows you to assign aliases and use them just as you would commands. The shell maintains a list of the aliases you define.

After the shell scans the command line, it divides it into distinct words and checks the first word of each command, left to right, to see if it has an alias. If it does, the shell uses the history mechanism to replace the text of the alias with the text of the command referenced by the alias. The resulting words replace the command and argument list. If no reference is made to the history list, the argument list is left unchanged.

For information about the C shell history mechanism, see “History Substitution in the C Shell” on page 222

The **alias** and **unalias** built-in commands establish, display, and modify the alias list. Use the alias command in the following format:

```
alias [Name [WordList]]
```

The optional *Name* variable specifies the alias for the specified name. If you specify a word list with the *WordList* variable, the command assigns it as the alias of the *Name* variable. If you issue the **alias** command without either optional variable, it displays all C shell aliases.

If the alias for the **ls** command is `ls -l`, the command:

```
ls /usr
```

is replaced by the command:

```
ls -l /usr
```

The argument list is undisturbed because there is no reference to the history list in the command with an alias. Similarly, if the alias for the **lookup** command is:

```
grep \!^ /etc/passwd
```

then the shell replaces `lookup bill` with:

```
grep bill /etc/passwd
```

In this example, `!^` refers to the history list and the shell replaces it with the first argument in the input line, in this case `bill`.

You can use special pattern-matching characters in an alias. The command:

```
alias lprint 'pr &bslash2.!* >
```

```
> print'
```

creates a command that formats its arguments to the line printer. The `!` character is protected from the shell in the alias by use of single quotation marks so that it is not expanded until the **pr** command runs.

If the shell locates an alias, it performs the word transformation of the input text and begins the alias process again on the reformed input line. If the first word of the next text is the same as the old, looping is prevented by flagging it to terminate the alias process. Other subsequent loops are detected and result in an error.

- “C Shell Related Information” on page 234

Variable and File Name Substitution in the C Shell

The C Shell permits you to do variable and file name substitutions.

The following sections offer information about creating and substituting variables in the C shell:

- “Variable Substitution in the C Shell”
- “File Name Substitution in the C Shell” on page 227
- “File Name Expansion” on page 227
- “File Name Abbreviation” on page 228
- “Character Classes” on page 229
- “C Shell Related Information” on page 234

Variable Substitution in the C Shell

The C shell maintains a set of variables, each of which has as its value a list of zero or more words. Some of these variables are set by the shell or referred to by it. For instance, the **argv** variable is an image of the shell variable list, and words that comprise the value of this variable are referred to in special ways.

You can change and display the values of variables with the **set** and **unset** commands. Of the variables referred to by the shell, a number are toggles (variables that turn something on and off). The shell does not examine toggles for a value, only for whether they are set or unset. For instance, the **verbose** shell variable is a toggle that causes command input to be echoed. The setting of this variable results from issuing the **-v** flag on the command line.

Other operations treat variables numerically. The **@** command performs numeric calculations and the result is assigned to a variable. Variable values are, however, always represented as (zero or more) strings. For numeric operations, the null string is considered to be zero, and the second and subsequent words of multiword values are ignored.

When you issue a command, the shell parses the input line and performs alias substitution. Next, before running the command, it performs variable substitution. The **\$** character keys the substitution. It is, however, passed unchanged if followed by a blank, tab, or new-line character. Preceding the **\$** character with a **** prevents this expansion, except in two cases:

- The command is enclosed in **" "**. In this case, the shell always performs the substitution.
- The command is enclosed in **' '**. In this case, the shell never performs the substitution. Strings enclosed by **' '** are interpreted for command substitution. (See “Command Substitution in the C Shell” on page 221.)

The shell recognizes input and output redirection before variable expansion, and expands each separately. Otherwise, the command name and complete argument list expands together. It is therefore possible for the first (command) word to generate more than one word, the first of which becomes the command name and the rest of which become parameters.

Unless enclosed in **" "** or given the **:q** modifier, the results of variable substitution might eventually be subject to command and file name substitution. When enclosed by double quotation marks, a variable with a value that consists of multiple words expands to a single word or a portion of a single word, with the words of the variable’s value separated by blanks. When you apply the **:q** modifier to a substitution, the variable expands to multiple words. Each word is separated by a blank and enclosed in double quotation marks to prevent later command or file name substitution.

The notations below allow you to introduce variable values into the shell input. Except as noted, it is an error to reference a variable that is not set with the **set** command.

You can apply the modifiers **:gh**, **:gt**, **:gr**, **:h**, **:r**, **:q**, and **:x** to the following substitutions. If { } appear in the command form, then the modifiers must appear within the braces. The current implementation allows only one **:** modifier on each variable expansion.

\$Name

\${Name} Replaced by the words assigned to the *Name* variable, each separated by a blank. Braces insulate the *Name* variable from any following characters that would otherwise be part of it. Shell variable names start with a letter and consist of up to 20 letters and digits, including the underline () character. If the *Name* variable does not specify a shell variable but is set in the environment, then its value is returned. The modifiers preceded by colons, as well as the other forms described here, are not available in this case.

\$Name[number]

\${Name[number]} Selects only some of the words from the value of the *Name* variable. The number is subjected to variable substitution and might consist of a single number, or two numbers separated by a -. The first word of a variable's string value is numbered 1. If the first number of a range is omitted, it defaults to 1. If the last number of a range is omitted, it defaults to ***\$#Name***. The * symbol selects all words. It is not an error for a range to be empty if the second argument is omitted or is in a range.

\$#Name

\${#Name} Gives the number of words in the *Name* variable. This is useful for use in a *[number]* as shown above. For example, *\$Name[\$#Name]*.

\$0

Substitutes the name of the file from which command input is being read. An error occurs if the name is not known.

\$number

\${number} Equivalent to *\$argv[number]*.

\$* Equivalent to *\$argv[*]*.

The following substitutions may not be changed with **:** modifiers:

\$?name

\${?name} Substitutes the string 1 if the *name* variable is set, zero (0) if this variable is not set.

\$?0 Substitutes 1 if the current input file name is known, zero (0) if the file name is not known.

\$\$ Substitutes the (decimal) process number of the parent shell.

\$< Substitutes a line from standard input, without further interpretation. Use this substitution to read from the keyboard in a shell procedure.

File Name Substitution in the C Shell

The C shell provides several abridgment features to save time and keystrokes. If a word contains any of the characters *****, **?**, **[]**, or **{ }**, or begins with a tilde (**~**), that word is a candidate for file name substitution. The C shell regards the word as a pattern and replaces the word with an alphabetically sorted list of file names matching the pattern.

The current collating sequence is used, as specified by the **LC_COLLATE** or **LANG** environment variables. In a list of words specifying file name substitution, an error results if no patterns match an existing file name. However, it is not required that every pattern match. Only the character-matching symbols *****, **?**, and **[]** indicate pattern-matching, or file name expansion. The tilde (**~**) and **{ }** characters indicate file name abbreviation.

File Name Expansion

The ***** character matches any string of characters, including the null string. For example, in a directory containing the files:

```
a aa aax alice b bb c cc
```

the command `echo a*` prints all files names beginning with the character `a`:

```
a aa aax alice
```

Note: When file names are matched, the characters DOT (.) and / must be matched explicitly.

The ? character matches any single character. The command:

```
ls a?x
```

lists every file name beginning with the letter a, followed by a single character, and ending with the letter x:

```
aax
```

To match a single character or a range of characters, enclose the character or characters inside of []. The command:

```
ls [abc]
```

lists all file names exactly matching one of the enclosed characters:

```
a b c
```

Within brackets, a lexical range of characters is indicated by [a-z]. The characters matching this pattern are defined by the current collating sequence.

File Name Abbreviation

The tilde (~) and { characters indicate file name abbreviation. A ~ at the beginning of a file name is used to represent home directories. Standing alone, the ~ character expands to your home directory as reflected in the value of the **home** shell variable. For example, the command:

```
ls ~
```

lists all files and directories located in your **\$HOME** directory.

When followed by a name consisting of letters, digits, and - characters, the shell searches for a user with that name and substitutes that user's \$HOME directory.

Note: If the ~ character is followed by a character other than a letter or /, or appears anywhere except at the beginning of a word, it does not expand.

To match characters in file names without typing the entire file name, use { } around the file names. The pattern a{b,c,d}e is shorthand for abe ace ade. The shell preserves the left-to-right order and separately stores the results of matches at a low level to preserve this order. This construct might be nested. Thus:

```
~/source/s1/{oldls,ls}.c
```

expands to:

```
/usr/source/s1/oldls.c /usr/source/s1/ls.c
```

if the home directory for source is /usr/source. Similarly:

```
../{memo,*box}
```

might expand to:

```
../memo ../box ../mbox
```

Note: memo is not sorted with the results of matching *box. As a special case, the {, }, and { } characters are passed undisturbed.

Character Classes

You can also use character classes to match file names within a range indication:

```
[:charclass:]
```

This format instructs the system to match any single character belonging to the specified class. The defined classes correspond to **ctype** subroutines.

Character Class	Definition
alnum	Alphanumeric characters
alpha	Uppercase and lowercase letters
cntrl	Control characters
digit	Digits
graph	Graphic characters
lower	Lowercase letters
print	Printable characters
punct	Punctuation character
space	Space, horizontal tab, carriage return, new-line, vertical tab, or form-feed character
upper	Uppercase characters
xdigit	Hexadecimal digits.

Suppose you are in a directory containing the following files:

```
a aa aax Alice b bb c cc
```

Type the following command at a C shell prompt:

```
ls [:lower:]
```

Press Enter.

The C shell lists all file names that begin with lowercase characters:

```
a aa aax b bb c cc
```

For more information about character class expressions, refer to the **ed** command.

Environment Variables in the C Shell

Certain variables have special meaning to the C shell. Of these, **argv**, **cwd**, **home**, **path**, **prompt**, **shell**, and **status** are always set by the shell. Except for the **cwd** and **status** variables, this action occurs only at initialization. These variables maintain their settings unless you explicitly reset them.

The **cs**h command copies the **USER**, **TERM**, **HOME**, and **PATH** environment variables into the **cs**h variables, **user**, **term**, **home**, and **path**, respectively. The values are copied back into the environment whenever the normal shell variables are reset. the **path** variable cannot set in other than in the **.cshrc** file, because **cs**h subprocesses import the path definition from the environment and reexport it if changed.

The following variables have special meanings:

argv	Contains the arguments passed to shell scripts. Positional parameters are substituted from this variable.
cdpath	Specifies a list of alternate directories to be searched by the chdir or cd command to find subdirectories.
cwd	Specifies the full path name of the current directory.

echo	Set when the -x command line flag is used; when set, causes each command and its arguments to echo just before being run. For commands that are not built-in, all expansions occur before echoing. Built-in commands are echoed before command and file name substitution because these substitutions are then done selectively.
histchars	Specifies a string value to change the characters used in history substitution. Use the first character of its value as the history substitution character, this replaces the default character, ! . The second character of its value replaces the ^ character in quick substitutions. Note: Setting the histchars value to a character used in command or file names might cause unintentional history substitution.
history	Contains a numeric value to control the size of the history list. Any command that is referenced in this many events is not discarded. Very large values of the history variable might cause the shell to run out of memory. Regardless of whether this variable is set, the C shell always saves the last command that ran on the history list.
home	Indicates your home directory, initialized from the environment. The file name expansion of the tilde (~) character refers to this variable.
ignoreeof	Specifies that the shell ignore an end-of-file character from input devices that are workstations. This prevents shells from accidentally being killed when it reads an end-of-file character (Ctrl-D).
mail	Specifies the files where the shell checks for mail. This is done after each command completion which results in a prompt if a specified time interval has elapsed. The shell displays the message <i>Mail in file.</i> if the file exists with an access time less than its change time. If the first word of the value of the mail variable is numeric, it specifies a different mail checking time interval (in seconds); the default is 600 (10 minutes). If you specify multiple mail files, the shell displays the message <i>New mail in file,</i> when there is mail in the specified file.
noclobber	Places restrictions on output redirection to ensure that files are not accidentally destroyed and that redirections append to existing files.
noglob	Inhibits file name expansion. This is most useful in shell scripts that are not dealing with file names, or when a list of file names has been obtained and further expansions are not desirable.
nonomatch	Specifies that no error results if a file name expansion does not match any existing files; rather, the primitive pattern returns. It is still an error for the primitive pattern to be malformed.
notify	Specifies that the shell send asynchronous notification of changes in job status. The default presents status changes just before displaying the shell prompt.
path	Specifies directories in which commands are sought for execution. A null word specifies the current directory. If there is no path variable set, then only full path names can run. The default search path (from the /etc/environment file used during login) is: <code>/usr/bin /etc /usr/sbin /usr/ucb /usr/bin/X11 /sbin</code> A shell given neither the -c nor the -t flag normally hashes the contents of the directories in the path variable after reading the .cshrc and also each time the path variable is reset. If new commands are added to these directories while the shell is active, you must give the rehash command, or the commands might not be found.
prompt	Specifies the string displayed before each command is read from an interactive workstation input. If an ! appears in the string, it is replaced by the current event number. If the ! character is in a quoted string enclosed by single or double quotation marks, the ! character must be preceded by a \ . The default prompt for users without root authority is % . The default prompt for the root user is # .
savehist	Specifies a numeric value to control the number of entries of the history list that are saved in the ~/.history file when you log out. Any command referenced in this number of events is saved. During startup, the shell reads ~/.history into the history list, enabling history to be saved across logins. Very large values of the savehist variable slow down the shell startup.
shell	Specifies the file in which the C shell resides. This is used in forking shells to interpret files that have execute bits set, but which are not executable by the system. This is initialized to the home of the C shell.
status	Specifies the status returned by the last command. If the command ends abnormally, 0200 is added to the status. Built-in commands that are unsuccessful return an exit status of 1. Successful built-in commands set status to a value of 0.
time	Controls automatic timing of commands. If this variable is set, any command that takes more than the specified number of CPU seconds will display a line of resources used, at the end of execution. For more information about the default outputs, see the built-in time command.

verbose Set by the **-v** command line flag, this variable causes the words of each command to display after history substitution.

- “C Shell Related Information” on page 234

Input and Output Redirection in the C Shell

Before the C shell executes a command, it scans the command line for redirection characters. These special notations direct the shell to redirect input and output.

You can redirect the standard input and output of a command with the following syntax statements:

- < File** Opens the specified *File* (which is first variable, command, and file name expanded) as the standard input.
- <<Word** Reads the shell input up to the line that matches the value of the *Word* variable. The *Word* variable is not subjected to variable, file name, or command substitution. Each input line is compared to the *Word* variable before any substitutions are done on the line. Unless a quoting character (`\`, `"`, `'` or `.`) appears in the *Word* variable, the shell performs variable and command substitution on the intervening lines, allowing the `\` character to quote the `$`, `\`, and `'` characters. Commands that are substituted have all blanks, tabs, and new-line characters preserved, except for the final new-line character, which is dropped. The resultant text is placed in an anonymous temporary file, which is given to the command as standard input.
- > File**
- >!File**
- >& File**
- >&! File** Uses the specified *File* as standard output. If *File* does not exist, it is created. If *File* exists, it is truncated, and its previous contents are lost. If the **noclobber** shell variable is set, *File* must not exist or be a character special file, or an error results. This helps prevent accidental destruction of files. In this case, use the forms including an `!` to suppress this check. *File* is expanded in the same way as `<` input file names. The form `>&` redirects both standard output and standard error to the specified *File*. The following example shows how to separately redirect standard output to **/dev/tty** and standard error to **/dev/null**. The parentheses are required to allow standard output and standard error to be separate.
- ```
% (find / -name vi -print > /dev/tty) >& /dev/null
```
- >>File**
- >>! File**
- >>& File**
- >>&! File** Uses the specified *File* as standard output like `>`, but *appends* output to the end of *File*. If the **noclobber** shell variable is set, an error results if *File* does not exist, unless one of the forms including an `!` is given. Otherwise, it is similar to `>`.

A command receives the environment in which the shell was invoked, as changed by the input/output parameters and the presence of the command as a pipeline. Thus, unlike some previous shells, commands that run from a shell script do not have access to the text of the commands by default. Rather, they receive the original standard input of the shell. Use the `<<` mechanism to present inline data. This lets shell command files function as components of pipelines and also lets the shell block read its input. Note



that the default standard input for a command run detached is not changed to the empty `/dev/null` file. Rather, the standard input remains the original standard input of the shell.

To redirect the standard error through a pipe with the standard output, use the form `l&` rather than just the `l`.

## Control Flow

The shell contains commands that can be used to regulate the flow of control in command files (shell scripts) and (in limited but useful ways) from shell command-line input. These commands all operate by forcing the shell to repeat, or skip, in its input.

The **foreach**, **switch**, and **while** statements, and the **if-then-else** form of the **if** statement, require that the major keywords appear in a single simple command on an input line.

If the shell input is not searchable, the shell buffers input whenever a loop is being read and searches the internal buffer to do the rereading implied by the loop. To the extent that this is allowed, backward **gotos** succeed on inputs that you cannot search.

- “C Shell Related Information” on page 234

---

## Job Control in the C Shell

The shell associates a job number with each process. It keeps a table of current jobs and assigns them small integer numbers. When you start a job in the background with an `&`, the shell prints a line that looks like:

```
[1] 1234
```

This line indicates that the job number is 1 and that the job is composed of a single process with a process ID of 1234. Use the built-in **jobs** command to see the table of current jobs.

A job running in the background competes for input if it tries to read from the workstation. Background jobs can also produce output for the workstation that gets interleaved with the output of other jobs.

There are several ways to refer to jobs in the shell. Use the `%` character to introduce a job name. This name can be either the job number or the command name that started the job, if this name is unique. So, for example, if a **make** process is running as job 1, you can refer to it as `%1`. You can also refer to it as `%make`, if there is only one suspended job with a name that begins with the string `make`. You can also use: `String`

to specify a job whose name contains the `String` variable, if there is only one such job.

The shell detects immediately whenever a process changes state. If a job becomes blocked so that further progress is impossible, the shell sends a message to the workstation. This message is displayed only after you press the Enter key. If, however, the **notify** shell variable is set, the shell immediately issues a message that indicates changes in the status of background jobs. Use the built-in **notify** command to mark a single process so that its status changes are promptly reported. By default, the **notify** command marks the current process.

- “C Shell Related Information” on page 234

---

## List of C Shell Built-in Commands

|              |                                                                                                |
|--------------|------------------------------------------------------------------------------------------------|
| <b>alias</b> | Displays specified aliases or all aliases.                                                     |
| <b>bg</b>    | Puts the current or specified jobs into the background.                                        |
| <b>break</b> | Resumes running after the end of the nearest enclosing <b>foreach</b> or <b>while</b> command. |



|                 |                                                                                                                                                                                                                                                                                                                                                                         |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>breaksw</b>  | Breaks from a <b>switch</b> command.                                                                                                                                                                                                                                                                                                                                    |
| <b>case</b>     | Defines a label in a <b>switch</b> command.                                                                                                                                                                                                                                                                                                                             |
| <b>cd</b>       | Changes the current directory to the specified directory.                                                                                                                                                                                                                                                                                                               |
| <b>chdir</b>    | Changes the current directory to the specified directory.                                                                                                                                                                                                                                                                                                               |
| <b>continue</b> | Continues execution of the nearest enclosing <b>foreach</b> or <b>while</b> command.                                                                                                                                                                                                                                                                                    |
| <b>default</b>  | Labels the default case in a <b>switch</b> statement.                                                                                                                                                                                                                                                                                                                   |
| <b>dirs</b>     | Displays the directory stack.                                                                                                                                                                                                                                                                                                                                           |
| <b>echo</b>     | Writes character strings to the standard output of the shell.                                                                                                                                                                                                                                                                                                           |
| <b>else</b>     | Runs the commands that follow the second <b>else</b> in an <b>if (Expression) then ...else if (Expression2) then ... else ... endif</b> command sequence.                                                                                                                                                                                                               |
| <b>end</b>      | Signifies the end of a sequence of commands preceded by the <b>foreach</b> command. Also see the <b>while</b> command.                                                                                                                                                                                                                                                  |
| <b>endif</b>    | Runs the commands that follow the second then statement in an <b>if (Expression) then ... else if (Expression2) then ... else ... endif</b> command sequence.                                                                                                                                                                                                           |
| <b>endsw</b>    | Marks the end of a <b>switch (String) case String : ... breaksw default: ... breaksw endsw</b> command sequence. This command sequence successively matches each case label against the value of the <i>String</i> variable. Execution continues after the <b>endsw</b> command if a <b>breaksw</b> command is executed or if no label matches and there is no default. |
| <b>eval</b>     | Reads variable values as input to the shell and executes the resulting command or commands in the context of the current shell.                                                                                                                                                                                                                                         |
| <b>exec</b>     | Runs the specified command in place of the current shell.                                                                                                                                                                                                                                                                                                               |
| <b>exit</b>     | Exits the shell with either the value of the status shell variable or the value of the specified expression.                                                                                                                                                                                                                                                            |
| <b>fg</b>       | Brings the current or specified jobs into the foreground, continuing them if they are stopped.                                                                                                                                                                                                                                                                          |
| <b>foreach</b>  | Successively sets a <i>Name</i> variable for each member specified by the <i>List</i> variable and a sequence of commands, until reaching an <b>end</b> command.                                                                                                                                                                                                        |
| <b>glob</b>     | Displays list using history, variable, and file name expansion.                                                                                                                                                                                                                                                                                                         |
| <b>goto</b>     | Continues to run after a specified line.                                                                                                                                                                                                                                                                                                                                |
| <b>hashstat</b> | Displays statistics indicating how successful the hash table has been at locating commands.                                                                                                                                                                                                                                                                             |
| <b>history</b>  | Displays the history event list.                                                                                                                                                                                                                                                                                                                                        |
| <b>if</b>       | Runs a specified command if a specified expression is true.                                                                                                                                                                                                                                                                                                             |
| <b>jobs</b>     | Lists the active jobs.                                                                                                                                                                                                                                                                                                                                                  |
| <b>kill</b>     | Sends either the <b>TERM</b> (terminate) signal or the signal specified by the <i>Signal</i> variable to the specified job or process.                                                                                                                                                                                                                                  |
| <b>limit</b>    | Limits usage of a specified resource by the current process and each process it creates.                                                                                                                                                                                                                                                                                |
| <b>login</b>    | Ends a login shell and replaces it with an instance of the <b>/usr/sbin/login</b> command.                                                                                                                                                                                                                                                                              |
| <b>logout</b>   | Ends a login shell.                                                                                                                                                                                                                                                                                                                                                     |
| <b>nice</b>     | Sets the priority of commands run in the shell.                                                                                                                                                                                                                                                                                                                         |
| <b>nohup</b>    | Causes hangups to be ignored for the remainder of a procedure.                                                                                                                                                                                                                                                                                                          |
| <b>notify</b>   | Causes the shell to notify you asynchronously when the status of the current or a specified job changes.                                                                                                                                                                                                                                                                |
| <b>onintr</b>   | Controls the action of the shell on interrupts.                                                                                                                                                                                                                                                                                                                         |
| <b>popd</b>     | Pops the directory stack and returns to the new top directory.                                                                                                                                                                                                                                                                                                          |
| <b>pushd</b>    | Exchanges elements of the directory stack.                                                                                                                                                                                                                                                                                                                              |
| <b>rehash</b>   | Causes recomputation of the internal hash table containing the contents of the directories in the path shell variable.                                                                                                                                                                                                                                                  |
| <b>repeat</b>   | Runs the specified command, subject to the same restrictions as the <b>if</b> command, the number of times specified.                                                                                                                                                                                                                                                   |
| <b>set</b>      | Shows the value of all shell variables.                                                                                                                                                                                                                                                                                                                                 |
| <b>setenv</b>   | Modifies the value of the specified environment variable.                                                                                                                                                                                                                                                                                                               |
| <b>shift</b>    | Shifts the specified variable to the left.                                                                                                                                                                                                                                                                                                                              |
| <b>source</b>   | Reads command specified by the <i>Name</i> variable.                                                                                                                                                                                                                                                                                                                    |
| <b>stop</b>     | Stops the current or specified jobs running in the background.                                                                                                                                                                                                                                                                                                          |
| <b>suspend</b>  | Stops the shell as if a <b>STOP</b> signal has been received.                                                                                                                                                                                                                                                                                                           |

|                 |                                                                                                                                                                                                                                                                                                                               |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>switch</b>   | Starts a <b>switch (String) case String : ... breaksw default: ... breaksw endsw</b> command sequence. This command sequence successively matches each case label against the value of the <i>String</i> variable. If none of the labels match before a default label is found, the execution begins after the default label. |
| <b>time</b>     | Displays a summary of the time used by the shell and its child processes.                                                                                                                                                                                                                                                     |
| <b>umask</b>    | Determines file permissions.                                                                                                                                                                                                                                                                                                  |
| <b>unalias</b>  | Discards all aliases with names that match the <i>Pattern</i> variable.                                                                                                                                                                                                                                                       |
| <b>unhash</b>   | Disables the use of the internal hash table to locate running programs.                                                                                                                                                                                                                                                       |
| <b>unlimit</b>  | Removes resource limitations.                                                                                                                                                                                                                                                                                                 |
| <b>unset</b>    | Removes all variables having names that match the <i>Pattern</i> variable.                                                                                                                                                                                                                                                    |
| <b>unsetenv</b> | Removes all variables from the environment whose names match the specified <i>Pattern</i> variable.                                                                                                                                                                                                                           |
| <b>wait</b>     | Waits for all background jobs.                                                                                                                                                                                                                                                                                                |
| <b>while</b>    | Evaluates the commands between the <b>while</b> and the matching <b>end</b> command sequence while an expression specified by the <i>Expression</i> variable evaluates nonzero.                                                                                                                                               |
| <b>@</b>        | Displays the value of specified shell variables.                                                                                                                                                                                                                                                                              |

See “C Shell Built-In Commands” on page 214 for more information.

---

## C Shell Related Information

“Chapter 11. Shells” on page 149

“C Shell Commands” on page 214

“History Substitution in the C Shell” on page 222

“Alias Substitution in the C Shell” on page 225

“Variable and File Name Substitution in the C Shell” on page 226

“Environment Variables in the C Shell” on page 229

“Input and Output Redirection in the C Shell” on page 231

“Job Control in the C Shell” on page 232

The **cs**h command, **ed** command.

The **alias**, **unalias**, **jobs**, **notify** and **set** C Shell built-in commands.

---

## Chapter 12. Miscellaneous Tools and Utilities

The following are some common tasks that you can perform by using operating system commands. The command and an example of how to use the command are presented for each of the following:

- “Locating a Command by Keyword (apropos Command)”
- “Displaying a Calendar (cal Command)”
- “Displaying Reminder Messages (calendar Command)” on page 236
- “Displaying Help Information for New Users (help Command)” on page 236
- “Starting Computer-Aided Instruction Courses (learn Command)” on page 237
- “Reminding Yourself When to Leave (leave Command)” on page 237
- “Factoring a Number (factor Command)” on page 238
- “Converting Units of Measure (units Command)” on page 238
- “Sending Messages to Another Logged-In User (write Command)” on page 240
- “Command Summary for Miscellaneous Tools and Utilities” on page 243

---

### Locating a Command by Keyword (apropos Command)

You can display the manual sections that contain any of the given *Keywords* in their title with the **apropos** command. The **apropos** command considers each word separately and does not take into account if a letter is in uppercase or lowercase. Words that are part of other words are also displayed. For example, when looking for the word `compile`, the **apropos** command also finds all instances of the word `compiler`.

The **apropos** command is equivalent to using the **man** command with the **-k** option.

For example, to find the manual sections that contain the word `password` in their titles, type:

```
apropos password
```

Press Enter.

See the **apropos** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

---

### Displaying a Calendar (cal Command)

The **cal** command writes to standard output a calendar for the specified year or month.

The *Month* parameter names the month for which you want the calendar. It can be a number from 1 through 12 for January through December, respectively. If no *Month* is specified, the **cal** command defaults to the current month.

The *Year* parameter names the year for which you want the calendar. Because the **cal** command can display a calendar for any year from 1 through 9999, type the full year rather than just the last two digits. If no *Year* is specified, the **cal** command defaults to the present year.

For example, to display a calendar for February 1984 at your workstation, type:

```
cal 2 1984
```

Press Enter.

For example, to print a calendar for 1984, type:

```
cal 1984 | qprt
```

Press Enter.

For example, to display a calendar for the year 84 A.D., type:

```
cal 84
```

Press Enter.

See the **cal** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

---

## Displaying Reminder Messages (calendar Command)

You can read a file named **calendar**, which you create in your home directory with the **calendar** command. The command writes to standard output any line in the file that contains today's or tomorrow's date.

The **calendar** command recognizes date formats such as Dec. 7 or 12/7. It also recognizes the special character \* (asterisk) when it is followed by a / (slash). It interprets \*/7, for example, as signifying the seventh day of every month.

On Fridays, the **calendar** command writes all lines containing the dates for Friday, Saturday, Sunday, and Monday. It does not, however, recognize holidays, so it will function as usual and give only the next day's schedule.

A typical **calendar** file might look like the following:

```
*/25 - Prepare monthly report
Aug. 12 - Fly to Denver
aug 23 - board meeting
Martha out of town - 8/23, 8/24, 8/25
8/24 - Mail car payment
sat aug/25 - beach trip
August 27 - Meet with Simmons
August 28 - Meet with Wilson
```

If today is Friday, August 24, then the **calendar** command displays the following:

```
*/25 - Prepare monthly report
Martha out of town - 8/23, 8/24, 8/25
8/24 - Mail car payment
sat aug/25 - beach trip
August 27 - Meet with Simmons
```

See the **calendar** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

---

## Displaying Help Information for New Users (help Command)

You can present a one-page display of information with the **help** command.

At the prompt, type:

```
help
```

Press Enter.

The system displays information similar to the following:

```
Look in a printed manual for general help if you can. You should
have someone show you some things and then read "Using and Managing
AIX" manual.
```

The commands:

```

man -k keyword lists commands relevant to a keyword
man command prints out the manual pages for a command

```

are helpful; other basic commands are:

```

cat - concatenates files (and just prints them out)
ex - text editor
ls - lists contents of directory
mail - sends and receives mail
passwd - changes login password
scscshelp - views information on the Source Code Control System
smit - system management interface tool
tset - sets terminal modes
who - who is on the system
write - writes to another user

```

You could find programs about mail by the command: `man -k mail`  
and print out the man command documentation via: `man mail`  
You can log out by typing "exit".

See the **help** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

---

## Starting Computer-Aided Instruction Courses (learn Command)

You can practice using files, editors, macros, and other features with the **learn** command, which provides computer-aided instruction courses. The first time you use the **learn** command, you are guided through a series of questions to determine what type of instruction you want to receive. After the first time, you are positioned at the place where you ended your previous **learn** command session.

The **learn** command searches for the first lesson containing the subject you specified. You can specify any of the following as subjects:

- Files
- Editor
- More files
- Macros
- EQN
- C.

For example, to take the online lesson about files, type:

```
learn files
```

Press Enter.

You will then be prompted for further input.

See the **learn** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

---

## Reminding Yourself When to Leave (leave Command)

You can have the system remind you to leave at a specified time with the **leave** command. You are reminded at 5 minutes and 1 minute before the actual time, then again at the specified time, and at every minute thereafter. When you log out, the **leave** command exits just before it would have displayed the next message.

If you do not specify a time, the **leave** command prompts with When do you have to leave? A reply of newLine causes the **leave** command to exit; otherwise, the reply is assumed to be a time. This form is suitable for inclusion in a **.login** or **.profile** file.

Enter the time in the *hhmm* format. All times are converted to a 12-hour clock and assumed to relate to the next 12 hours. You can use the **+** flag to set the number of hours and minutes from the current time for the alarm to go off.

**Note:** The **leave** command ignores interrupt, quit, and terminate operations. To clear the **leave** command, you should either log out or use the **kill -9** command and provide the process ID.

For example, to remind yourself to leave at 3:45, type:

```
leave 345
```

Press Enter.

For example, to remind yourself to leave in 20 minutes, type:

```
leave +0020
```

Press Enter.

See the **leave** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

---

## Factoring a Number (factor Command)

You can factor numbers with the **factor** command. When called without specifying a value for the *Number* parameter, the **factor** command waits for you to enter a positive number less than 1E14 (100,000,000,000,000). It then writes the prime factors of that number to standard output. It displays each factor the proper number of times. To exit, enter 0 (zero) or any non-numeric character.

When called with an argument, the **factor** command determines the prime factors of the *Number* parameter, writes the results to standard output, and exits.

For example, to calculate the prime factors of 123, type:

```
factor 123
```

Press Enter.

The following is displayed:

```
123
3
41
```

See the **factor** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

---

## Converting Units of Measure (units Command)

You can convert quantities expressed in one measurement to their equivalents in another with the **units** command. The **units** command is an interactive command. It prompts you for the unit you want to convert from and the unit you want to convert to.

**Note:** This command only does multiplicative scale changes. That is, it can convert from one value to another only when the conversion involves a multiplication. For example, it cannot convert between degrees Fahrenheit and degrees Celsius because the value of 32 must be added or subtracted in the conversion.

The **units** command recognizes **lb** as a unit of mass, but considers **pound** to be the British pound sterling. Compound names are run together (such as **lightyear**). Prefix British units differing from their

American counterparts with **br** (**brgallon**, for instance). The **/usr/share/lib/unittab** file contains a complete list of the units that the **units** command uses. You can also define new units in the **unittab** file or create and use your own *File* that overrides the standard conversion factor values in the **unittab** file.

Most familiar units, abbreviations, and metric prefixes are recognized by the **units** command, as well as the following:

|              |                                        |
|--------------|----------------------------------------|
| <b>pi</b>    | Ratio of circumference to diameter     |
| <b>c</b>     | Speed of light                         |
| <b>e</b>     | Charge on an electron                  |
| <b>g</b>     | Acceleration of gravity                |
| <b>force</b> | Same as <b>g</b>                       |
| <b>mole</b>  | Avogadro's number                      |
| <b>water</b> | Pressure head per unit height of water |
| <b>au</b>    | Astronomical unit                      |

For example, to display conversion factors for inches to centimeters, type:

```
units
```

```
you have: in
you want: cm
```

Press Enter.

The **units** command returns the following values:

```
* 2.540000e+00
/ 3.937008e-01
```

The output tells you to multiply the number of inches by 2.540000e+00 to get centimeters, and to multiply the number of centimeters by 3.937008e-01 to get inches.

These numbers are in standard exponential notation, so 3.937008e-01 means  $3.937008 \times 10^{-1}$ , which is the same as 0.3937008.

**Note:** The second number is always the reciprocal of the first; for example, 2.54 equals  $1/0.3937008$ .

For example, to convert a measurement to different units, type:

```
units
you have: 5 years
you want: microsec
```

Press Enter.

The **units** command returns the following values:

```
* 1.577846e+14
/ 6.337753e-15
```

The output shows that 5 years equals  $1.577846 \times 10^{14}$  microseconds, and that one microsecond equals  $6.337753 \times 10^{-15}$  years.

For example, to give fractions in measurements, type:

```
units
you have: 1|3 mi
you want: km
```

Press Enter.

The **units** command returns the following values:

```
* 5.364480e-01
/ 1.864114e+00
```

The | (vertical bar) indicates division, so 1|3 means one-third. This shows that one-third mile is the same as 0.536448 kilometers.

For example, to include exponents in measurements, type:

```
units
you have: 1.2-5 gal
you want: floz
```

Press Enter.

The **units** command returns the following values:

```
* 1.536000e-03
/ 6.510417e+02
```

The expression 1.2-5 gal is the equivalent of  $1.2 \times 10^{-5}$ . Do *not* type an e before the exponent (that is, 1.2e-5 gal is not valid). This example shows that  $1.2 \times 10^{-5}$  (0.000012) gallons equal  $1.536 \times 10^{-3}$  (0.001536) fluid ounces.

If the units you specify after you have: and you want: are incompatible:

```
you have: ft
you want: lb
```

The **units** command returns the following message and values:

```
conformability
3.048000e-01 m
4.535924e-01 kg
```

The conformability message means the units you specified cannot be converted. Feet measure length, and pounds measure mass, so converting from one to the other does not make sense. Therefore, the **units** command displays the equivalent of each value in standard units.

In other words, this example shows that one foot equals 0.3048 meters and that one pound equals 0.4535924 kilograms.

See the **units** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

---

## Sending Messages to Another Logged-In User (write Command)

You can send messages to other users over the system in real time with the **write** command. It provides conversation-like communication with another logged-in user. Each user alternately sends and receives short messages from the other workstation. Long messages can be sent by putting the complete message in a file and then redirecting that file as input to the **write** command.

When the **write** command is issued, it immediately sends the following message, along with an attention-getting sound (the ASCII BEL character) to the message recipient or target:

```
Message from SenderID on SenderHostname (ttynn) [Date] ...
```

With a successful connection, the **write** command sends two ASCII BEL characters to both workstations. The beep alerts the sender that the message can begin, and it alerts the receiving user that a message is coming.



For example, to write a message to user `june` who is logged in, type:

```
write june
```

Press Enter.

Type:

```
I need to see you! Meet me in the computer room at 12:30.
```

Press Enter.

Then press the Ctrl-D key sequence to terminate the **write** command mode.

If your user ID is `karen` and you are using workstation `tty3`, `june`'s workstation displays:

```
Message from karen on trek tty3 Aug 17 11:55:24 ...
I need to see you! Meet me in the computer room at 12:30.
<EOT>
```

For example, to hold a conversation with user `june`, type:

```
write june
```

Press Enter.

Type:

```
Meet me in the computer room at 12:30.o
```

Press Enter.

This starts the conversation. The `o` at the beginning of the next line means the message is over. It tells `June` that you are waiting for a response. Do not press Ctrl-D if you wish to continue.

Now `June` replies by typing:

```
write karen
```

She presses the Enter key and types:

```
I'm running tests at 12:30. Can we meet at 3?
o
```

And you might respond:

```
OK--the computer room at 3.
oo
```

The `oo` means "over and out," telling `June` that you have nothing more to say. If `June` is also finished `oo`, then you both press Ctrl-D to end the conversation.

For example, to write user `june` a prepared message, type:

```
write june < message.text
```

Press Enter.

This writes the contents of the **message.text** file to `june`'s workstation.

For example, to write to the person using the workstation `console`, type:

```
write console
```

Press Enter.

Type:

```
The printer in building 998 has jammed.
Please send help.
```

Press Enter.

Then press the Ctrl-D key sequence.

This writes the message to the person logged in at the workstation `/dev/console`.

You can use the **write** command to converse with users on other hosts. You can identify a user on a remote host by using the **-n***Hostname* flag or the *User@Host* parameter. In order to write to a user on a remote host, the **writesrv** daemon must be running on both the current host and the remote host.

For example, to send a message to user spuds at remote host partya, type:

```
write -n partya spuds
```

Press Enter.

Type:

```
Your new tape has just arrived,
come see me to pick it up.
Thanks!
```

Press Enter.

Then press the Ctrl-D key sequence.

OR

```
write spuds@partya
```

Type:

```
Your new tape has just arrived,
come see me to pick it up.
Thanks!
```

Press Enter.

Then press the Ctrl-D key sequence.

See the **write** command in the *AIX 5L Version 5.1 Commands Reference* for the exact syntax.

## Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 9. File and System Security” on page 119

“Chapter 2. User Environment and System Information” on page 11

---

## Command Summary for Miscellaneous Tools and Utilities

|                 |                                                                                                                |
|-----------------|----------------------------------------------------------------------------------------------------------------|
| <b>apropos</b>  | Locates commands by keyword lookup.                                                                            |
| <b>cal</b>      | Displays a calendar.                                                                                           |
| <b>calendar</b> | Writes reminder messages to standard output.                                                                   |
| <b>factor</b>   | Factors a number.                                                                                              |
| <b>help</b>     | Provides help information for new users.                                                                       |
| <b>learn</b>    | Provides computer-aided instruction courses and practice for using files, editors, macros, and other features. |
| <b>leave</b>    | Provides reminder messages.                                                                                    |
| <b>units</b>    | Converts units in one measure to equivalent units in another measure.                                          |
| <b>write</b>    | Sends messages to other users on the system.                                                                   |

### Related Information

“Commands Overview” on page 20

“Processes Overview” on page 30

“File Systems” on page 52

“Directory Overview” on page 55

“Chapter 6. Files” on page 67

“Chapter 9. File and System Security” on page 119

“Chapter 2. User Environment and System Information” on page 11



---

## Chapter 13. Documentation Library Service

---

### Introduction

The Documentation Library Service allows you to read, search, and print online HTML documents. It provides a library application that appears in your web browser. The application includes links to read installed documents and a search form that you can use to search for text. When you search, a results page displays the results of the search with links to the documents containing the search target words.

Starting with AIX 5.1, you can also download printable versions of books by using the **Print Tool** button in the documentation library service form.

Two types of forms are provided: a global search form that shows all the volumes installed on a search server, and a specific search form that just searches a specific set of volumes such as the manuals for an application.

The documentation library service allows you to search documents that have been registered with the search service. Registration is done by the system administrator. You cannot search the Internet or any unregistered documents on your search server.

If you write HTML documents at your site, your system administrator can add these documents to the documentation library so that you can read, search, and print the documents.

---

### Using the Documentation Library Service

To use the Library:

- To read the documentation installed in your system's default library, do one of the following:
  - Type `docsearch` at the command line.
  - Open the CDE Desktop Help subpanel. Click on the documentation search service icon, which looks like binoculars.

**Note:** If you have a copy of the AIX 4.3 (or later version) CD, you can read it on a PC. Insert the CD into the CD-ROM drive on your PC. If the documentation CD is AIX 4.3.3 or newer, use a web browser to open the CD file called **readme.htm** that is in the top directory of the CD. If you have a AIX 4.3.0 to AIX 4.3.2 version of the Base Documentation CD, open the **usr/share/man/info/en\_US/a\_doc\_lib/aixgen/topnav/topnav.htm** file:

- To open a library stored on a remote documentation server, in your browser's location bar type the following URL:

```
http://server_name[:port_number]/cgi-bin/ds_form
```

This URL opens the global search form to search the documents stored on the server with the name you specified in *server\_name*.

**Note:** You only need to type the *port\_number* if the port is not the standard 80.

For example, if you want to search the registered documents on a search server named *hinson* and it uses port 80, type:

```
http://hinson/cgi-bin/ds_form
```

Once the search form for a server appears in your browser, you can create a bookmark that takes you back to the server. Your system administrator can also create a web page that contains links to all the different documentation servers in an organization.

The documentation is also available for reading and searching at the Internet site [www.ibm.com/servers/aix/library](http://www.ibm.com/servers/aix/library). Note that while this site contains the base operating system manuals, it might not contain other documentation installed on your local documentation server.

- **Specific search forms** are usually launched from search links inside HTML documents. They typically appear on the pages of applications manuals or help files. For example, a "search" link is on each page in the library. Clicking on one of these search links launches a specific search form that allows you to search just the library volumes.
- Select the volumes you want to search. Click on the checkbox next to each volume name displayed. By default, all volumes are searched unless you specify otherwise.

After the library application opens, you can click on the Help link in the upper right corner for instructions on how to use the library.

---

## How to Change the Documentation Library Service Language

By default, when you open the CDE Desktop icons for the operating system Documentation Search Service or the Base Library, the documents that are displayed appear in the same language as your CDE Desktop.

However, you might need to see the documentation in a language that is different than your desktop language. For example, your desktop runs in your native language but the manuals may only be available in English. You can change your documentation language so that documents appear in a different language than that used in your desktop.

### Notes:

1. These techniques do not affect the language used if you are opening a document or search form from an HTML link inside another document. These techniques only affect the language used for the Documentation Search Service or the Base Library desktop icons.
2. Make sure there is documentation installed for the language you want to use.

You can change your documentation language by running the following command:

```
/usr/bin/chdoclang locale
```

Where *locale* is replaced by the locale name that is the new language for viewing and searching documentation. Locale names can be found in the Locale Naming Conventions in *AIX 5L Version 5.1 System Management Concepts: Operating System and Devices*.

### Notes:

1. You must log out and then log back in to see the language change take effect.
2. If you are using the CDE Desktop, you must also edit your Desktop file **\$HOME/.dtprofile** so that your documentation language setting in your **\$HOME/.profile** file will be read during CDE login. To do this, complete the following steps:
  - Open your **.dtprofile** file in the dtpad editor by typing the following command:

```
dtpad $HOME/.dtprofile
```
  - Find the line that contains the text:

```
DTSOURCEPROFILE=true
```
  - If there are any comment (**#**) characters at the start of that line, delete just the **#** characters, not the entire line. If there are no comment characters, close the editor.
  - Save your changed **.dtprofile** file.
  - Log out and log back in.

For example, if you want to change your documentation language to Spanish (es\_ES), type the following command:

```
/usr/bin/chdoclang es_ES
```

Log out and log back in to your desktop.

After you change your documentation language, you can delete the language setting so that documentation will again appear in the same language as your desktop. To delete your language setting, type the following command:

```
/usr/bin/chdoclang -d
```

Log out and log back in to your desktop.





---

## Appendix A. Accessing Information with InfoExplorer

**Note:** InfoExplorer is no longer shipped with the base operating system. Documentation is now viewed using the Documentation Library Service. This section is included for legacy users who are still using InfoExplorer from a previous release.

This section describes the different types of documentation available in the *Hypertext Information Base Library* and how you can use InfoExplorer to access information.

---

### Using the InfoExplorer ASCII Interface

The InfoExplorer program ASCII interface provides a tutorial for first-time users and contains procedures for performing other tasks as described in the following overview.

The InfoExplorer program is the tool you use to learn about this operating system and other software. As an ASCII interface user, you have access to many volumes of software and hardware documentation. Because InfoExplorer information is *hypertext*, you can read this information without turning a single page. Instead, you view the information on your display and select links to move from one "article" to another. This way, you can choose your own path through the hypertext documentation.

### Using InfoExplorer Screens

In the InfoExplorer ASCII interface, different screens contain different types of information. For example, you use some screens specifically for moving around. These screens, which include the Topic & Task Index and the Books, are *navigation* screens. The InfoExplorer program displays one navigation screen at a time. The contents of this screen are replaced each time you select a function that displays its information in this location.

Another type of screen contains the text you want to read. These are called *reading* screens. Reading screens provide conceptual, procedural, or reference information. They display articles that teach you about a topic, explain how to do something, or provide you with information about commands, calls, subroutines, files, or file formats.

From navigation and reading screens you can open other screens to perform specific tasks. The InfoExplorer program provides the following task-oriented screens:

|                            |                                                                                                                                                           |
|----------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Simple Search</b>       | Handles searches on a title or information base for a single set of words.                                                                                |
| <b>Compound Search</b>     | Handles searches on compound search strings within one or more selected information bases.                                                                |
| <b>Search Matches List</b> | Displays where search matches were found, how many matches were found, and the number of articles in which they were found.                               |
| <b>Glossary</b>            | Displays a glossary term or phrase selected from a reading screen.                                                                                        |
| <b>Defaults Editor</b>     | Allows you to set default values for various InfoExplorer functions.                                                                                      |
| <b>Preferences Editor</b>  | Provides a way to customize InfoExplorer program options.                                                                                                 |
| <b>List of Links</b>       | Allows you to select a previous link and access the information, delete a previous link from the list, clear all of the lists, or rename a previous link. |
| <b>List of Files</b>       | Allows you to load a previously saved file, save a list to a file, or delete a file.                                                                      |

When you start a session, the InfoExplorer program displays first the navigation screen and then the reading screen. The reading screen contains the "Welcome to the InfoExplorer ASCII Interface" article, which shows you how to perform basic operations and explains how to access InfoExplorer Help, copyrights, and trademarks. Return to the navigation screen by typing Ctrl-w.

## Using Menus

The InfoExplorer ASCII interface displays a menu bar at the top of each screen. You select options in the menus to access specific InfoExplorer features.

## Getting Help

To get more information on how to use the InfoExplorer program, you can use InfoExplorer Help. By using Help, you can find out more information on using the current screen. Or you can move to a list of articles that explain how the InfoExplorer program works.

To get Help, press the Ctrl-O key sequence, use the arrow keys to highlight the word **Help**, and press the Enter key. You can then choose between the following options:

|                      |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>On Screen</b>     | Displays specific help information for the screen you are viewing, including links to articles that describe the screen, as well as functions available from that screen and a list of menus available in the screen, with links to descriptions of the menu options.<br><br>You can select links to display information that you want to read. To return to the help information screen after selecting a link, use the <b>Path</b> or <b>.History</b> menu option on the menu bar. |
| <b>List of Helps</b> | Displays the <b>List of Helps</b> , a list of hypertext links to articles that describe key aspects of the InfoExplorer program and documentation, along with links to the helps for each individual screen.                                                                                                                                                                                                                                                                         |

---

## Getting Started

**Note:** InfoExplorer is no longer shipped with the base operating system. Documentation is now viewed using the Documentation Library Service. This section is included for legacy users who are still using InfoExplorer from a previous release.

The InfoExplorer program is a powerful text retrieval tool with several information navigation aids to help you find and manage information. Learning just a few of these aids, however, is all you need to begin using it. Use the basic procedures that you learn in this section to explore in the InfoExplorer information base where you will find useful information.

Follow the tutorial step-by-step using the Page Up and Page Down keys on the keyboard, or link to individual procedures.

In this article you learn about:

- “Starting the InfoExplorer ASCII Program” on page 251
- “Recognizing Screen Types” on page 251
- “Selecting a Hypertext Link” on page 252
- “Scrolling Information” on page 252
- “Selecting a Menu Option” on page 253
- “Returning to a Previous Location” on page 253
- “Searching for Information” on page 254
- “Printing Information” on page 256
- “Accessing Help” on page 257
- “Using Special Keys and Key Sequences” on page 258
- “Starting an Alternate InfoExplorer Library” on page 259
- “Stopping the InfoExplorer ASCII Program” on page 259

## Starting the InfoExplorer ASCII Program

To start the InfoExplorer program, type `info` at an operating system command prompt and press the Enter key.

**Note:** If you want to start InfoExplorer ASCII within a window, type `info -a` at an operating system prompt, and press the Enter key.

Either the "Welcome to the InfoExplorer ASCII Interface" article or the "Navigation Screen" displays in the reading screen. The welcome screen explains how to do basic screen operations and how to access InfoExplorer Help, copyrights, and trademarks.

## Recognizing Screen Types

Two primary screen types exist in the InfoExplorer program: the "Navigation Screen", and the "Reading Screen".

### Navigation Screen

The navigation screen is the starting point for finding documentation about the operating system and other programs available on your workstation and contains information designed to assist you in finding the desired documentation. Information is organized by topic and task, by book, or alphabetically by commands or programming reference item. The primary navigation routes display in the navigation screen:

|                               |                                                                                         |
|-------------------------------|-----------------------------------------------------------------------------------------|
| <b>Topic &amp; Task Index</b> | Displays information by task. It is the default navigation article.                     |
| <b>Commands</b>               | Displays an alphabetical list of available commands.                                    |
| <b>Books</b>                  | Displays articles in book order.                                                        |
| <b>Programming Reference</b>  | Displays lists of programming functions in alphabetical order by functional categories. |

**Note:** The navigation information in this section applies to the InfoExplorer program. The navigation information might or might not apply to other libraries.

The first line of the screen contains the menu bar, and the second line displays a reverse-video title bar. The title of the screen displays at the right end of the title bar. This title bar also separates the menu options from the article text.

While you are viewing the InfoExplorer program through the ASCII interface, only one navigation screen is available at a time. Each time you select a link to another navigation article, the contents of the article you select replace the contents of the original article. For example, if you are viewing the Topic & Task Index and decide to view Commands, a list of commands replaces the Topic & Task index in the navigation screen.

### Reading Screen

The reading screen contains procedural, conceptual, and reference information. Procedural information explains how to accomplish a task, conceptual information discusses various topics, and reference information provides you with information about commands, subroutines, and so on.

As in the navigation screen, the first line of the screen displays the menu options, and the second line displays a reverse-video title bar. "Info Document" displays at the right end of the title bar. This title bar also separates the menu options from the article text.

While you are viewing the InfoExplorer program through the ASCII interface, only one reading screen is available at a time. Each time you select a link to another article, the contents of the article you select replace the contents of the original article. For example, if you are viewing the "Starting the InfoExplorer

Program (ASCII Interface)" article and decide to view the **info** command article, the **info** command article replaces the "Starting the InfoExplorer Program (ASCII Interface)" article in the reading screen.

## To Move between the Screens

To display the navigation screen from the reading screen (or to go back to a current reading screen from the navigation screen), press and hold the Control key (Ctrl) and press the w key (Ctrl-w). The Ctrl-w key sequence toggles between the navigation screen and the reading screen. You can also move between the screens using menu options available on the menu bar.

Before you continue, toggle back and forth a few times between the navigation and reading screens. Note the differences between them.

Some additional screen types are *search*, *glossary*, *file*, and *utility*. To find out more about the various screen types, see the online InfoExplorer article "To Access Help on a Specific Screen" on page 257.

## Selecting a Hypertext Link

Suppose you need information about how to print a file on a line printer. You could start the search with a primary navigation route such as the List of Tasks. From the List of Tasks, you can follow hypertext links until you reach the screen containing the information you want.

A hypertext link is a connection between one piece of information and another. These links display as underlined text. When you move to a link, the link changes to reverse video. To display the target or connected piece of information, press the Enter key.

The Welcome screen displays five links. They appear as a list of five underlined items.

To move to the next hypertext link, press either the Tab key or the Ctrl-f key sequence. If the next link is not currently visible on the screen, the screen is updated to show the link. To move back to the previous link, press the Ctrl-b key sequence.

To select a hypertext link, follow these steps:

1. If the text cursor is not in the text area of the screen, press the Ctrl-o key sequence.
2. Move to the next hypertext link by pressing the Tab key or the Ctrl-f key sequence.
3. Move to the previous link by pressing the Ctrl-b key sequence.
4. To select the link, press the Enter key. The target text appears on the screen.

Practice moving the cursor from one link to another with the Ctrl-f and Ctrl-b key sequences. Before you continue with the next section, try selecting one of the links in the Welcome screen. Remember that you can return to the primary navigation screen by pressing the Ctrl-w key sequence.

**Note:** To avoid losing this screen, do not select any links in this article.

You cannot display artwork on an ASCII terminal. When a link to a piece of artwork is selected, a pop-up panel displays with a message that the artwork cannot be displayed. The message prompts you to press a key to continue. For example, command articles contain syntax diagrams that can only be viewed on a graphics display. However, you can view the brackets-and-braces version of the syntax on an ASCII terminal.

## Scrolling Information

You can move forward and backward through text displayed in either the navigation screen or in the reading screen by using keys and key sequences that have been defined for this purpose. For more information, see "Using Special Keys and Key Sequences" on page 258".

- To move to the previous screen, use either the Page Up key or the Ctrl-P key sequence.
- To move to the next screen, use either the Page Down key or the Ctrl-N key sequence.
- To move the text cursor up one line, press the Up Arrow key.
- To move the text cursor down one line, press the Down Arrow key.

Before you continue, try moving up and down through the text on the terminal screen.

## Selecting a Menu Option

Each InfoExplorer screen contains a menu bar that is located across the top of the screen. The menu bars contain many of the menus that you need to use InfoExplorer features. For example, the Display menu allows you to choose the navigation document you want to display in the navigation screen and the Help menu provides you with help on using the InfoExplorer program.

To select a menu option, do the following:

1. Activate the menu bar by pressing the Ctrl-O key sequence.
2. Use the Left and Right Arrow keys to highlight the title of the menu you want to display and press Enter, or type the underlined character in the menu title. The menu is displayed as a pull-down panel with several options.
3. Use the Up and Down Arrow keys to highlight a menu option and press Enter, or type the underlined character in the menu option. The option you select is invoked or another menu is displayed in a pop-up panel. The menu options are displayed in the menu bar of this menu.

After you display a menu, you might want to remove it without selecting an option. To do this, press the Ctrl-O key sequence. The cursor returns to the screen.

To select an option in a pop-up panel, do the following:

1. Activate the menu bar as you normally would, using the Ctrl-O key sequence.
2. Highlight an option by either typing the underlined character in the option that you want, or by using the Left and Right Arrow keys.
3. Select the option by pressing the Enter key. The pop-up panel closes and the appropriate action is taken.

After you display a pop-up panel, you might want to remove it without selecting an option. To do this, press the Ctrl-O key sequence and select **Quit** in the menu bar.

Before you continue with the next section, practice using menus. Try displaying the Path menu and selecting the **Show List** option. A pop-up panel displays the Path list. To close the pop-up panel, select **Quit** in the menu bar.

**Note:** To avoid losing this article, do not select a location from the Path list.

## Returning to a Previous Location

During the InfoExplorer session, the InfoExplorer program keeps two different records of where you have previously been: the History List and the Path List. These lists enable you to return to previous locations in the information base.

The History List records every location that you have been in the information base. To view the History List, display the .History menu and select the **List All** option. To learn how to use the History List, go to the Help menu and select the **List of Helps** from the pull-down menu. **Finding Information in InfoExplorer** in the List of Helps provides information about the History function.

The Path List keeps track of your navigation route starting with a primary navigation article (Topic & Task Index, Books, Commands, or Programming Reference). Every time you return to a primary navigation screen, your previous path list is overwritten.

The Path menu contains three options: **Show List**, **Previous**, and **Next**. Use the **Show List** option to display the Path List. Use the **Previous** and **Next** options to jump to the previous or next location without displaying the Path List.

To return to a previous location in the InfoExplorer program, do the following:

1. Activate the menu bar by pressing the Ctrl-O key sequence.
2. Type P to display the Path menu.
3. Type S to display the Path List. A pop-up box displays a list of locations in the path. If you are in a primary navigation screen, you receive a message stating that the Path List is empty.
4. Highlight the location that you want to return by using the Up and Down Arrow keys.
5. Select the **Go to** option in the menu bar. The text displays in the reading screen.

Before you continue, try following the path up and down using the **Next** and **Previous** options. Remember, if you follow the path back to a primary navigation article (such as the Task Index), your path list is wiped out and you are unable to follow a path down until you start a new path. If you want to return to a location that is not in the current path, use the History function.

**Note:** To avoid losing this screen, do not use the Path function from this screen.

## Searching for Information

The early part of this chapter described how to find information using primary navigation routes. But what if you do not know what the task or command is or in which book the information might be? You can search on virtually every word in the InfoExplorer information base. Using the InfoExplorer search facility, you can look for information by word or phrase.

Two types of searches are available in the InfoExplorer program: the simple search and the compound search. The *simple search* allows you to search on a word or string of words (in exact order) in text, article titles, or both. (In the ASCII version of InfoExplorer, the Article Title selection on the Search menu gives you a simple search of article titles.) The *compound search* allows you to search on a word, set of words, or several sets of words. You can further specify the search with the following options:

- **AND**, **OR**, and **BUT NOT** connective options
- Proximity options
- Search categories

You can specify the information bases to be searched for both simple and compound searches. There are two ways to specify an information base selection:

- You can specify a temporary information base selection from the Compound Search window. This selection applies to both simple and compound searches, and stays in effect for the current session of InfoExplorer, or until you change it during the session.
- You can specify an information base selection as a default by choosing Defaults from the info menu, and selecting the **DBselect** option. An information base selection made from the Defaults window applies to both simple and compound searches, and stays in effect for future sessions of Info. (Temporary information base selections made from the Compound Search window can override the default selection during an InfoExplorer session, but the default selection returns when you restart InfoExplorer.)

As an example, the following steps take you through a simple search for the **qprt** command, and then further specify the search with a database selection from the Compound Search menu.



**Note:** To avoid losing this article, do not attempt to perform a search from this screen. If your system is set up to print, you can print a copy of this article using the info menu by selecting the **Print Article** option. Use the printed copy to follow the procedure.

To perform a simple search for the **qprt** command, follow these steps:

1. Display the Search menu in the menu bar.
2. Select the **Simple** option in the Search menu. The Simple Search pop-up panel displays.
3. In the Find field, type **qprt** command and press the Enter key. The Search Match List pop-up panel displays the following information:
  - Information bases where search matches were found
  - The number of matches that were found
  - The number of articles in which they were found
4. Using the Up and Down Arrow keys, highlight **User Guides, System Management Guides, and Commands Reference** from the list of information bases and press the Enter key. The Search: List of Titles pop-up panel displays with the list of article titles that contain the search string (**qprt**).

**Note:** If only one article contains the search string, that article displays in a reading screen (no pop-up panels are displayed).

5. Select the second title on the list **qprt Command**, and press the Enter key. The article displays in the reading screen. Notice that the phrase "qprt Command" is highlighted to show where the word is discussed in the article.
6. To display the next match, go to the menu bar and select the Search menu.
7. Select the **Next Match** menu option and press the Enter key. The next match for "qprt command" displays. This function lets you move up and down through the information base to other places in the article or to other articles where the phrase "qprt command" is discussed.
8. To display the previous match, select the **Previous Match** option in the Search menu, and press the Enter key. The previous match for "qprt Command" displays.
9. To display the list of titles again, select the **Show Hit List** option from the Search menu, and press the Enter key. The list of titles displays again.

If there are many matches, it can be difficult to find the right information. You might have to read through several articles to find the information you want. Or, you can use a compound search to narrow down the search. To learn about a compound search, use the InfoExplorer **List of Helps**, which allows you to view step-by-step instructions to commonly used InfoExplorer procedures. From the List of Helps, select **Performing a Compound Search**.

Another way to narrow the scope of the search even further is to go to the compound search menu and select the database that is most likely to contain the information that you want. There are several databases to choose from depending on your system. For example, if you want to limit your search to information about using and managing, choose the **Using, Managing, and Commands** database.

To specify a database from the compound search pop-up panel, follow these steps:

1. Press the Ctrl-O key sequence to go to the menu bar.
2. Select the **DBselect** option. The Databases List displays.
3. A >(greater than) sign displayed to the left of an information base in this list indicates that the information base is included in the current compound search.
4. Mark the databases that you want to exclude from the search by doing the following:
  - a. Use the Up and Down Arrow keys to select a database currently included in the search that you do not want to search. The database is highlighted.
  - b. Press the Ctrl-O key sequence to go to the menu bar in the Databases List pop-up panel.
  - c. Select the **Bypass** option. The > is removed from the margin.

Repeat this procedure for each database that you do not want to search.

5. Mark the databases that you want to include from the search by doing the following:
  - a. Use the Up and Down Arrow keys to select a database currently not included in the search. The database is highlighted.
  - b. Press the Ctrl-O key sequence to go to the menu bar in the Databases List pop-up panel.
  - c. Select the **Select** option. The > is displayed to the left of the selected database.

Repeat this procedure for each database that you want to search.

6. When you have finished selecting databases, press the Ctrl-O key sequence to go to the menu bar and select the **Quit** option. The Compound Search pop-up panel is displayed again (with all information bases displayed in the Search Field) and you can continue with your search.

When you specify a database selection from the Compound Search menu, the selection is retained until you change it again, or until you quit the InfoExplorer session. This database selection will apply to both simple and compound searches. You can save a database selection for future sessions of InfoExplorer from the Defaults window under the info menu.

## Printing Information

You can print the following information from the InfoExplorer ASCII interface:

- “To Print an Article from a Reading Screen”
- “To Print an Article from a Navigation Screen”
- “To Print References from a Navigation Screen”
- “To Print Articles from a Search Match List”
- “To Print Public and Private Notes” on page 257

**Note:** You must have one or more printers configured for your system.

### To Print an Article from a Reading Screen

1. Press the Ctrl-O key sequence to activate the menu bar. The **info** menu option is the default and is highlighted.
2. Press the Enter key to display the **info** menu options.
3. Press the P key to select the **Print Article** option. The article currently displayed in the reading screen is printed.

### To Print an Article from a Navigation Screen

1. Press the Ctrl-O key sequence to activate the menu bar. The **info** menu option is the default and is highlighted.
2. Press the Enter key to display the **info** menu options. The **Print Article** option is the default and is highlighted.
3. Press the Enter key. The current navigation article is printed.

### To Print References from a Navigation Screen

1. Press the Ctrl-O key sequence to activate the menu bar. The **info** menu option is the default and is highlighted.
2. Press the Enter key to display the **info** menu options.
3. Press the Down Arrow key until the **Print References** option is highlighted.
4. Press the Enter key to print all referenced articles in the navigation screen.

### To Print Articles from a Search Match List

1. Press the Ctrl-O key sequence to activate the menu bar. The **info** option is the default and is highlighted.



2. Press the S key to select the **Search** menu option.
3. Press the Down Arrow key until the **Show Hit List** option is highlighted, then press the Enter key. The Search: List of Titles pop-up panel is displayed.
4. Press the Ctrl-O key sequence to activate the menu bar in the Search: List of Titles pop-up panel.
5. Press the P key to select the **Print** option. All articles referred to in the Search: List of Titles pop-up panel are printed.

### To Print Public and Private Notes

1. Press the Ctrl-O key sequence to activate the menu bar. The **info** option is the default and is highlighted.
2. Press the N key to select the **Notes** option. The **List All** option is the default and is highlighted.
3. Press the Enter key to display the Notes List pop-up panel.
4. Press the Ctrl-O key sequence to activate the menu bar in the Notes List pop-up panel.
5. Press the P key to select the **Print** option. All notes in the Notes List pop-up panel are printed.

## Accessing Help

From an InfoExplorer screen, you can view help information about the functions and options available on the InfoExplorer screen you are viewing or you can search through a list of topics for which help information is provided.

### To Access Help on a Specific Screen

The InfoExplorer program uses many different kinds of screens in addition to the basic navigation and reading screens, such as:

- Glossary screens
- List of links screens
- File screens
- Simple and compound search screens

Each screen type serves a different purpose and provides a different function. The Help menu in each screen contains an **On Screen** option, which displays an article describing the function that is available in the current screen.

To display Help on a specific screen, do the following:

1. Activate the menu bar by pressing the Ctrl-O key sequence.
2. Use the arrow keys to highlight **Help** and press the Enter key to display the Help menu.
3. Use the arrow keys to select the **On Screen** option and press the Enter key. A Help article replaces the current reading article.

Before you continue with the next section, try looking at the Help articles available for the screens currently open. Use the Path function to return to this screen.

### To Access the List of Helps

The Help menu provides two help options, the **List of Helps** and **On Screen**. **On Screen** allows you to find out about the current screen. For more information about this option, see "To Access Help on a Specific Screen". The **List of Helps** option in the Help menu displays a list of InfoExplorer help topics. To use the list of helps, do the following:

1. Activate the menu bar by pressing the Ctrl-O key sequence.
2. Use the arrow keys to highlight the Help menu and press the Enter key. The Help menu displays.
3. Select the **List of Helps** option to display the list of helps.
4. Select a help topic and press the Enter key.

The list of helps contains step-by-step procedures for a wide range of tasks. Before you go on to the next section, select an option or two in the list of helps. See what is available, and then try using the helps to learn and practice some new skills.

## Using Special Keys and Key Sequences

In the InfoExplorer ASCII Interface, you use special keys and key sequences to move within a screen, select items from a menu, access additional screens, and start processes. Different keys and key sequences are active depending on whether you are working from a text area or a menu bar. For more information on both text areas and menu bars, see *“Keys and Key Sequences Used in Text Areas”* and *“Keys and Key Sequences Used in Menu Bars”*, respectively.

### Keys and Key Sequences Used in Text Areas

You can use the following keys and key sequences in text areas:

| <b>Keys</b>                       | <b>Action</b>                                                                                                                                                                                                                                                                       |
|-----------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Ctrl-W</b>                     | Moves between the navigation screen and the reading screen. If the navigation screen is displayed, you can press the Ctrl-W key sequence to display the reading screen. If the reading screen is displayed, you can press the Ctrl-W key sequence to display the navigation screen. |
| <b>Ctrl-F</b> or <b>Tab</b>       | Moves to the next hypertext link.                                                                                                                                                                                                                                                   |
| <b>Ctrl-B</b>                     | Moves to the previous hypertext link.                                                                                                                                                                                                                                               |
| <b>Enter</b> or <b>Return</b>     | Activates the operation. For example, if you have moved to a hypertext link and press the Enter key, the system follows the link and displays the target information.                                                                                                               |
| <b>Ctrl-L</b>                     | Refreshes the screen.                                                                                                                                                                                                                                                               |
| <b>Ctrl-N</b> or <b>Page Down</b> | Scrolls vertically to the next screen.                                                                                                                                                                                                                                              |
| <b>Ctrl-P</b> or <b>Page Up</b>   | Scrolls vertically to the previous screen.                                                                                                                                                                                                                                          |
| <b>Left Arrow</b>                 | Moves the text cursor one character to the left. If the text can be scrolled horizontally and the text cursor is at the left edge of the screen, the text scrolls one character.                                                                                                    |
| <b>Right Arrow</b>                | Moves the text cursor one character to the right. If the text can be scrolled horizontally and the text cursor is at the right edge of the screen, the text scrolls one character.                                                                                                  |
|                                   | <b>Note:</b> The Left and Right Arrow keys do not function for the InfoExplorer program on WYSE terminals.                                                                                                                                                                          |
| <b>Up Arrow</b>                   | Moves the text cursor up one line. If the text cursor is on the top line of the screen, the text scrolls vertically, one line at a time.                                                                                                                                            |
| <b>Down Arrow</b>                 | Moves the text cursor down one line. If the text cursor is on the last line of the screen, the text scrolls vertically, one line at a time.                                                                                                                                         |
| <b>&lt;</b>                       | Moves the text cursor 20 characters to the left. If the text can be scrolled horizontally, the text scrolls 20 characters to the left.                                                                                                                                              |
| <b>&gt;</b>                       | Moves the text cursor 20 characters to the right. If the text can be scrolled horizontally, the text scrolls 20 characters to the right.                                                                                                                                            |

### Keys and Key Sequences Used in Menu Bars

The following keys and key sequences help you work with items in the menu bar:

| <b>Keys</b>                     | <b>Action</b>                                                                                                                                                                                                                                                                                                                      |
|---------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Ctrl-O</b>                   | Makes the menu bar active or inactive. If your text cursor is located in the text area of the screen, you can press the Ctrl-O key sequence to make the menu bar active. If the menu bar is already active, you can press the Ctrl-O key sequence to make it inactive, which moves the text cursor to the text area.               |
| <b>Esc-Esc</b> or <b>Ctrl-O</b> | Closes a menu bar pull-down menu and places the cursor in the text area.                                                                                                                                                                                                                                                           |
| <b>Tab</b>                      | Moves to the next menu bar option in the menu bar. If a pull-down menu is not displayed and you press the Right Arrow key, the next menu bar option is displayed in reverse video.<br><br>In pop-up screen menu bars, moves the cursor from the menu bar into the text area if no menu bar pull-down menus are currently selected. |

| <b>Keys</b>            | <b>Action</b>                                                                                                                                                                                                                                                                                                                     |
|------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Left Arrow</b>      | Moves to the previous menu bar option. If a pull-down menu is not displayed and you press the Left Arrow key, the previous menu bar option is displayed in reverse video.<br><br>If a pull-down menu is displayed and you press the Left Arrow key, the previous menu bar option is selected and its pull-down menu is displayed. |
| <b>Right Arrow</b>     | Moves to the next menu bar option. If a pull-down menu is not displayed and you press the Right Arrow key, the next menu bar option is displayed in reverse video.<br><br>If a pull-down menu is displayed and you press the Right Arrow key, the next menu bar option is selected and its pull-down menu is displayed.           |
| <b>Up Arrow</b>        | Displays the pull-down menu for the selected menu bar option or moves the selection to the previous option in a pull-down menu.                                                                                                                                                                                                   |
| <b>Down Arrow</b>      | Displays the pull-down menu for the selected menu bar option or moves the selection to the next option in a pull-down menu.                                                                                                                                                                                                       |
| <b>Enter or Return</b> | Activates the selected operation. For example, if a menu bar option is displayed in reverse video and you press the Enter key, the pull-down menu is displayed. If a pull-down menu is already displayed and you press the Enter key, the appropriate action is taken on the item shown in reverse video.                         |

In some cases, the menu bar within a pop-up screen contains options that start or stop a process. The following keys can also be used to move within a pop-up screen or to cycle through options in the screen:

| <b>Keys</b>            | <b>Action</b>                                                                       |
|------------------------|-------------------------------------------------------------------------------------|
| <b>Tab</b>             | Moves to the next field.                                                            |
| <b>Left Arrow</b>      | Moves to the previous option in an option ring.                                     |
| <b>Right Arrow</b>     | Moves to the next option in an option ring.                                         |
| <b>Spacebar</b>        | Cycles through the options in an option ring.                                       |
| <b>Up Arrow</b>        | Selects the previous item in a list.                                                |
| <b>Down Arrow</b>      | Selects the next item in a list.                                                    |
| <b>Enter or Return</b> | Activates the selected operation or ends text entry and advances to the next field. |

## Starting an Alternate InfoExplorer Library

You can request the InfoExplorer program to load an alternate database library by using the **-l** flag with the **info** command. For example, if you wish to start the InfoExplorer Library containing C++, FORTRAN and Ada documentation, start that library with the following command:

```
info -l compiler
```

## Stopping the InfoExplorer ASCII Program

To leave the InfoExplorer program from either the navigation screen or the reading screen, do the following:

1. Activate the menu bar by pressing the Ctrl-O key sequence.
2. Use the arrow keys to highlight the Exit menu and press the Enter key. The Exit menu displays.
3. Select the **Confirm** option by pressing Enter. The operating system command prompt displays and the InfoExplorer program stops.

---

## Customizing the InfoExplorer ASCII Program

You can customize many features of the InfoExplorer program to suit your style and needs. To do this, you set InfoExplorer defaults and preferences. For example, you can determine which information bases to use and which printer to use as the default. You can also specify your preferences for such things as the number of history events to track and the type of print output.

The primary differences between defaults and preferences are that most defaults are initiated by the program at startup and that different defaults can be specified for different libraries, but preferences apply to all libraries. When you change some defaults, such as the navigation article, you must exit and then restart. Defaults like print command take effect when they are saved. When you set preferences, all changes take place immediately.

The following sections describe customizing the InfoExplorer ASCII Interface:

- “Changing Defaults in the InfoExplorer ASCII Interface”
- “Changing Preferences in the InfoExplorer ASCII Interface” on page 261

### Changing Defaults in the InfoExplorer ASCII Interface

With the InfoExplorer program, you can set many defaults. These are the settings that the InfoExplorer program uses at startup. You can select **Defaults** under **Options** in the InfoExplorer pull-down menu to set defaults for:

- “Designating a Default Navigation Article”
- “Designating Default Files”
- “Designating a Default Note Template File”
- “Changing the Default Search Database” on page 261
- “Designating Default Printers” on page 261

#### Designating a Default Navigation Article

By system default, the InfoExplorer program initially displays the Topic & Task Index as the primary navigation article. You can change this default to the navigation article that best suits your purposes. Then, at startup, the InfoExplorer program automatically displays the new default navigation article.

For procedural information, see Setting Defaults (InfoExplorer ASCII) in the InfoExplorer online help.

#### Designating Default Files

You might want a trainee to follow a specific path while using the InfoExplorer program, or you might want to retrace your path from a previous session. To handle this, you can designate a specific history file as the default history file. Then, when you use the **.History** option, the default history file leads you or a trainee down the designated path.

You can also designate a bookmarks file or notes file as the default bookmarks or notes file and then follow those specific paths in subsequent sessions.

For procedural information, see Setting Defaults (InfoExplorer ASCII) in the InfoExplorer online help.

#### Designating a Default Note Template File

When you create a note in the hypertext documentation, the editor screen is initially blank. You can type the note into the blank screen. To use a specific form when writing notes, you can specify a note template. If you have built and saved many note templates, you can designate one of them as the default. Then, when you use the **Note** option, the InfoExplorer program displays the default note template.

For procedural information, see Setting Defaults (InfoExplorer ASCII) in the InfoExplorer online help.

## Changing the Default Search Database

By default, when you search with the InfoExplorer program, the search includes the information bases loaded with the program. However, it is not always necessary to include every information base in your search. To make your searches more efficient, you can specify which information bases to search during current and future sessions. You can also easily reset the information base selection to its original form (system default) so the information bases loaded with the program are again included in the search.

For procedural information, see Setting Defaults (InfoExplorer ASCII) in the InfoExplorer online help.

## Designating Default Printers

Some printers are better suited for either simple or pretty print. In the InfoExplorer program, you can designate a default printer for the different types of print: simple or pretty. The **Pretty Print** option might use the **troff** program to convert a document to output for a phototypesetter. When you issue a print command for a screen, the printer you have designated automatically receives that particular command. If you don't specify a print queue, the default is to use the first queue specified in your **/etc/qconfig** file.

For example, if you have designated printer daves3812 as the printer and if your preference has been set for pretty print, when you choose the **Print** option, the print job is automatically sent to that printer.

**Note:** The **troff** document-formatting program must be installed on your system before you can use the pretty print option.

For procedural information, see Setting Defaults (InfoExplorer ASCII) in the InfoExplorer online help.

## Changing Preferences in the InfoExplorer ASCII Interface

With the InfoExplorer program, you can set many preferences. You use the **Preferences** option in the info pull-down menu to set preferences for:

- "Changing the History List Size"
- "Choosing the Notes Editor"
- "Changing the Print Output" on page 262

### Changing the History List Size

A history list can range in size from 0 (zero) to 1000 events. The system default for the history list size is 100 events. You can change the default size to fit your particular situation. You can then apply the changes to the current session only or save them for current and future sessions.

For procedural information, see Setting Preferences (InfoExplorer ASCII) in the InfoExplorer online help.

### Choosing the Notes Editor

There are several notes editors available in the InfoExplorer ASCII interface, including INed and vi. The system default notes editor is vi. If you prefer to use INed or another editor to write your notes, you can change the default. You can then apply the changes to the current session only or save them for current and future sessions.

For procedural information, see Setting Preferences (InfoExplorer ASCII) in the InfoExplorer online help.

## Changing the Print Output

There are two types of print output available in the InfoExplorer ASCII Interface: simple and pretty. The system default for print output is simple print, which does not support highlighting or font differences. If you prefer to use pretty print, you can change the default.

**Note:** The **troff** document-formatting program must be installed on your system before you can use the pretty print feature. The **troff** program converts a document to output for a phototypesetter.

You can then apply the changes to the current session only or to current and future sessions.

For procedural information, see Setting Preferences (InfoExplorer ASCII) in the InfoExplorer online help.

---

## X Resources Available for the InfoExplorer Program

You can customize window color, position, and size in the InfoExplorer program by setting X resources in the **.Xdefaults** file. You can do this for the following types of windows:

| Window Type        | Resource Name            |
|--------------------|--------------------------|
| Bookmark List      | blistTopLevelShell       |
| Citations          | citTopLevelShell         |
| Compound Search    | compoundTopLevelShell    |
| Database Selection | dbSelectionTopLevelShell |
| Defaults Editor    | defTopLevelShell         |
| Document (Reading) | docTopLevelShell         |
| File (file link)   | fileTopLevelShell        |
| File Selection     | fileSelTopLevelShell     |
| Footnote           | footTopLevelShell        |
| Glossary           | glossaryTopLevelShell    |
| Graphic            | graphicTopLevelShell     |
| History List       | hlistTopLevelShell       |
| Introduction       | introTopLevelShell       |
| Library Definition | libinstTopLevelShell     |
| Library Selection  | libSelTopLevelShell      |
| List of Titles     | tlistTopLevelShell       |
| Message            | messageTopLevelShell     |
| Match List         | mlSelectionTopLevelShell |
| Navigation         | navTopLevelShell         |
| Note Editor        | neditTopLevelShell       |
| Note List          | nlistTopLevelShell       |
| Outline            | outlineTopLevelShell     |
| Path List          | plistTopLevelShell       |
| Preferences        | prefTopLevelShell        |
| References         | refTopLevelShell         |
| Simple Search      | searchTopLevelShell      |

The highest-level resource name in InfoExplorer is Info-gr. For example, to change the window width for the navigation window, add the following resource name to your **.xdefaults** file:

```
Info_gr.navTopLevelShell.width: 800
```

To display ISOfonts, add the following resource name to your **.xdefaults** file:

```
Info_gr.fontfilestr: isofonts
```

---

## Appendix B. Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service. IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
North Castle Drive  
Armonk, NY 10504-1785  
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106, Japan

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:** INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you. This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation  
Dept. LRAS/Bldg. 003  
11400 Burnet Road  
Austin, TX 78758-3498  
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and

cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.



---

# Index

## Special Characters

- .. (dot,dot) directories 57
- . (dot) directories 57
- ~ (home) directory 57
- /dev/rfd0 device 107
- /dev/rmt0 device
  - tape device
  - using 107
- .env file 136
- /etc/environment file 135
- /etc/profile file 134
- \$HOME directory 57
- .mwmrc file 139
- .profile file 135, 136
- .Xdefaults file 138
- .xinitrc file 137

## Numerics

- 410ap148416 208

## A

- access control
  - displaying information 129
  - editing information 130
  - extended permissions 126
  - lists 126, 127
  - setting information 129
- access modes
  - base permissions 126
  - controlling 121
  - default
    - numeric representation for 123
    - symbolic representation for 122
  - directories 121
  - files 121
  - group information
    - displaying 123
  - representation of
    - numeric 123
    - symbolic 122
  - user classes 122
- acledit command 130
- aclget command 129
- aclput command 129
- aixterm command 17
- alias command 27
- alias substitution
  - C shell 225
- aliasing
  - command
    - Korn or POSIX shell 160
- append redirection operator (>>) 43
- apropos command 235
- arguments 22
- arithmetic
  - converting units 238

- arithmetic (*continued*)
  - factoring numbers 238
- arithmetic evaluation
  - Korn or POSIX shell 166
- artwork
  - display preference 146
- ASCII files
  - printing on PostScript printer 102
- ASCII interface
  - customizing
    - overview 260
  - defaults
    - overview 260
  - overview 249
- ASCII to PostScript
  - automating conversion 103
  - converting files 103
- at command 36, 37
- atq command 36
- auto-hold feature
  - Window interface 146

## B

- backend
  - printer 93
- background processes
  - definition 30
- backup
  - command 114
  - compressing files before 111
  - guidelines 105
  - how to 114
  - purpose of 105
  - tapes
    - advantages of 107
    - using smit command 115
- banner command 48
- base permissions 126
- bidirectional languages 17
- Bourne shell
  - command substitution 204
  - commands
    - built-in 201
    - list 200
    - using 198
  - conditional substitution 209
  - environment 196
  - file name substitution 210
  - pattern matching 210
  - positional parameters 210
  - quoting characters 199
  - redirecting input and output 211
  - reserved words 200
  - signal handling 199
  - special commands 201
  - starting 196
  - variables 206

Bourne shell (*continued*)  
    predefined special 208  
    substitution 205  
    user-defined 205  
bsh command 151, 196  
built-in commands 174  
    Bourne shell 201  
    C shell 214  
bytes  
    counting number of 79

## C

C shell  
    alias substitution 225  
    command substitution 221  
    commands  
        built-in 214  
        using 214  
    expressions 220  
    file name substitution 227  
    history substitution 222  
    job control 232  
    limitations 213  
    operators 220  
    predefined and environmental variables 229  
    redirecting input and output 231  
    signal handling 214  
    starting 212  
    variable substitution 226  
cal command 235  
calendar  
    command 236  
    displaying 235  
capture command 47  
cat command 43, 77  
cd command 56, 59  
CD-ROM file system (CDRFS) 52  
CDRFS 52  
chfont command 141  
chmod command 125  
chown command 121  
chpq command 103  
classes  
    user 122  
clear command 46  
clearing your screen 46  
colrm command 82  
command aliasing  
    Korn or POSIX shell 160  
    tilde substitution 161  
command history  
    Korn or POSIX shell 174  
command list  
    nice 33  
command substitution  
    Bourne shell 204  
    C shell 221  
    Korn or POSIX shell 165

commands  
    alias  
        creating 27  
    Bourne shell 198  
    built-in 174  
        Bourne shell 201  
        C shell 214  
    C shell 214  
    case-sensitive 21  
    command name  
        definition 21  
    entering 20  
    flags  
        using 21  
    function  
        description 24  
    history, editing 26  
    information about  
        displaying 23  
    Korn or POSIX shell 155  
    long commands on multiple lines  
        entering 21  
    multiple commands on one line  
        entering 20  
    overview 20  
    parameters 22  
    repeating 25  
    saving entered 24  
    shortcut names  
        creating 27  
    spaces between 20  
    substituting strings 26  
    syntax 20  
    text-formatting 28  
    usage statements 22  
commands list 96, 97  
    > 42  
    >> 43  
    <<<< 43  
    | 45  
    acledit 130  
    aclget 129  
    aclput 129  
    aixterm 17  
    alias 27  
    apropos 235  
    at 36  
    atq 36  
    backup 114  
    banner 48  
    bsh 151, 196  
    cal 235  
    calendar 236  
    capture 47  
    cat 43, 77  
    cd 56, 59  
    chfont 141  
    chmod 125  
    chown 121  
    chpq 103  
    clear 46

commands list 96, 97 *(continued)*

colrm 82  
 compress 111  
 cp 60, 73  
 cpio -i 110  
 cpio -o command 109  
 csh 151, 212  
 cut 80  
 del 85  
 df 54  
 diff 78  
 dircmp 63  
 dosdel 87  
 dosdir 87  
 dosread 86  
 doswrite 87  
 echo 47  
 env 15  
 exit 4  
 export 141  
 factor 238  
 fc 174  
 fdformat 107  
 file 75  
 find 74  
 flcopy 109  
 format 107  
 fsck 108  
 grep 46, 77  
 groups 121  
 head 79  
 help 236  
 history 24  
 id 7  
 kill 37  
 ksh 151, 173  
   regular built-in commands 180, 181, 182, 183,  
   184  
   special built-in commands 175, 176, 178, 179,  
   180  
 learn 237  
 leave 237  
 ln 84  
 lock 130  
 login 3  
 logname 6  
 logout 4  
 ls 61  
 lscfg 11  
 lscons 12  
 lsdisp 13  
 lsfont 13  
 lsgroup 123  
 lskbd 14  
 lspp 14  
 man 23  
 mkdir 58  
 more 76  
 mv 72  
 mmdir 59  
 mwm 137

commands list 96, 97 *(continued)*

nice 33  
 nl 82  
 pack 111  
 page 76  
 passwd 8  
 paste 81  
 pg 76  
 pr 100  
 printenv 16  
 ps 32  
 psh 151, 173  
 pwd 59  
 qcan 96  
 qchk 97  
 qhld 99  
 qmov 100  
 qpri 98  
 qpri 98  
 qprt 94  
 r 25  
 renice 33, 34  
 restore 115  
 rm 72, 85  
 rmdir 62  
 rsh 151  
 Rsh 151, 197  
 script 48  
 sh 151  
 shutdown 4  
 smit 23, 96, 115  
 sort 77  
 stty 15, 142  
 su 3  
 tail 80  
 tapechk 111  
 tar 116  
 tcopy 111  
 tee 46  
 touch 4  
 tsh 151  
 tty 13  
 uname 6  
 uncompress 113  
 units 238  
 unpack 113  
 wc 79  
 whatis 24  
 whereis 23  
 who 6  
 who am i 5  
 whoami 5  
 write 240  
 xlock 130  
 comparing files 78  
 compress command 111  
 compressing files 111  
 computer-aided instruction 237  
 concatenating text files 43  
 conditional substitution  
   Bourne shell 209

- console
  - displaying name 12
- control keys
  - changing 142
  - displaying settings 15
- converting units of measure
  - units command 238
- coprocess facility
  - Korn or POSIX shell 171
- copying
  - files from tape or disk 110
  - files to tape or disk 109
  - to or from diskettes 109
  - to or from tape 111
- copying screen to file 47
- cp command 60, 73
- cpio -i command 110
- cpio -o command 109
- cs command 151, 212
- customizing
  - InfoExplorer
    - ASCII interface 260
    - Window interface 144
  - system environment 141
- cut command 80
- cutting sections 80

## D

- daemon process
  - description 31
- defaults
  - InfoExplorer bookmark file
    - ASCII interface 260
    - Window interface 145
  - InfoExplorer history file
    - ASCII interface 260
    - Window interface 145
  - InfoExplorer information bases
    - ASCII interface 261
    - Window interface 145
  - InfoExplorer navigation article
    - ASCII interface 260
    - Window interface 144
  - InfoExplorer note template
    - ASCII interface 260
    - Window interface 145, 260
  - InfoExplorer notes file
    - ASCII interface 260
    - Window interface 145
  - InfoExplorer printers
    - ASCII interface 261
    - Window interface 145
- del command 85
- deleting
  - directories 62
  - files 72
- devices
  - displaying information about 11
- df command 54
- diff command 78
- dircmp command 63

- directories 56
  - abbreviations 57
  - access modes 121
  - changing 59
  - changing ownership 121
  - changing permissions 125
  - comparing contents 63
  - copying 60
  - creating 58
  - definition 51
  - deleting 62
  - displaying
    - contents 61
    - current 59
  - home 56
  - linking 83
  - listing DOS files 87
  - listing files 61
  - moving 59
  - naming conventions 56
  - organization 56
  - overview 55
  - parent 56
  - path names 56
  - removing 62
  - renaming 59
  - root
    - definition 51
  - specifying with abbreviations 57
  - structure 56
  - subdirectories 56
  - types 55
  - working 56
- discarding output 44
- diskettes
  - copying to or from 109
  - formatting 107
  - handling 107
- displaying
  - access control information 129
  - calendar 235
  - console name 12
  - displays available 13
  - file contents 76
  - file directory
    - contents 61
    - current 59
  - files
    - first lines 79
    - last lines 80
  - fonts available 13
  - help information 236
  - login name 5
  - reminder messages 236
  - software products 14
  - system name 6
  - terminal name 13
  - text in large letters on screen 48
  - user group information 123
  - user ID 7

- displays
  - listing currently available on system 13
- DOS files
  - converting 86
  - copying 86
  - deleting 87
  - listing contents 87
- dosdel command 87
- dosdir command 87
- dosread command 86
- doswrite command 87

## E

- echo command 47
- ed editor 71
- editing
  - inline
    - Korn or POSIX shell 187
- editors 71, 187
- education
  - computer-aided instruction 237
- emacs editor 188
- env command 15
- environment
  - displaying current 15
  - setting
    - user 135
    - system 11
- environment file 135
- environment variables
  - displaying values 16
- exit command 4
- exit status
  - Korn or POSIX shell 172
- export command 141
- expressions
  - finding files with matching 74
- extended permissions 126

## F

- factor command 238
- factoring numbers
  - factor command 238
- fc command 174
- fdformat command 107
- file
  - command 75
  - descriptors 44
  - permissions 121
  - trees 52
- file name substitution
  - Bourne shell 210
  - C shell 227
  - Korn or POSIX shell 168
- file systems
  - checking for consistency 108
  - conducting interactive repairs 108
  - definition 51
  - example
    - illustration 69

- file systems (*continued*)
  - overview 52
  - root 53
  - space available
    - showing 54
  - structure 53
  - types
    - journalized file system (JFS) 52
    - network file system (NFS) 52

- files
  - access mode
    - setting 84
  - access modes 121
  - appending single line of text 47
  - archiving 116
  - ASCII 68
  - backing up 114
  - binary 68
  - changing
    - from a linked file 84
    - ownership 121
    - permissions 125
  - columns, removing 82
  - comparing 63, 78
  - compressing 111
  - concatenating 43
  - copying 73
    - from DOS 86
    - from screen 47
    - from tape or disk 110
    - to DOS 87
  - counting
    - bytes 79
    - lines 79
    - words 79
  - creating with redirection from keyboard 43
  - cutting selected fields from 80
  - definition 51
  - deleting 72
  - deleting DOS 87
  - displaying
    - contents 76
    - first lines 79
    - last lines 80
  - environment 135
  - executable 68
  - expanding 113
  - formatting
    - for display 76
    - for printing 100
  - handling 71
  - identifying type 75
  - joining 43
  - linked, removing 85
  - linking 83, 84
  - locating sections 23
  - matching expressions
    - finding 74
  - merging the lines of several 81
  - metacharacters 70
  - moving 72

- files *(continued)*
  - naming conventions 69
  - numbering lines 82
  - overview 67
  - ownership 84, 121
  - packing 111
  - pasting text 81
  - path names 56, 69
  - permissions 68
  - regular expressions 70
  - removing 72
  - renaming 72
  - restoring
    - using smit command 116
  - restoring backed-up 115
  - retrieving from storage 116
  - searching for a string 77
  - sorting text 77
  - types
    - directory 68
    - regular 68
    - showing 75
    - special 68
  - uncompressing 113
  - unpacking 113
  - wildcards 69
  - writing to output
    - from specified point 80
- filters
  - definition 45
- find command 74
- flags
  - in commands 21
- fcopy command 109
- font
  - changing 141
  - Window interface 146
- fonts
  - listing available for use 13
- foreground processes
  - definition 30
- format command 107
- formatting diskettes 107
- fsck command 108

## G

- grep command 46, 77
- groups command 121

## H

- head command 79
- help
  - command 236
  - displaying information 236
- here document 45, 170
- history
  - command 24
  - editing 26
  - event
    - changing size 146

- history *(continued)*
  - list
    - setting size 261
  - substitution
    - C shell 222

## I

- i-node number 55, 68, 83
- I/O redirection
  - Bourne shell 211
  - C shell 231
  - Korn or POSIX shell 169
- id command 7
- IDs
  - user 121
- index node reference number 55
- InEd editor 71
- InfoExplorer ASCII interface
  - alternate libraries, starting 259
  - exiting 259
  - help 250, 257
  - hypertext links
    - selecting 252
  - menu options, selecting 253
  - moving through text 252
  - printing 256
  - screens
    - moving between 252
    - types 251
  - searching 254
  - stopping 259
- InfoExplorer ASCII program
  - customizing 260
  - defaults
    - changing 260
  - navigation article
    - designing default 260
  - notes editor
    - choosing 261
  - preferences
    - changing settings 261
  - print output
    - changing 262
  - printers
    - designating default 261
  - search database
    - changing default 261
- InfoExplorer program
  - exiting 259
  - overview
    - ASCII interface 249
    - starting 251
    - stopping 259
- InfoExplorer Windows program
  - customizing 144
- inline editing
  - Korn or POSIX shell 187
    - emacs mode 188
    - vi editing mode 189
- inline input documents 45

- input and output redirection 211
- input redirection 42
- input redirection operator (<<<<) 43
- integer arithmetic 166
- international character support
  - text formatting 28

## J

- JFS 52
- job control
  - C shell 232
  - Korn or POSIX shell 186
- jobs
  - listing scheduled 36
  - removing from schedule 37
  - scheduling 35
- journalled file system (JFS) 52

## K

- keyboard maps
  - listing currently available 14
- keyword search
  - apropos command 235
- kill command 37
- Korn shell 192
- Korn shell inline editing
  - emacs mode 188
  - vi editing mode 189
- Korn shell or POSIX shell
  - arithmetic evaluation 166
  - built-in commands 174
  - command aliasing 160
    - tilde substitution 161
  - command history 174
  - command substitution 165
- commands
  - built-in 174
  - compound 156
  - functions 157
  - using 155
- conditional expressions 185
- coprocess facility 171
- coprocesses
  - redirecting input and output from 171
- editing 187
- environment 173
- exit status 172
- field splitting 168
- file name substitution 168
- job control 186
- parameter substitution 161
- pattern matching 168
- quote removal 169
- quoting 158
- redirecting input and output 169
- reserved words 159
- signal handling 187
- starting 173
- variables
  - predefined 164

- Korn shell or POSIX shell (*continued*)
  - variables (*continued*)
    - user-defined 164
- ksh command 151, 173
- ksh93 shell 192

## L

- languages
  - bidirectional 17
- learn command 237
- leave command 237
- library
  - preferred
    - Window interface 146
- line of text
  - appending to file 47
- lines
  - counting number of 79
- linked files
  - removing 85
- links
  - creating 84
  - hard 84
  - overview 83
  - removing 85
  - symbolic 84
  - types 84
- In command 84
- local printers 93
- lock command 130
- locking your terminal 130
- login
  - command 3
  - how to 2
  - messages
    - suppressing 4
  - multiple on same system 3
  - name
    - displaying 5
  - remote 1
  - user ID, as another 3
- login files
  - .env file 136
  - /etc/environment file 135
  - /etc/profile file 134
  - .profile file 135, 136
- login messages, suppressing 4
- login user ID 120
- logname command 6
- logout
  - command 4
  - how to 4
- ls command 61
- lscfg command 11
- lscons command 12
- lsdisp command 13
- lsfont command 13
- lsgroup command 123
- lskbd command 14
- lslpp command 14

## M

- man command 23
- man pages
  - finding with keyword searches 235
- maps
  - keyboard 14
- messages
  - displaying on screen 47
  - sending to other users 240
  - sending to standard output 47
- metacharacters 70
- mkdir command 58
- more command 76
- multibyte character support
  - text formatting 29
- mv command 72
- mmdir command 59
- mwm command 137

## N

- names, displaying
  - login 5
  - operating system 6
- naming conventions
  - directories 56
  - files 69
- network
  - displaying name
    - with uname command 6
- network file system (NFS) 52
- NFS 52
- nice command 33
- nl command 82
- notes
  - printing
    - InfoExplorer 257
  - setting preferred editor
    - ASCII interface 261
  - template default
    - ASCII interface 260

## O

- operating system
  - displaying name
    - with uname command 6
  - logging in 2
  - logging out 4
- options
  - in commands 21
- output
  - discarding with /dev/null file 44
  - redirecting to a file 42
- output redirection operator (>) 42

## P

- pack command 111
- page command 76
- parameters
  - in commands 22

- parameters (*continued*)
  - Korn or POSIX shell 161
- passwd command 8
- passwords
  - changing or setting 8
  - guidelines 8
  - setting to null 9
- paste command 81
- path names
  - absolute 57, 69
  - definition 69
  - directory 56
- paths
  - directory 56
- pattern matching
  - Bourne shell 210
  - Korn or POSIX shell 168
- permissions
  - base 126
  - directory 125
  - extended 126
  - file 125
- pg command 76
- PID number
  - description 30
- pipelining
  - definition 20, 45
- pipes
  - definition 45
- positional parameters
  - Bourne shell 210
- POSIX shell 172, 192
- PostScript files
  - converting from ASCII 103
- PostScript printer
  - printing ASCII files 102
- pr command 100
- preferences
  - overview
    - Window interface 145
- print file types
  - overriding automatic determination 103
- print jobs
  - canceling 96
  - definition 91
  - displaying status 97
  - formatting files for 100
  - holding 99
  - moving 100
  - prioritizing 98
  - releasing 99
  - starting 94
- print spooler 92
- printenv command 16
- printers 91
  - backend 93
  - canceling a job 96
  - default
    - ASCII interface 261
    - Window interface 145
  - local 93



- printers 91 (*continued*)
  - qdaemon 92
  - queue 91
  - queue device 92
  - real 92
  - remote 93
  - showing status of job 98
  - spooler 92
  - starting a job 94
  - status conditions 98
  - virtual 92
- printing 91, 100
  - ASCII files on PostScript printer 102
  - formatting files for 100
  - holding print jobs 99
  - moving print jobs 100
  - releasing print jobs 99
- printing from InfoExplorer 256
- process identification number 30
- processes
  - background 30
  - canceling 34
    - foreground process 34
  - changing priority 33
  - daemon 31
  - description 30
  - displaying all active 32
  - displaying status 32
  - foreground 30
  - listing scheduled 36
  - removing from schedule 37
  - restarting stopped 34
  - scheduling for later operation 35
  - setting initial priority 33
  - starting 31
  - stopping 34
    - background process 37
  - zombie 31
- profile files
  - using 134
- program
  - copying output into a file 46
- prompt
  - changing system 143
- ps command 32
- psh command 151, 173
- pwd command 59

## Q

- qcan command 96
- qchk command 97
- qdaemon 92
- qhld command 99
- qmov command 100
- qpri command 98
- qprt command 94
- queue
  - device 92
  - print 91
- quote removal
  - Korn or POSIX shell 169

- quoting characters
  - Bourne shell 199
  - Korn or POSIX shell 158

## R

- r (repeat) command 25
- reading the three-digit display 2
- real printers 92
- realtime messages
  - sending to other users 240
- redirecting
  - output to a file 42
  - standard error output 44
  - standard input 43
  - standard output 42
- redirecting input and output
  - from coprocesses 171
- references
  - printing from InfoExplorer screens 256
- regular expressions 70
- reminder messages
  - calendar command 236
- reminders to leave
  - leave command 237
- remote
  - login 1
  - printers 93
- renaming
  - directories 59
  - files 72
- renice command 33, 34
- reserved words
  - Korn or POSIX shell 159
- resource files
  - modifying 138, 139
- resource names
  - Window interface 262
- resources
  - description 138
- restore command 115
- restricted shell
  - starting 197
- rm command 72, 85
- rmdir command 62
- root file 53
- rsh command 151
- Rsh command 151, 197

## S

- screens
  - clearing 46
  - copying display to a file 46
  - copying to file 47
  - designating navigation default 260
  - displaying text in large letters 48
  - displaying text one screen at a time 76
- script command 48
- searching
  - information base default
    - ASCII interface 261

- searching (*continued*)
  - keywords 235
- security
  - file 119
  - system 119
  - threats 119
- sh command 151
- shell
  - programs 153
  - scripts
    - creating 153
    - specifying a shell 154
  - variables
    - exporting 141
- shells
  - available 151
  - Bourne
    - built-in commands 201
    - command substitution 204
    - conditional substitution 209
    - environment 196
    - file name substitution 210
    - positional parameters 210
    - predefined special variables 208
    - redirecting input and output 211
    - starting 196
    - user-defined variables 205
    - variable substitution 205
    - variables 206
- C
  - alias substitution 225
  - built-in commands 214
  - command substitution 221
  - file name substitution 227
  - history substitution 222
  - job control 232
  - predefined and environmental variables 229
  - redirecting input and output 231
  - signal handling 214
  - starting 212
  - variable substitution 226
- features 150
- Korn or POSIX
  - arithmetic evaluation 166
  - built-in commands 174
  - command 160, 165, 174
  - compound commands 156
  - conditional expressions 185
  - coprocess facility 171
  - environment 173
  - exit status 172
  - file name substitution 168
  - inline editing 187, 188, 189
  - job control 186
  - parameters 161
  - quoting 158
  - redirecting input and output 169
  - reserved words 159
  - signal handling 187
  - starting 173
  - using commands 155
- shells (*continued*)
  - restricted
    - starting 197
  - scripts
    - specifying a shell 154
  - shell scripts
    - creating 153
  - terms
    - definitions 152
    - trusted, starting 151
    - types 151
    - understanding 149
- Shells 192
- shortcut name for commands
  - creating 27
- shutdown command 4
- signal handling
  - Bourne shell 199
  - C shell 214
  - Korn or POSIX shell 187
- SMIT
  - printing
    - control of 93
- smit command 23, 96, 115
- software products
  - displaying information about 14
- sort command 77
- space
  - showing available 54
- special commands
  - Bourne shell 201
- standard error output
  - redirecting 44
- standard input
  - copying to a file 46
  - definition 41
  - redirecting 43
- standard output
  - appending to a file 43
  - definition 42
  - redirecting 42
- standard shell
  - conditional expressions 185
- starting
  - Bourne shell 196
  - C shell 212
  - Korn or POSIX shell 173
  - windows Window Manager 137
  - X 136
- startup
  - controlling windows and applications at 137
- startup files
  - C shell 213
  - system 134
- strings
  - finding in text files 77
- stty command 15, 142
- su command 3
- switches
  - in commands 21

- system
  - customizing environment 141
  - default variables 134
  - displaying name 6
  - environment 11
  - management
    - file systems tasks 52
  - powering on 2
  - prompt
    - changing 143
  - security 119
  - shutdown 4
  - startup files 134

## T

- tail command 80
- tapechk command 111
- tapes
  - checking consistency 111
  - copying to or from 111
- tar command 116
- tcop command 111
- tee command 46
- terminal
  - displaying name 13
  - displaying settings 16
  - locking 130
  - reserving
    - using lock command 130
- text
  - appending to a file 47
  - displaying in large letters 48
- text files
  - columns
    - removing 82
  - concatenating 43
  - creating from keyboard input 43
  - finding strings 77
  - lines
    - numbering 82
  - sections
    - cutting 80
    - pasting 81
  - sorting 77
- text formatting
  - extended single-byte characters 28
  - international character support 28
  - multibyte character support 29
- text-formatting commands 28
- three-digit display 2
- tilde substitution
  - aliasing commands
    - Korn or POSIX shell 161
- time management
  - creating reminders 237
  - writing reminder messages 236
- touch command 4
- tsh command 151
- tty command 13

- types
  - CD-ROM file system (CDRFS) 52

## U

- uname command 6
- uncompress command 113
- units command 238
- units of measure
  - converting 238
- unpack command 113
  - purpose of 111
- usage statements
  - for commands 22
- user
  - classes 122
  - groups
    - definition 121
    - displaying information 123
  - ID
    - changing to another 3
- users
  - displaying current system 6
  - displaying system ID 7
  - sending messages to other 240

## V

- variable substitution
  - Bourne shell 205
  - C shell 226
  - Korn or POSIX shell 164
- variables
  - Bourne shell 206
    - predefined special 208
    - user-defined 205
  - C shell
    - predefined and environmental 229
  - exporting shell 141
  - Korn or POSIX shell
    - predefined 164
    - user-defined 164
- vi editor 189
- virtual printers 92

## W

- wc command 79
- Web-based System Manager command 99
- whatis command 24
- whereis command 23
- who am i command 5
- who command 6
- whoami command 5
- wildcards 69
- Window interface
  - customizing 144
  - X resources available in 262
- windows Window Manager
  - starting 137
- words
  - counting number of 79

write command 240

## **X**

X resources

    Window interface 262

X Window System

    starting 136, 137

xlock command 130

## **Z**

zombie process 31

---

# Readers' Comments — We'd Like to Hear from You

AIX 5L Version 5.1  
System User's Guide: Operating System and Devices

Overall, how satisfied are you with the information in this book?

|                      | Very Satisfied           | Satisfied                | Neutral                  | Dissatisfied             | Very Dissatisfied        |
|----------------------|--------------------------|--------------------------|--------------------------|--------------------------|--------------------------|
| Overall satisfaction | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |

How satisfied are you that the information in this book is:

|                          | Very Satisfied           | Satisfied                | Neutral                  | Dissatisfied             | Very Dissatisfied        |
|--------------------------|--------------------------|--------------------------|--------------------------|--------------------------|--------------------------|
| Accurate                 | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Complete                 | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Easy to find             | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Easy to understand       | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Well organized           | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Applicable to your tasks | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |

Please tell us how we can improve this book:

Thank you for your responses. May we contact you?  Yes  No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

---

Name

---

Address

---

Company or Organization

---

Phone No.

**Readers' Comments — We'd Like to Hear from You**



Cut or Fold  
Along Line

Fold and Tape

**Please do not staple**

Fold and Tape

PLACE  
POSTAGE  
STAMP  
HERE

IBM Corporation  
Publications Department  
Internal Zip 9561  
11400 Burnet Road  
Austin, TX  
78758-3493

Fold and Tape

**Please do not staple**

Fold and Tape

Cut or Fold  
Along Line





Printed in U.S.A