



Tivoli Storage Manager for AIX

Administrator's Guide

Version 4 Release 2

GC35-0403-01



Tivoli Storage Manager for AIX

Administrator's Guide

Version 4 Release 2

GC35-0403-01

Note!

Before using this information and the product it supports, be sure to read the general information under “Notices” on page 571.

Second Edition (June 2001)

- | This edition applies to Version 4 Release 2 of the Tivoli Storage Manager for AIX® (product numbers 5698-TSM and 5698-DRM) and to any subsequent releases until otherwise indicated in new editions or technical newsletters.
- | Changes since the July 2000 edition are marked with a vertical bar (|) in the left margin. Ensure that you are using the correct edition for the level of the product.

Order publications through your sales representative or the branch office serving your locality.

Your feedback is important in helping to provide the most accurate and high-quality information. If you have comments about this book or any other Tivoli Storage Manager documentation, please see “Contacting Customer Support” on page xxiii.

© Copyright International Business Machines Corporation 1993, 2001. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Preface xxi

Who Should Read This Publication.....	xxi
What You Should Know before Reading This Publication.....	xxi
Tivoli Storage Manager Web Site.....	xxi
Conventions Used in This Book.....	xxi
Tivoli Storage Manager Publications.....	xxii
Related IBM® Hardware Products Publications.....	xxiii
IBM International Technical Support Center Publications (Redbooks).....	xxiii
Contacting Customer Support.....	xxiii
Reporting a Problem.....	xxiv
Translations.....	xxiv

Summary of Changes for Tivoli Storage Manager xxv

Technical Changes for Version 4 Release 2—June 2001.....	xxv
Technical Changes for Version 4 Release 1—July 2000.....	xxvi

Part I. Tivoli Storage Manager Basics..... 1

Chapter 1. Introducing Tivoli Storage Manager..... 3

How Tivoli Storage Manager Stores Client Data.....	5
Tivoli Storage Manager Device Support.....	7
Putting It All Together.....	7
Automating Client Operations.....	9
Working with a Network of Tivoli Storage Manager Servers.....	10

Chapter 2. Administrator Tasks..... 13

Interfaces to Tivoli Storage Manager.....	13
Using Magnetic Disk Devices with Tivoli Storage Manager.....	14
Using Removable Media Devices with Tivoli Storage Manager.....	14
Managing Removable Media Operations.....	14
Defining Drives and Libraries.....	14
Defining Device Classes.....	15
Managing Storage Pools.....	15
Adding Client Nodes.....	15
Managing Client Nodes.....	16
Implementing Policies for Client Data.....	16

Managing Data for Client Nodes	16
Scheduling Operations for Client Nodes.	17
Managing Schedules for Client Nodes	17
Working with a Network of Tivoli Storage Manager Servers	17
Managing Server Operations	17
Automating Server Operations	17
Managing the Database and Recovery Log.	18
Monitoring the Tivoli Storage Manager Server.	18
Exporting and Importing Data	18
Protecting and Recovering Your Server	18
Using Tivoli Disaster Recovery Manager	19

Part II. Configuring and Managing Server Storage 21

Chapter 3. Introducing Storage Devices 23

I How to Use the Server Storage Chapters	23
How Tivoli Storage Manager Represents Storage Devices	24
Disk Devices.	24
Removable Media Devices	24
Files on Disk as Sequential Volumes	25
Sequential Volumes on Another Tivoli Storage Manager Server	25
How Tivoli Storage Manager Represents Storage Media.	26
Tivoli Storage Manager Storage Objects	26
Library	26
Drive	29
Device Class	29
Storage Pool	30
Storage Pool Volume	31
Server	31
How Tivoli Storage Manager Uses Sequential Access Devices	31
Putting It All Together.	32
How Tivoli Storage Manager Uses and Reuses Removable Media	33
Scratch Volumes and Private Volumes	35
Scratch and Private Volumes in Automated Libraries	35
Storage Area Network (SAN) Support	36
How TSM Servers Share Devices Over a SAN	36
How TSM Clients Directly Access Devices Over a SAN	37
Planning for Server Storage.	39

Configuring Devices	40
Mapping Devices to Device Classes	40
Mapping Storage Pools to Device Classes and Devices	41
Chapter 4. Using Magnetic Disk Devices	43
Configuring Disk Devices	43
Configuring Random Access Volumes on Disk Devices	44
Configuring FILE Sequential Volumes on Disk Devices	45
Varying Disk Volumes Online or Offline	45
Using Cache	46
Freeing Space on Disk	46
Specifying Scratch FILE Volumes	46
Using FILE Volumes for Database Backups and Export Operations	46
Chapter 5. Attaching Devices to the Server System	49
Attaching a Manual Drive	49
Attaching an Automated Library Device	50
Setting the Library Mode	50
Installing and Configuring Device Drivers	51
Mapping Tivoli Storage Manager Devices to Device Drivers	51
Determining Device Special File Names	52
Installing Device Drivers for IBM SCSI Tape Drives	52
Installing Device Drivers for IBM 349X Libraries	53
Configuring an Autochanger or a Robot Device Driver for a Library	53
Configuring a Device Driver for a Tape or an Optical Drive for Use by TSM	54
Chapter 6. Configuring Storage Devices	57
Device Configuration Overview	57
Server Storage Options	59
Configurations Not in a Storage Area Network	59
Configuring Manually Mounted Devices	59
Configuring Removable File Devices	61
Configuring SCSI Libraries	63
Configuring 349X Libraries	65
Configuring Libraries Controlled by Media Manager Programs	69
Configuring ACSLS-Managed Libraries	71
Configurations in a Storage Area Network	73
Configuring SCSI Libraries in a SAN	73
Configuring IBM 349X Libraries in a SAN	75

Server Operations	78
Configuring TSM Clients to Directly Access SAN-Attached Devices	79
Defining Drives and Libraries	81
Defining Libraries	81
Defining Drives.....	82

Chapter 7. Managing Removable Media Operations..... 83

Preparing Removable Media	83
Labeling Removable Media Volumes	84
Checking New Volumes into a Library.....	87
Managing the Volume Inventory	90
Controlling Access to Volumes	90
Reusing Tapes in Storage Pools	91
Reusing Volumes Used for Database Backups and Export Operations.....	91
Maintaining a Supply of Scratch Volumes	92
Maintaining a Supply of Volumes in a WORM Library	92
Managing Volumes in Automated Libraries	93
Changing the Status of a Volume.....	93
Removing Volumes from a Library	93
Returning Volumes to a Library.....	94
Managing a Full Library	94
Auditing a Library's Volume Inventory	95
Maintaining a Supply of Scratch Volumes in an Automated Library	96
Managing Server Requests for Media.....	96
Using the Administrative Client for Mount Messages	96
Mount Operations for Manual Libraries	96
Handling Messages for Automated Libraries	96
Requesting Information about Pending Operator Requests	96
Replying to Operator Requests.....	97
Canceling an Operator Request	97
Responding to Requests for Volume Check-In	98
Determining Which Volumes Are Mounted	98
Dismounting an Idle Volume	98
Managing Libraries	99
Requesting Information About Libraries.....	99
Updating Libraries.....	99
Deleting Libraries	100
Managing Drives.....	100
Requesting Information about Drives	100

Updating Drives	100
Deleting Drives	104

Chapter 8. Defining Device Classes 105

Defining and Updating Device Classes for Sequential Media	105
Defining and Updating Device Classes for Tape Devices	107
Defining and Updating Device Classes for Generic Tape Devices	109
Defining and Updating Device Classes for Optical Devices	110
Defining and Updating Device Classes for REMOVABLEFILE Devices	111
Defining and Updating FILE Device Classes	111
Defining and Updating SERVER Device Classes	112
Requesting Information about a Device Class	114
Deleting a Device Class	115
How TSM Fills Volumes	115
Using Data Compression	116
Tape Volume Capacity and Data Compression	116

Chapter 9. Managing Storage Pools and Volumes 119

Overview: Storage Pools	120
Primary Storage Pool	120
Copy Storage Pool	121
An Example of Server Storage	121
Defining or Updating Primary Storage Pools	123
Task Tips for Storage Pools	126
Overview: Volumes in Storage Pools	127
Random Access Storage Pool Volumes	127
Sequential Access Storage Pool Volumes	127
Preparing Volumes for Random Access Storage Pools	128
Preparing Volumes for Sequential Access Storage Pools	129
Updating Storage Pool Volumes	130
Access Modes for Storage Pool Volumes	131
Overview: The Storage Pool Hierarchy	133
Setting Up a Storage Pool Hierarchy	133
How the Server Groups Files before Storing	134
Where the Files Are Stored	135
How the Server Stores Files in a Storage Hierarchy	136
Using Copy Storage Pools to Back Up a Storage Hierarchy	137
Using the Hierarchy to Stage Client Data from Disk to Tape	137
Migration of Files in a Storage Pool Hierarchy	138

Migration for Disk Storage Pools.	139
Migration for Sequential Access Storage Pools.	144
Migration and Copy Storage Pools.	146
Using Cache on Disk Storage Pools.	146
How the Server Removes Cached Files	147
Effect of Caching on Storage Pool Statistics.	147
Keeping a Client's Files Together: Collocation.	147
The Effects of Collocation on Operations.	148
How the Server Selects Volumes with Collocation Enabled	149
How the Server Selects Volumes with Collocation Disabled	150
Turning Collocation On or Off.	151
Collocation on Copy Storage Pools	151
Reclaiming Space in Sequential Access Storage Pools	152
How Tivoli Storage Manager Reclamation Works.	152
Choosing a Reclamation Threshold	154
Reclaiming Volumes in a Storage Pool with One Drive	155
Reclamation for WORM Optical Media	155
Reclamation of Volumes with the Device Type of SERVER	155
Reclamation for Copy Storage Pools	156
How Collocation Affects Reclamation	158
Estimating Space Needs for Storage Pools	159
Estimating Space Needs in Random Access Storage Pools	159
Estimating Space Needs in Sequential Access Storage Pools.	160
Monitoring Storage Pools and Volumes	161
Monitoring Space Available in a Storage Pool	161
Monitoring the Use of Storage Pool Volumes.	162
Monitoring Migration Processes.	169
Monitoring the Use of Cache Space on Disk Storage	172
Requesting Information on the Use of Storage Space	173
Moving Files from One Volume to Another Volume	176
Moving Data to Other Volumes in the Same Storage Pool	176
Moving Data to Another Storage Pool	177
Moving Data from an Offsite Volume in a Copy Storage Pool	177
Procedure for Moving Data	177
Renaming a Storage Pool.	180
Defining a Copy Storage Pool	180
Example: Defining a Copy Storage Pool	181
Comparing Primary and Copy Storage Pools	182
Deleting a Storage Pool.	183

Deleting Storage Pool Volumes	184
Deleting an Empty Storage Pool Volume	184
Deleting a Storage Pool Volume with Data.	185

Part III. Managing Client Operations 187

Chapter 10. Adding Client Nodes 189

Overview of Clients and Servers as Nodes	190
Installing Client Node Software	190
Registering Nodes with the Server	190
Accepting Default Closed Registration or Enabling Open Registration	190
Registering Nodes with Client Options Sets	192
Registering a Source Server as a Node on a Target Server	192
Registering an Application Programming Interface to the Server.	192
Connecting Nodes with the Server	193
Required Client Options	193
Non-Required Client Options	194
UNIX Client Options.	194
Methods for Creating or Updating a Client Options File.	194
Using a Text Editor	194
Using the Client Configuration Wizard.	194
Comparing Network-Attached Nodes to Local Nodes	194
Adding Clients from the Administrative Command Line Client.	195
Enabling Open Registration	195
Configuring the Client Options File to Connect with the Server	195
Example: Register Three Client Nodes Using the Administrative Command Line	196

Chapter 11. Managing Client Nodes. 197

Managing Client Node Registration Techniques	198
Managing Nodes	198
Updating Client Node Information	198
Renaming Client Nodes	198
Locking and Unlocking Client Nodes.	199
Deleting Client Nodes	199
Displaying Information about Client Nodes	199
Overview of Remote Access to Web Backup-Archive Clients	200
Managing Client Access Authority Levels	202
Managing File Spaces	204
Supporting Unicode-Enabled Clients (Windows NT and Windows 2000)	204

Displaying Information about File Spaces	213
Deleting File Spaces and Client Nodes.	213
Modifying Client Option Files	214
All Nodes	214
Creating Client Option Sets from the Server.	215
Creating a Client Option Set	215
Adding Client Options in an Option Set.	215
Registering Client Nodes and Assigning Them to an Option Set.	215
Managing Client Options from the Server Using Client Option Sets	216
Updating the Sequence Number for a Client Option	216
Deleting an Option from a Client Option Set	216
Copying a Client Option Set	216
Requesting Information about a Client Option Set	216
Updating the Description for a Client Option Set	216
Deleting a Client Option Set	216
Managing Tivoli Storage Manager Sessions	217
Displaying Information about Tivoli Storage Manager Sessions	217
Canceling a Tivoli Storage Manager Session	218
When a Client Session is Automatically Canceled	219
Freeing Links for SNA LU6.2 Client Connections	219
Disabling or Enabling Access to the Server	220
Managing Client Restartable Restore Sessions	220
Managing Tivoli Storage Manager Security	222
Managing Tivoli Storage Manager Administrators	222
Managing Levels of Administrative Authority	225
Managing Access to the Server and Clients	227
Managing Passwords	227
Managing the Server Console	229
Overview of Client Nodes and File Spaces.	229
File Spaces for Clients.	230
Overview of Tivoli Storage Manager Privilege Classes.	230
System Privilege	230
Unrestricted Policy Privilege	231
Restricted Policy Privilege.	231
Unrestricted Storage Privilege	231
Restricted Storage Privilege	232
Operator Privilege	232
Analyst Privilege.	232
Node Privilege.	232

Chapter 12. Implementing Policies for Client Data	233
Basic Policy Planning	234
The Standard Policy	235
Getting Users Started.....	236
Overview: Changing Policy	237
File Expiration and Expiration Processing	237
Client Operations Controlled by Policy	238
Backup and Restore.....	238
Archive and Retrieve.....	238
Client Migration and Recall.....	239
The Parts of a Policy.....	240
More on Management Classes	241
Contents of a Management Class	242
Default Management Classes	242
The Include-Exclude List.....	243
How Files and Directories Are Associated with a Management Class	244
How Tivoli Storage Manager Selects Files for Policy Operations	246
Incremental Backup.....	246
Selective Backup.....	248
Logical Volume Backup.....	249
Archive.....	249
Automatic Migration from a Client Node.....	250
How Client Migration Works with Backup and Archive	250
Creating Your Own Policies.....	251
Example: Sample Policy Objects	252
Defining and Updating a Policy Domain	253
Defining and Updating a Policy Set.....	254
Defining and Updating a Management Class	254
Defining and Updating a Backup Copy Group	255
Defining and Updating an Archive Copy Group.....	261
Assigning a Default Management Class	262
Validating and Activating a Policy Set	263
Assigning Client Nodes to a Policy Domain.....	264
Running Expiration Processing to Delete Expired Files	264
Running Expiration Processing Automatically	265
Using Commands and Scheduling to Control Expiration Processing	265
Additional Expiration Processing with Tivoli Disaster Recovery Manager.....	265
Configuring Policy for Specific Cases	266

Configuring Policy for Direct-to-Tape Backups	266
Configuring Policy for Tivoli Data Protection Application Clients.	267
Policy for Logical Volume Backups	267
Configuring Policy for Managed System for SAN	268
Policy for Tivoli Storage Manager Servers as Clients	270
Setting Policy to Enable Point-in-Time Restore for Clients	270
Distributing Policy Using Enterprise Configuration.	270
Querying Policy	271
Querying Copy Groups	271
Querying Management Classes	272
Querying Policy Sets	273
Querying Policy Domains	273
Deleting Policy	273
Deleting Copy Groups	274
Deleting Management Classes	274
Deleting Policy Sets	274
Deleting Policy Domains	275

Chapter 13. Managing Data for Client Nodes 277

Creating and Using Client Backup Sets	277
Generating Client Backup Sets on the Server	278
Restoring Backup Sets from a Backup-Archive Client	280
Moving Backup Sets to Other Servers	280
Managing Client Backup Sets	280
Enabling Clients to Use Subfile Backup.	282
Example of Subfile Backups	283
Setting Up Clients to Use Subfile Backup	283
Managing Subfile Backups	283

Chapter 14. Scheduling Operations for Client Nodes 285

Prerequisites to Scheduling Operations.	286
Scheduling a Client Operation	286
Defining Client Schedules	286
Associating Client Nodes with Schedules.	287
Starting the Scheduler on the Clients	287
Displaying Schedule Information	288
Creating Schedules for Running Command Files	289
Updating the Client Options File to Automatically Generate a New Password.	289
Comparing Tivoli Storage Manager Scheduling Across Operating Systems and Components	290

Commands for Scheduling Client Operations	291
---	-----

Chapter 15. Managing Schedules for Client Nodes 293

Managing Tivoli Storage Manager Schedules	293
Verifying that the Schedule Ran	293
Adding New Schedules	294
Copying Existing Schedules	294
Modifying Schedules	294
Deleting Schedules	294
Displaying Information about Schedules	295
Managing Node Associations with Schedules	295
Adding New Nodes to Existing Schedules	295
Moving Nodes from One Schedule to Another	295
Displaying Nodes Associated with Schedules	296
Removing Nodes from Schedules	296
Managing Event Records	296
Displaying Information about Scheduled Events	296
Managing Event Records in the Server Database	298
Managing the Throughput of Scheduled Operations	298
Modifying the Default Scheduling Mode	299
Specifying the Schedule Period for Incremental Backup Operations	300
Balancing the Scheduled Workload for the Server	301
Controlling How Often Client Nodes Contact the Server	302
Specifying One-Time Actions for Client Nodes	304
Determining How Long the One-Time Schedule Remains Active	304

Part IV. Maintaining the Server 307

Chapter 16. Working with a Network of Tivoli Storage Manager Servers 309

Concepts for Working with a Network of Servers	309
Configuring and Managing Servers: Enterprise Configuration	310
Performing Tasks on Multiple Servers	311
Central Monitoring	311
Storing Data on Another Server	312
Example Scenarios	312
Planning for Enterprise Administration	313
Setting Up Communications Among Servers	314
Setting Up Communications for Enterprise Configuration and Enterprise Event Logging	314
Setting Up Communications for Command Routing	317

Updating and Deleting Servers	321
Setting Up an Enterprise Configuration	321
Enterprise Configuration Scenario	322
Creating the Default Profile on a Configuration Manager	326
Creating and Changing Configuration Profiles	326
Getting Information about Profiles	333
Subscribing to a Profile	335
Refreshing Configuration Information	339
Returning Managed Objects to Local Control	340
Setting Up Administrators for the Servers	340
Handling Problems with Synchronization of Profiles	341
Switching a Managed Server to a Different Configuration Manager	341
Deleting Subscribers from a Configuration Manager	342
Renaming a Managed Server	342
Performing Tasks on Multiple Servers	342
Using Tivoli Storage Manager Enterprise Logon	343
Routing Commands	343
Setting Up Server Groups	345
Querying Server Availability	347
Using Virtual Volumes to Store Data on Another Server	348
Setting Up Source and Target Servers for Virtual Volumes	349
Performing Operations at the Source Server	350
Reconciling Virtual Volumes and Archive Files	352

Chapter 17. Managing Server Operations 355

Licensing Tivoli Storage Manager	355
Registering Licensed Features	356
Saving Your Licenses	358
Monitoring Licenses	358
Starting and Halting the Server	359
Starting the Server	359
Halting the Server	364
Changing the Date and Time on the Server	365
Managing Server Processes	365
Requesting Information about Server Processes	366
Canceling Server Processes	367
Preemption of Client or Server Operations	367
Setting the Server Name	368
Adding or Updating Server Options	368

Adding or Updating a Server Option without Restarting the Server	368
Automatic Tuning of Server Options	369
Getting Help on Commands and Error Messages	369

Chapter 18. Automating Server Operations..... 371

Automating a Basic Administrative Command Schedule	371
Defining the Schedule	372
Verifying the Schedule	372
Tailoring Schedules	373
Example: Defining and Updating an Administrative Command Schedule	374
Copying Schedules	375
Deleting Schedules	375
Managing Scheduled Event Records	375
Querying Events	375
Removing Event Records from the Database	376
Tivoli Storage Manager Server Scripts	376
Defining a Server Script	377
Managing Server Scripts	380
Running a Server Script	382
Using Macros	383
Writing Commands in a Macro	383
Writing Comments in a Macro	384
Using Continuation Characters	384
Using Substitution Variables in a Macro	385
Running a Macro	385
Controlling Command Processing in a Macro	386

Chapter 19. Managing the Database and Recovery Log 387

How Tivoli Storage Manager Processes Transactions	388
How Space Is Managed by the Server	388
Available Space	389
Assigned Capacity	389
Utilization	389
The Advantages of Using Journal File System Files	390
Estimating and Monitoring Database and Recovery Log Space Requirements	390
Monitoring the Database and Recovery Log	392
Increasing the Size of the Database or Recovery Log	393
Automating the Increase of the Database or Recovery Log	393
Recovering When the Recovery Log Runs Out of Space	394

Manually Increasing the Database or Recovery Log	395
Decreasing the Size of the Database or Recovery Log	397
Step 1: Determining If Volumes Can Be Deleted	397
Step 2: Reducing the Capacity of the Database or Recovery Log	398
Step 3: Deleting a Volume from the Database or Recovery Log	399
Optimizing the Performance of the Database and Recovery Log	399
Dynamically Adjusting the Database Buffer Pool Size	400
Manually Adjusting the Database Buffer Pool Size	400
Adjusting the Recovery Log Buffer Pool Size	401
Reorganizing the Database	402

Chapter 20. Monitoring the Tivoli Storage Manager Server 405

Using Tivoli Storage Manager Queries to Display Information	405
Requesting Information about Tivoli Storage Manager Definitions	406
Requesting Information about Client Sessions	406
Requesting Information about Server Processes	407
Requesting Information about Server Settings	408
Querying Server Options	408
Querying the System	409
Using SQL to Query the Tivoli Storage Manager Database	410
Using the ODBC Driver	410
Issuing SELECT Commands	410
Using SELECT Commands in Tivoli Storage Manager Scripts	414
Canceling a SELECT Command	414
Controlling the Format of SELECT Results	414
Querying the SQL Activity Summary Table	415
Creating Output for Use by Another Application	415
Using the Tivoli Storage Manager Activity Log	416
Requesting Information from the Activity Log	416
Setting the Activity Log Retention Period	417
Changing the Size of the Activity Log	417
Logging Tivoli Storage Manager Events to Receivers	418
Enabling and Disabling Events	419
Beginning and Ending Event Logging	419
Logging Events to the Tivoli Storage Manager Server Console and Activity Log	420
Logging Events to a File Exit and a User Exit	420
Logging Events to the Tivoli/Enterprise Console	421
Logging Events to an SNMP Manager	423
Enterprise Event Logging: Logging Events to Another Server	428

Querying Event Logging	430
Using Tivoli Decision Support	430
Scheduling the Decision Support Loader with Tivoli Storage Manager	431
Monitoring Tivoli Storage Manager Accounting Records	431
Daily Monitoring Scenario	433
Chapter 21. Exporting and Importing Data	435
Data That Can Be Exported and Imported	435
Preparing to Export or Import Data	436
Using Preview before Exporting or Importing Data	436
Planning for Sequential Media Used to Export Data	437
Monitoring Export and Import Processes	438
Requesting Information about an Export or Import Process	438
Viewing Information from the Server Console	438
Viewing Information from an Administrative Client	439
Querying the Activity Log for Export or Import Information	440
Exporting Data to Sequential Media Volumes	441
Deciding When to Export Data	442
Exporting Server Data	443
Exporting Administrator Information	443
Exporting Client Node Information	444
Exporting Policy Information	445
Importing Data from Sequential Media Volumes	445
Step 1: Previewing Information before You Import Data	446
Step 2: Importing Definitions	448
Step 3: Tailoring Server Storage Definitions on the Target Server	450
Step 4: Importing File Data Information	451
Considerations When Importing Data	452
Recovering from Errors during the Import Process	453
Exporting and Importing Data from Virtual Volumes	454
Part V. Protecting the Server	455
Chapter 22. Protecting and Recovering Your Server.....	457
Levels of Protection	458
Storage Pool Protection: An Overview	458
How Restore Processing Works	458
How the Destroyed Volume Access Mode Works	459
Database and Recovery Log Protection: An Overview	460

Mirroring	460
Database and Recovery Log Protection	460
Snapshot Database Protection.....	462
Mirroring the Database and Recovery Log.....	462
Separating Disk Volume Copies On Separate Physical Disks When Mirroring the Database and Recovery Log.....	463
Defining Database or Recovery Log Mirrored Volume Copies	463
Specifying Mirroring and Database Page Shadowing Server Options	464
Requesting Information about Mirrored Volumes	465
Backing Up Storage Pools.....	465
Delaying Reuse of Sequential Access Volumes.....	467
Using Copy Storage Pools to Improve Data Availability.....	468
Example: Simple Hierarchy with One Copy Storage Pool.....	468
Backing Up the Database.....	468
Defining Device Classes for Backups.....	469
Setting the Recovery Log Mode.....	469
Estimating the Size of the Recovery Log	469
Scheduling Database Backups	470
Automating Database Backups.....	471
Saving the Volume History File	472
Saving the Device Configuration File.....	474
Saving the Server Options	476
Saving the Database and Recovery Log Setup Information	476
Doing Full and Incremental Backups	476
Doing Snapshot Database Backups.....	477
Recovering Your Server Using Database and Storage Pool Backups	477
Restoring a Database to a Point-in-Time	478
Restoring a Database to its Most Current State.....	482
Restoring Storage Pools.....	483
Restoring Your Server Using Mirrored Volumes	485
Restoring Storage Pool Volumes	485
What Happens When a Volume Is Restored	486
When a Volume Restoration Is Incomplete.....	486
Auditing a Storage Pool Volume	487
What Happens When You Audit Storage Pool Volumes	487
Auditing a Volume in a Disk Storage Pool.....	489
Auditing Multiple Volumes in a Sequential Access Storage Pool.....	489
Auditing a Single Volume in a Sequential Access Storage Pool.....	490
Correcting Damaged Files	490

Maintaining the Integrity of Files	491
Restoring Damaged Files	491
Backup and Recovery Scenarios	492
Protecting Your Database and Storage Pool	492
Recovering to a Point-in-Time from a Disaster	493
Recovering a Lost or Damaged Storage Pool Volume	495

Chapter 23. Using Tivoli Disaster Recovery Manager 497

Specifying Defaults for Tivoli Disaster Recovery Manager	498
Specifying Defaults for the Disaster Recovery Plan File	498
Specifying Defaults for Offsite Recovery Media Management	500
Specifying Recovery Instructions for Your Site	502
Specifying Information About Your Server and Client Node Machines	504
Specifying Recovery Media for Client Machines	506
Creating and Storing the Disaster Recovery Plan	506
Storing the Disaster Recovery Plan Locally	507
Storing the Disaster Recovery Plan on a Target Server	508
Managing Disaster Recovery Plan Files Stored on Target Servers	508
Displaying Information about Recovery Plan Files	508
Displaying the Contents of a Recovery Plan File	509
Restoring a Recovery Plan File	509
Expiring Recovery Plan Files Automatically	509
Deleting Recovery Plan Files Manually	510
Moving Backup Media	510
Moving Backup Volumes Offsite	512
Moving Backup Volumes Onsite	513
Summary of Tivoli Disaster Recovery Manager Daily Tasks	515
Staying Prepared for a Disaster	516
Recovering From a Disaster	517
Server Recovery Scenario	518
Client Recovery Scenario	520
Recovering When Using Different Hardware at the Recovery Site	523
Automated SCSI Library at the Original Site and a Manual SCSI Library at the Recovery Site	523
Automated SCSI Library at the Original and Recovery Sites	524
Managing Copy Storage Pool Volumes at the Recovery Site	525
Tivoli Disaster Recovery Manager Checklist	525
The Disaster Recovery Plan File	528
Breaking Out a Disaster Recovery Plan File	528

Structure of the Disaster Recovery Plan File	528
Example Disaster Recovery Plan File.	530

Part VI. Appendixes 553

Appendix A. External Media Management Interface Description 555

l CreateProcess Call.	555
Processing during Server Initialization	556
Processing for Mount Requests	556
Processing for Release Requests	556
Processing for Batch Requests	557
Error Handling	557
Begin Batch Request	558
End Batch Request	558
Volume Query Request	558
Initialization Requests	559
Volume Eject Request	560
Volume Release Request	560
Volume Mount Request	561
Volume Dismount Request.	564

Appendix B. User Exit and File Exit Receivers 565

Sample User Exit Declarations.	566
Sample User Exit Program.	569
Readable Text File Exit (FILETEXTEXTIT) Format	570

Appendix C. Notices 571

Programming Interface.	572
Trademarks	573

Glossary 575

Index 601

Preface

Tivoli® Storage Manager (TSM) is a client/server program that provides storage management solutions to customers in a multivendor computer environment. TSM provides an automated, centrally scheduled, policy-managed backup, archive, and space-management facility for file servers and workstations.

Who Should Read This Publication

This guide is intended for anyone who has been assigned an administrator user ID and an administrative privilege class for TSM. While TSM can be managed by a single administrator, administrative responsibilities can be divided among several people as you require.

All of the administrator commands you need to operate and maintain TSM can be invoked from a workstation connected to the server, or from a workstation with a Web browser that has support for Java™ at the appropriate level. See *Quick Start* for details.

What You Should Know before Reading This Publication

You should be familiar with the operating system on which the server resides and the communication protocols required for the client/server environment.

For information on installing TSM, see *Tivoli Storage Manager for AIX Quick Start*.

You also need to understand the storage management practices of your organization, such as how you are currently backing up your workstation files and how you are using random access media and sequential access media.

Tivoli Storage Manager Web Site

TSM publications are available on the TSM home page on the World Wide Web at the following address:

http://www.tivoli.com/support/storage_mgr/tivolimain.html

By accessing the TSM home page, you can access subjects that interest you. You can also keep up-to-date with the newest product information.

Conventions Used in This Book

To help you recognize where example commands are to be entered, this book uses the following conventions:

- Command to be entered on the AIX command line:
 > dsmadm
- Command to be entered on the command line of an administrative client:
 query devclass

Tivoli Storage Manager Publications

The following table lists TSM server publications.

Publication Title	Order Number
<i>Tivoli Storage Manager Messages</i>	GC35-0405
<i>Tivoli Storage Management Products License Information</i>	GH09-4572
<i>Tivoli Storage Manager for AIX Quick Start</i>	GC35-0402
<i>Tivoli Storage Manager for AIX Administrator's Guide</i>	GC35-0403
<i>Tivoli Storage Manager for AIX Administrator's Reference</i>	GC35-0404
<i>Tivoli Storage Manager for AIX Managed System for SAN Storage Agent User's Guide</i>	GC36-0001
<i>Tivoli Storage Manager for Sun Solaris Managed System for SAN Storage Agent User's Guide</i>	GC36-0002
<i>Tivoli Storage Manager for Windows Managed System for SAN Storage Agent User's Guide</i>	GC35-0434

The following table lists the TSM client publications.

Publication Title	Order Number
<i>Tivoli Space Manager for UNIX Using the Hierarchical Storage Management Clients</i>	SH26-4115
<i>Tivoli Storage Manager for Macintosh Using the Backup-Archive Client</i>	SH26-4120
<i>Tivoli Storage Manager for UNIX Using the Backup-Archive Clients</i>	SH26-4122
<i>Tivoli Storage Manager for NetWare Using the Backup-Archive Client</i>	SH26-4116
<i>Tivoli Storage Manager for Windows Using the Backup-Archive Clients</i>	SH26-4117
<i>Tivoli Storage Manager Installing the Clients</i>	SH26-4119
<i>Tivoli Storage Manager Quick Reference for the Backup-Archive Clients</i>	SH26-4118
<i>Tivoli Storage Manager Trace Facility Guide</i>	SH26-4121
<i>Tivoli Storage Manager Using the Application Programming Interface</i>	SH26-4123

The following table lists Tivoli Data Protection publications.

Publication Title	Order Number
<i>Tivoli Data Protection for Informix Installation and User's Guide</i>	SH26-4095
<i>Tivoli Data Protection for Lotus Domino, S/390 Edition Licensed Program Specifications</i>	GC26-7305
<i>Tivoli Data Protection for Lotus Domino for UNIX Installation and User's Guide</i>	SH26-4088
<i>Tivoli Data Protection for Lotus Domino for Windows NT Installation</i>	GC26-7320
<i>Tivoli Data Protection for Lotus Notes on AIX Installation and User's Guide</i>	SH26-4067
<i>Tivoli Data Protection for Lotus Notes on Windows NT Installation and User's Guide</i>	SH26-4065
<i>Tivoli Data Protection for Microsoft Exchange Server Installation and User's Guide</i>	SH26-4110
<i>Tivoli Data Protection for Microsoft SQL Server Installation and User's Guide</i>	SH26-4111
<i>Tivoli Data Protection for Oracle for UNIX Installation and User's Guide</i>	SH26-4112
<i>Tivoli Data Protection for Oracle for Windows NT Installation and User's Guide</i>	SH26-4113

Publication Title	Order Number
<i>Tivoli Data Protection for R/3 Version 2.7 Installation and User's Guide</i>	SC33-6388
<i>Tivoli Data Protection for Workgroups for Windows NT User's Guide</i>	GC35-0359
<i>Tivoli Data Protection for Workgroups for NetWare User's Guide</i>	GC32-0444

Related IBM® Hardware Products Publications

The following table lists related IBM hardware products publications.

Title	Order Number
<i>IBM 3490 Magnetic Tape Subsystem Enhanced Capability Models E01 and E11 User's Guide</i>	GA32-0298
<i>IBM SCSI Tape Drive, Medium Changer, and Library Device Drivers: Installation and User's Guide</i>	GC35-0154
<i>Magstar 3494 Tape Library Operator Guide</i>	GA32-0280
<i>Magstar 3494 Tape Library Introduction and Planning Guide</i>	GA32-0279
<i>IBM Magstar 3590 Tape Subsystem Operator's Guide</i>	GA32-0330
<i>IBM 3570 Magstar MP Tape Subsystem Operator's Guide</i>	GA32-0345

IBM International Technical Support Center Publications (Redbooks)

The International Technical Support Center (ITSC) publishes redbooks, which are books on specialized topics such as using TSM to back up databases. You can order publications through your IBM representative or the IBM branch office serving your locality. You can also search for and order books of interest to you by visiting the IBM Redbooks home page on the World Wide Web at this address:

<http://www.redbooks.ibm.com/redbooks>

Contacting Customer Support

For support for this or any Tivoli product, you can contact Tivoli Customer Support in one of the following ways:

- Visit the Tivoli Storage Manager technical support Web site at http://www.tivoli.com/support/storage_mgr/tivolimain.html.
- Submit a problem management record (PMR) electronically at **IBMSERV/IBMLINK**. You can access IBMLINK at <http://www2.ibmink.ibm.com>.
- Submit a problem management record (PMR) electronically at <http://www.tivoli.com/support>. See "Reporting a Problem" on page xxiv for details.
- Send e-mail to support@tivoli.com.

Customers in the United States can also call 1-800-TIVOLI8 (1-800-848-6548). For product numbers 5697-TS9, 5697-DRS or 5697-DPM call 1-800-237-5511.

International customers should consult the Web site for customer support telephone numbers.

You can also review the *Customer Support Handbook*, which is available on our Web site at <http://www.tivoli.com/support/handbook/>.

When you contact Tivoli Customer Support, be prepared to provide identification information for your company so that support personnel can readily assist you. Company identification information may also be needed to access various online services available on the Web site.

The support Web site offers extensive information, including a guide to support services (the Customer Support Handbook); frequently asked questions (FAQs); and documentation for all Tivoli products, including Release Notes, Redbooks, and Whitepapers. The documentation for some product releases is available in both PDF and HTML formats. Translated documents are also available for some product releases.

You can order documentation by e-mail at swdist@tivoli.com. Please provide the publication number, part number, or order number of the desired document. Alternatively, you can provide the document title, version number, and date of publication.

We are very interested in hearing about your experience with Tivoli products and documentation. We also welcome your suggestions for improvements. If you have comments or suggestions about our documentation, please contact us in one of the following ways:

- Send e-mail to pubs@tivoli.com.
- Complete our customer feedback survey at <http://www.tivoli.com/support/feedback/>.

Reporting a Problem

Please have the following information ready when you report a problem:

- The Tivoli Storage Manager server version, release, modification, and service level number. You can get this information by entering the `QUERY STATUS` command at the TSM command line.
- The Tivoli Storage Manager client version, release, modification, and service level number. You can get this information by entering `dsmc` at the command line.
- The communication protocol (for example, TCP/IP), version, and release number you are using.
- The activity you were doing when the problem occurred, listing the steps you followed before the problem occurred.
- The exact text of any error messages.

Translations

Selected TSM publications have been translated into languages other than American English. Contact your sales representative for more information about the translated publications and whether these translations are available in your country.

Summary of Changes for Tivoli Storage Manager

This section summarizes changes made to the Tivoli Storage Manager (TSM) product and this publication.

Technical Changes for Version 4 Release 2—June 2001

The following changes have been made to the product for this edition:

Expanded Support for Managed System for SAN Environments

The types of clients that can use LAN-free data transfer now include backup-archive clients and API clients on Windows[®], AIX, and Sun operating systems. Also now included are additional Tivoli Data Protection application clients, on the Sun and AIX operating systems. Tivoli Data Protection application clients for Microsoft[®] Exchange Server, Microsoft SQL Server, and Lotus[®] Domino[™] already had this support.

See “Configuring TSM Clients to Directly Access SAN-Attached Devices” on page 79. Also see *TSM Managed System for SAN Storage Agent User’s Guide* and the user’s guide for the appropriate client.

Additional Devices that Support LAN-Free Data Transfer for Clients

Support has been added for using the following devices for LAN-free data transfer:

- IBM 3494 libraries
- Shared libraries via a TSM server that is either a library manager or a library client
- Disk devices on a storage area network (SAN), via a shared FILE device class

See “Configuring TSM Clients to Directly Access SAN-Attached Devices” on page 79.

Maximum Size of the Recovery Log Increased

The maximum size of the recovery log is increased to 13GB. Significantly increasing the size of your recovery log could also significantly increase the time required to restart the server, to back up the database, and to restore the database. See “Managing the Database and Recovery Log” on page 387.

Support for Unicode-enabled Client File Spaces

For Windows NT[®] and Windows 2000 client systems that are Unicode, the server now supports storing Unicode file space names, directory names, and file names in *Unicode-enabled file spaces*. Unicode is a universal character encoding standard that supports the interchange, processing, and display of text that is written in any of the languages of the modern world. The Unicode-enabled TSM client software must be installed on the client systems. New clients that do not yet have data stored on the server automatically store data in Unicode-enabled file spaces.

While clients that already have data stored on the server will store any new file spaces as Unicode-enabled, these clients do not automatically store their *existing* data in Unicode-enabled file spaces. As an administrator, you can migrate these clients by using the function for automatic file space renaming. TSM renames existing file spaces to force the creation of new, Unicode-enabled file spaces. You can also allow clients to make the choice about renaming. Once the existing file spaces are renamed on the server, a backup or archive operation causes the file spaces to be created again in server storage, this time as Unicode-enabled file

spaces. If you have a large number of clients that are Unicode, or a large amount of data on clients that are Unicode, you need to plan the migration. For information on migration, see “Supporting Unicode-Enabled Clients (Windows NT and Windows 2000)” on page 204.

The addition of support for Unicode may affect the results of some SELECT commands, because the sorting of information such as file space names is affected.

Using the TSM Client Acceptor to Manage the Scheduler

The client acceptor daemon or service manages the Web backup-archive client. Users can now select to have the client acceptor also manage the scheduler on the clients. The client acceptor starts the scheduler and the client only when needed to run a TSM schedule. Using the client acceptor to start the scheduler can alleviate problems with memory that is consumed by the scheduler. Also, if users are already running the client acceptor to manage the Web client, they can reduce the number of processes that are running continuously on their machines. See the user’s guide for the appropriate client. Also see “Scheduling Operations for Client Nodes” on page 285.

Improved ANR9999D Messages

You can set message context reporting to ON to get additional information when the server issues ANR9999D messages. The additional information can help to identify problem causes. See the SET CONTEXTMESSAGING command in *Administrator’s Reference*. Also see *Messages*.

Reclaiming Space in Aggregates During Data Movement

You can specify to have the server reconstruct aggregates during data movement. Reconstruction reclaims empty space that has accumulated as a result of deletion of logical files from an aggregate. See “Reclaiming Space in Aggregates During Data Movement” on page 179.

Technical Changes for Version 4 Release 1—July 2000

The following changes have been made for this edition:

Support for Mobile Clients

This enhancement allows mobile users to backup files and afterwards make subsequent backups to the portion (*a subfile*) of the file that has changed, rather than the entire file. This type of backup allows remote or mobile users using modems with limited bandwidth to reduce connection time, network traffic, and the time it takes to do a backup. This enhancement also uses encryption to protect clients’ data. See “Enabling Clients to Use Subfile Backup” on page 282.

Managed System for SAN Environments

Tivoli Storage Manager has been enhanced to support LAN-free data movement in storage area network (SAN) environments. Support is currently limited. The support allows client data to move directly from the client system to a server-managed storage device on the SAN, instead of moving first from the client system to the server over the LAN and then to the device. This enhancement reduces data movement on the LAN so that more bandwidth is available to other applications. This enhancement also increases tape library sharing for multiple TSM servers.system to the server over the LAN and then to the device. See “Configuring TSM Clients to Directly Access SAN-Attached Devices” on page 79.

Storage Area Network (SAN) Tape Library Sharing

Tivoli Storage Manager takes advantage of SAN-attached tape libraries by sharing

devices among TSM servers. One of the servers acts as the library manager and the other servers are library clients. The other servers can be on different operating systems, as long as the servers also support tape library sharing. See “Configurations in a Storage Area Network” on page 73.

Licensing

A client is now licensed as a *managed system*. A managed system can be a client or server that requires backup services from the TSM server. Each managed system that moves data to and from storage over a local area network requires a Managed System for LAN license. Each managed system that moves data to and from storage over a storage area network requires a Managed System for SAN license. See “Licensing Tivoli Storage Manager” on page 355 for details. The following table lists changes to license names:

Table 1. License Name Changes

Former name	Current name	Notes
Client Connections	Managed System for LAN and Managed System for SAN	A managed system that moves data to and from storage both on a LAN and on a SAN, requires only the Managed System for SAN license.
OpenSystem	AFS/DFS Support	The S/390 [®] platform includes the S/390 UNIX [®] client as part of Managed System for LAN.
Extended Device Support	Managed Library	

I — Tivoli Storage Manager Basics

1

Introducing Tivoli Storage Manager

Tivoli Storage Manager (TSM) is an enterprise-wide storage management application for the network. It provides automated storage management services to multivendor workstations, personal computers, and local area network (LAN) file servers. TSM includes the following components:

Server

Allows a server system to provide backup, archive, and space management services to workstations. The server maintains a database and recovery log for TSM resources, users, and user data.

The server controls storage objects called storage pools. These are groups of random and sequential access media that store backed-up, archived, and space-managed files.

You can set up multiple servers in your enterprise network to balance storage, processor, and network resources. TSM allows you to manage and control multiple servers from a single interface that runs in a Web browser (the enterprise console).

Administrative interface

Allows administrators to control and monitor server activities, define management policies for client files, and set up schedules to provide services at regular intervals. Administrative functions are available from an administrative client command line and from a Web browser interface. A server console is also available.

Backup-archive client

Allows users to maintain backup versions of their files, which they can restore if the original files are lost or damaged. Users can also archive files for long-term storage and retrieve the archived files when necessary. Users themselves or administrators can register workstations and file servers as client nodes with a TSM server.

Application program interface (API)

Allows users to enhance existing applications with back up, archive, restore, and retrieve services. When users install the TSM API client on their workstations, they can register as client nodes with a TSM server.

TSM also supports the following client programs:

Tivoli Data Protection for applications (application clients)

Allows users to perform online backups of data that is used by applications such as database programs. After the database initiates a backup or restore, the application client acts as the interface to TSM. The TSM server then applies its storage management functions to the data. The application client can perform its functions while users are working, with minimal disruption.

Tivoli Space Manager

Provides space management services for workstations on some platforms. Tivoli

Space Manager users can free workstation storage by migrating less frequently used files to server storage. These migrated files are also called *space-managed files*. Users can recall space-managed files automatically simply by accessing them as they would normally. Tivoli Space Manager is also known as the hierarchical storage management (HSM) client.

Figure 1 shows an example of a client/server environment with TSM. In this example, an administrator uses an administrative interface to monitor the system, for example, the administrative client program that is installed on a workstation. An administrator can also monitor a server by using a Web browser with the appropriate Java support.

The backup-archive client program and HSM client program have been installed on workstations connected through a LAN and registered as client nodes. From these client nodes, users can back up, archive, or migrate files to the server.

Using rules in TSM policies that are assigned to files, the server stores client files on disk, optical, or tape volumes in server storage. Server storage is divided into storage pools that are groups of storage volumes.




Figure 1. Sample Client/Server Environment

The following sections present key concepts and information about TSM. The sections describe how TSM manages client files based on information provided in administrator-defined policies, and manages devices and media based on information provided in administrator-defined TSM storage objects.

Concepts:
“How Tivoli Storage Manager Stores Client Data”
“Tivoli Storage Manager Device Support” on page 7
“Automating Client Operations” on page 9
“Working with a Network of Tivoli Storage Manager Servers” on page 10

How Tivoli Storage Manager Stores Client Data

Clients use TSM to store data for any of the following purposes:

Backup

Copying data from client workstations to server storage to ensure against loss of data. The server retains copies of multiple versions of a file according to policy. Policy includes the number of versions and the retention time for versions.

Archiving

Copying data from client workstations to server storage for long-term storage. The server retains archive copies according to the policy for retention time.

Space Management

Freeing up client storage space by copying files from workstations with Tivoli Space Manager to server storage. This process is also called hierarchical storage management (HSM). On the client, Tivoli Space Manager replaces the original file with a stub file that points to the original in server storage.

The process of moving the client file to server storage is also called **migration**.

TSM policy governs how the client data is stored and managed. Administrators define policy by defining policy domains, policy sets, management classes, and backup and archive copy groups. When you install TSM, you have a policy that consists of a policy domain named STANDARD. The STANDARD policy domain contains a policy set, a management class, a backup copy group, and an archive copy group, all named STANDARD. For information about this default policy, see “The Standard Policy” on page 235.

Figure 2 on page 6 shows how policy is part of the TSM process for storing client data. The steps in the process are as follows:

- 1** A client initiates a backup, archive, or migration operation. The file involved in the operation is bound to a management class. The management class is either the default or one specified for the file in the client’s include-exclude list.
- 2** If the file is a candidate for backup, archive, or migration based on information in the management class, the client sends the file and file information to the server.
- 3** The server checks the management class that is bound to the file to determine the *storage destination*, the name of the TSM storage pool where the server initially stores the file. For backed-up and archived files, storage destinations are assigned in the backup and archive copy groups, which are within management classes. For space-managed files, storage destinations are assigned in the management class itself.
The storage pool can be a group of disk volumes, tape volumes, or optical volumes.
- 4** The server stores the file in the storage pool identified as the storage destination.

TSM saves information in the TSM database about each file that it backs up, archives, or migrates. This information includes the file name, file size, file owner, management class, copy group, and location of the file in TSM server storage.

If server storage is structured in a hierarchy, TSM can later migrate the file to a different storage pool. For example, you may want to set up server storage so that TSM migrates files from a disk storage pool to tape volumes in a tape storage pool.




Figure 2. How Tivoli Storage Manager Controls Backup, Archive, and Migration

Files remain in server storage until they expire and expiration processing occurs, or until they are deleted from server storage. A file expires because of criteria set in policy or because the file is deleted from the client's file system.

For information on assigning storage destinations in copy groups and management classes, and binding management classes to client files, see “Implementing Policies for Client Data” on page 233.

For information on managing the database, see “Managing the Database and Recovery Log” on page 387.

For information about storage pools and storage pool volumes, see “Managing Storage Pools and Volumes” on page 119.

Tivoli Storage Manager Device Support

Tivoli Storage Manager represents physical storage devices and media with the following administrator-defined objects:

Library

A TSM library is one or more drives (and possibly robotic devices) with similar media mounting requirements.

Drive Each TSM drive represents a drive mechanism in a tape or optical device.

Device Class

Each device is associated with a device class that specifies the device type and how the device manages its media. TSM has a predefined device class (DISK) for random access devices.

Storage Pools and Volumes

A storage pool is a named collection of storage volumes of the same media type. A storage pool is associated with a device class. For example, an 8mm tape storage pool contains only 8mm tape volumes. A storage pool volume is associated with a specific storage pool.

“Putting It All Together” summarizes the relationships among the physical device environment, TSM storage objects, and TSM clients. The numbers below correspond to the numbers in the figure.

For a detailed description of device concepts, see “Introducing Storage Devices” on page 23.

Putting It All Together

Figure 3 on page 8 summarizes the relationships among the physical device environment, TSM storage and policy objects, and clients. The numbers in the following list correspond to the numbers in the figure.

- 1** When clients are registered, they are associated with a policy domain. Within the policy domain are the policy set, management class, and copy groups.
- 2**, **3** When a client backs up, archives, or migrates a file, it is bound to a management class. A management class and the backup and archive copy groups within it specify where files are stored and how they are managed when they are backed up, archived, or migrated (space-managed files).

- 4**, **5** Storage pools are the destinations for backed-up, archived, or space-managed files. Copy groups specify storage pools for backed-up or archived files. Management classes specify storage pools for space-managed files.

Storage pools are mapped to device classes, which represent devices. The storage pool contains volumes as indicated by the device type associated with the device class. For example, a storage pool that is mapped to a device class with a device type of 8MM contains only 8mm tapes.

All devices require a device class that specifies at least a device type. Tape and optical devices also require a library and drive for management of media, including the mounting of that media.

- 6** Files that are initially stored on disk storage pools can migrate to tape or optical disk storage pools if the pools are set up in a storage hierarchy.




Figure 3. Putting It All Together

Automating Client Operations

You can automate operations such as backup for the clients. You can perform the operations immediately or schedule them to occur at regular intervals. Figure 4 on page 10 shows the TSM objects that may be involved in automated client operations. The key objects that interact are:

Include-exclude list (file for UNIX clients) on each client

Determines which files are backed up or space-managed, and determines management classes for files

Management class

Determines where client files are initially stored and how they are managed

Schedule

Determines when client operations such as backup occur

Association defined between client and schedule

Determines which schedules are run for a client

The client can specify a management class for a file or set of files, or can use the default management class for the policy domain. The client specifies a management class by using an INCLUDE option in the client's include-exclude list or file. (See **A** in Figure 4 on page 10.) You can have central control of client options such as INCLUDE and EXCLUDE by defining client option sets on the server. When you register a client, you can specify a client option set for that client to use. See “Modifying Client Option Files” on page 214 for details.

The management class contains information that determines how TSM handles files that clients backup, archive, or migrate. For example, the management class contains the backup copy group and the archive copy group. Each copy group points to a *destination*, a storage pool where files are first stored when they are backed up or archived. (See **E** in Figure 4 on page 10.)

Clients are assigned to a policy domain when they are registered. Schedules that can automate client operations are also associated with a policy domain. (See **C** in Figure 4 on page 10.) To automate client operations, you define schedules for a domain. Then you define associations between schedules and clients in the same domain. (See **B** in Figure 4 on page 10.)

For a schedule to work on a particular client, the client machine must be turned on and must be running the client scheduler.

The scheduled client operations are called *events*. TSM stores information about events in the TSM database. (See **D** in Figure 4 on page 10.) For example, you can query the server to determine which scheduled events completed successfully and which failed.

For how to set up policy domains and management classes, see “Implementing Policies for Client Data” on page 233. For how to automate client operations, see “Scheduling Operations for Client Nodes” on page 285. See the client publications for how to install and run the scheduler on client machines.




Figure 4. Automating Client Operations

Working with a Network of Tivoli Storage Manager Servers

You may have a number of TSM servers in your network, at the same or different locations. For example, you may have users scattered across many locations, and have located TSM servers close to the users to manage network bandwidth limitations. You may set up multiple servers for organization purposes. You may have multiple servers on your network to make disaster recovery easier. TSM provides functions to help you configure, manage, and monitor the servers connected to a network. For example, an administrator working at one TSM server can work with TSM servers at other locations around the world, as Figure 5 on page 11 illustrates.



Figure 5. Connecting Tivoli Storage Manager Servers around the World

The Enterprise Administration functions allow you to do the following:

- Maintain and distribute server configuration information such as policy from a single configuration manager to many managed servers
- Monitor many servers and clients from a single server
- Issue commands on one server to one or more other servers and groups of servers

For detailed information on these tasks, see “Working with a Network of Tivoli Storage Manager Servers” on page 309.

With server-to-server virtual volumes, you can use the storage on one server for data from another server. See “Using Virtual Volumes to Store Data on Another Server” on page 348 for details.

With the Tivoli Disaster Recovery Manager (DRM), you can store a recovery plan file for one server on another server. You can also back up the server database and storage pools to another server. See “Using Tivoli Disaster Recovery Manager” on page 497 for details. See “Licensing Tivoli Storage Manager” on page 355 for information about licensing the TSM server to use DRM.

2

Administrator Tasks

This chapter provides a brief overview of the tasks that TSM administrators can do. It also points to the sections in this publication that present the details of those tasks and the concepts you need to understand to complete them. The tasks are in the order in which they appear in the chapters of this book:

- **Configuring and Managing Server Storage**
 - Using magnetic disk devices with TSM
 - Using removable media devices with TSM
 - Managing removable media operations
 - Defining drives and libraries
 - Defining device classes
 - Managing storage pools
 - Managing storage volumes
- **Managing Client Operations**
 - Adding nodes
 - Managing client nodes
 - Implementing policies for client data
 - Managing data for client nodes
 - Scheduling operations for client nodes
 - Managing scheduling operations for client nodes
- **Maintaining the Server**
 - Working with a network of TSM servers
 - Managing server operations
 - Automating server operations
 - Managing the database and recovery log
 - Monitoring the TSM server
 - Exporting and importing data
- **Protecting the Server**
 - Protecting and recovering your server
 - Using Tivoli Disaster Recovery Manager (DRM)

Interfaces to Tivoli Storage Manager

There are four types of interfaces to Tivoli Storage Manager:

- Graphical user interfaces (GUIs).
For information about using the GUIs, see the online information or see *Quick Start*.
- Web interfaces for server administration and for the backup-archive client.

The administrative Web interface allows you to access TSM server functions from any workstation with a Web browser that has the appropriate support for Java. See *Quick Start* for information about the administrative Web interface.

The Web backup-archive client (Web client) allows an authorized user to remotely access a client to run backup, archive, restore, and retrieve processes. The Web browser must have the appropriate support for Java. See *Tivoli Storage Manager Installing the Clients* for requirements.

- The command-line interface. For information about using the command-line interface of the administrative client, see *Administrator's Reference*. For information about using the command-line interface of the backup-archive client, see the user's guide for that client.
- The application program interface. For more information, see *Tivoli Storage Manager Using the Application Programming Interface*.

Using Magnetic Disk Devices with Tivoli Storage Manager

Magnetic disk devices can be used with TSM for two purposes:

- Storage of the database and recovery log
- Storage of client data that is backed up, archived, or migrated from client nodes

The server can store data on magnetic disk using random access volumes (device type of DISK) or sequential access volumes (device type of FILE).

For guidance in setting up storage pools on disk devices, see “Using Magnetic Disk Devices” on page 43.

Using Removable Media Devices with Tivoli Storage Manager

Removable media devices can be used with TSM for the following purposes:

- Storage of client data that is backed up, archived, or migrated from client nodes
- Storage of database backups
- Exporting data

For guidance and scenarios on configuring your removable media devices, see “Configuring Storage Devices” on page 57.

Managing Removable Media Operations

TSM allows you to use and reuse removable media to store data. You must prepare removable media for initial use by TSM. You also control how and when media are reused.

When the server requires that a volume be mounted, it generates a request. You need to monitor and respond to the requests.

For information about managing removable media operations, see “Managing Removable Media Operations” on page 83.

Defining Drives and Libraries

To use removable media devices with TSM, you must define libraries and drives.

For more information, see “Configuring Storage Devices” on page 57. For additional detailed information about these tasks, see “Defining Drives and Libraries” on page 81.

Defining Device Classes

A device class represents a set of storage devices with similar availability, performance, and storage characteristics. You must define device classes for the types of drives available to the TSM server. You specify a device class when you define a storage pool, which is a named collection of volumes for storing user data.

For more information about defining device classes, see “Defining Device Classes” on page 105.

Managing Storage Pools

Backed up, archived, and space-managed files are stored in groups of volumes called storage pools. The data on these primary storage pools can be backed up to copy storage pools for disaster recovery purposes. Because each storage pool is assigned to a device class, you can logically group your storage devices to meet your storage management needs.

You can establish a hierarchy of storage pools. The hierarchy may be based on the speed or the cost of the devices associated with the pools. TSM migrates client files through this hierarchy to ensure the most efficient use of a server’s storage devices.

When defining or modifying a storage pool, you can specify any or all of the following:

Cache When the server migrates files from disk storage pools, duplicate copies of the files may remain in cache (disk storage) for faster retrieval. Cached files are deleted only when space is needed. However, client backup operations that use the disk storage pool may have poorer performance.

Collocation

TSM can keep each client’s files on a minimal number of volumes within a storage pool. Because client files are consolidated, restoring collocated files requires fewer media mounts. However, backing up files from different clients requires more mounts.

Reclamation

Files on sequential access volumes may expire, move, or be deleted. The reclamation process consolidates the active, unexpired data on many volumes onto fewer volumes. The original volumes can then be reused for new data.

You manage storage volumes by defining, updating, and deleting volumes, and by monitoring the use of server storage. You can also move files within and across storage pools to optimize the use of server storage.

For more information about storage pools and volumes and taking advantage of storage pool features, see “Managing Storage Pools and Volumes” on page 119.

Adding Client Nodes

The TSM server views its registered clients, application clients, host servers, and source servers as nodes that require services and resources from the server.

You can register the following types of clients and servers as client nodes:

- Tivoli Storage Manager backup-archive client

-
- Tivoli Data Protection application clients
 - Tivoli Space Manager (HSM client)
 - Tivoli Data Protection (TDP) host servers
 - Tivoli Storage Manager source server registered as a node on a target server

For more information, see “Adding Client Nodes” on page 189.

Managing Client Nodes

You can ensure that only authorized administrators and client nodes are communicating with the server, by requiring the use of passwords. You can also set the following requirements for passwords:

- Length of passwords
- Password expiration
- A limit on the number of consecutive invalid password attempts. When the client exceeds the limit, TSM locks the client node from access to the server.

You can define sets of client options for clients to use.

You can control access to the server by administrators. An organization may name a single administrator or may distribute the workload among a number of administrators and grant them different levels of authority.

For more information about managing clients, see “Managing Client Nodes” on page 197.

Implementing Policies for Client Data

From a backup-archive client node, files can be backed up, archived, or migrated to the server. This process ensures that current data can be restored or retrieved if it is accidentally deleted or corrupted on the workstations.

As the administrator, you define the rules for these operations based on user requirements for backing up, archiving, or migrating data. The rules are called *policies*. Policy identifies backup, archive, and migration criteria, where the client data is stored, and how the data is managed by the server.

For more information about establishing and managing policies, see “Implementing Policies for Client Data” on page 233.

Managing Data for Client Nodes

You can generate a backup set of a client node’s active, backed-up files from the server onto sequential media that can be read by the device restoring the backup set.

You can also set the server to allow a client node to back up a portion of a file that has been previously backed up, rather than the entire file. The portion of the file that is backed up is called a *subfile*.

For more information about these tasks, see “Managing Data for Client Nodes” on page 277.

Scheduling Operations for Client Nodes

You can create schedules to automatically process client operations such as backup and restore. For more information about scheduling operations, see “Scheduling Operations for Client Nodes” on page 285.

Managing Schedules for Client Nodes

After you have created schedules, you can manage and coordinate those schedules. For example, you can:

- Verify that the schedule ran successfully
- Determine how long TSM retains event records on the database
- Balance the workload on the server so that all scheduled operations complete

For more information about these tasks, see “Managing Schedules for Client Nodes” on page 293.

Working with a Network of Tivoli Storage Manager Servers

When you have a network of TSM servers, you can simplify configuration and management of the servers by using Enterprise Administration functions. You can do the following:

- Designate one server as a configuration manager that distributes configuration information such as policy to other servers.
- Route commands to multiple servers while logged on to one server.
- Log events such as error messages to one server.
- Store data for one TSM server in the storage of another TSM server.
- Store the DRM plan file on another server.

For how to set up and use these functions, see “Working with a Network of Tivoli Storage Manager Servers” on page 309.

Managing Server Operations

You can monitor an installation’s compliance with the terms of its license agreement. TSM lets you check license compliance and modify the terms. For more information about these tasks, see “Licensing Tivoli Storage Manager” on page 355.

You can manage server operations such as starting and stopping the server, maintaining and suspending client sessions with the server, and controlling server processes.

For details about the day-to-day tasks involved in administering the server, see “Managing Server Operations” on page 355.

Automating Server Operations

You can define schedules for the automatic processing of most administrative commands. For more information about scheduling TSM commands and operations, see “Automating Server Operations” on page 371.

Managing the Database and Recovery Log

The TSM database contains information about the client data in storage pools, registered client nodes, TSM policies, and TSM schedules. The server recovery log, which records changes made to the database, is used to restore the database to a consistent state and to maintain consistency across server start-up operations.

You manage the database and recovery log space to tune database and recovery log performance.

For more information about the TSM database and recovery log and about the tasks associated with administering them, see “Managing the Database and Recovery Log” on page 387.

Monitoring the Tivoli Storage Manager Server

TSM provides you with many sources of information about server and client status and activity, the state of the database, and resource usage. By monitoring this information, you can provide reliable services to users while making the best use of available resources.

You can use TSM queries and SQL queries to get information about the server. You can also set up logging of information about TSM clients and server events. For more information about these tasks, see “Monitoring the Tivoli Storage Manager Server” on page 405.

Exporting and Importing Data

As your storage needs increase, you can move data from one server to another. You can *export* part or all of a server’s data to sequential media, such as tape or a flat file, so that you can then *import* the data to another server. For more information about moving data between servers, see “Exporting and Importing Data” on page 435.

Protecting and Recovering Your Server

TSM provides a number of ways to protect and recover your server from media failure or from the loss of the TSM database or storage pools due to a disaster. These recovery methods are based on the following preventive measures:

- Mirroring, by which the server maintains one or more copies of the database or recovery log, allowing the system to continue when one of the mirrored disks fails
- Periodic backup of the database
- Periodic backup of the storage pools
- Recovery of damaged files
- Backing up the device configuration and volume history files

In addition, with the Tivoli Disaster Recovery Manager, you can prepare a disaster recovery plan to guide you through the recovery process.

For more information about protecting your data and for details about recovering from a disaster, see “Protecting and Recovering Your Server” on page 457.

Using Tivoli Disaster Recovery Manager

Tivoli Disaster Recovery Manager (DRM) is an optional product that assists an administrator with preparing a disaster recovery plan. An administrator can use the disaster recovery plan as a guide for disaster recovery as well as for audit purposes to certify the recoverability of the TSM server.

The disaster recovery methods of DRM are based on the following measures:

- Enabling Tivoli Disaster Recovery Manager
- Creating a backup copy of server primary storage pools and database
- Sending server backup volumes offsite
- Moving reclaimed or expired volumes back onsite
- Creating the disaster recovery plan file for the TSM server
- Storing client machine information
- Defining and tracking client recovery media

II — Configuring and Managing Server Storage

3

Introducing Storage Devices

This chapter introduces key concepts that you must be familiar with to work with TSM storage devices. It also describes what you will find in the storage device chapters.

Concepts:
“How Tivoli Storage Manager Represents Storage Devices” on page 24
“How Tivoli Storage Manager Represents Storage Media” on page 26
“Tivoli Storage Manager Storage Objects” on page 26
“How Tivoli Storage Manager Uses and Reuses Removable Media” on page 33
“Scratch Volumes and Private Volumes” on page 35
“Storage Area Network (SAN) Support” on page 36
“Planning for Server Storage” on page 39
“Configuring Devices” on page 40

How to Use the Server Storage Chapters

If you are new to Tivoli Storage Manager, you should begin by familiarizing yourself with the concepts presented in this chapter. The other chapters in this part of the book will help you to do the following:

Goal	Chapter
To configure and manage magnetic disk devices, which Tivoli Storage Manager uses to store client data, the database, database backups, recovery log, and export data.	“Using Magnetic Disk Devices” on page 43
To physically attach storage devices to your system and to install and configure device drivers for those storage devices.	“Attaching Devices to the Server System” on page 49
To configure devices to use with Tivoli Storage Manager, and to see detailed scenarios of representative device configurations.	“Configuring Storage Devices” on page 57
To perform routine operations such as labeling volumes, checking volumes into automated libraries, and maintaining storage volumes and devices.	“Managing Removable Media Operations” on page 83
To define and manage device classes.	“Defining Device Classes” on page 105
To understand storage pool and storage volume concepts, and to define and manage storage pools and storage volumes.	“Managing Storage Pools and Volumes” on page 119

How Tivoli Storage Manager Represents Storage Devices

Tivoli Storage Manager supports many devices for storing data. These devices may be real physical devices, such as disk drives or tape drives. They may also be logical devices, such as files on a disk (FILE device type) or storage on another server (SERVER device type). TSM represents physical and logical devices with administrator-defined storage objects: library, drive, and device class. You define the storage objects when you configure devices for TSM.

At a minimum, each type of device requires a device class. The device class contains information for the management of devices and media that are of a specific device type. The device type determines whether TSM also requires a library and drive definition. For example, a manually mounted tape device requires a library, a drive, and a device class. See the following sections for details:

- “Disk Devices”
- “Removable Media Devices”
- “Files on Disk as Sequential Volumes” on page 25
- “Sequential Volumes on Another Tivoli Storage Manager Server” on page 25

For a summary, see Table 2 on page 40.

For details about devices that are supported, visit the Tivoli Storage Manager Web site at this URL:

http://www.tivoli.com/support/storage_mgr/tivolimain.html

Disk Devices

Magnetic disk devices are the only devices in the random access category. All disk devices share the same TSM device type and device class: DISK. TSM has a predefined DISK device class.




Figure 6. Magnetic Disk Devices Are Represented by Only a Device Class

Removable Media Devices

In addition to a device class, a removable media device is also represented by a library object and a drive object. See Figure 7 on page 25.




Figure 7. Removable Media Devices Are Represented by a Library, Drive, and Device Class

Sequential devices for which an operator must perform volume mounts require a different TSM library than devices that are associated with an automated library with robotics. TSM provides a manual library type for stand-alone devices that are loaded by an operator and automated library types for devices loaded by a robot.

Sequential devices that are managed by an external media management system require a library definition, but not a drive definition.

Files on Disk as Sequential Volumes

TSM allows administrators to create volumes on server disk space that have the characteristics of sequential access volumes such as tape. TSM supports these sequential volumes through the FILE device type. FILE is a sequential device type that, because it is on disk, does not require the administrator to define a library or drive object; only a device class is required.

You may want to use FILE volumes as a way to use disk storage without having to define volumes to TSM. FILE volumes can also be useful when transferring data for purposes such as electronic vaulting.

Sequential Volumes on Another Tivoli Storage Manager Server

TSM allows administrators to create volumes that exist as archived files in the storage hierarchy of another TSM server. The volumes created are a special type of sequential access volume called a *virtual volume*. Virtual volumes have the characteristics of sequential access volumes such as tape. TSM supports virtual volumes through the SERVER device type. The administrator must define a device class and a server that will store the data. No library or drive definition is required.

Virtual volumes are useful for the following purposes:

- Centralization of physical tape resources. You can have one server attached to a large tape library. Other TSM servers can use that library indirectly through a SERVER device class.
- Data-sharing between servers, by using a SERVER device class to export and import data. You do not need to move any physical media from location to location.

-
- Immediate offsite storage of storage pool backups and TSM database backups, without physically moving media to another location.
 - Offsite storage of the Tivoli Disaster Recovery Manager (DRM) recovery plan file.
 - Electronic vaulting.

How Tivoli Storage Manager Represents Storage Media

TSM represents units of storage media with administrator-defined TSM objects: storage pool volumes and storage pools. Figure 8 shows storage pool volumes grouped into a storage pool. Each storage pool represents only one type of media. For example, a storage pool for 8mm devices represents collections of only 8mm tapes.




Figure 8. Relationships of Storage Pool Volumes, Storage Pools, and Media

For DISK device classes, you must define volumes. For other device classes, such as tape, you can allow the TSM server to dynamically acquire scratch volumes and define those volumes as needed. For details, see “Preparing Volumes for Random Access Storage Pools” on page 128 and “Preparing Volumes for Sequential Access Storage Pools” on page 129.

Tivoli Storage Manager Storage Objects

An administrator defines the following TSM storage objects, which are collections of information that the TSM server uses to communicate with devices and to manage media:

- Library
- Drive
- Device class
- Storage pool
- Storage volume
- Server

Library

A TSM library is a collection of one or more drives that share similar media mounting requirements. The library can include an automated mounting mechanism. Each tape or optical disk device must be associated with a TSM library.

Use different libraries to identify devices that are mounted by different means (for example, an operator instead of robotics). You can define these types of libraries:

- **MANUAL**, for groups of devices that are loaded by an operator

-
- SCSI, for drives in a SCSI-attached autochanger device
 - 349X, for drives in an IBM 3494, an automated library
 - ACSLS, for drives in a library controlled by StorageTek Automated Cartridge System Library Software (ACSL)
 - EXTERNAL, for drives that are managed by an external media management program
 - SHARED, for drives on a storage area network (SAN) that are managed by another TSM server and shared among TSM servers

Manual Libraries

In a MANUAL library, an operator mounts the volumes. Define a MANUAL library if you have one or more drives for which operators must mount volumes (drives that are not part of an automated library). You can combine drives with different device types, such as DLT and 8MM, in a single MANUAL library.

When the TSM server determines that a volume needs to be mounted in a drive that is part of a MANUAL library, the server issues mount request messages that prompt an operator to mount the volume. The server sends these messages to the server console and to administrative clients that were started by using the special *mount mode* or *console mode* parameter.

For help on configuring a MANUAL library, see “Configuring Storage Devices” on page 57. For information on how to monitor mount messages for a MANUAL library, see “Mount Operations for Manual Libraries” on page 96.

SCSI Libraries

A SCSI library is a collection of drives for which volume mounts and demounts are handled automatically by a robot or other mechanism. This type applies to automated libraries that are attached via a SCSI interface (other than the IBM 3494). Some examples of SCSI libraries are:

- The IBM 3570 tape device, with its cartridge-handling mechanism
- The IBM 3590 tape device, with its Automatic Cartridge Facility (ACF)
- The Exabyte EXB-210
- The IBM 3581 tape device

When you define a SCSI library to the TSM server, you must specify the library device name. To mount and dismount a volume in a drive that resides in the SCSI library, TSM uses the library name.

For help on configuring a SCSI library, see “Configuring Storage Devices” on page 57. For an example of how to add volumes to a SCSI library, see “Check in and Label Library Volumes” on page 65.

349X Libraries

A 349X library is a collection of drives in an IBM 3494 Tape Library Dataserver. Volume mounts and demounts are handled automatically by the automation in the library.

When you define a 349X library to the TSM server, you must specify the device name of one or more *library management control points* (LMCP). Each LMCP provides an

independent interface to the robot mechanism within a given 349X library. To mount and dismount a volume in a drive that is in a 3494 library, TSM uses an LMCP.

Note: For each 3494, you can define only one TSM library.

For help on configuring a 349X library, see “Configuring Storage Devices” on page 57. For an example of how to add volumes to a 349X library, see “Preparing Removable Media” on page 83.

ACSLs Libraries

An *ACSLs* library is a collection of drives in an automated library that is controlled by the StorageTek software, Automated Cartridge System Library Software (ACSLs). TSM can act as a client application to the ACSLS software to use the drives.

External Libraries

An *EXTERNAL* library is a collection of drives managed by a media management system that is not part of TSM. TSM provides an interface that allows external media management systems to operate in conjunction with the TSM server. To use the interface for one or more devices, you must define a library with library type *EXTERNAL*.

For *EXTERNAL* libraries, TSM uses the external media management system to perform the following functions:

- Volume mounts (specific and scratch)
- Volume dismounts
- Freeing of library volumes (return to scratch)

The external media manager selects the appropriate drive for media access operations. You do not define the drives, check in media, or label the volumes in an *EXTERNAL* library to TSM.

When you issue the *MOVE MEDIA* or *MOVE DRMEDIA* command for media in *EXTERNAL* libraries, TSM uses the external media management system to perform the following functions:

- Volume ejects
- Volume query

The *EXTERNAL* library type allows flexibility in grouping drives into libraries and storage pools. An *EXTERNAL* library may be one drive, a collection of drives, or even a part of an automated library.

For a definition of the interface that TSM provides to the external media management system, see “External Media Management Interface Description” on page 555.

Shared Libraries

A *SHARED* library is a collection of drives in a library that is attached via a storage area network (SAN). TSM servers can share the drives in the library. One TSM server acts as the library manager to control media mounts and other operations. Other servers that share the drives are called library clients. For details, see “Configurations in a Storage Area Network” on page 73.

Drive

Each drive mechanism within a device that uses removable media is represented by a TSM drive. For devices with multiple drives, including automated libraries, each drive is separately defined to TSM. Each drive is associated with a TSM library.

Device Class

Each device is associated with one TSM device class. A device class contains information about the device type and the way the device manages its media.

For devices that access data randomly, TSM provides a device class named DISK that is already defined and cannot be changed.

For devices such as tape drives that access data sequentially, the administrator must define the device class. Devices that access data sequentially also include FILE and SERVER device types. For FILE device classes, data resides in files on the server's disk storage. For SERVER device classes, data resides in the storage of another TSM server.

If the sequential device is a tape drive or optical disk, the device class is associated with a library. The library object is required for sequential devices because of the variations in media type (for example, 8mm tape and optical disk) and because of the need to manage multiple drives and automation.

The Device Class for Random Access Devices

Devices that access their media randomly share a common TSM device type. TSM provides a single, random-access device class, named DISK. You cannot define other random access device classes. You do not define a TSM library for random access devices.

Random access device types store data in blocks of storage that can be scattered across the available space on a disk. As the server deletes data that has expired, the space occupied by that data can be reused.

Device Classes for Sequential Access Devices

Tape devices, optical disk devices, FILE device types, and SERVER device types are members of the sequential access category of devices. All of these devices access their data sequentially. A device class for a sequential device contains a device type and media management information.

For tape and optical sequential devices, the device class also specifies a library. Figure 9 shows the contents of a device class for a typical sequential access device.




Figure 9. Contents of a Device Class for Sequential Access Devices

Sequential access device types begin to store data at the beginning of a volume and append new data after existing data. As data is deleted or expired, the space is not immediately

reused. The server can reclaim space later by using the reclamation process (see “Reclaiming Space in Sequential Access Storage Pools” on page 152 for details).

Device Type

Every sequential access device class requires one of the TSM device types as part of its definition. A device type identifies a device as a member of a group of devices that share similar media characteristics. TSM provides device types for many devices. For example, TSM provides an 8MM device type for tape drives that use 8mm tape.

FILE is a sequential device type in TSM that allows the administrator to create sequential volumes by creating files on disk storage. To the TSM server, these files have the characteristics of a tape volume.

A device type called REMOVABLEFILE supports devices that have removable media and are attached to the server as local, removable file systems. TSM sees each unit of media, for example an optical disk, as a single, sequential access file.

The sequential device type called SERVER allows the server to store data on another TSM server. This data has the characteristics of a tape volume from the view of the source server. On the target server, this data appears as archived files that belong to a special type of node.

Library

For sequential access device types (excluding FILE and SERVER), you must specify a library in the device class definition. The library you specify must be one that you have defined to TSM, as discussed in “Library” on page 26.

Media Management Information

Every sequential access device class contains media management information, such as recording format and labeling prefixes.

For more information about how TSM helps to manage media, see the following:

- “Configuring FILE Sequential Volumes on Disk Devices” on page 45
- “Using Virtual Volumes to Store Data on Another Server” on page 348
- “Configuring Storage Devices” on page 57
- “Defining Drives and Libraries” on page 81

Storage Pool

A storage pool is a named collection of storage volumes that are associated with one device class. Each storage pool represents a collection of volumes that are the same media type. For example, a storage pool that is associated with a device class for 8mm tape volumes contains only 8mm tape volumes. You can control the characteristics of storage pools, such as whether scratch volumes are used, by specifying parameters. For details on the parameters, see “Managing Storage Pools and Volumes” on page 119.

TSM supplies default disk storage pools that are named BACKUPPOOL, ARCHIVEPOOL, and SPACEMGPOOL. For more information, see “Configuring Random Access Volumes on Disk Devices” on page 44.

Storage Pool Volume

A TSM storage pool volume represents space on media that is available for storing client data. A storage pool volume is associated with a storage pool. For example, 8mm tapes and optical disks become storage pool volumes when they are assigned to a TSM storage pool.

See “Managing Storage Pools and Volumes” on page 119 for more information about TSM storage pool volumes.

Server

To store data in the storage of another TSM server, you use a SERVER device type in the device class. You also define a server object to communicate with the target server (where data is actually stored).

When you define a server object to one TSM server (a source server), you specify the communication attributes necessary for establishing a connection to another TSM server (a target server). The source server can then use the target server as a sequential device for storing data. This data on the target server is one or more archived files that are stored on behalf of the source server. For more information, see “Using Virtual Volumes to Store Data on Another Server” on page 348.

How Tivoli Storage Manager Uses Sequential Access Devices

Each TSM library is a collection of drives. A device class, which governs how data is stored, is associated with one *library*. When you define a storage pool, you associate the pool with a device class. Volumes are associated with pools. Figure 10 shows these relationships.




Figure 10. Relationships between Storage and Device Objects

When the TSM server determines that data is to be stored into or retrieved from a storage pool, it performs the following procedure:

1. Selects a volume from the given storage pool. The selection is based on the type of operation:

Retrieval

The name of the volume is stored in the server database.

Store If a defined volume in the storage pool can be used for the data being stored, the server chooses this volume name.

If no defined volumes in the storage pool can be used for the data, and if the MAXSCRATCH parameter of the storage pool permits it, the server may try a *scratch mount*.

2. Determines the name of the library containing the drives that can be used for the operation by checking the device class associated with the storage pool.
 - The server evaluates the status of each drive in the library until an available drive is found or until all drives have been checked. Drive status can be:
 - The drive is offline.
 - The drive is busy and cannot be used for this mount.
 - The drive is in an error state and cannot be used for this mount.
 - The drive is available and can be used for this mount.
3. Performs the volume mount operation:
 - If the library is manually operated, the server displays request messages for a mount operator, asks that the desired volume, or a scratch volume, be mounted in the selected drive.
 - If the library is automated, the server directs a robotic device to move the volume from a storage slot into the selected drive. No manual intervention is required. If a scratch mount is requested, the server checks the library's volume inventory to see if there is a volume with a status code of SCRATCH. The volume inventory is established and managed by using the commands described in "Managing Volumes in Automated Libraries" on page 93. Volume status codes are described in "Scratch and Private Volumes in Automated Libraries" on page 35. If a scratch volume is found, its volume status code is changed to PRIVATE and it is mounted in the drive. Eventually, it is automatically defined as part of the original storage pool. However, if the library's volume inventory does not contain any volumes with a status code of SCRATCH, the mount request fails.
4. Dismounts the volume from the drive when it has finished accessing the volume and the mount retention period has elapsed.
 - If the library is manually operated, the server ejects the volume from the drive so that a mount operator can place it in an appropriate storage location.
 - If the library is automated, the server interacts with a robotic device to move the volume from the drive back to its original storage slot in the library.

Putting It All Together

See Figure 3 on page 8 for a summary of the relationships among the physical device environment, TSM storage and policy objects, and clients.

How Tivoli Storage Manager Uses and Reuses Removable Media

TSM helps you to manage removable media by providing ways to control how removable media are used and reused. The following describes a typical life cycle for a piece of media. The numbers (such as **1**) refer to numbers in Figure 11.

1. You label **1** and check in **2** the media.
2. If you are planning to define volumes to a storage pool associated with a device, TSM recommends that you check the volume in with STATUS=PRIVATE. Use of scratch volumes is more convenient in most cases.




Figure 11. Simplified View of the Life Cycle of a Tape

3. A client sends data to the server for backup, archive, or space management. The server stores the client data on the volume. Which volume the server selects **3** depends on:
 - The policy domain to which the client is assigned.
 - The management class for the data (either the default management class for the policy set, or the class specified by the client in the client's include/exclude list or file).
 - The storage pool specified as the destination in either the management class (for space-managed data) or copy group (for backup or archive data). The storage pool is associated with a device class, which determines which device and which type of media is used.

- Whether the MAXSCRATCH value is reached when the scratch volumes are selected.
- Whether collocation is enabled for that storage pool. When collocation is enabled, TSM attempts to place data for different clients or client nodes on separate volumes.

See Figure 12.




Figure 12. How Tivoli Storage Manager Affects Media Use

- The contents of the volume change over time as a result of:
 - Expiration of files **4** (affected by management class and copy group attributes, and the frequency of expiration processing)
 - Movement and deletion of file spaces (by a TSM administrator)
 - Automatic reclamation of media by TSM **5**

The amount of data on the volume and the reclamation threshold set for the storage pool affects when the volume is reclaimed. When the volume is reclaimed, any valid, unexpired data is moved to other volumes or possibly to another storage pool (for storage pools with single-drive libraries).

If the volume becomes empty because all valid data either expires or is moved to another volume, the volume is available for reuse (after any time delay specified by the REUSEDelay parameter for the storage pool). The empty volume becomes a scratch volume if it was initially a scratch volume. The volume starts again at step 3 on page 33.

- You determine when the media has reached its end of life.

For volumes that you defined (private volumes), check the statistics on the volumes by using the `QUERY VOLUME` command. The statistics include the number of write passes on a volume (compare with the number of write passes recommended by the manufacturer) and the number of errors on the volume.

You must move any valid data off a volume that has reached end of life. Then, if the volume is in an automated library, check out the volume from the library. If the volume is not a scratch volume, delete the volume from the TSM database.

Scratch Volumes and Private Volumes

A scratch volume is a labeled volume that is empty or contains no valid data, and can be used to satisfy any request to mount a scratch volume. A private volume is a volume that is in use or owned by an application, and may contain valid data. Volumes that you define to TSM are private volumes. A private volume is only used to satisfy a request to mount that volume by name. For each storage pool, you must decide whether to use scratch volumes.

If you use scratch volumes, TSM uses volumes as needed, and returns the volumes to scratch when they become empty (for example, when all data on the volume expires). If you do not use scratch volumes, you must define each volume you want TSM to use. Volumes that you define to TSM are private volumes, and do not return to scratch when they become empty.

For more information on defining volumes, see “Preparing Removable Media” on page 83.

Scratch and Private Volumes in Automated Libraries

In the volume inventory for each automated library, TSM tracks whether a volume is in scratch or private status. If a storage pool contains scratch volumes, TSM can choose a scratch volume from those that have been checked into the library. When TSM uses a scratch volume, TSM defines the volume and changes its status to private. Volumes that were scratch volumes return to scratch status when they become empty. You lose the usage statistics on the volumes when the status of the volumes is changed.

For information on changing the status of a volume in an automated library, see “Changing the Status of a Volume” on page 93.

The Volume Inventory for an Automated Library

A library’s volume inventory includes only those volumes that have been checked into that library. This inventory is not necessarily identical to the list of volumes in the storage pools associated with the library:

- A volume can be checked into the library but not in a storage pool (a scratch volume).
- A volume can be defined to a storage pool associated with the library (a private volume), but not checked into the library.

For more information on how to check in volumes, see “Checking New Volumes into a Library” on page 87.

Private Volumes in an Automated Library

To specify which volumes are used by specific storage pools, you must define the volumes (`DEFINE VOLUME` command). To mount a private volume, you must provide the volume name. If you are doing database backup, dump, or load, or import or export operations, you must list the volumes to use if you want to use private volumes.

Scratch Volumes in an Automated Library

When TSM needs a new volume for a drive in an automated library, the server can choose any scratch volume in the library. The scratch volume is selected only if scratch volumes are allowed in the storage pool. After a volume is mounted, its status changes to private, and it is defined as part of the storage pool for which the mount request was made. When that volume is deleted from the storage pool (for example, after all the data it contains expires), the volume returns to scratch and can be reused by any storage pool associated with the library.

One benefit of scratch volumes is any storage pools associated with the same automated library can dynamically acquire volumes from the library's pool of scratch volumes. You do not need to allocate volumes to the different storage pools. Another benefit, even if only one storage pool is associated with a library, is that you do not need to explicitly define all the volumes for the storage pool. Volumes are automatically added to and deleted from the storage pool by the server.

Note: A disadvantage of using scratch volumes is that volume usage information, which you can use to determine when the media has reached its end of life, is deleted when the private volume is returned to the scratch volume pool.

If a scratch volume is used for a database backup or export operation, TSM changes the volume status to private. The volume returns to the scratch pool only when an administrator determines that the volume's data is no longer needed, and uses the UPDATE LIBVOLUME command to change the status of the volume to scratch.

Storage Area Network (SAN) Support

A storage area network (SAN) is a dedicated storage network that isolates access to shared data to improve system performance. A SAN differs from a typical network. A typical network not only provides data access, but also provides communications functions like electronic mail, terminal connection, and application program communication. A SAN can allow you to consolidate storage, and can relieve the distance, scalability, and bandwidth limitations inherent in LAN and wide area network (WAN) environments.

Using a SAN with TSM allows the following functions:

- Multiple TSM servers to share storage devices
- TSM clients to directly access storage devices (LAN-free data movement)

TSM can use a Storage Area Network (SAN) to enable the sharing of storage devices that are supported by the TSM or RMSS device driver. This includes most IBM 349X devices and SCSI devices.

For information about supported Fibre Channel hardware and configurations, visit the TSM home page at the following address:

http://www.tivoli.com/support/storage_mgr/tivolimain.html. Also see

http://www.tivoli.com/support/storage_mgr/san/overview.html for detailed information on support.

How TSM Servers Share Devices Over a SAN

Figure 13 on page 37 shows a SAN configuration in which two TSM servers share a library device.




Figure 13. Storage Area Network (SAN) Configuration. The servers communicate over the LAN. The library manager controls the library via the SAN. The library client stores data to the library devices via the SAN.

When TSM servers share a storage device, one server, the *library manager*, controls device operations. These operations include mount, dismount, volume ownership, and library inventory. Other servers, *library clients*, use server-to-server communications to contact the library manager and request device service. Data moves over the SAN between each server and the storage device. See “Configurations in a Storage Area Network” on page 73.

TSM servers use the following features when sharing an automated library device:

Partitioning of the Volume Inventory

The inventory of media volumes in the shared library device is partitioned among servers. Either one TSM server owns a particular volume, or the volume is in the global scratch pool. No server owns the scratch pool at any given time.

Serialized Drive Access

Only one TSM server accesses each tape drive at a time. Drive access is serialized and controlled so that servers do not dismount other servers’ volumes or write to drives where other servers mount their volumes.

Serialized Mount Access

The library device’s autochanger performs a single mount or dismount operation at a time. A single server (library manager) performs all mount operations to provide this serialization.

How TSM Clients Directly Access Devices Over a SAN

Figure 14 on page 38 shows a SAN configuration in which a TSM client directly accesses a tape of disk library device to read or write data.




Figure 14. SAN Data Movement. Client and server communicate over the LAN. The server controls the device on the SAN. Client data moves over the SAN to the device.

SAN data movement by a client requires the installation of a storage agent on the client machine. The TSM server maintains the TSM database and recovery log, and acts as the library manager. The storage agent on the client handles the data transfer to the device on the SAN. This implementation frees up bandwidth on the LAN that would otherwise be used for client data movement.

The following outlines a typical backup scenario for a TSM client that uses SAN data movement:

1. The client begins a backup operation. The client and the server exchange policy information over the LAN to determine the destination of the backed up data.
For a client using LAN-free data movement, the destination is a storage pool that uses a device on the SAN. That device must also be mapped for the client.
2. Because the destination is on the SAN, the client contacts the storage agent, which will handle the data transfer. The storage agent sends a request for a volume mount to the server.
3. The server contacts the storage device and, in the case of a tape library, mounts the appropriate media.
4. The server notifies the client of the location of the mounted media.
5. The client, via the storage agent, writes the backup data directly to the device over the SAN.
6. The storage agent sends file attribute information to the TSM server and the server stores the information in its database.

See “Configuring TSM Clients to Directly Access SAN-Attached Devices” on page 79.

Note: See the TSM home page at http://www.tivoli.com/support/storage_mgr/tivolimain.html for the latest information on clients that support the feature.

Planning for Server Storage

Businesses often back up data to a variety of storage devices ranging from high-performance disk devices to slower and less expensive tape devices. Administrators must balance the data availability requirements of users with the costs of storage devices.

This section discusses how to evaluate your current environment to determine the device classes and storage pools for your server storage.

Before configuring devices, evaluate the hardware available to the server.

1. Determine the storage devices that are available to the server. For example, determine how many tape drives you have that you will allow the server to use.

The server expects to have exclusive use of the drives defined to it. If another application tries to use a drive defined to the server while the server is running, some server functions may fail.

2. Determine the TSM device type and class for each of the available devices. Group together similar devices and identify their device classes. For example, create separate categories for 4mm and 8mm devices.

Note: For sequential access devices, you can categorize the type of removable media based on their capacity.

3. Determine how the mounting of volumes is accomplished for the devices:
 - Devices that require operators to load volumes must be part of a MANUAL library defined to TSM.
 - Devices that are automatically loaded must be part of a SCSI or 349X library defined to TSM. Each automated library device is a separate TSM library.
 - Devices that are controlled by StorageTek Automated Cartridge System Library Software (ACSL) must be part of an ACSL library defined to TSM.
 - Devices that are managed by an external media management system must be part of an EXTERNAL library defined to TSM.
4. If you are considering storing data for one TSM server using the storage of another TSM server (SERVER device type), consider network bandwidth and network traffic. If your network resources constrain your environment, you may have problems using the SERVER device type efficiently.

Also consider the storage resources available on the target server. Ensure that the target server has enough storage space and drives to handle the load from the source server.
5. Determine the storage pools to set up, based on the devices you have and on user requirements. Gather users' requirements for data availability. Determine which data needs quick access and which does not.
6. Be prepared to label removable media to be used by TSM. You may want to create a new labeling convention for TSM media so that you can distinguish them from media used for other purposes.

Configuring Devices

Before a device can be used by TSM, the device must be configured to the operating system as well as to TSM. Table 2 summarizes the TSM definitions that are required for different device types.

Table 2. Required TSM Definitions for Storage Devices

Device	Device Types	Required TSM Definitions		
		Library	Drive	Device Class
Magnetic Disk	DISK	—	—	Yes ¹
	FILE	—	—	Yes
Tape	3570	Yes	Yes	Yes
	3590			
	4MM			
	8MM			
	CARTRIDGE ²			
	DLT			
	DTF			
	ECARTRIDGE ³			
	GENERICTAPE			
	LTO			
QIC				
Optical	OPTICAL	Yes	Yes	Yes
	WORM			
	WORM12			
	WORM14			
Removable Media (File System)	REMOVABLEMEDIA	Yes	Yes	Yes
Virtual volumes	SERVER	—	—	Yes

¹ The DISK device class exists at installation and cannot be changed.

² The CARTRIDGE device type is for IBM 3480, 3490, and 3490E tape drives.

³ The ECARTRIDGE device type is for cartridge tape drives such as the StorageTek SD-3, 9480, 9890, and 9940 drives.

Mapping Devices to Device Classes

As an example of mapping devices to device classes, assume you have the following devices to use for server storage:

- Internal disk drives
- An automated tape library with 8mm drives
- A manual DLT tape drive

You can map storage devices to device classes as shown in Table 3.

Table 3. Mapping Storage Devices to Device Classes

Device Class	Description
DISK	Storage volumes that reside on the internal disk drive TSM provides one DISK device class that is already defined. You do not need and cannot define another device class for disk storage.
8MM_CLASS	Storage volumes that are 8mm tapes, used with the drives in the automated library
DLT_CLASS	Storage volumes that are DLT tapes, used on the DLT drive

You must define any device classes that you need for your removable media devices such as tape drives. See “Defining Device Classes” on page 105 for information on defining device classes to support your physical storage environment.

Mapping Storage Pools to Device Classes and Devices

After you have categorized your storage devices, identify availability, space, and performance requirements for client data that is stored in server storage. These requirements help you determine where to store data for different groups of clients and different types of data. You can then create storage pools that are storage destinations for backed-up, archived, or space-managed files to match requirements.

For example, you determine that users in the business department have three requirements:

- Immediate access to certain backed-up files, such as accounts receivable and payroll accounts.
These files should be stored on disk. However, you need to ensure that data is moved from the disk to prevent it from becoming full. You can set up a storage hierarchy so that files can migrate automatically from disk to the automated tape library.
- Periodic access to some archived files, such as monthly sales and inventory reports.
These files can be stored on 8mm tapes, using the automated library.
- Occasional access to backed-up or archived files that are rarely modified, such as yearly revenue reports.
These files can be stored using the DLT drive.

To match user requirements to storage devices, you define storage pools, device classes, and, for device types that require them, libraries and drives. To set up the storage hierarchy so that data migrates from the BACKUPPOOL to 8mm tapes, you specify BACKTAPE1 as the next storage pool for BACKUPPOOL. See Table 4.

Table 4. Mapping Storage Pools to Device Classes, Libraries, and Drives

Storage Pool	Device Class	Library (Hardware)	Drives	Volume Type	Storage Destination
BACKUPPOOL	DISK	—	—	Storage volumes on the internal disk drive	For a backup copy group for files requiring immediate access
BACKTAPE1	8MM_CLASS	AUTO_8MM (Exabyte EXB-210)	DRIVE01, DRIVE02	8mm tapes	For overflow from the BACKUPPOOL and for archived data that is periodically accessed
BACKTAPE2	DLT_CLASS	MANUAL_LIB (Manually mounted)	DRIVE03	DLT tapes	For backup copy groups for files that are occasionally accessed

Note: TSM has default disk storage pools named BACKUPPOOL, ARCHIVEPOOL, and SPACEMGPOOL. For more information, see “Configuring Random Access Volumes on Disk Devices” on page 44.

4

Using Magnetic Disk Devices

Tivoli Storage Manager uses magnetic disk devices to do the following:

- Store the database and the recovery log. For details, see “Managing the Database and Recovery Log” on page 387.
- Store client data that has been backed up, archived, or migrated from client nodes. The client data is stored in storage pools. Procedures for configuring disk storage of client data are described in this chapter.
- Store backups of the TSM database and export and import TSM data. See “Using FILE Volumes for Database Backups and Export Operations” on page 46.

See the following sections:

Tasks:
“Configuring Random Access Volumes on Disk Devices” on page 44
“Configuring FILE Sequential Volumes on Disk Devices” on page 45
“Varying Disk Volumes Online or Offline” on page 45
“Using Cache” on page 46
“Freeing Space on Disk” on page 46
“Specifying Scratch FILE Volumes” on page 46
“Using FILE Volumes for Database Backups and Export Operations” on page 46

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Note: Some of the tasks described in this chapter require an understanding of TSM storage objects. For an introduction to these storage objects, see “Tivoli Storage Manager Storage Objects” on page 26.

Configuring Disk Devices

TSM stores data on magnetic disks in two ways:

- In random access volumes, as data is normally stored on disk. See “Configuring Random Access Volumes on Disk Devices” on page 44.

- In files on the disk that are treated as sequential access volumes. See “Configuring FILE Sequential Volumes on Disk Devices” on page 45.

Task	Required Privilege Class
Configuring Random Access Volumes on Disk Devices	System
Configuring FILE Sequential Volumes on Disk Devices	

Configuring Random Access Volumes on Disk Devices

TSM provides a defined DISK device class that is used with all disk devices.

Tip: For performance reasons, define storage pool volumes on disk drives that reside on the TSM server machine, not on remotely mounted file systems.

Do the following to use random access volumes on a disk device:

1. Define a storage pool that is associated with the DISK device class, or use one of the default storage pools that TSM provides (ARCHIVEPOOL, BACKUPPOOL, and SPACEMGPOOL).

For example, enter the following command on the command line of a TSM administrative client:

```
define stgpool engback1 disk maxsize=5m highmig=85 lowmig=40
```

This command defines storage pool ENGBACK1.

See “Example: Defining Storage Pools” on page 125 for details.

2. Prepare a volume for use in a random access storage pool by defining the volume. For example, you want to define a 21MB volume for the ENGBACK1 storage pool. You want the volume to be located in the path `/usr/tivoli/tsm/server/bin` and named `stgvol.002`. Enter the following command:

```
define volume engback1 /usr/tivoli/tsm/server/bin/stgvol.002 formatsize=21
```

If you do not specify a full path name, the command uses the current path. See “Defining Storage Pool Volumes” on page 130 for details.

This one-step process replaces the former two-step process of first formatting a volume (using DSMFMT) and then defining the volume. If you choose to use the two-step process, the DSMFMT utility is available from the operating system command line. See *Administrator’s Reference* for details.

Another option for preparing a volume is to create a raw logical volume by using SMIT.

3. Do one of the following:
 - Specify the new storage pool as the destination for client files that are backed up, archived, or migrated, by modifying existing policy or creating new policy. See “Implementing Policies for Client Data” on page 233 for details.
 - Place the new storage pool in the storage pool migration hierarchy by updating an already defined storage pool. See “Example: Updating Storage Pools” on page 126.

Configuring FILE Sequential Volumes on Disk Devices

Another way to use magnetic disk storage is to use files as volumes that store data sequentially (as on tape volumes). FILE sequential volumes are often useful when transferring data for purposes such as electronic vaulting.

To use files as volumes that store data sequentially, do the following:

1. Define a device class with device type FILE.

For example, enter the following command on the command line of a TSM administrative client:

```
define devclass fileclass devtype=file mountlimit=2
```

This command defines device class FILECLASS with a device type of FILE.

See “Defining and Updating FILE Device Classes” on page 111.

To store TSM database backups or exports on FILE volumes, this step is all you need to do to prepare the volumes. For more information, see “Defining Device Classes for Backups” on page 469 and “Planning for Sequential Media Used to Export Data” on page 437.

2. Define a storage pool that is associated with the new FILE device class.

For example, enter the following command on the command line of a TSM administrative client:

```
define stgpool engback2 fileclass maxscratch=100 mountlimit=2
```

This command defines storage pool ENGBACK2 with device class FILECLASS.

See “Defining or Updating Primary Storage Pools” on page 123 for details.

To allow the server to use scratch volumes for this device class, specify a value greater than zero for the number of maximum scratch volumes when you define the device class. If you do set MAXSCRATCH=0 to not allow scratch volumes, you must define each volume to be used in this device class. See “Preparing Volumes for Sequential Access Storage Pools” on page 129 for details.

3. Do one of the following:

- Specify the new storage pool as the destination for client files that are backed up, archived, or migrated, by modifying existing policy or creating new policy. See “Implementing Policies for Client Data” on page 233 for details.
- Place the new storage pool in the storage pool migration hierarchy by updating an already defined storage pool. See “Example: Updating Storage Pools” on page 126.

Varying Disk Volumes Online or Offline

Task	Required Privilege Class
Vary a disk volume online or offline	System or operator

To perform maintenance on a disk volume or to upgrade disk hardware, you can vary a disk volume offline. For example, to vary the disk volume named */storage/pool001* offline, enter:

```
vary offline /storage/pool001
```

If the server encounters a problem with a disk volume, the server automatically varies the volume offline.

You can make the disk volume available to the server again by varying the volume online. For example, to make the disk volume named `/storage/pool001` available to the server, enter:

```
vary online /storage/pool001
```

Using Cache

When you define a storage pool that uses disk random access volumes, you can choose to enable or disable cache. When you use cache, a copy of the file remains on disk storage even after the file has been migrated to the next pool in the storage hierarchy (for example, to tape). The file remains in cache until the space it occupies is needed to store new files.

Using cache can improve how fast a frequently accessed file is retrieved. Faster retrieval can be important for clients storing space-managed files. If the file needs to be accessed, the copy in cache can be used rather than the copy on tape. However, using cache can degrade the performance of client backup operations and increase the space needed for the TSM database. For more information, see “Using Cache on Disk Storage Pools” on page 146.

Freeing Space on Disk

As client files expire, the space they occupy is not freed for other uses until you run expiration processing on the server.

Expiration processing deletes from the TSM database information about any client files that are no longer valid according to the policies you have set. For example, suppose four backup versions of a file exist in server storage, and only three versions are allowed in the backup policy (the management class) for the file. Expiration processing deletes information about the oldest of the four versions of the file. The space that the file occupied in the storage pool becomes available for reuse.

You can run expiration processing automatically or by command. See “Running Expiration Processing to Delete Expired Files” on page 264.

Specifying Scratch FILE Volumes

You can specify a maximum number of scratch volumes for a storage pool that has a FILE device type. When the server needs a new volume, the server automatically creates a file that is a scratch volume, up to the number you specify. When scratch volumes used in storage pools become empty, the files are deleted.

Using FILE Volumes for Database Backups and Export Operations

When you back up the database or export server information, the server records information about the volumes used for these operations in the *volume history*. The server will not allow you to reuse these volumes until you delete the volume information from the volume history. To reuse volumes that have previously been used for database backup or export, use the DELETE VOLHISTORY command. For information about the volume history and volume history files, see “Saving the Volume History File” on page 472.

Note: If your server is licensed for the Tivoli Disaster Recovery Manager (DRM) product, the volume information is automatically deleted during MOVE DRMEDIA command processing. For additional information about DRM, see “Using Tivoli Disaster Recovery Manager” on page 497.

5

Attaching Devices to the Server System

For TSM to use a device, you must attach the device to your server system and install the appropriate device driver.

Tasks:
“Attaching a Manual Drive”
“Attaching an Automated Library Device” on page 50
“Installing and Configuring Device Drivers” on page 51

Attaching a Manual Drive

1. Install the SCSI adapter card in your system, if not already installed.
2. Determine the SCSI IDs available on the SCSI adapter card to which you are attaching the device. Find one unused SCSI ID for each drive.
3. Follow the manufacturer’s instructions to set the SCSI ID for the drives to the unused SCSI IDs that you found. Usually this means setting switches on the back of the device.

Note: Each device that is connected in a chain to a single SCSI bus must be set to a unique SCSI ID. If each device does not have a unique SCSI ID, you may have serious system problems.

4. Follow the manufacturer’s instructions to attach the device to your server system hardware.

Attention:

- a. Power off your system before attaching a device to prevent damage to the hardware.
 - b. Attach a terminator to the last device in the chain of devices connected on one SCSI adapter card.
5. Install the appropriate device drivers. See “Installing and Configuring Device Drivers” on page 51.
 6. Find the device worksheet that applies to your device. See http://www.tivoli.com/support/storage_mgr/tivolimain.html.
 7. Determine the name for the device and record the name on the device worksheet.
The device name for a tape drive is a special file name. See “Determining Device Special File Names” on page 52 for details.

Keep the Worksheets: The information you record on the worksheets can help you when you need to perform operations such as adding volumes. Keep the worksheets for future reference.

Attaching an Automated Library Device

1. Install the SCSI adapter card in your system, if not already installed.
2. Determine the SCSI IDs available on the SCSI adapter card to which you are attaching the device. Find one unused SCSI ID for each drive, and one for the library or autochanger controller.

Note: In some automated libraries, the drives and the autochanger share a single SCSI ID, but have different LUNs. For these libraries, only a single SCSI ID is required. Check the documentation for your device.

3. Follow the manufacturer's instructions to set the SCSI ID for the drives and library controller to the unused SCSI IDs that you found. Usually this means setting switches on the back of the device.

Note: Each device that is connected in a chain to a single SCSI bus must be set to a unique SCSI ID. If each device does not have a unique SCSI ID, you may have serious system problems.

4. Follow the manufacturer's instructions to attach the device to your server system hardware.

Attention:

- a. Power off your system before attaching a device to prevent damage to the hardware.
 - b. You must attach a terminator to the last device in the chain of devices connected on one SCSI adapter card. Detailed instructions should be in the documentation that came with your hardware.
5. Install the appropriate device drivers. See "Installing and Configuring Device Drivers" on page 51.
 6. Find the device worksheet that applies to your device. See http://www.tivoli.com/support/storage_mgr/tivolimain.html.
 7. Determine the name for the device, which is needed to define the device to TSM, and record the name on the device worksheet.

The device name for a tape drive is a special file name. See "Determining Device Special File Names" on page 52 for details.

Keep the Worksheets: The information you record on the worksheets can help you when you need to perform operations such as adding volumes to an autochanger. Keep the worksheets for future reference.

Setting the Library Mode

For TSM to access a SCSI library, the device must be set for the appropriate mode. The mode that TSM requires is usually called *random* mode. However, terminology may vary from one device to another. Two examples follow:

- Some libraries have front panel menus and displays that can be used for explicit operator requests. However, if the device is set to respond to such requests, it typically will not respond to requests that are made by TSM.
- Some libraries can be placed in *sequential* mode, in which volumes are automatically mounted in drives by using a sequential approach. This mode conflicts with how TSM accesses the device.

Refer to the documentation for your device to determine how to set it to a mode appropriate for TSM.

Installing and Configuring Device Drivers

For TSM to use a device, you must install the appropriate device driver.

IBM tape drives, tape autochangers, and tape libraries

Install the device driver that IBM supplies. See “Installing Device Drivers for IBM SCSI Tape Drives” on page 52, “Installing Device Drivers for IBM 349X Libraries” on page 53, and *IBM SCSI Device Drivers: Installation and User’s Guide*.

Non-IBM tape drives and tape autochangers

You must ensure that you have installed the appropriate device drivers. When you install TSM, you must choose whether to install the TSM device driver or the native operating system device driver for tape devices.

Optical devices

Install the TSM device drivers. See http://www.tivoli.com/support/storage_mgr/tivolimain.html and “Configuring a Device Driver for a Tape or an Optical Drive for Use by TSM” on page 54.

Other removable media devices

See “Configuring Removable File Devices” on page 61.

Mapping Tivoli Storage Manager Devices to Device Drivers

Table 5 lists device types and the device drivers needed for them. Also listed are the library types associated with the associated devices.

Table 5. Device Drivers for AIX

Device Type	Device Driver	Device Class	Library Type
4MM drive	TSM Device Driver	4MM	External, Manual, SCSI
8MM drive	TSM Device Driver	8MM	External, Manual, SCSI
DLT drive	TSM Device Driver	DLT	External, Manual, SCSI, ACSLS
DTF drive	TSM Device Driver	DTF	External, Manual, SCSI
QIC drive	TSM Device Driver	QIC	External, Manual, SCSI
STK SD3, 9840, 9490, 9940 drive	TSM Device Driver	ECARTRIDGE	External, Manual, SCSI, ACSLS
Optical (See Devices Supported URL)	TSM Device Driver	OPTICAL	External, Manual, SCSI
WORM (See Devices Supported URL)	TSM Device Driver	WORM	External, Manual, SCSI
IBM 3570 drive	Atape	3570	External, Manual, SCSI
IBM 3480, 3490, 3490E drive	Atape	CARTRIDGE	External, Manual, SCSI, ACSLS, 349X

Table 5. Device Drivers for AIX (continued)

Device Type	Device Driver	Device Class	Library Type
IBM 3590, 3590E drive	Atape	3590	External, Manual, SCSI, 349X, ACSLS
IBM LTO 3580 drive	Atape	LTO	External, Manual, SCSI
IBM 3570, 3575 Library	Atape	3570	SCSI
IBM LTO 3581, 3583, 3584 Library	Atape	LTO	SCSI
IBM 3494, 3495 Library	atlld	CARTRIDGE, 3590	349X

Note: All other libraries (see http://www.tivoli.com/support/storage_mgr/tivolimain.html) use the TSM device driver.

Determining Device Special File Names

To identify and work with removable media devices, TSM needs the device's special file name. You specify the device special file name when you issue the DEFINE DRIVE or DEFINE LIBRARY commands. You can use SMIT to get the device special file.

When a device configures successfully, a logical file name is returned. See Table 6.

The following table specifies the name of the device (or the special file name) that corresponds to the drive. See the examples in this table. In this table, *x* denotes any number from 0 to 9.

Table 6. Device Examples

Device Example	Logical File Name	Description
/dev/mtx	mtx	Device name for TSM-supported tape drives (not supported by IBM hardware device drivers)
/dev/lbx	lbx	Device name for TSM-supported SCSI libraries
/dev/ropx	opx	Device name for TSM-supported optical drives
/dev/rmtx.smc	rmtx	Device name for GENERICTAPE and 3570 devices, and to define the Automatic Cartridge Facility feature of the IBM 3590 B11 as a library
/dev/smcx	smcx	Device name for IBM 3575, 3581, 3583, 3584 libraries
/dev/lmcpx	lmcpx	Device name for 349X automatic tape libraries
/dev/cdx	cdx	Mount point to use on REMOVABLEFILE device type (CD-ROM)
/zip	Not applicable	Filesystem to use on REMOVABLEFILE device type (zip drive)

Installing Device Drivers for IBM SCSI Tape Drives

For IBM 3490, 3570, 358X, and 3590 devices, see *IBM SCSI Device Drivers: Installation and User's Guide* for instructions for installing the device drivers.

After completing the procedure in the manual, you receive a message from the system:

- If you are installing the device driver for an IBM 3480 or 3490 tape device, you receive a message (logical filename) of the form:

rmtx Available

where *x* is a number. Note the value of *x*, which is assigned automatically by the system. Use this information to complete the Device Name field on the worksheet.

For example, if the message is *rmt0 Available*, the special file name for the device is */dev/rmt0*. Enter */dev/rmt0* in the Device Name field for the drive on the worksheet. Always use the */dev/* prefix with the name provided by the system.

- If you are installing the device driver for an IBM 3570, 3575, 3581, 3583, 3584, or 3590 Model B11, you receive a message of the form:

rmtx Available

Note the value of *x*, which is assigned automatically by the system. The special file name for the **drive** is */dev/rmtx*. The special file name for the **media changer** device (what TSM considers a library) is */dev/smcx*. (The filetype *smc* stands for SCSI media changer.)

For example, if the message is *rmt0*, enter */dev/rmt0* in the Device Name field for the drive. Enter ***/dev/smc0*** in the Device Name field on the worksheet for the library's robotics. Always use the */dev/* prefix with the name provided by the system.

Note: For multidrive devices (for example, IBM 3570 Model B12 or B22, or IBM 3575), you need only one *smcx*. Although you will receive a */dev/smcx* for each *rmt* device in the library, you need only one *smc* for the TSM library on the worksheet.

Installing Device Drivers for IBM 349X Libraries

For an IBM 3494 or 3495 Tape Library Dataserver, refer to either *IBM SCSI Tape Drive, Medium Changer, and Library Device Drivers* or *IBM AIX Parallel and ESCON Channel Tape Attachment/6000 Installation and User's Guide*.

After completing the procedure in the manual, you will receive a message (logical filename) of the form:

lmcpx Available

where *x* is a number assigned automatically by the system. Use this information to complete the Device Name field on your worksheet. For example, if the message is **lmcpx0 Available**, enter ***/dev/lmcpx0*** on the worksheet in the Device Name field for the library. Always use the */dev/* prefix with the name provided by the system.

Configuring an Autochanger or a Robot Device Driver for a Library

Use the procedure in this section to configure TSM device drivers for autochangers and robot devices, **excluding IBM tape libraries**. See "Installing Device Drivers for IBM 349X Libraries" for the IBM 3494 and 3495 libraries.

Run the SMIT program to configure the device driver for each autochanger or robot:

1. Select **Devices**.
2. Select **TSM Devices**.
3. Select **Library/MediumChanger**.
4. Select **Add a Library/MediumChanger**.

-
5. Select the TSM-SCSI-LB for any TSM supported library.
 6. Select the parent adapter to which you are connecting the device. This number is listed in the form: 00-0X, where X is the slot number location of the SCSI adapter card.
 7. When prompted, enter the CONNECTION address of the device you are installing. The connection address is a two-digit number. The first digit is the SCSI ID (the value you recorded on the worksheet). The second digit is the device's SCSI logical unit number (LUN), which is usually zero, unless otherwise noted.

For example, a connection address of 40 has a SCSI ID=4 and a LUN=0. If you are using AIX Version 4.1, then a connection address of 4,1 has a SCSI ID=4 and LUN=1. You need a comma (,) between the SCSI ID and the LUN.

8. Click on the **DO** button.

You will receive a message (logical filename) of the form **lbX Available**. Note the value of X, which is a number assigned automatically by the system. Use this information to complete the Device Name field on your worksheet.

For example, if the message is **lb0 Available**, the Device Name field is `/dev/lb0` on the worksheet. Always use the `/dev/` prefix with the name provided by SMIT.

Configuring a Device Driver for a Tape or an Optical Drive for Use by TSM

Use the procedure in this section to configure TSM device drivers for tape or optical drives, **excluding IBM tape drives**. See "Installing Device Drivers for IBM SCSI Tape Drives" on page 52. For details on LAN-free configuration, see *TSM Managed System for SAN Storage Agent User's Guide*.

Attention: TSM cannot write over *tar* or *dd* tapes, but *tar* or *dd* can write over TSM tapes.

Note: Tape drives can be shared only when the drive is not defined to TSM or TSM is not started. The MKSYSB command will not work if both TSM and AIX are sharing the same drive or drives. To use the operating system's native tape device driver in conjunction with a SCSI drive, the device must be configured to AIX first and then configured to TSM. See your AIX documentation regarding these native device drivers.

Run the SMIT program to configure the device driver for each drive (including drives in libraries) as follows:

1. Select **Devices**.
2. Select **TSM Devices**.
3. Select **Tape Drive** or **Optical R/W Disk Drive**, depending on whether the drive is tape or optical.
4. Select **Add a Tape Drive** or **Add an Optical Disk Drive**, depending on whether the drive is tape or optical.
5. Select the TSM-SCSI-MT for any TSM-supported tape drive or TSM-SCSI-OP for any TSM-supported optical drive.
6. Select the adapter to which you are connecting the device. This number is listed in the form: 00-0X, where X is the slot number location of the SCSI adapter card.

-
7. When prompted, enter the CONNECTION address of the device you are installing. The connection address is a two-digit number. The first digit is the SCSI ID (the value you recorded on the worksheet). The second digit is the device's SCSI logical unit number (LUN), which is usually zero, unless otherwise noted.
For example, a connection address of 40 has a SCSI ID=4 and LUN=0. If you are using AIX Version 4.1, then a connection address of 4,1 has a SCSI ID=4 and LUN=1. You need a comma (,) between the SCSI ID and the LUN.
 8. Click on the **DO** button.

The message you receive next depends on whether you are configuring the device driver for a tape or an optical device:

- If you are configuring the device driver for a tape device (other than an IBM 3480, 3490, or 3590), you will receive a message (logical filename) of the form **mtX Available**. Note the value of X, which is a number assigned automatically by the system. Use this information to complete the Device Name field on the worksheet.
For example, if the message is **mt0 Available**, the Device Name field is `/dev/mt0` on the worksheet. Always use the `/dev/` prefix with the name provided by SMIT.
- If you are configuring the device driver for an optical device, you will receive a message of the form **opX Available**. Note the value of X, which is a number assigned automatically by the system. Use this information to complete the Device Name field on the worksheet.
For example, if the message is **op0 Available**, the Device Name field is `/dev/rop0` on the worksheet. Always use the `/dev/r` prefix with the name provided by SMIT.

6

Configuring Storage Devices

This chapter presents an overview of device configuration, detailed descriptions of specific configurations, and detailed descriptions of library and drive definitions. The following table points to these sections.

Overview:
“Device Configuration Overview”
Configurations not in a Storage Area Network:
“Configuring Manually Mounted Devices” on page 59
“Configuring Removable File Devices” on page 61
“Configuring SCSI Libraries” on page 63
“Configuring 349X Libraries” on page 65
“Configuring Libraries Controlled by Media Manager Programs” on page 69
“Configuring ACSLS-Managed Libraries” on page 71
Storage Area Network Configurations:
“Configuring SCSI Libraries in a SAN” on page 73
“Configuring IBM 349X Libraries in a SAN” on page 75
“Configuring TSM Clients to Directly Access SAN-Attached Devices” on page 79
Library and Drive Definitions:
“Defining Libraries” on page 81
“Defining Drives” on page 82

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.


Note: Some of the tasks described in this chapter require an understanding of TSM storage objects. For an introduction to these storage objects, see “Tivoli Storage Manager Storage Objects” on page 26.

Device Configuration Overview

Before Tivoli Storage Manager can use a removable media device, you must typically perform the steps described in this section.


1. Attach the device to the server system, and ensure that the appropriate device driver is installed and configured.

For more information about which device drivers to use, see “Installing and Configuring Device Drivers” on page 51.




2. Define the device to Tivoli Storage Manager.

Define the TSM library, drive, device class, storage pool, and storage volume objects. For an introduction to these objects, see “Tivoli Storage Manager Storage Objects” on page 26 and “Configuring Devices” on page 40.




3. Define the TSM policy that links client data with media for the device.

Define or update the policy that associates clients with the pool of storage volumes and the device. For an introduction to TSM policy, see “How Tivoli Storage Manager Stores Client Data” on page 5. For a description of the default policy, see “The Standard Policy” on page 235.



Note: As an alternative to creating or modifying a TSM policy, you can place the new storage pool in the storage pool migration hierarchy by updating an already defined storage pool.

4. Register clients to the domain associated with the policy that you defined or updated in the preceding step.



5. Prepare storage volumes for use by the device. At a minimum, you must label volumes for the device.

Server Storage Options

Tivoli Storage Manager provides a number of options that you can specify in the server options file (`dsmserv.opt`) to configure certain server storage operations. The following table provides brief descriptions of these options. See the *Administrator's Reference* for details.

Table 7. Server Storage Options

Option	Description
3494SHARED	Enables sharing of an IBM 3494 library with applications other than Tivoli Storage Manager.
ACSACCESSID	Specifies the ID for the Automatic Cartridge System (ACS) access control.
ACSLOCKDRIVE	Allows the drives within ACSLS libraries to be locked.
ACSQUICKINIT	Allows a quick or full initialization of the ACSLS library.
ACSTIMEOUTX	Specifies the multiple for the built-in timeout value for ACSLS API.
ASSISTVCRRECOVERY	Specifies whether the server assists an IBM 3570 or 3590 drive in recovering from a lost or corrupted Vital Cartridge Records (VCR) condition.
DRIVEACQUIRERETRY	Specifies how many times the server retries the acquisition of a drive in an IBM 349x library that is shared among multiple applications.
ENABLE3590LIBRARY	Enables support for IBM 3590 tape drives in an IBM 349x automated library.
RESOURCE TIMEOUT	Specifies how long the server waits for a resource before canceling the pending acquisition of a resource.
SEARCHMPQUEUE	Specifies the order in which the server satisfies requests in the mount queue.

Configurations Not in a Storage Area Network

This section presents scenarios for the following device configurations not in a SAN:

- “Configuring Manually Mounted Devices”
- “Configuring Removable File Devices” on page 61
- “Configuring SCSI Libraries” on page 63
- “Configuring 349X Libraries” on page 65
- “Configuring Libraries Controlled by Media Manager Programs” on page 69
- “Configuring ACSLS-Managed Libraries” on page 71

Configuring Manually Mounted Devices

In the following example, two 8mm drives are attached to the server system. Because an operator must mount tapes for these drives, you must define the drives as part of a *manual* library.

Set up the Device on the Server System

You must first set up the device on the server system. This involves the following tasks:

1. Set the appropriate SCSI ID for the device.
2. Physically attach the device to the server hardware.
3. Install and configure the appropriate device driver for the device.
4. Determine the device name that is needed to define the device to Tivoli Storage Manager.

See “Attaching a Manual Drive” on page 49 and “Installing and Configuring Device Drivers” on page 51 for details.

Define the Device to Tivoli Storage Manager

1. Define a manual library named MANUAL8MM:

```
define library manual8mm libtype=manual
```

2. Define the drives that belong to the library:

```
define drive manual8mm drive01 device=/dev/mt1
define drive manual8mm drive02 device=/dev/mt2
```

In this example, the drive known to the device driver by the special file name */dev/mt1* is given the name DRIVE01. Drive */dev/mt2* is given the name DRIVE02. You might prefer to have the device driver name and the TSM name match. For more about device names, see “Determining Device Special File Names” on page 52.

See “Defining Drives” on page 82 and http://www.tivoli.com/support/storage_mgr/tivolimain.html.

3. Classify the drives according to type by defining a device class named TAPE8MM_CLASS. We recommend that you use FORMAT=DRIVE as the recording format only if all the drives associated with the device class are identical.

```
define devclass tape8mm_class library=manual8mm devtype=8mm format=drive
```

A closer look: When you associate more than one drive to a single device class through a manual library, ensure that the recording formats and media types of the devices are compatible. If you have a 4mm tape drive and an 8mm tape drive, you must define separate manual libraries and device classes for each drive.

See “Defining and Updating Device Classes for Tape Devices” on page 107.

4. Verify your definitions by issuing the following commands:

```
query library
query drive
query devclass
```

See “Requesting Information About Libraries” on page 99, “Requesting Information about Drives” on page 100, and “Requesting Information about a Device Class” on page 114.

5. Define a storage pool named TAPE8MM_POOL associated with the device class named TAPE8MM_CLASS:

```
define stgpool tape8mm_pool tape8mm_class maxscratch=20
```

Key choices:

- a. Scratch volumes are labeled, empty volumes that are available for use. If you allow scratch volumes for the storage pool by specifying a value for the maximum number of scratch volumes, TSM can use any scratch volumes available without further action on your part. If you do not allow scratch volumes (MAXSCRATCH=0), you must perform the extra step of explicitly defining each volume to be used in the storage pool.
- b. Collocation is turned off by default. Collocation is a process by which the server attempts to keep all files belonging to a client node or client file space on a minimal number of volumes. Once clients begin storing data in a storage pool with collocation off, you cannot easily change the data in the storage pool so that it is collocated. To understand the advantages and disadvantages of collocation, see “Keeping a Client’s Files Together: Collocation” on page 147 and “How Collocation Affects Reclamation” on page 158.

See “Defining or Updating Primary Storage Pools” on page 123.

Using the Devices to Store Client Data

After you have attached and defined your devices, you can store client data in two ways:

- Have clients back up data directly to tape. For details, see “Configuring Policy for Direct-to-Tape Backups” on page 266.
- Have clients back up data to disk. The data is later migrated to tape. For details, see “Overview: The Storage Pool Hierarchy” on page 133.

Label Volumes

Use the following procedure to ensure that volumes are available to TSM:

1. Label volumes that do not already have a standard label. For example, enter the following command to use one of the drives to label a volume with the ID of vol001:


```
label libvolume manual8mm vol001
```

Keep enough labeled volumes on hand so that you do not run out during an operation such as client backup.

2. Depending on whether you use scratch volumes or private volumes, do one of the following:
 - If you use only scratch volumes, ensure that enough scratch volumes are available. For example, you may need to label more volumes. As volumes are used, you may also need to increase the number of scratch volumes allowed in the storage pool that you defined for this library.
 - If you want to use private volumes in addition to or instead of scratch volumes in the library, define volumes to the storage pool you defined. The volumes you define must have been already labeled. For information on defining volumes, see “Defining Storage Pool Volumes” on page 130.

Configuring Removable File Devices

Removable file support includes Iomega ZIP drives and JAZ drives, and CD-ROM drives.

Support for removable file devices allows portability of media between UNIX systems. It also allows this media to be used to transfer data between systems that support the media. Removable file support allows TSM to read data from a FILE device class that is copied to

removable file media through third-party software. The media is then usable as input media on a target TSM server that uses the REMOVABLEFILE device class for input.

Note: Software for writing CD-ROMs may not work consistently across platforms.

Use a MAXCAPACITY value that is less than one CD-ROM's usable space to allow for a one-to-one match between files from the FILE device class and copies that are on CD-ROM. Use the DEFINE DEVCLASS or UPDATE DEVCLASS commands to set the MAXCAPACITY parameter of the FILE device class to a value less than 650MB.

Example of Removable File Support

Use these steps as an example of TSM REMOVABLEFILE (CD-ROM) support. This example takes an export object and moves it from one server to another.

Server A

1. Define a device class with a device type of FILE.

```
define devclass file devtype=file directory=/home/user1
```
2. Export the node. This command results in a file name */home/user1/CDR03* that contains the export data for node USER1.

```
export node user1 filedata=all devclass=file vol=cdr03
```

You can use software for writing CD-ROMs to create a CD with volume label CDR03 that contains a single file that is also named CDR03.

Server B

1. Follow the manufacturer's instructions to attach the device to your server.
2. Issue this command on your system to mount the CD-ROM.

```
mount -r -v cdrfs /dev/cd0 /cdrom
```

-r Specifies a read-only file system

-v cdrfs

Specifies that the media has a CD file system

/dev/cd0

Specifies the physical description of the first CD-ROM on the system

/cdrom

Specifies the mount point of the first CD-ROM drive

Note: CD-ROM drives lock while the file system is mounted. This prevents use of the eject button on the drive.

3. Ensure that the media is labeled. The software that you use for making a CD also labels the CD. Before you define the drive, you must put formatted, labeled media in the drive. For label requirements, see "Labeling Requirements for Optical and Other Removable Files Devices" on page 63. When you define the drive, TSM verifies that a valid file system is present.
4. Define a library that is named CDROM. The library type must be MANUAL.

```
define library cdrom libtype>manual
```
5. Define a drive named CDDRIVE at mount point */cdrom*.

```
define drive cdrom cddrive device=/cdrom
```

- Define a device class with a device type of REMOVABLEFILE. The device type must be REMOVABLEFILE.

```
define devclass cdrom devtype=removablefile library=cdrom
```

- Issue the following TSM command to import the node data on the CD-ROM volume CDR03.

```
import node user1 filedata=all devclass=cdrom vol=cdr03
```

Labeling Requirements for Optical and Other Removable Files Devices

TSM does not provide utilities to format or label media for the REMOVABLEFILE device type. You must use another application to copy the FILE device class data to the CD-ROM to a file that has the same name as the volume label. This software also labels the removable media.

The label on the media must meet the following restrictions:

- No more than 11 characters
- No embedded blanks or periods
- File name the same as the volume label

Configuring SCSI Libraries

In the following example, an automated SCSI library containing two drives is attached to the server system.

Set up the Device on the Server System

You must first set up the device on the server system. This involves the following tasks:

- Set the appropriate SCSI ID for each drive and for the library or autochanger controller.
- Physically attach the devices to the server hardware.
- Install and configure the appropriate device drivers for the devices.
- Determine the device names that are needed to define the devices to Tivoli Storage Manager.

For details, see “Attaching an Automated Library Device” on page 50 and “Installing and Configuring Device Drivers” on page 51.

Define the Device to Tivoli Storage Manager

- Define the library to TSM. In this example, AUTO8MMLIB is specified as the library name. The library type is *SCSI* because the library is a SCSI-attached automated library. Enter the following command:

```
define library auto8mmlib libtype=scsi device=/dev/lb3
```

The *DEVICE* parameter specifies the device driver’s name for the library, which is the special file name.

See “Defining Libraries” on page 81 and “SCSI Libraries” on page 27.

- Define the drives in that library that TSM will use. For example:

```
define drive auto8mmlib drive01 device=/dev/mt4 element=82
define drive auto8mmlib drive02 device=/dev/mt5 element=83
```

Both drives belong to the AUTO8MMLIB library. The DEVICE parameter specifies the device driver's name for the drive. In this example, each drive is given a TSM name that is unique to the device driver name. For more about device names, see "Determining Device Special File Names" on page 52.

Element address: The element address is a number that indicates the physical location of a drive within an automated library. TSM needs the element address to connect the physical location of the drive to the drive's SCSI address. When you define a drive, the element address is required if more than one drive is in an automated library. The element numbers are taken from the device worksheet filled out in step 7 on page 49. See http://www.tivoli.com/support/storage_mgr/tivolimain.html to determine the element numbers.

See "Defining Drives" on page 82.

- l 3. Classify drives according to type by defining TSM device classes. We recommend that
l you use FORMAT=DRIVE as the recording format only if all the drives associated with
l the device class are identical. For example, to define two drives in the AUTO8MMLIB
l library, use the following command to define a device class named AUTO8MM_CLASS:
l
- ```
define devclass auto8mm_class library=auto8mmlib devtype=8mm format=drive
```

l See "Defining and Updating Device Classes for Tape Devices" on page 107.

- l 4. Verify your definitions by issuing the following commands:

```
query library
query drive
query devclass
```

See "Requesting Information About Libraries" on page 99, "Requesting Information about Drives" on page 100, and "Requesting Information about a Device Class" on page 114 .

- l 5. Define a storage pool named AUTO8MM\_POOL associated with the device class named  
l AUTO8MM\_CLASS.  
l
- ```
define stgpool auto8mm_pool auto8mm_class maxscratch=20
```

Key choices:

- a. Scratch volumes are labeled, empty volumes that are available for use. If you allow scratch volumes for the storage pool by specifying a value for the maximum number of scratch volumes, TSM can choose from the scratch volumes available in the library, without further action on your part. If you do not allow scratch volumes, you must perform the extra step of explicitly defining each volume to be used in the storage pool.
- b. Collocation is turned off by default. Collocation is a process by which the server attempts to keep all files belonging to a client node or client file space on a minimal number of volumes. Once clients begin storing data in a storage pool with collocation off, you cannot easily change the data in the storage pool so that it is collocated. To understand the advantages and disadvantages of collocation, see "Keeping a Client's Files Together: Collocation" on page 147 and "How Collocation Affects Reclamation" on page 158.

For more information, see "Defining or Updating Primary Storage Pools" on page 123.

Using the Devices to Store Client Data

After you have attached and defined your devices, you can store client data in two ways:

- Have clients back up data directly to tape. For details, see “Configuring Policy for Direct-to-Tape Backups” on page 266.
- Have clients back up data to disk. The data is later migrated to tape. For details, see “Overview: The Storage Pool Hierarchy” on page 133.

Check in and Label Library Volumes

Ensure that enough volumes are available to TSM in the library. Keep enough labeled volumes on hand so that you do not run out during an operation such as client backup.

1. Check in the library inventory. The following shows two examples. In both cases, the server uses the name on the barcode label as the volume name.
 - Check in volumes that are already labeled:
`checkin libvolume auto8mmlib search=yes status=scratch checklabel=barcode`
 - Label and check in volumes:
`label libvolume auto8mmlib search=yes labelsource=barcode checkin=scratch`
2. Depending on whether you use scratch volumes or private volumes, do one of the following:
 - If you use only scratch volumes, ensure that enough scratch volumes are available. For example, you may need to label more volumes. As volumes are used, you may also need to increase the number of scratch volumes allowed in the storage pool that you defined for this library.
 - If you want to use private volumes in addition to or instead of scratch volumes in the library, define volumes to the storage pool you defined. The volumes you define must have been already labeled and checked in. See “Defining Storage Pool Volumes” on page 130.

Configuring 349X Libraries

In the following example, an IBM 3494 library containing two drives is attached to the server system.

Set up the Device on the Server System

You must first set up the 349X library on the server system. This involves the following tasks:

1. Set the 349X Library Manager Control Point, or LMCP. This procedure is described in the *IBM SCSI Tape Drive, Medium Changer, and Library Device Drivers Installation and User's Guide* for AIX.
2. Physically attach the devices to the server hardware.
3. Install and configure the appropriate device drivers for the devices.
4. Determine the device names that are needed to define the devices to Tivoli Storage Manager.

For details, see “Attaching an Automated Library Device” on page 50 and “Installing and Configuring Device Drivers” on page 51.

Define the Device to Tivoli Storage Manager

1. Define the library to TSM. In this example, 3494LIB is specified as the library name. The library type is 349X . Enter the following command:

```
define library 3494lib libtype=349x device=/dev/lmcp0,/dev/lmcp1
```

The DEVICE parameter specifies the device driver's name for the LMCP, the special file name.

See "Defining Libraries" on page 81 and "SCSI Libraries" on page 27.

2. Define the drives that TSM will use in that library. For example:

```
define drive 3494lib drive01 device=/dev/rmt0
define drive 3494lib drive02 device=/dev/rmt1
```

Both drives belong to the 3494LIB library. The DEVICE parameter gives the device driver's name for the drive. In this example, each drive is given a TSM name that is unique to the device driver name. For more about device names, see "Determining Device Special File Names" on page 52.

See "Defining Drives" on page 82.

3. Classify drives according to type by defining TSM device classes. We recommend that you use FORMAT=DRIVE as the recording format only if all the drives associated with the device class are identical. For example, to define the two drives in the 3494LIB library, use the following command to define a device class named 3494_CLASS:

```
define devclass 3494_class library=3494lib devtype=3590 format=drive
```

See "Defining and Updating Device Classes for Tape Devices" on page 107.

4. Verify your definitions by issuing the following commands:

```
query library
query drive
query devclass
```

See "Requesting Information About Libraries" on page 99, "Requesting Information about Drives" on page 100, and "Requesting Information about a Device Class" on page 114.

5. Define a storage pool named 3494_POOL associated with the device class named 3494_CLASS.

```
define stgpool 3494_pool 3494_class maxscratch=20
```

Key choices:

- a. Scratch volumes are labeled, empty volumes that are available for use. If you allow scratch volumes for the storage pool by specifying a value for the maximum number of scratch volumes, TSM can choose from the scratch volumes available in the library, without further action on your part. If you do not allow scratch volumes, you must perform the extra step of explicitly defining each volume to be used in the storage pool.
- b. Collocation is turned off by default. Collocation is a process by which the server attempts to keep all files belonging to a client node or client file space on a minimal number of volumes. Once clients begin storing data in a storage pool with collocation off, you cannot easily change the data in the storage pool so that it is collocated. To

understand the advantages and disadvantages of collocation, see “Keeping a Client’s Files Together: Collocation” on page 147 and “How Collocation Affects Reclamation” on page 158.

For more information, see “Defining or Updating Primary Storage Pools” on page 123.

Categories in 349X Automated Libraries

The 349X library control unit tracks the category number of each volume in the library. A single category number identifies all volumes used for the same purpose or application. These category numbers are useful when multiple systems share the resources of a single library.

Attention: If other systems or other TSM servers connect to the same 349X library, each must use a unique set of category numbers. Otherwise, two or more systems may try to use the same volume, and cause a corruption or loss of data.

Typically, a software application that uses a 349X library device uses volumes in one or more categories that are reserved for that application. To avoid loss of data, each application sharing the library must use unique categories. When you define a 349X library to TSM, you can use the `PRIVATECATEGORY` and `SCRATCHCATEGORY` parameters to specify the category numbers for private TSM volumes and scratch TSM volumes respectively in that library. See “Scratch and Private Volumes in Automated Libraries” on page 35 for more information on private and scratch volumes.

When a volume is first inserted into the library, either manually or automatically at the convenience I/O station, the volume is assigned to the insert category (`X'FF00'`). A software application, such as TSM, can contact the library control unit to change a volume’s category number. For TSM, you would use the `CHECKIN LIBVOLUME` command (see “Checking New Volumes into a Library” on page 87).

The number of categories that TSM requires depends on whether you have enabled support for 3590 drives. If support is not enabled for 3590 drives, TSM reserves two category numbers in each 349X library that it accesses: one for private volumes and one for scratch volumes. If you enable 3590 support, the server reserves three categories in the 349X library: private, scratch for 3490 drives, and scratch for 3590 drives.

The default values for the `PRIVATECATEGORY` and `SCRATCHCATEGORY` parameters are the same as when 3590 support is not enabled. However, TSM automatically creates the scratch category for 3590 drives, by adding the number 1 to the `SCRATCHCATEGORY` value you specify. For example, suppose you enter the following command:

```
define library my3494 libtype=349x device=3494a privatecategory=400 scratchcategory=401
```

TSM uses the following categories in the library:

- **400 (X'190')** Private volumes (for both 3490 and 3590 drives)
- **401 (X'191')** Scratch volumes for 3490 drives
- **402 (X'192')** Scratch volumes for 3590 drives

To avoid overlapping categories, ensure that the value specifies for the private category is not equal to the scratch category value plus 1.

Attention: The default values for the categories may be acceptable in most cases. However, if you connect other systems or TSM servers to a single 349X library, ensure that each uses unique category numbers. Otherwise, two or more systems may try to use the same volume, and cause a corruption or loss of data.

Also, if you share a 349X library between TSM and other applications or systems, be careful when enabling 3590 support to prevent loss of data. See “Enabling Support for IBM 3590 Drives in Existing 349X Libraries”.

Enabling Support for IBM 3590 Drives in Existing 349X Libraries

The new category that TSM creates for 3590 scratch volumes can duplicate a category already assigned to another application and cause loss of data. If you are currently sharing a 349X library between TSM and other applications or systems and you enable TSM’s support for 3590 drives, you need to be careful. TSM automatically creates a third category for 3590 scratch volumes by adding one to the existing scratch category for any 349X libraries defined to TSM.

To prevent potential data loss, enable 3590 support by adding the following line to the server options file (dsmserv.opt):

```
ENABLE3590LIBRARY YES
```

Stop and start the server to make this change effective.

To prevent loss of data, do either one of the following before enabling 3590 support:

- Update other applications and systems to ensure that there is no conflicting use of category numbers.
- Delete the existing TSM library definition and then define it again using a new set of category numbers that do not conflict with categories used by other systems or applications using the library. Do the following:
 1. Use an external utility (such as mtlb) to reset all of the TSM volumes to the insert category.
 2. Delete the 349X library from TSM.
 3. Define the 349X library to TSM again, using new category numbers.
Check in the TSM volumes that you put in the insert category in step 1.

For more information about checking in volumes, see “Checking New Volumes into a Library” on page 87.

Using the Devices to Store Client Data

After you have attached and defined your devices, you can store client data in two ways:

- Have clients back up data directly to tape. For details, see “Configuring Policy for Direct-to-Tape Backups” on page 266.
- Have clients back up data to disk. The data is later migrated to tape. For details, see “Overview: The Storage Pool Hierarchy” on page 133.

Label and Check In a Library Volume

Ensure that enough volumes are available to TSM in the library. Keep enough labeled volumes on hand so that you do not run out during an operation such as client backup.

1. Check in the library inventory. The following shows two examples. In both cases, the server uses the name on the barcode label as the volume name.
 - Check in volumes that are already labeled:
`checkin libvolume 3494lib search=yes status=scratch checklabel=barcode`
 - Label and check in volumes:
`label libvolume 3494lib search=yes labelsource=barcode checkin=scratch`
2. Depending on whether you use scratch volumes or private volumes, do one of the following:
 - If you use only scratch volumes, ensure that enough scratch volumes are available. For example, you may need to label more volumes. As volumes are used, you may also need to increase the number of scratch volumes allowed in the storage pool that you defined for this library.
 - If you want to use private volumes in addition to or instead of scratch volumes in the library, define volumes to the storage pool you defined. The volumes you define must have been already labeled and checked in. See “Defining Storage Pool Volumes” on page 130.

Configuring Libraries Controlled by Media Manager Programs

You can use an external media manager program with TSM to manage your removable media. While TSM tracks and manages client data, the media manager, operating entirely outside of the I/O data stream, labels, catalogs, and tracks physical volumes. The media manager also controls library drives, slots, and doors.

TSM provides a programming interface that lets you use a variety of media managers. See “External Media Management Interface Description” on page 555 for a complete description of this interface. See “Setting up TSM to Work with an External Media Manager” for setup procedures.

To use a media manager with TSM, define an EXTERNAL-type TSM library that has a library type of EXTERNAL. The library definition will point to the media manager rather than a physical device.

Setting up TSM to Work with an External Media Manager

To use the External Media Management Interface with a media manager, do the following procedure. This example is for an 8mm autochanger device containing two drives.

1. Set up the media manager to interface with TSM. For more information, see “External Media Management Interface Description” on page 555.
2. Define a TSM library named MEDIAMGR:
`define library mediamgr libtype=external externalmanager=/u/server/mediamanager`

In the EXTERNALMANAGER parameter, specify the media manager’s installed path.

Note: You do not define to TSM the drives in an externally managed library.

3. Define device class, EXTCLASS, for the library with a device type of 8mm:
`define devclass extclass library=mediamgr mountretention=5 mountlimit=2`

The MOUNTLIMIT parameter specifies the number of drives in the library device.

Notes:

- a. For environments in which devices are shared across storage applications, the MOUNTRETENTION setting should be carefully considered. This parameter determines how long an idle volume remains in a drive. Because some media managers will not dismount an allocated drive to satisfy pending requests, you might need to tune this parameter to satisfy competing mount requests while maintaining optimal system performance.
 - b. It is recommended that you explicitly specify the mount limit instead of using MOUNTLIMIT=DRIVES.
4. Define a storage pool, EXPOOL, for the device class. For example:
- ```
define stgpool extpool extclass maxscratch=500
```

**Key choices:**

- a. Scratch volumes are labeled, empty volumes that are available for use. If you allow scratch volumes for the storage pool by specifying a value for the maximum number of scratch volumes, TSM can choose from the scratch volumes available in the library, without further action on your part. If you do not allow scratch volumes, you must perform the extra step of explicitly defining each volume to be used in the storage pool.
- b. Collocation is turned off by default. Collocation is a process by which the server attempts to keep all files belonging to a client node or client file space on a minimal number of volumes. Once clients begin storing data in a storage pool with collocation off, you cannot easily change the data in the storage pool so that it is collocated. To understand the advantages and disadvantages of collocation, see “Keeping a Client’s Files Together: Collocation” on page 147 and “How Collocation Affects Reclamation” on page 158.

**Using the Devices to Store Client Data**

After you have attached and defined your devices, you can store client data in two ways:

- Have clients back up data directly to tape. For details, see “Configuring Policy for Direct-to-Tape Backups” on page 266.
- Have clients back up data to disk. The data is later migrated to tape. For details, see “Overview: The Storage Pool Hierarchy” on page 133.

**Managing Externally Controlled TSM Media**

Refer to the documentation for the media manager for detailed setup and management information. The following are some TSM-specific issues that you should consider:

**Labeling Media**

The media manager handles the labelling of media. However, you must ensure that an adequate supply of blank media is available.

**Checking Media into the Library**

Externally managed media is not tracked in the TSM volume inventory. Therefore, you will not perform library check-in procedures.

**Using Tivoli Disaster Recovery Manager**

If you are using DRM, you can use the MOVE DRMEDIA command to request the removal of media from the library. For more information, see “Using Tivoli Disaster Recovery Manager” on page 497.

### Migrating Media to External Media Manager Control

We strongly recommend that you not migrate media from TSM control to control by an external media manager. Instead, use external media management on a new TSM configuration or when defining externally managed devices to TSM.

### Deleting Tivoli Storage Manager Storage Pools from Externally Managed Libraries

Before deleting externally managed storage pools, first delete any volumes associated with the TSM library. For more information, see “Deleting a Storage Pool Volume with Data” on page 185.

### Troubleshooting Database Errors

Error conditions can cause the TSM volume database and the media manager’s volume database to become unsynchronized. The most likely symptom of this problem is that the volumes in the media manager’s database are not known to TSM, and thus not available for use. Verify the TSM volume list and any disaster recovery media. If volumes not identified to TSM are found, use the media manager interface to deallocate and delete the volumes.

## Configuring ACSLS-Managed Libraries

TSM supports tape libraries controlled by StorageTek Automated Cartridge System Library Software (ACSLs). The ACSLS library server manages the physical aspects of tape cartridge storage and retrieval. The ACSLS client application communicates with the library server to access tape cartridges in an automated library. TSM is one of the client applications that gains access to tape cartridges by interacting with ACSLS through its client, which is known as the control path. TSM reads and writes data on tape cartridges by interacting directly with tape drives through the data path. The control path and the data path are two different paths. The ACSLS client daemon must be initialized before starting the TSM server. See `/usr/tivoli/tsm/devices/bin/rc.acs_ssi` for the client daemon invocation. For detailed installation, configuration, and system administration of ACSLS, refer to the appropriate StorageTek documentation.

### Set up the Device on the Server System

The library is attached to the ACSLS server, and the drives are attached to the Tivoli Storage Manager server. The ACSLS server and the Tivoli Storage Manager server must be on different systems. Refer to the ACSLS installation documentation for details about how to set up the library.

### Define the Device to Tivoli Storage Manager

1. Define the library to TSM. In this example, define the library named ACSLIB by issuing the following command:

```
define library acslib libtype=acsls acsid=1
```

The parameter ACSID specifies the number that Automatic Cartridge System System Administrator (ACSSA) assigned to the library. Issue QUERY ACS in your system to determine the number for your library ID.

2. Decide which drives in ACSLIB TSM will use and define the drives to TSM:

```
define drive acslib drive01 device=/dev/mt0 acsdrvid=1,2,3,4
define drive acslib drive02 device=/dev/mt1 acsdrvid=1,2,3,5
```

The DEVICE parameter specifies the device driver’s name for the drive. In this example, each drive is given a TSM name that is unique to the device driver name. For more about device names, see “Determining Device Special File Names” on page 52.

---

The ACSDRVID parameter specifies the ID of the drive and indicates the physical location of the drive in the library. See the Storage Tek documentation for details.

See “Defining Drives” on page 82.

3. Classify drives according to type by defining TSM device classes. We recommend that you use `FORMAT=DRIVE` as the recording format only if all the drives associated with the device class are identical. For example, to define the two drives in the `ACSLIB` library, use the following command to define a device class named `ACS_CLASS`:
- ```
define devclass acs_class library=acslib devtype=ecartridge format=drive
```

See “Defining and Updating Device Classes for Tape Devices” on page 107.

4. To check what you have defined, enter the following commands:

```
query library
query drive
query devclass
```

See “Requesting Information About Libraries” on page 99, “Requesting Information about Drives” on page 100, and “Requesting Information about a Device Class” on page 114.

5. Create the storage pool to use the devices in the device class you just defined. For example, define a storage pool named `ACS_POOL` associated with the device class `ACS_CLASS`:

```
define stgpool acs_pool acs_class maxscratch=20
```

Key choices:

- a. Scratch volumes are labeled, empty volumes that are available for use. If you allow scratch volumes for the storage pool by specifying a value for the maximum number of scratch volumes, TSM can choose from the scratch volumes available in the library, without further action on your part. If you do not allow scratch volumes, you must perform the extra step of explicitly defining each volume to be used in the storage pool.
- b. Collocation is turned off by default. Collocation is a process by which the server attempts to keep all files belonging to a client node or client file space on a minimal number of volumes. Once clients begin storing data in a storage pool with collocation off, you cannot easily change the data in the storage pool so that it is collocated. To understand the advantages and disadvantages of collocation, see “Keeping a Client’s Files Together: Collocation” on page 147 and “How Collocation Affects Reclamation” on page 158.

For more information, see “Defining or Updating Primary Storage Pools” on page 123.

Using the Devices to Store Client Data

After you have attached and defined your devices, you can store client data in two ways:

- Have clients back up data directly to tape. For details, see “Configuring Policy for Direct-to-Tape Backups” on page 266.
- Have clients back up data to disk. The data is later migrated to tape. For details, see “Overview: The Storage Pool Hierarchy” on page 133.

Label and Check In a Library Volume

Ensure that enough volumes are available to TSM in the library. You must label volumes that do not already have a standard label. Keep enough labeled volumes on hand so that you do not run out during an operation such as client backup.

1. Check in the library inventory. The following shows two examples. In both cases, the server uses the name on the barcode label as the volume name.
 - Check in volumes that are already labeled:
`checkin libvolume acslib search=yes status=scratch overwrite=no checklabel=barcode`
 - Label and check in volumes:
`label libvolume acslib search=yes overwrite=no checkin=scratch`
2. Depending on whether you use scratch volumes or private volumes, do one of the following:
 - If you use only scratch volumes, ensure that enough scratch volumes are available. For example, you may need to label more volumes. As volumes are used, you may also need to increase the number of scratch volumes allowed in the storage pool that you defined for this library.
 - If you want to use private volumes in addition to or instead of scratch volumes in the library, define volumes to the storage pool you defined. The volumes you define must have been already labeled and checked in. See “Defining Storage Pool Volumes” on page 130.

Configurations in a Storage Area Network

This section presents scenarios for the following device configurations not in a SAN:

- “Configuring SCSI Libraries in a SAN”
- “Configuring IBM 349X Libraries in a SAN” on page 75
- “Configuring TSM Clients to Directly Access SAN-Attached Devices” on page 79

Using a SAN with TSM allows the following functions:

- Multiple TSM servers share storage devices. See “Configurations in a Storage Area Network”.
- TSM clients directly access storage devices, both tape libraries and disk storage, that are defined to a TSM server (LAN-free data movement). See “Configuring TSM Clients to Directly Access SAN-Attached Devices” on page 79.

Note: Tivoli Storage Manager supports library sharing and LAN-free features with IBM 349X libraries. If you are already using an IBM 349X library with Tivoli Storage Manager in a non-SAN environment, see “Migrating an IBM 349X Library to SAN Support” on page 77.

Configuring SCSI Libraries in a SAN

The following tasks are required for TSM servers to share library devices over a SAN:

1. Set up server-to server communications.
2. Set up the library on the library manager server.
3. Set up the library on the library client server.

Setting up Server Communications

Before TSM servers can share a storage device over a SAN, you must set up server communications. This requires configuring each server for Enterprise Administration and defining the servers to each other, using the cross-define function. See “Setting Up Communications Among Servers” on page 314 for details.

Set up the Device on the Server System

You must first set up the device on the server system. This involves the following tasks:

1. Set the appropriate SCSI ID for each drive and for the library or autochanger controller.
2. Physically attach the devices to the server hardware.
3. Install and configure the appropriate device drivers for the devices.
4. Determine the device names that are needed to define the devices to Tivoli Storage Manager.

For details, see “Attaching an Automated Library Device” on page 50 and “Installing and Configuring Device Drivers” on page 51.

Setting up the Library Manager Server

Use the following procedure as an example of how to set up a TSM server as a library manager:

1. Define a library whose library type is SCSI. For example:

```
define library sangroup libtype=scsi device=/dev/rmt1.smc shared=yes
```
2. Define the drives in the library:

```
define drive sangroup drivea device=/dev/rmt4 element=16
define drive sangroup driveb device=/dev/rmt5 element=17
```
3. Define at least one device class that is associated with the shared library. Set the mount wait times to different values for each server.

```
define devclass tape library=sangroup devtype=3570 mountretention=2 mountwait=10
```
4. Check in the library inventory. The following shows two examples. In both cases, the server uses the name on the barcode label as the volume name.
 - Check in volumes that are already labeled:

```
checkin libvolume sangroup search=yes status=scratch checklabel=barcode
```
 - Label and check in volumes:

```
label libvolume sangroup search=yes labelsource=barcode checkin=scratch
```
5. Set up a storage pool for the shared library with a maximum of 50 scratch volumes.

```
define stgpool backtape tape maxscratch=50
```

Setting up Each Library Client Server

Use the following procedure as an example of how to set up a TSM server as a library client:

1. Define the server that is the library manager:

```
define server astro serverpassword=secret haddress=9.115.3.45 lladdress=1580
crossdefine=yes
```
2. Define the shared library, SANGROUP:

Note: Ensure that the library name agrees with the library name on the library manager.


```
define library sangroup libtype=shared primarylibmanager=astro
```

3. Define the drives to the library by using the same names as the drives on the library manager. Element addresses are not required for shared libraries when defining drives on the library client.

```
define drive sangroup drivea device=/dev/rmt4
define drive sangroup driveb device=/dev/rmt5
```

Note: We recommend that you define all the drives in the shared library to the library client and manager servers.

4. Define at least one device class that is associated with the shared library. Set the mount wait times to different values for each server.

```
define devclass tape library=sangroup devtype=3570 mountretention=2 mountwait=10
```

5. Define the storage pool, BACKTAPE, that will use the shared library.

```
define stgpool backtape tape maxscratch=50
```

Using the Devices to Store Client Data

After you have attached and defined your devices, you can store client data in two ways:

- Have clients back up data directly to tape. For details, see “Configuring Policy for Direct-to-Tape Backups” on page 266.
- Have clients back up data to disk. The data is later migrated to tape. For details, see “Overview: The Storage Pool Hierarchy” on page 133.

Configuring IBM 349X Libraries in a SAN

The following tasks are required for TSM servers to share library devices over a SAN:

1. Set up server-to server communications.
2. Set up the library on the library manager server.
3. Set up the library on the library client server.

See “Categories in 349X Automated Libraries” on page 67 and “Enabling Support for IBM 3590 Drives in Existing 349X Libraries” on page 68 for additional information about configuring 349X libraries.

Set up the Device on the Server System

You must first set up the device on the server system. This involves the following tasks:

1. Set the 349X Library Manager Control Point (LMCP). This procedure is described in the *IBM SCSI Tape Drive, Medium Changer, and Library Device Drivers Installation and User's Guide* for AIX.
2. Physically attach the devices to the server hardware.
3. Install and configure the appropriate device drivers for the devices.
4. Determine the device names that are needed to define the devices to Tivoli Storage Manager.

For details, see “Attaching an Automated Library Device” on page 50 and “Installing and Configuring Device Drivers” on page 51.

Setting up the Library Manager Server

Use the following procedure as an example of how to set up a TSM server as a library manager:

1. Define a library named 3494SAN whose library type is 349X. For example:

```
define library 3494san libtype=349x device=device=/dev/lmcp0,/dev/lmcp1 shared=yes
```

2. Define the drives in the library:

```
define drive 3494san drivea device=/dev/rmt0  
define drive 3494san driveb device=/dev/rmt1
```

3. Define at least one device class associated with the shared library. Set the mount wait times to different values for each server.

```
define devclass 3494_class library=3494san devtype=3590 mountretention=2 mountwait=10
```

4. Check in the library inventory. The following shows two examples. In both cases, the server uses the name on the barcode label as the volume name.

To check in volumes that are already labeled, use the following command:

```
checkin libvolume 3494san search=yes status=scratch
```

To label and check in the volumes, use the following command:

```
label libvolume 3494san checkin=scratch search=yes
```

5. Set up a storage pool for the shared library with a maximum of 50 scratch volumes.

```
define stgpool 3494_sanpool tape maxscratch=50
```

Setting up the Library Client Servers

Use the following procedure as an example of how to set up a TSM server as a library client:

1. Define the server that is the library manager:

```
define server astro serverpassword=secret hladdress=9.115.3.45 lladdress=1580  
crossdefine=yes
```

2. Define the shared library, SANGROUP:

Note: Ensure that the library name agrees with the library name on the library manager.

```
define library sangroup libtype=shared primarylibmanager=astro
```

3. Define the drives to the library by using the same names as the drives on the library manager. Element addresses are not required for shared libraries when defining drives on the library client.

```
define drive 3494san drivea device=/dev/rmt0  
define drive 3494san driveb device=/dev/rmt1
```

Note: We recommend that you define all the drives in the shared library to both the library client and manager servers.

4. Define at least one device class associated with the shared library. Set the mount wait times to different values for each server.

```
define devclass 3494_class library=sangroup devtype=3590 mountretention=2 mountwait=10
```

5. Define the storage pool, BACKTAPE, that will use the shared library.

```
define stgpool 3494_san_pool 3494_class maxscratch=50
```

6. Repeat this procedure to define additional servers as library clients.

Migrating an IBM 349X Library to SAN Support

If you are already using an IBM 349X library with Tivoli Storage Manager in a non-SAN environment, you will have to perform the following procedure to migrate and correctly configure the library for a SAN environment. You must ensure that the 3494SHARED option is disabled in the dsmserv.opt file. This is accomplished by proceeding as follows:

1. Do the following on each server sharing a 3494 library:
 - a. Update the storage pools using the UPDATE STGPOOL command. Set the value for the HIGHMIG and LOWMIG parameters to 100%.
 - b. Stop the server by issuing the HALT command or accessing the TSM Console and clicking **Stop** for the server.
 - c. Edit the dsmserv.opt file:
 - 1) Comment out the 3494SHARED YES option line
 - 2) Activate the **disablescheds yes** option line if it is not active
 - 3) Activate the **expinterval x** option line if it is not active and change the value to 0; **expinterval 0**
 - d. Start the server.
 - e. Enter the following TSM command:


```
disable sessions
```
2. Set up the library manager on a TSM server of your choosing.
3. Do the following on the remaining TSM servers:
 - a. Save the volume history file.
 - b. Check out all the volumes in the library inventory. Use the CHECKOUT LIBVOLUME command with REMOVE=NO.
 - c. Follow the library client setup procedure.
4. Do the following on the library manager server:
 - a. Check in each library client's volumes. Use the CHECKIN LIBVOLUME command with the following parameter settings:
 - STATUS=PRIVATE
 - OWNER=<library client name>

Note: You can use the saved volume history files from the library clients as a guide.
 - b. Check in any remaining volumes as scratch volumes. Use the CHECKIN LIBVOLUME command with STATUS=SCRATCH.
5. Halt all the servers.
6. Edit the dsmserv.opt file and comment out the **disablescheds yes** and **expinterval 0** option lines.
7. Start the servers.

Using the Devices to Store Client Data

After you have attached and defined your devices, you can store client data in two ways:

- Have clients back up data directly to tape. For details, see “Configuring Policy for Direct-to-Tape Backups” on page 266.
- Have clients back up data to disk. The data is later migrated to tape. For details, see “Overview: The Storage Pool Hierarchy” on page 133.

Server Operations

When the library manager starts and the storage device initializes, or after a library manager is defined to a library client, the library client contacts the library manager. The library client confirms that the contacted server is the library manager for the named library device. The library client also compares drive definitions with the library manager for consistency. The library client contacts the library manager for each of the following operations:

Volume Mount

A library client sends a request to the library manager for access to a particular volume in the shared library device. For a scratch volume, the library client does not specify a volume name. If the library manager cannot access the requested volume, or if scratch volumes are not available, the library manager denies the mount request. If the mount is successful, the library manager returns the name of the drive where the volume is mounted.

Volume Release (free to scratch)

When a library client no longer needs to access a volume, it notifies the library manager that the volume should be returned to scratch. The library manager’s database is updated with the volume’s new location. The volume is deleted from the volume inventory of the library client.

Table 8 shows the interaction between library clients and the library manager in processing TSM operations.

Table 8. How SAN-enabled Servers Process TSM Operations

Operation (Command)	Library Manager	Library Client
Query library volumes (QUERY LIBVOLUME)	Displays the volumes that are checked into the library. For private volumes, the owner server is also displayed.	Not applicable.
Check in and check out library volumes (CHECKIN LIBVOLUME, CHECKOUT LIBVOLUME)	Performs the commands to the library device.	Not applicable. When a check-in operation must be performed because of a client restore, a request is sent to the library manager server.
Move media and move DRM media (MOVE MEDIA, MOVE DRMEDIA)	Only valid for volumes used by the library manager server.	Requests that the library manager server perform the operations. Generates a checkout process on the library manager server.
Audit library inventory (AUDIT LIBRARY)	Performs the inventory synchronization with the library device.	Performs the inventory synchronization with the library manager server.
Label a library volume (LABEL LIBVOLUME)	Performs the labeling and check-in of media.	Not applicable.

Table 8. How SAN-enabled Servers Process TSM Operations (continued)

Operation (Command)	Library Manager	Library Client
Dismount a volume (DISMOUNT VOLUME)	Sends the request to the library device.	Requests that the library manager server perform the operation.
Query a volume (QUERY VOLUME)	Checks whether the volume is owned by the requesting library client server and checks whether the volume is in the library device.	Requests that the library manager server perform the operation.

Configuring TSM Clients to Directly Access SAN-Attached Devices

This section describes how to configure the TSM client and server so that the client can, through a storage agent, move its data to storage on a SAN. This function, called LAN-free data movement, is provided by the Managed System for SAN feature. As part of the configuration, a storage agent is installed on the client system. TSM supports both tape libraries and FILE libraries. The configuration steps are somewhat different. Only the tape library setup is shown in this publication. See *TSM Managed System for SAN Storage Agent User's Guide* for detailed information about configuring the TSM client, storage agent, and server for both tape and FILE libraries.

TSM Client Setup

Setting up the client to directly access a storage device over a SAN consists of installing and configuring the storage agent on the TSM client machine and enabling the option for the API to allow the data movement. You also need to set up the TSM device driver. Thereafter, the client communicates with the storage agent, which in turn communicates with the TSM server. For details on these steps, see *TSM Managed System for SAN Storage Agent User's Guide*.

TSM Server Setup

Note: If you will be migrating an existing 349X library to a SAN configuration, see “Migrating an IBM 349X Library to SAN Support” on page 77.

1. Obtain the library and drive information for the SAN library device.
 - a. Run the SMIT program.
 - b. Select **Devices**.
 - c. Select **Tivoli Storage Manager Devices**.
 - d. Select **Fibre Channel SAN Attached devices**
 - e. Select **Discover Devices Supported by TSM**. (The discovery process can take some time.)
 - f. Go back to the Fibre Channel menu, and select **List Attributes of a Discovered Device**.
 - g. Note the 3-character identifier for the device, which you will use in defining the device to TSM. For example, in the list a tape drive has the identifier, mt2.
2. Define a library named SANGROUP, using the SHARED=YES parameter.

```
define library sangroup libtype=scsi device=/dev/lb0 shared=yes
```

-
3. Define the drives in the library.

```
define drive sangroup drivea device=/dev/mt4 element=1030
define drive sangroup driveb device=/dev/mt5 element=1031
```

4. Define a device class for the drives.

```
define devclass santape library=sangroup devtype=3570 mountretention=1 mountwait=10
```

5. Define a storage pool, SANPOOL.

```
define stgpool sanpool santape maxscratch=50
```

For each client for which you want to enable SAN data transfer, do the following:

6. **On the server:**

Define the client's storage agent as if it were a server. The name must match the name specified during storage agent configuration. For example, if the storage agent's name is IRIS, issue the following command:

```
define server iris serverpassword=jonquil hladdress=sanclient.tucson.ibm.com lladdress=1500
```

7. **On the client system:**

- a. Start the TSM device driver.
- b. Determine the device name by which the storage agent knows the device.

For details on these steps, see *TSM Managed System for SAN Storage Agent User's Guide*.

8. **On the server:**

- a. Define drive mapping for every drive that the storage agent will access, by using the DEFINE DRIVEMAPPING command.

Note: Before issuing the following commands to map your drives, review "Guidelines for Mapping Drives".

For the device name, specify the device name by which the storage agent knows the device:

```
define drivemapping iris sangroup drivea device=mt5.0.0.1
define drivemapping iris sangroup driveb device=mt5.2.0.1
```

- b. Set up the policy so that the client uses the new storage pool as the destination for backup operations. See "Configuring Policy for Managed System for SAN" on page 268 for details.

9. **On the client system:**

- a. Start the storage agent.
- b. Start a backup operation to verify that the setup is complete. To verify whether your configuration was successful, review the information described in "Determining Whether the Data Movement was LAN-Free" on page 81.

For details on these steps, see *TSM Managed System for SAN Storage Agent User's Guide*.

Guidelines for Mapping Drives

Consider the following guidelines before you begin mapping your SAN drives:

- Map *all* drives – Problems can occur if you do not define drive mappings on the server for each drive in a library. For example, during backup operations, all drives that have

been mapped can be used by storage agents that are backing up data. If other drives in a library are available but you have *not* mapped them, the storage agent cannot access them. This will cause backup operations to fail.

When you define drive mappings for each drive in a library, backup operations wait until the next drive is available for the transfer of data.

- Limit the number of drives – Use the MAXNUMMP parameter on the REGISTER NODE or UPDATE NODE command to limit the number of drives that are available for the storage agent to use on behalf of the client.
- Review device names – For the same device, the device name as known to the server will probably not match the device name as known to the storage agent. If you have a number of drives on the SAN, matching up drives from the viewpoint of a server with that from a client system may be difficult and could require trial-and-error methods.

Determining Whether the Data Movement was LAN-Free

You can use the following guidelines to help you determine whether the data movement was LAN-free:

- Issue either of the following QUERY ACTLOG commands on the server to which the client is connected:

```
query actlog search=storage_agent_name msgno=8337
```

Or

```
query actlog search=storage_agent_name
```

Note: If the query finds entries in the activity log that relate to the storage agent, the client is using LAN-free data transfer.

- Review the amount of data being transmitted from the client to the server via TCP/IP. The client backup data is passed over the SAN. Therefore, the amount of data being transferred to the server should be considerably less than the amount of data being backed up. From the command line, issue the following command:

```
netstat -D
```

Defining Drives and Libraries

The following sections describe how to define libraries and drives to TSM. See “Managing Libraries” on page 99 and “Managing Drives” on page 100 for information about displaying library and drive information, and updating and deleting libraries and drives.

Defining Libraries

Task	Required Privilege Class
Define or update libraries	System or unrestricted storage

Before you can use a drive, you must first define the library to which the drive belongs. This is true for both manually mounted drives and drives in automated libraries. For example, you have several stand-alone tape drives. You could define a library named MANUALMOUNT for these drives by using the following command:

```
define library manualmount libtype=manual
```

For automated libraries, you use the DEFINE LIBRARY command to define a SCSI or 349X library and specify the DEVICE parameter. The DEVICE parameter is required and specifies the device name created by the device driver, by which the library's robotic mechanism is known. See "Installing and Configuring Device Drivers" on page 51 for details.

This example applies to any SCSI library. It assumes that you have already configured the device driver and determined the device name. If you have an Exabyte EXB-120 device, you could define a library named ROBOTMOUNT using the following command:

```
define library robotmount libtype=scsi device=/dev/lb0
```

If you have an IBM 3590 B11 device with device special file name /dev/rmt0.smc, you can define a library named MAINMOUNT using the following command:

```
define library mainmount libtype=scsi device=/dev/rmt0.smc
```

Suppose you have an IBM 3494 Tape Library Dataserver connected to your system, and that you have defined one LMCP whose device name is /dev/lmcp0. You can define a library named AUTOMOUNT using the following command:

```
define library automount libtype=349x device=/dev/lmcp0
```

Defining Drives

Task	Required Privilege Class
Define drives	System or unrestricted storage

To inform the server about a drive that can be used to access storage volumes, issue the DEFINE DRIVE command. When issuing this command, you must provide some or all of the following information:

Library name

The name of the library in which the drive resides.

Drive name

The name assigned to the drive.

Device name

The device name to be used to access the drive.

Element address

The element address of the drive. The ELEMENT parameter applies only to SCSI libraries. The element address is a number that indicates the physical location of a drive within an automated library. TSM needs the element address to connect the physical location of the drive to the drive's SCSI address. You can get the element address from this Web site:

http://www.tivoli.com/support/storage_mgr/tivolimain.html.

For example, to define a drive that belongs to the manual library named MANLIB, enter this command:

```
define drive manlib tapedrv3 device=/dev/mt3
```


7

Managing Removable Media Operations

This chapter describes routine removable media operations including the following:

- Preparing media for use (checking volumes into automated libraries and labeling volumes)
- Controlling how and when media are reused
- Ensuring that sufficient media are available
- Responding to TSM requests to operators
- Managing libraries and drives (including drive cleaning)

See the following sections:

Tasks:
“Preparing Removable Media”
“Labeling Removable Media Volumes” on page 84
“Checking New Volumes into a Library” on page 87
“Controlling Access to Volumes” on page 90
“Reusing Tapes in Storage Pools” on page 91
“Reusing Volumes Used for Database Backups and Export Operations” on page 91
“Managing Volumes in Automated Libraries” on page 93
“Managing Server Requests for Media” on page 96
“Managing Libraries” on page 99
“Managing Drives” on page 100

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator's Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Preparing Removable Media

When TSM accesses a removable media volume, it checks the volume name in the label header to ensure that the correct volume is being accessed. To prepare a volume for use, do the following:

1. Label the volume. Any tape or optical volumes must be labeled before the server can use them. See “Labeling Removable Media Volumes” on page 84.

-
2. For automated libraries, check the volume into the library. See “Checking New Volumes into a Library” on page 87.

Tip: When you use the LABEL LIBVOLUME command with drives in an automated library, you can label and check in the volumes with one command.

3. You can skip this step if you allowed scratch volumes in the storage pool by specifying a nonzero MAXSCRATCH parameter.

If the storage pool can contain scratch volumes, identify the volume to TSM by name so that it can be accessed later. For details, see “Defining Storage Pool Volumes” on page 130.

Labeling Removable Media Volumes

You can use the LABEL LIBVOLUME command from the server console or an administrative client to check in and label volumes in one operation. When you use the command, you can provide parameters that specify:

- The name of the library where the storage volume is located
- The name of the storage volume
- Whether to overwrite a label on the volume
- Whether to search an autoated library for volumes for labeling
- Whether to read media labels:
 - To prompt for volume names in SCSI libraries
 - To read the bar-code label for each cartridge in SCSI libraries
- Whether to check in the volume:
 - To add the volume to the scratch pool
 - To designate the volume as private
- The type of device (applies to 349X libraries only)

To use the LABEL LIBVOLUME command, there must be a drive that is not in use by another TSM process. This includes volumes that are mounted but idle. If necessary, use the DISMOUNT VOLUME command to dismount the idle volume to make that drive available.

By default, the LABEL LIBVOLUME command does not overwrite an existing label. However, if you want to overwrite an existing label, you can specify OVERWRITE=YES parameter.

Attention: By overwriting a volume label, you destroy all of the data that resides on the volume. Use caution when overwriting volume labels to avoid destroying important data.

When you use the LABEL LIBVOLUME command, you can identify the volumes to be labeled in one of the following ways:

- Explicitly name one or more volumes.
- Enter a range of volumes by using the VOLRANGE parameter.
- Use the VOLLIST parameter to specify a file that contains a list of volume names.

For automated libraries, you are prompted to insert the volume in the entry/exit slot of the library. If no entry/exit slot is available, insert the volume in an empty slot. For manual libraries, you are prompted to load the volume directly into a drive.

Labeling Volumes In a Manual Drive

Suppose that you want to label a few new volumes by using a manual tape drive that is defined as `/dev/mt5`. The drive is attached at SCSI address 5. Enter the following command:

```
label libvolume tsmlibname volname
```

Note: The LABEL LIBVOLUME command selects the next free drive. If you have more than one free drive, this may not be `/dev/mt5`.

If the server is not available, use the following command:

```
> dsmlabel -drive=/dev/mt5
```

The DSMLABEL utility, which is an offline utility for labeling sequential access volumes for TSM, must read the `dsmserv.opt` file to pick up the language option. Therefore, you must issue the DSMLABEL command from the `/usr/tivoli/tsm/server/bin/` directory, or you must set the DSMSEV_DIR and DSMSEV_CONFIG environment variables.

Labeling Volumes in a SCSI or ACSLS Library

You can label volumes one at a time or let TSM search the library for volumes.

Labeling Volumes One at a Time

If you choose to label volumes one at a time, you do the following:

1. Insert volumes into the library when prompted to do so. The library mounts each inserted volume into a drive.
2. When you are prompted, enter a volume name. A label is written to the volume using the name that you entered.
3. If the library does not have an entry/exit port, you are prompted to remove the tape from a specified slot number (not a drive). If the library has an entry/exit port, the command by default returns each labeled volume to the entry/exit port of the library.

Labeling New Volumes in a Library

Suppose you want to label a few new volumes in a SCSI library. You want to manually insert each new volume into the library, and you want the volumes to be placed in storage slots inside the library after their labels are written. You know that none of the new volumes contains valid data, so it is acceptable to overwrite existing volume labels. You only want to use one of the library's four drives for these operations.

Note: This example works for libraries that do not have entry and exit ports. Enter the following command:

```
label libvolume tsmlibname volname overwrite=yes
```

If the server is not available, use the following command:

```
> dsmlabel -drive=/dev/mt0,116 -library=/dev/lb0 -overwrite -keep
```

Searching the Library

The LABEL LIBVOLUME command searches all of the storage slots in the library for volumes and tries to label each one that it finds. You choose this mode when you specify the SEARCH parameter. After a volume is labeled, the volume is returned to its original location in the library.

Specify SEARCH=BULK if you want TSM to search the library's entry/exit ports for usable volumes to be labeled. When you use the LABELSOURCE=PROMPT parameter, the volume is moved from the entry/exit ports to the drive. You are prompted to issue the REPLY command containing the label string, and that label is written to the tape.

If the library has a bar-code reader, the LABEL LIBVOLUME command can use the reader to obtain volume names, instead of prompting you for volume names. Use the SEARCH=YES and LABELSOURCE=BARCODE parameters. When you specify the LABELSOURCE=BARCODE parameter, the volume's bar code is read and the tape is moved from the entry/exit to a drive where the barcode label is written. After the tape is labeled, it is moved back to the entry/exit port or to a storage slot if the CHECKIN option is specified. For bar-code support to work correctly, the TSM server and the device driver must be at the same level for TSM-controlled libraries. Bar-code support is available for TSM-controlled libraries using the TSM device driver or the RMSS Magstar or LTO Ultrium device driver.

Suppose you want to label all of the volumes in a SCSI library. Although the library contains four drives, you only want to use two of them to label volumes. The drives are at element addresses 116 and 117. Enter the following command:

```
label libvolume tsmllibname search=yes labelsource=barcode
```

Note: The LABELSOURCE=BARCODE parameter is valid only for SCSI libraries.

If the server is not available, use the following command:

```
> dsmlabel -drive=/dev/mt0,116 -drive=/dev/mt1,117 -library=/dev/lb0 -search
```

Labeling Volumes in a 349X Library

The labeling process for a 349X library attempts to label only those volumes in the INSERT category. All other volumes are ignored by the labeling process. This precaution prevents the inadvertent destruction of that data on volumes being actively used by other systems connected to the library device.

Note: The LABEL LIBVOLUME command labels volumes in the INSERT category and in the PRIVATE, 3490SCRATCH, and 3590SCRATCH categories, but not the volumes already checked into the library.

Suppose you want to label all of the volumes that are in the INSERT category in an IBM 3494 tape library. Enter the following command:

```
label libvolume tsmllibname search=yes devtype=3590
```

Note: If the volumes to be labeled are 3590 media, you must add DEVTYPE=3590.

If the server is not available, use the following command:

```
> dsmlabel -drive=/dev/rmt1 -drive=/dev/rmt2 -library=/dev/lmcp0
```

Labeling Optical Volumes

You can use the LABEL LIBVOLUME command to label optical disks (3.5-inch and 5.25-inch).

```
label libvolume opticlib search=yes labelsource=prompt
```

You can also use the DSMLABEL utility to format and label 3.5-inch and 5.25-inch optical disks. Use the `-format` parameter when starting the DSMLABEL utility.

The DSMLABEL utility, which is an offline utility for labeling sequential access volumes for TSM, must read the `dsmserv.opt` file to pick up the language option. Therefore, you must issue the DSMLABEL command from the `/usr/tivoli/tsm/server/bin/` directory, or you must set the DSMSEV_DIR and DSMSEV_CONFIG environment variables.

```
> dsmlabel -drive=/dev/rop1,117 -library=/dev/lb0 -search -format
```

Checking New Volumes into a Library

Task	Required Privilege Class
Inform the server when a new volume is available in an automated library	System or unrestricted storage

You inform the server that a new volume is available in an automated library by checking in the volume with the CHECKIN LIBVOLUME or LABEL LIBVOLUME command. When a volume is checked in, the server adds the volume to its library volume inventory. You can use the LABEL LIBVOLUME command to check in and label volumes in one operation.

Note: Do not mix volumes with bar-code labels and volumes without bar-code labels in a library device because bar-code scanning can take a long time for unlabeled volumes.

Processing time: Wait for the CHECKIN LIBVOLUME process to complete before defining volumes or the defining process will fail. Because the CHECKIN LIBVOLUME command involves device access, it may take a long time to complete. For this reason, the command always executes as a background process.

When you check in a volume, you must supply the name of the library and the status of the volume (private or scratch).

To check in one or just a few volumes, you can specify the name of the volume with the command, and issue the command for each volume. See “Checking Volumes into a SCSI Library One at a Time” on page 88.

To check in a larger number of volumes, you can use the search capability of the CHECKIN command (see “Checking in Volumes in Library Slots” on page 89) or you can use the VOLRANGE parameter of the CHECKIN command.

When using the CHECKIN LIBVOLUME command, be prepared to supply some or all of the following information:

Library name

Specifies the name of the library where the storage volume is to be located.

Volume name

Specifies the volume name of the storage volume being checked in.

Status Specifies the status that is assigned to the storage volume being checked in. If you

check in a volume that has already been defined in a storage pool or in the volume history file, you must specify a volume status of *private* (STATUS=PRIVATE). This status ensures that the volume is not overwritten when a scratch mount is requested. The server does not check in a volume with scratch status when that volume already belongs to a storage pool or is a database, export, or dump volume.

Check label

Specifies whether TSM should read sequential media labels of volumes during CHECKIN command processing, or use a bar-code reader. See “Checking Media Labels” on page 90.

For optical volumes being checked in to an automated library, you must specify CHECKLABEL=YES. TSM must read the label to determine the type of volume: rewritable (OPTICAL device type) or write-once read-many (WORM or WORM12 device type).

Swap Specifies whether TSM will initiate a swap operation when an empty slot is not available during CHECKIN command processing. See “Allowing Swapping of Volumes When the Library Is Full” on page 90.

Mount wait

Specifies the maximum length of time, in minutes, to wait for a storage volume to be mounted.

Search

Specifies whether TSM searches the library for volumes that have not been checked in. See “Checking Volumes into a SCSI Library One at a Time”, “Checking in Volumes in Library Slots” on page 89, and “Checking in Volumes in Library Entry/Exit Ports” on page 89.

Device type

This parameter only applies to 349X libraries containing 3590 devices. This parameter allows you to specify the device type for the volume being checked in.

Checking Volumes into a SCSI Library One at a Time

Specify SEARCH=NO if you want to check in only a single volume that is not currently in the library. TSM requests that the mount operator load the volume in the entry/exit port of the library.

If the library does not have an entry/exit port, TSM requests that the mount operator load the volume into a slot within the library. The request specifies the location with an *element address*. For any library or autochanger that does not have an entry/exit port, you need to know the element addresses for the cartridge slots and drives. If there is no worksheet listed for your device in http://www.tivoli.com/support/storage_mgr/tivolimain.html, see the documentation that came with your library.

Note: Element addresses are sometimes numbered starting with a number other than one. Check the worksheet to be sure.

For example, To check in volume VOL001 manually (if the library does have an entry/exit port), enter the following command:

```
checkin libvolume tapelib vol001 search=no status=scratch
```

You are prompted to insert a cartridge into the entry/exit port. If the library does not have an entry/exit port, you are prompted to insert a cartridge into one of the slots in the library.

Element addresses identify these slots. You can find these element addresses in the worksheet for the device. (See http://www.tivoli.com/support/storage_mgr/tivolimain.html to find the worksheet.) For example, TSM finds that the first empty slot is at element address 5. The message is:

```
ANR8306I 001: Insert 8MM volume VOL001 R/W in slot with element
address 5 of library TAPELIB within 60 minutes; issue 'REPLY' along
with the request ID when ready.
```

Check the worksheet for the device if you do not know the location of element address 5 in the library. When you have inserted the volume as requested, respond to the message from a TSM administrative client. Use the request number (the number at the beginning of the mount request):

```
reply 1
```

Checking Volumes into a 349XI Library One at a Time

Specify `SEARCH=NO` for a 349X library, to search for volumes that have already been inserted into the library via the convenience or bulk I/O station.

```
checkin libvolume 3494lib vol001 search=no status=scratch
```

If the volume has already been inserted, the server finds and processes it. If not, you can insert the volume into the I/O station during the processing of the command.

Checking in Volumes in Library Slots

Specify this option if you want TSM to automatically search the library slots for new volumes that have not already been added to the library volume inventory. Use this mode when you have a large number of volumes to check in, and you want to avoid issuing an explicit `CHECKIN LIBVOLUME` command for each volume.

When you search the library, you cannot specify a volume name because the server searches for multiple new volumes in the library.

For example, for a SCSI library you can simply open the library access door, place all of the new volumes in unused slots, close the door, and issue the `CHECKIN LIBVOLUME` command with `SEARCH=YES`.

If you are using a 349X library, the server searches only for new volumes in the following categories:

- Insert
- TSM's private category (`PRIVATECATEGORY`, specified when the library was defined to TSM)
- TSM's scratch category (`SCRATCHCATEGORY`, specified when the library was defined to TSM)

If 3590 support is enabled, the server searches for two scratch categories: `SCRATCHCATEGORY`, and `SCRATCHCATEGORY + 1`.

This restriction prevents the server from using volumes owned by another application that is accessing the library simultaneously.

Checking in Volumes in Library Entry/Exit Ports

Specify `SEARCH=BULK` if you want TSM to search the library's entry/exit ports for volumes that can be checked in automatically. For SCSI libraries, the server scans all of the

entry/exit ports in the library for volumes. If a volume is found that contains a valid volume label, it is checked in automatically. The CHECKLABEL option NO is invalid with this SEARCH option. When you use the CHECKLABEL=YES parameter, the volume is moved from the entry/exit ports to the drive where the label is read. After reading the label, the tape is moved from the drive to a storage slot. When you use the CHECKLABEL=BARCODE parameter, the volume's bar code is read and the tape is moved from the entry/exit port to a storage slot. For bar-code support to work correctly, the TSM or RMSS device driver must be installed for TSM-controlled libraries.

Checking Media Labels

When you check in a volume, you can specify whether TSM should read the labels of the media during check-in processing. When label-checking is on, TSM mounts each volume to read the internal label and only checks in a volume if it is properly labeled. This can prevent future errors when volumes are actually used in storage pools, but also increases processing time at check in. For information on how to label new volumes, see “Preparing Removable Media” on page 83.

If a library has a bar-code reader and the volumes have bar-code labels, you can save time in the check in process. TSM uses the characters on the label as the name for the volume being checked in. If a volume has no bar-code label, TSM mounts the volumes in a drive and attempts to read the recorded label. For example, to use the bar-code reader to check in all volumes found in the TAPELIB library as scratch volumes, enter the following command:

```
checkin libvolume tapelib search=yes status=scratch checklabel=barcode
```

Allowing Swapping of Volumes When the Library Is Full

If no empty slots are available in the library when you are checking in volumes, the check-in fails unless you allow *swapping*. If you allow swapping and the library is full, TSM selects a volume to eject before checking in the volume you requested.

Use the CHECKIN LIBVOLUME command to allow swapping. When you specify YES for the SWAP parameter, TSM initiates a swap operation if an empty slot is not available to check in a volume. TSM ejects the volume that it selects for the swap operation from the library and replaces the ejected volume with the volume that is being checked in. For example:

```
checkin libvolume auto wpdv00 swap=yes
```

TSM selects the volume to eject by checking first for any available scratch volume, then for the least frequently mounted volume.

Managing the Volume Inventory

With TSM, you manage your volume inventory by performing the following tasks:

- Controlling TSM access to volumes
- Reusing tapes in storage pools
- Reusing volumes used for database backups and export operations
- Maintaining a supply of scratch volumes

Controlling Access to Volumes

TSM expects to be able to access all volumes it knows about. For example, TSM tries to fill up tape volumes. If a volume containing client data is only partially full, TSM will later request that volume be mounted to store additional data. If the volume cannot be mounted, an error occurs.

To make volumes that are not full available to TSM but not available for further writing, you can change the access mode of the volumes. For example, use the `UPDATE VOLUME` command with `ACCESS=READONLY`. The server will not attempt to mount a volume that has an access mode of unavailable.

If you want to make volumes unavailable to send the data they contain offsite for safekeeping, a more controlled way to do this is to use a copy storage pool. You can back up your primary storage pools to a copy storage pool and then send the copy storage pool volumes offsite. You can track these copy storage pool volumes by changing their access mode to offsite, and updating the volume history to identify their location. For more information, see “Backing Up Storage Pools” on page 465.

Reusing Tapes in Storage Pools

To reuse tapes in TSM storage pools, you must do two things:

- Run expiration processing regularly so that client files that have *expired* (are no longer valid) are deleted. See “Expiration Processing of Client Files”.
- Move data to consolidate valid, unexpired files onto fewer tapes. TSM offers an automated process called *reclamation* that does this. See “Reclamation”.

Expiration Processing of Client Files

Expiration processing deletes from the TSM database information about any client files that are no longer valid according to the policies you have set. For example, suppose four backup versions of a file exist in TSM server storage, and only three versions are allowed in the backup policy (the management class) for the file. Expiration processing deletes information about the oldest of the four versions of the file. The space that the file occupied in the storage pool can then be reclaimed.

You can run expiration processing automatically or by command. See “Running Expiration Processing to Delete Expired Files” on page 264.

Reclamation

You can have TSM reclaim volumes that pass a *reclamation threshold*, a percentage of unused space on the volume. The reclamation threshold is set for each storage pool. See “Reclaiming Space in Sequential Access Storage Pools” on page 152.

For a storage pool associated with a library that has more than one drive, the reclaimed data is moved to other volumes in the same storage pool. For a storage pool associated with a library that has only one drive, the reclaimed data is moved to volumes in another storage pool that you must define, called a reclamation storage pool. See “Reclaiming Volumes in a Storage Pool with One Drive” on page 155.

Reusing Volumes Used for Database Backups and Export Operations

When you back up the database or export server information, TSM records information about the volumes used for these operations in the *volume history* file. TSM will not allow you to reuse these volumes until you delete the volume information from the volume history file. To reuse volumes that have previously been used for database backup or export, use the `DELETE VOLHISTORY` command. For information about the volume history file, see “Saving the Volume History File” on page 472.

Note: If your server is licensed for the DRM product, the volume information is automatically deleted during `MOVE DRMEDIA` command processing. For additional information about DRM, see “Using Tivoli Disaster Recovery Manager” on page 497.

Maintaining a Supply of Scratch Volumes

When you define a storage pool, you must specify the maximum number of scratch volumes that the storage pool can use. TSM automatically requests a scratch volume when needed. When the number of scratch volumes that TSM is using for the storage pool exceeds the maximum number of scratch volumes specified, the storage pool can run out of space.

Ensure that you set the maximum number of scratch volumes high enough for the expected usage. When you exceed this number, you can do one or both of the following:

- Increase the maximum number of scratch volumes by updating the storage pool definition. Label new volumes to be used as scratch volumes if needed.
- Make volumes available for reuse by running expiration processing and reclamation, to consolidate data onto fewer volumes. See “Reusing Tapes in Storage Pools” on page 91.

For automated libraries, see also “Maintaining a Supply of Scratch Volumes in an Automated Library” on page 96.

Maintaining a Supply of Volumes in a WORM Library

For libraries with WORM drives, try to prevent cancellation of data storage transactions by maintaining a supply of scratch or new private volumes in the library. Canceled transactions can cause wasted WORM media. TSM cancels (rolls back) a transaction if volumes, either private or scratch, are not available to complete the data storage operation. After TSM begins a transaction by writing to a WORM volume, the written space on the volume cannot be reused, even if the transaction is canceled.

For example, if a client starts to back up data and does not have sufficient volumes in the library, TSM cancels the backup transaction. The WORM volumes to which TSM had already written for the canceled backup are wasted because the volumes cannot be reused. Suppose that you have WORM platters that hold 2.6GB each. A client starts to back up a 12GB file. If TSM cannot acquire a fifth scratch volume after filling four volumes, TSM cancels the backup operation. The four volumes that TSM already filled cannot be reused.

To minimize cancellation of transactions, do the following:

- Ensure that you have enough volumes available in the library to handle expected client operations such as backup.
 - Verify that you set the maximum number of scratch volumes for the storage pool that is associated with the library to a high enough number.
 - Check enough scratch or private volumes into the library to handle the expected load.
- If your clients tend to store files of smaller sizes, controlling the transaction size can affect how WORM platters are used. Smaller transactions waste less space if a transaction such as a backup must be canceled. The TXNGROUPMAX server option and the TXNBYTELIMIT client option control transaction size. See “How the Server Groups Files before Storing” on page 134 for information.

Managing Volumes in Automated Libraries

TSM tracks the scratch and private volumes available in an automated library through a *library volume inventory*. TSM maintains an inventory for each automated library. The library volume inventory is separate from the inventory of volumes for each storage pool. To add a volume to a library's volume inventory, you *check in* a volume to that TSM library. For details on the check-in procedure, see "Checking New Volumes into a Library" on page 87.

To ensure that TSM's library volume inventory remains accurate, you must *check out* volumes when you need to physically remove volumes from a SCSI, 349X, or ACSLS library. When you check out a volume that is being used by a storage pool, the volume remains in the storage pool. If TSM requires the volume to be mounted while it is checked out, a message to the mount operator's console is displayed with a request to check in the volume. If the check in is not successful, TSM marks the volume as unavailable.

While a volume is in the library volume inventory, you can change its status from scratch to private.

To check whether TSM's library volume inventory is consistent with the volumes that are physically in the library, you can audit the library. The inventory can become inaccurate if volumes are moved in and out of the library without informing the server via volume check-in or check-out.

Task	Required Privilege Class
Changing the status of a volume in an automated library	System or unrestricted storage
Removing volumes from a library	
Returning volumes to a library	

Changing the Status of a Volume

The UPDATE LIBVOLUME command lets you change the status of a volume in an automated library from scratch to private, or private to scratch. However, you cannot change the status of a volume from private to scratch if the volume belongs to a storage pool.

You can use this command if you make a mistake when checking in volumes to the library and assign the volumes the wrong status.

Removing Volumes from a Library

You may want to remove a volume from an automated library. The following two examples illustrate this:

- You have exported data to a volume in the library and want to take it to another system for an import operation.
- All of the volumes in the library are full, and you want to remove some that are not likely to be accessed to make room for new volumes that can be used to store more data.

To remove a volume from an automated library, use the CHECKOUT LIBVOLUME command. By default, the server mounts the volume being checked out and verifies the internal label. When the label is verified, the server removes the volume from the library

volume inventory, and then moves it to the entry/exit port of the library. If the library does not have an entry/exit port, TSM requests that the mount operator remove the volume from a slot within the library.

For SCSI libraries with multiple entry/exit ports, use the REMOVE=BULK parameter of the CHECKOUT LIBVOLUME command to eject the volume to the next available entry/exit port.

If you check out a volume that is defined in a storage pool, the server may attempt to access it later to read or write data. If this happens, the server requests that the volume be checked in.

Returning Volumes to a Library

When you check out a volume that is defined to a storage pool, to make the volume available again, do the following:

1. Check in the volume for the library, with private status. Use the CHECKIN LIBVOLUME command with the parameter STATUS=PRIVATE.
2. If the volume was marked unavailable, update the volume's ACCESS value to read/write or read-only. Use the UPDATE VOLUME command with the ACCESS parameter.

Managing a Full Library

As TSM fills volumes in a storage pool, the number of volumes needed for the pool may exceed the physical capacity of the library. To make room for new volumes while keeping track of existing volumes, you can define a storage pool overflow location near the library. You then move media to the overflow location as needed. The following shows a typical sequence of steps to manage a full library:

1. Define or update the storage pool associated with the automated library, including the overflow location parameter. For example, you have a storage pool named ARCHIVEPOOL associated with an automated library. Update the storage pool to add an overflow location of Room2948. Enter this command:

```
update stgpool archivepool ovflocation=Room2948
```

2. When the library becomes full, move the full volumes out of the library and to the overflow location that you defined for the storage pool. For example, to move all full volumes in the specified storage pool out of the library, enter this command:

```
move media * stgpool=archivepool
```

All full volumes are checked out of the library. TSM records the location of the volumes as Room2948. You can use the DAYS parameter to specify the number of days that must elapse before a volume is eligible for processing by the MOVE MEDIA command.

3. Check in new scratch volumes, if needed.
4. Reuse the empty scratch storage volumes in the overflow location. For example, enter this command:

```
query media * stg=* whereovflocation=Room2948 wherestatus=empty  
move media * stg=* wherestate=mountablenotinlib wherestatus=empty  
cmd="checkin libvol autolib &vol status=scratch"  
cmdfilename=/tsm/move/media/checkin.vols
```

For more information, see *Administrator's Reference*.

5. As requested through TSM mount messages, check in volumes that TSM needs for operations. The mount messages include the overflow location of the volumes.

To find the overflow location of a storage pool, you can use the QUERY MEDIA command. This command can also be used to generate commands. For example, you can issue a QUERY MEDIA command to get a list of all volumes in the overflow location, and at the same time generate the commands to check in all those volumes to the library. For example, enter this command:

```
query media format=cmd stgpool=archivepool whereovflocation=Room2948
cmd="checkin libvol autolib &vol status=private"
cmdfilename="/tsm/move/media/checkin.vols"
```

Use the DAYS parameter to specify the number of days that must elapse before the volumes are eligible for processing by the QUERY MEDIA command.

The file that contains the generated commands can be run using the TSM MACRO command. For this example, the file may look like this:

```
checkin libvol autolib TAPE13 status=private
checkin libvol autolib TAPE19 status=private
```

Auditing a Library's Volume Inventory

Task	Required Privilege Class
Audit the volume inventory of a library	System or unrestricted storage

You can audit an automated library to ensure that TSM's library volume inventory is consistent with the volumes that physically reside in the library. You may want to do this if the server's library volume inventory is disturbed due to manual movement of volumes within the library or to problems with the server database. Use the AUDIT LIBRARY command to restore the inventory to a consistent state. Missing volumes are deleted and the locations of the moved volumes are updated; however, new volumes are not added during an audit. Unless your library has a bar-code reader, the server mounts each volume during the audit process to verify the internal labels on volumes.

Note: Audit library processing waits until all volumes have been dismounted from drives within the specified library. If one or more volumes are mounted, but are in the IDLE state, you can force the volumes to be dismounted by issuing the DISMOUNT VOLUME command. Otherwise, the audit operation remains in a wait state until the idle volumes have been dismounted (the idle volumes are dismounted after the MOUNTRETENTION period expires).

Issue the AUDIT LIBRARY command when there is no other mount activity and all the drives are empty. If there are volumes mounted but they are in the IDLE state, force the volumes to be dismounted by issuing the DISMOUNT VOLUME command.

If a library has a bar-code reader, you can save time in the audit process by using the bar-code reader to verify the identity of volumes. If a volume has a bar-code label, TSM uses the characters on the label as the name for the volume during the audit. The volume is *not* mounted to verify that the external bar-code name matches the internal, recorded volume name. If a volume has no bar-code label, TSM mounts the volume in a drive and attempts to read the recorded label.

For example, to audit the TAPELIB library using its bar-code reader, enter the following command:

```
audit library tapelib checklabel=barcode
```

Maintaining a Supply of Scratch Volumes in an Automated Library

When you define a storage pool that is associated with an automated library (through the device class), you must specify a maximum number of scratch volumes equal to the physical capacity of the library. When the number of scratch volumes that TSM is using for the storage pool exceeds that number, do the following:

1. Add scratch volumes to the library by checking in volumes. Label them if necessary. You may need to use an overflow location to move volumes out of the library to make room for these scratch volumes. See “Maintaining a Supply of Scratch Volumes” on page 92.
2. Increase the maximum number of scratch volumes by updating the storage pool definition. The increase should equal the number of scratch volumes that you checked in.

Managing Server Requests for Media

TSM displays requests and status messages to all administrative clients that are started in console mode. These request messages often have a time limit. If the request is not fulfilled within the time limit, the operation times out and fails.

For manual libraries, TSM detects when there is a cartridge loaded in a drive, and no operator reply is necessary. For automated libraries, commands such as CHECKIN LIBVOLUME, LABEL LIBVOLUME, and CHECKOUT LIBVOLUME involve inserting or removing cartridges from the library and issuing a reply message.

Using the Administrative Client for Mount Messages

The server sends mount request status messages to the server console and to all administrative clients in mount mode or console mode parameter. For example, to start an administrative client in mount mode, enter this command:

```
> dsmadm -mountmode
```

Mount Operations for Manual Libraries

Volumes are mounted as a result of mount requests from TSM. For manual libraries, you can monitor the mount requests on the server console or through an administrative client in mount mode or console mode. Someone you designate as the operator must respond to the mount requests by putting in tape volumes as requested.

Handling Messages for Automated Libraries

For automated libraries, mount messages are sent to the library and not to an operator. Messages about problems with the library are sent to the mount message queue. You can see these messages on administrative clients in mount mode or console mode. However, you cannot use the TSM REPLY command to respond to these messages.

Requesting Information about Pending Operator Requests

Task	Required Privilege Class
Request information about operator requests or mounted volumes	Any administrator

You can get information about pending operator requests either by using the QUERY REQUEST command or by checking the mount message queue on an administrative client started in mount mode.

When you issue the `QUERY REQUEST` command, TSM displays requested actions and the amount of time remaining before the requests time out. For example, you enter the command as follows:

```
query request
```

The following shows an example of a response to the command:

```
ANR8352I Requests outstanding:
ANR8326I 001: Mount 8MM volume DSM001 R/W in drive TAPE01 (/dev/mt1)
of MANUAL8MM within 60 minutes.
```

Replying to Operator Requests

Task	Required Privilege Class
Reply to operator requests	Operator

When the server requires that an explicit reply be provided when a mount request is completed, you can reply with the `REPLY` command. The first parameter for this command is the request identification number that tells the server which of the pending operator requests has been completed. This 3-digit number is always displayed as part of the request message. It can also be obtained by issuing a `QUERY REQUEST` command. If the request requires the operator to provide a device to be used for the mount, the second parameter for this command is a device name.

For example, enter the following command to respond to request 001 for tape drive TAPE01:

```
reply 1
```

Canceling an Operator Request

Task	Required Privilege Class
Cancel operator requests	Operator

If a mount request for a manual library cannot be satisfied, you can issue the `CANCEL REQUEST` command. This command forces the server to cancel the request and cause the operation that needed the requested volume to fail.

The `CANCEL REQUEST` command must include the request identification number. This number is included in the request message. You can also obtain it by issuing a `QUERY REQUEST` command, as described in “Requesting Information about Pending Operator Requests” on page 96.

You can specify the `PERMANENT` parameter if you want to mark the requested volume as `UNAVAILABLE`. This process is useful if, for example, the volume has been moved to a remote site or is otherwise inaccessible. By specifying `PERMANENT`, you ensure that the server does not try to mount the requested volume again.

For most of the requests associated with automated (SCSI) libraries, an operator must perform a hardware or system action to cancel the requested mount. For such requests, the CANCEL REQUEST command is not accepted by the server.

Responding to Requests for Volume Check-In

If the server cannot find a particular volume it needs to be mounted in an automated library, the server requests that the operator check in the volume. For example, a client requests that an archived file be retrieved. The file was archived in a storage pool in an automated library. The server looks for the volume containing the file in the automated library, but cannot find the volume. The server then requests that the volume be checked in.

If the volume that the server requests is available, put the volume in the library and check in the volume using the normal procedures (“Checking New Volumes into a Library” on page 87).

If the volume requested is unavailable (lost or destroyed), update the access mode of the volume to UNAVAILABLE by using the UPDATE VOLUME command. Then cancel the server’s request for check-in by using the CANCEL REQUEST command. (Do *not* cancel the client process that caused the request.) To get the ID of the request to cancel, use the QUERY REQUEST command.

If you do not respond to the server’s check-in request within the mount-wait period of the device class for the storage pool, the server marks the volume as unavailable.

Determining Which Volumes Are Mounted

Task	Required Privilege Class
Request information about which volumes are mounted	Operator

For a report of all volumes currently mounted for use by the server, you can issue the QUERY MOUNT command. The report shows which volumes are mounted, which drives have accessed them, and if the volumes are currently being used.

Dismounting an Idle Volume

Task	Required Privilege Class
Request a volume dismount	Operator

After a volume becomes idle, the server keeps it mounted for a time specified by the mount retention parameter for the device class. Using mount retention can reduce the access time if volumes are repeatedly used.

An administrator can explicitly request that an idle volume be dismounted by issuing the DISMOUNT VOLUME command. This command causes the server to dismount the named volume from the drive in which it is currently mounted.

For information about setting mount retention times, see “Mount Retention Period” on page 108.

Managing Libraries

You can query, update, and delete libraries.

Requesting Information About Libraries

By using the `QUERY LIBRARY` command, you can obtain information about libraries. You can request either a standard or a detailed report. For example, to display information about all libraries, issue the following command:

```
query library
```

The following shows an example of the output from this command.

Library Name	Library Type	Device	Private Category	Scratch Category	External Manager
MANLIB	MANUAL				
EXB	SCSI	/dev/lb2			
3494LIB	349X	/dev/lmcp0,/dev/lmcp1	300	301	

Updating Libraries

You can update a previously defined library by issuing the `UPDATE LIBRARY` command.

Note: You cannot update a `MANUAL` library.

Automated Libraries

If your system or device is reconfigured causing the device name to change, you may need to update the device name. The examples below show how you can use the `UPDATE LIBRARY` command for the following library types:

- SCSI
- 349X
- ACSLS
- External

Examples:

1. SCSI Library

Update a SCSI library named `SCSILIB` with a new device name.

```
update library scsilib device=/dev/lb1
```

2. 349X Library

Update a 3494 shared library named `3494LIB` with new device names.

```
update library 3494lib shared=yes device=/dev/lmcp1,/dev/lmcp2,/dev/lmcp3
```

3. ACSLS Library

Update an ACSLS library named `ACSLSLIB` with a new ID number.

```
update library acslslib ascid=1
```

4. External Library

Update an external library named `EXTLIB` with a new media manager path name.

```
update library extlib externalmanager=/v/server/mediamanager
```

Deleting Libraries

Task	Required Privilege Class
Delete libraries	System or unrestricted storage

Before deleting a library with the `DELETE LIBRARY` command, all of the drives that have been defined as part of the library must be deleted. See “Deleting Drives” on page 104.

For example, you want to delete a library named `MANUALMOUNT`. After deleting all of the drives defined as part of this library, issue the following command to delete the library itself:

```
delete library manualmount
```

Managing Drives

You can query, update, and delete drives.

Requesting Information about Drives

Task	Required Privilege Class
Request information about drives	Any administrator

You can request information about drives by using the `QUERY DRIVE` command. This command accepts wildcard characters for both a library name and a drive name. See *Administrator's Reference* for information about using wildcard characters.

For example, to query all drives associated with your server, enter the following command:
`query drive`

The following shows an example of the output from this command.

Library Name	Drive Name	Device Type	Device	On Line
MANLIB	8MM.0	8MM	/dev/mt1	Yes
AUTOLIB	8MM.2	8MM	/dev/mt2	Yes

Updating Drives

Task	Required Privilege Class
Update drives	System or unrestricted storage

You can change the attributes of a drive by issuing the `UPDATE DRIVE` command. The `UPDATE DRIVE` command allows you to change the following attributes:

- The device name, if you are reconfiguring your system
- The element address, if the drive resides in a SCSI library
- The ID of a drive in an ACSLS library
- The cleaning frequency

- Change whether the drive is online or offline

You cannot change the device name or element number if the drive is in use. See “Taking Drives Offline” on page 104.

If a drive has a volume mounted, but the volume is idle, it can be explicitly dismounted as described in “Dismounting an Idle Volume” on page 98. For example, suppose you have a drive DRIVE3 and you want to change the element address to 119. Enter the following command:

```
update drive auto drive3 element=119
```

Cleaning Drives

Task	Required Privilege Class
Clean drives	System or unrestricted storage

The server can control cleaning tape drives in SCSI libraries and offers partial support for cleaning tape drives in manual libraries. For automated library devices, you can automate cleaning by specifying the frequency of cleaning operations and checking a cleaner cartridge into the library’s volume inventory. TSM mounts the cleaner cartridge as specified. For manual library devices, TSM issues a mount request for the cleaner cartridge.

Deciding Whether the Server Controls Drive Cleaning

If your library device includes its own functions for drive cleaning, you need to decide which method to use: The device’s built-in drive cleaning or the TSM server’s drive cleaning. Device manufacturers that include automatic cleaning recommend its use to prevent premature wear on the read/write heads of the drives. For example, SCSI libraries such as STK 9710, IBM 3570, and IBM 3575 have their own automatic cleaning built into the device.

Drives and libraries from different manufacturers differ in how they handle cleaner cartridges and how they report the presence of a cleaner cartridge in a drive. Consult the manufacturer’s information that accompanies the library and the drives for an explanation of how the library and drive handle and report the presence of cleaner cartridges. The device driver may not be able to open a drive that contains a cleaner cartridge. Sense codes and error codes that are issued by devices for drive cleaning vary. If a library has its own automatic cleaning, the library usually tries to keep the process transparent to all applications. However, this is always the case. Because of this variability, the server may not always detect a cleaner cartridge in a drive for all hardware. The server also may not be able to determine if the library has started a cleaning process. Therefore, it is important to choose one method or the other, but not both.

Some devices require a small amount of idle time between mount requests to initiate the drive cleaning. However, the TSM server tries to minimize the idle time for a drive. These two conditions may combine to prevent the device’s control of drive cleaning to function effectively. If this happens, try using the TSM server to control drive cleaning. Set the frequency to match the cleaning recommendations from the manufacturer.

If you decide to have the TSM server control drive cleaning, disable the device’s own drive cleaning function to prevent problems. For example, while the device’s own drive cleaning function is enabled, some devices automatically move any cleaner cartridge found in the

library to slots in the library that are dedicated for cleaner cartridges. An application does not know these dedicated slots exist. You will not be able to check a cleaner cartridge into TSM's library inventory until you disable the device's own drive cleaning function.

If you decide to have the device control drive cleaning and then you have problems, consider using the drive cleaning control provided by the TSM server.

Cleaning Drives in an Automated Library

Set up server-controlled drive cleaning in an automated library with these steps:

1. Define or update the drives in a library, using the CLEANFREQUENCY parameter. The CLEANFREQUENCY parameter sets how often you want the drive cleaned. Refer to the DEFINE DRIVE and UPDATE DRIVE commands. Consult the manuals that accompany the drives for recommendations on cleaning frequency.

For example, to have DRIVE1 cleaned after 100GB is processed on the drive, issue the following command:

```
update drive autolib1 drive1 cleanfrequency=100
```

Consult the drive manufacturer's information for cleaning recommendations. If the information gives recommendations for cleaning frequency in terms of hours of use, convert to a gigabytes value by doing the following:

- a. Use the bytes-per-second rating for the drive to determine a gigabytes-per-hour value.
 - b. Multiply the gigabytes-per-hour value by the recommended hours of use between cleanings.
 - c. Use the result as the cleaning frequency value.
2. Check a cleaner cartridge into the library's volume inventory with the CHECKIN LIBVOLUME command. For example:

```
checkin libvolume autolib1 cleanv status=cleaner cleanings=10 checklabel=no
```

After the cleaner cartridge is checked in, the server will mount the cleaner cartridge in a drive when the drive needs cleaning. The server will use that cleaner cartridge for the number of cleanings specified. See "Checking In Cleaner Volumes" and "Operations with Cleaner Cartridges in a Library" on page 103 for more information.

For details on the commands, see *Administrator's Reference*.

Checking In Cleaner Volumes

You must check a cleaner cartridge into an automated library's volume inventory to have the server control drive cleaning without further operator intervention.

It is recommended that you check in cleaner cartridges one at a time and do not use the search function of check-in for a cleaner cartridge.

Attention: When checking in a cleaner cartridge to a library, ensure that it is correctly identified to the server as a cleaner cartridge. Also use caution when a cleaner cartridge is already checked in and you are checking in data cartridges. Ensure that cleaner cartridges are in their correct home slots, or errors and delays can result.

When checking in data cartridges with SEARCH=YES, ensure that a cleaner cartridge is not in a slot that will be detected by the search process. Errors and delays of 15 minutes or

more can result from a cleaner cartridge being improperly moved or placed. For best results, check in the data cartridges first when you use the search function. Then check in the cleaner cartridge separately.

For example, if you need to check in both data cartridges and cleaner cartridges, put the data cartridges in the library and check them in first. You can use the search function of the CHECKIN LIBVOLUME command (or the LABEL LIBVOLUME command if you are labeling and checking in volumes). Then check in the cleaner cartridge to the library by using one of the following methods.

- Check in without using search:

```
checkin libvolume autolib1 cleanv status=cleaner cleanings=10
checklabel=no
```

The server then requests that the cartridge be placed in the entry/exit port, or into a specific slot.

- Check in using search, but limit the search by using the VOLRANGE or VOLLIST parameter:

```
checkin libvolume autolib1 status=cleaner cleanings=10 search=yes checklabel=barcode
volland=cleanv
```

The process scans the library by using the barcode reader, looking for the CLEANV volume.

Manual Drive Cleaning in an Automated Library

If your library has limited capacity and you do not want to use a slot in your library for a cleaner cartridge, you can still make use of the server's drive cleaning function. Set the cleaning frequency for the drives in the library. When a drive needs cleaning based on the frequency setting, the server issues the message, ANR8914I. For example:

```
ANR89141I Drive DRIVE1 in library AUTOLIB1 needs to be cleaned.
```

You can use that message as a cue to manually insert a cleaner cartridge into the drive. However, the server cannot track whether the drive has been cleaned.

Operations with Cleaner Cartridges in a Library

When a drive needs to be cleaned, the server runs the cleaning operation after dismounting a data volume if a cleaner cartridge is checked in to the library. If the cleaning operation fails or is cancelled, or if no cleaner cartridge is available, then the indication that the drive needs cleaning is lost. Monitor cleaning messages for these problems to ensure that drives are cleaned as needed. If necessary, use the CLEAN DRIVE command to have the server try the cleaning again, or manually load a cleaner cartridge into the drive.

The server uses a cleaner cartridge for the number of cleanings that you specify when you check in the cleaner cartridge. If you check in more than one cleaner cartridge, the server uses one of them for its designated number of cleanings. Then the server begins to use the next cleaner cartridge.

Visually verify that cleaner cartridges are in the correct storage slots before issuing any of the following commands:

- AUDIT LIBRARY

- CHECKIN LIBVOLUME with SEARCH specified
- LABEL LIBVOLUME with SEARCH specified

To find the correct slot for a cleaner cartridge, use the QUERY LIBVOLUME command.

Cleaning Drives in a Manual Library

Cleaning a drive in a manual library is the same as setting up drive cleaning without checking in a cleaner cartridge for an automated library. The server issues the ANR8914I message when a drive needs cleaning. For example:

```
ANR89141I Drive DRIVE1 in library MANLIB1 needs to be cleaned.
```

Monitor the activity log or the server console for these messages and load a cleaner cartridge into the drive as needed. The server cannot track whether the drive has been cleaned.

Taking Drives Offline

You can take a drive offline while it is in use. For example, you might take a drive offline for another activity, such as maintenance. If you take a drive offline while it is in use, the mounted volume completes its current process. If this volume was part of a series of volumes in a transaction, the drive is no longer available to complete mounting the series. If no other drives are available, the active process may fail. The offline state is retained even if the server is halted and brought up again. If a drive is marked offline when the server is brought up, a warning is issued noting that the drive must be manually brought online. If all the drives in a library are taken offline, processes requiring a library mount point will fail, rather than queue up for one.

The ONLINE parameter specifies the value of the drive's online state, even if the drive is in use. ONLINE=YES indicates that the drive is available for use. ONLINE=NO indicates that the drive is not available for use (offline). Do not specify other optional parameters along with the ONLINE parameter. If you do, the drive will not be updated, and the command will fail when the drive is in use. You can specify the ONLINE parameter when the drive is involved in an active process or session, but this is not recommended.

Deleting Drives

Task	Required Privilege Class
Delete drives	System or unrestricted storage

A drive cannot be deleted if it is currently in use. If a drive has a volume mounted, but the volume is currently idle, it can be dismounted as described in "Dismounting an Idle Volume" on page 98.

Note: A library cannot be deleted until all of the drives defined within it are deleted.

8

Defining Device Classes

Tivoli Storage Manager uses device class definitions to determine which types of devices and volumes to use to:

- Store backup, archive, or space-managed data in primary storage pools
- Store copies of primary storage pool data in copy storage pools
- Store database backups
- Export or import TSM data

One device class can be associated with multiple storage pools, but each storage pool is associated with only one device class.

For random access storage, TSM supports only the DISK device class, which is defined by TSM. However, you can define many storage pools associated with the DISK device class.

See the following sections:

Tasks:
“Defining and Updating Device Classes for Tape Devices” on page 107
“Defining and Updating Device Classes for Generic Tape Devices” on page 109
“Defining and Updating Device Classes for Optical Devices” on page 110
“Defining and Updating Device Classes for REMOVABLEFILE Devices” on page 111
“Defining and Updating FILE Device Classes” on page 111
“Defining and Updating SERVER Device Classes” on page 112
“Requesting Information about a Device Class” on page 114
“Deleting a Device Class” on page 115

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Defining and Updating Device Classes for Sequential Media

Task	Required Privilege Class
Define or update device classes	System or unrestricted storage

For sequential access storage, TSM supports the following device types:

Device Type	Media Type	Device Examples
3570	IBM 3570 cartridges	IBM 3570 drives
3590	IBM 3590 cartridges	IBM 3590, 3590E drives
4MM	4mm cartridges	IBM 7206-005
8MM	8mm cartridges	IBM 7208-001 and 7208-011
CARTRIDGE	Tape cartridges	IBM 3480, 3490, and 3490E drives
DLT	Digital linear tape (DLT) cartridges	DLT2000, DLT4000, DLT7000 and DLT8000 drives
DTF	Digital tape format (DTF) cartridges	Sony GY-2120, Sony DMS-8400 drives
ECARTRIDGE	Tape cartridges	StorageTek SD-3 and 9490 drives
FILE	File system or storage volumes	Server
GENERICTAPE	Tape cartridges	Tape drives supported by operating system device drivers
LTO	LTO Ultrium cartridges	IBM 3580, 3581, 3583, 3584
OPTICAL	5.25-inch rewritable optical cartridges	5.25-inch optical drives
QIC	Quarter-inch tape cartridges	IBM 7207
REMOVABLEFILE	Iomega Zip or Jaz drives, or CDROM media	Removable media devices that are attached as local, removable file systems
SERVER	Storage volumes or files archived in another TSM server	TSM target server
WORM	5.25-inch write-once read-many (WORM) optical cartridges	5.25-inch optical drives
WORM12	12-inch write-once ready-many optical cartridges	12-inch optical drives
WORM14	14-inch write-once ready-many optical cartridges	14-inch optical drives

You can define multiple device classes for each device type. For example, you may need to specify different attributes for different storage pools that use the same type of tape drive. Variations may be required that are not specific to the device, but rather to how you want to use the device (for example, mount retention or mount limit).

For all device types other than FILE or SERVER, you must define libraries and drives to TSM before you define the device classes.

If you include the DEVCONFIG option in the dsmserv.opt file, the files you specify with that option are automatically updated with the results of this command. When you use this option, the files specified are automatically updated whenever a device class, library, or drive is defined, updated, or deleted.

The following sections explain the device classes for each supported device type.

Defining and Updating Device Classes for Tape Devices

To use tape devices, you must define a device class by issuing a `DEFINE DEVCLASS` command with the `DEVTYPE` parameter.

Note: For upgrades from TSM Enhanced Version 2 to Version 3 or later, you must define a device class with the `DEVTYPE` parameter set to `DLT` or `ECART`.

Other parameters specify how to manage data storage operations involving the new device class:

- `MOUNTLIMIT`
- `MOUNTWAIT`
- `MOUNTRETENTION`
- `PREFIX`
- `FORMAT`
- `ESTCAPACITY`
- `LIBRARY`

You can update the device class by issuing the `UPDATE DEVCLASS` command.

Mount Limit

The `MOUNTLIMIT` parameter specifies the maximum number of volumes that can be simultaneously mounted for a device class. You can limit the number of drives that the device class has access to at one time with the `MOUNTLIMIT` parameter.

The default mount limit value is `DRIVES`. The `DRIVES` parameter indicates that every time a mount point is allocated, the number of drives online and defined to the library is used to calculate the true mount limit value. The maximum value for this parameter is 256 and the minimum value is 0. A zero value prevents new transactions from gaining access to the storage pool.

When selecting a mount limit for a device class, be sure to consider the following questions:

- How many storage devices are connected to your system?

Do not specify a mount limit value that is greater than the number of associated available drives in your installation. If the server tries to mount as many volumes as specified by the mount limit and no drives are available for the required volume, an error occurs and client sessions may be terminated. (This does not apply when the `DRIVES` parameter is specified.)

Note: TSM cannot share drives between multiple device classes.

- How many TSM processes do you want to run at the same time, using devices in this device class?

TSM automatically cancels some processes to run other, higher priority processes. If the server is using all available drives in a device class to complete higher priority processes, lower priority processes must wait until a drive becomes available. For example, TSM cancels the process for a client backing up directly to tape if the drive being used is needed for a server migration or tape reclamation process. TSM cancels a tape reclamation process if the drive being used is needed for a client restore operation.

If processes are often canceled by other processes, consider whether you can make more drives available for TSM use. Otherwise, review your scheduling of operations to reduce the contention for drives.

Note: If the library associated with this device class is EXTERNAL type, it is recommended that you explicitly specify the mount limit instead of using MOUNTLIMIT=DRIVES.

Mount Wait Period

The MOUNTWAIT parameter specifies the maximum amount of time, in minutes, that the server waits for a drive to become available for the current mount request. The default mount wait period is 60 minutes. The maximum value for this parameter is 9999 minutes.

Note: This parameter is not valid for EXTERNAL or RSM library types.

Mount Retention Period

The MOUNTRETENTION parameter specifies the amount of time that a mounted volume should remain mounted after its last I/O activity. If this idle time limit is reached, the server dismounts the volume. The default mount retention period is 60 minutes. The maximum value for this parameter is 9999 minutes.

For example, if the mount retention value is 60, and a mounted volume remains idle for 60 minutes, then the server dismounts the volume.

If a volume is used frequently, you can improve performance by setting a longer mount retention period to avoid unnecessary mount and dismount operations.

If mount operations are being handled by manual, operator-assisted activities, you may want to use a large mount retention period. For example, if only one operator supports your entire operation on a weekend, then define a long mount retention period so that the operator is not being asked to mount volumes every few minutes.

While TSM has a volume mounted, the drive is allocated to TSM and cannot be used for anything else. If you need to free the drive for other uses, you can cancel TSM operations that are using the drive and then dismount the volume. For example, you can cancel server migration or backup operations. For information on how to cancel processes and dismount volumes, see “Canceling Server Processes” on page 367 and “Dismounting an Idle Volume” on page 98.

Tape Label Prefix

By using the PREFIX parameter, you can specify a prefix value that is used to construct the *file name* string that is stored in the label area of each tape volume.

Note: This parameter is used primarily in the OS/390 and z/OS platforms.

The prefix string is used as the prefix of the file name that is written to the label of each tape. The default value for the tape label prefix string is ADSM.

Recording Format

You can use the FORMAT parameter to specify the recording format used by TSM when writing data to removable media. See the *Administrator's Reference* for information about the recording formats for each device type.

Specify `FORMAT=DRIVE` parameter only if all drives associated with that device class are identical. If some drives associated with the device class support a higher density format than others and you specify `FORMAT=DRIVE`, mount errors can occur. For example, suppose a device class uses two incompatible devices such as an IBM 7208-2 and an IBM 7208-12. The server might select the high-density recording format of 8500 for each of two new volumes. Later, if the two volumes are to be mounted concurrently, one fails because only one of the drives is capable of the high-density recording format.

The recording format that TSM uses for a given volume is selected when the first piece of data is written to the volume. Updating the `FORMAT` parameter does not affect media that already contain data until those media are rewritten from the beginning. This process may happen after a volume is reclaimed or deleted, or after all of the data on the volume expires.

Estimated Capacity

TSM estimates the capacity of the volumes in a storage pool based on the parameters assigned to the device class associated with the storage pool. For tape device classes, the default values selected by the server depend on the recording format used to write data to the volume. You can either accept the default for a given device type or specify a value. See *Administrator's Reference* for information about the estimated capacities of recording formats for each device type.

TSM also uses estimated capacity to determine when to begin reclamation storage pool volumes. For more information on how TSM uses the estimated capacity value, see “How TSM Fills Volumes” on page 115.

Library

Before the server can mount a volume, it must know which drives can be used to satisfy the mount request. This process is done by specifying the library when the device class is defined. The library must contain drives that can be used to mount the volume.

Note that only one library can be associated with a given device class. However, multiple device classes can reference the same library. Unless you are using the `DRIVES` value for `MOUNTLIMIT`, you must ensure that the numeric value of the mount limits of all device classes do not exceed the number of drives defined in the referenced library.

There is no default value for this parameter. It is required, and so must be specified when the device class is defined.

Defining and Updating Device Classes for Generic Tape Devices

To use a tape device that is supported by an operating system device driver, you must define a device class whose device type is `GENERICTAPE`.

For a manual library with multiple drives of device type `GENERICTAPE`, ensure that the device types and recording formats of the drives are compatible. Because the devices are controlled by the operating system device driver, the TSM server is not aware of the following:

- The actual type of device: 4mm, 8mm, digital linear tape, and so forth. For example, if you have a 4mm device and an 8mm device, you must define separate manual libraries for each device.
- The actual cartridge recording format. For example, if you have a manual library defined with two device classes of `GENERICTAPE`, ensure the recording formats are the same for both drives.

You can update the device class information by issuing the UPDATE DEVCLASS command. Other parameters, in addition to device type, specify how to manage server storage operations:

Mount Limit

See “Mount Limit” on page 107.

Mount Wait Period

See “Mount Wait Period” on page 108.

Mount Retention Period

See “Mount Retention Period” on page 108.

Estimated Capacity

You can specify an estimated capacity value of any volumes defined to a storage pool categorized by a GENERICTAPE device class. The default ESTCAPACITY value for a volume in a GENERICTAPE device class is 1GB. Specify a capacity appropriate for your particular tape drive.

Library

See “Library” on page 109.

Defining and Updating Device Classes for Optical Devices

To use optical media, you must define a device class by issuing the DEFINE DEVCLASS command with a DEVTYPE parameter for one of the optical devices:

Parameter	Description
OPTICAL	5.25-inch rewritable optical media
WORM	5.25-inch write-once optical media
WORM12	12-inch write-once optical media.
WORM14	14-inch write once optical media.

Other parameters specify how to manage data storage operations involving the new device class:

Mount Limit

See “Mount Limit” on page 107.

Mount Wait Period

See “Mount Wait Period” on page 108.

Mount Retention

See “Mount Retention Period” on page 108.

Recording Format

See “Recording Format” on page 108.

Estimated Capacity

See “Estimated Capacity” on page 109.

Library

See “Library” on page 109.

You can update the device class information by issuing the UPDATE DEVCLASS command.

Defining and Updating Device Classes for REMOVABLEFILE Devices

Removable file devices include devices such as Iomega Zip drives or Jaz drives and CD-ROM drives. Define a device class for these devices by issuing the DEFINE DEVCLASS command with the DEVTYPE=REMOVABLEFILE parameter. See “Configuring Removable File Devices” on page 61 for more information.

Other parameters specify how to manage storage operations involving the new device class:

Mount Wait

See “Mount Wait Period” on page 108.

Mount Retention

See “Mount Retention Period” on page 108.

Library

See “Library” on page 109.

You can update the device class information by issuing the UPDATE DEVCLASS command.

Defining and Updating FILE Device Classes

The FILE device type is used for storing data on disk in *simulated* storage volumes. The storage volumes are actually files. Data is written sequentially into standard files in the file system of the server machine. You can define this device class by issuing a DEFINE DEVCLASS command with the DEVTYPE=FILE parameter. Because each volume in a FILE device class is actually a file, a volume name must be a fully qualified file name.

Note: Do not use raw partitions with a device class type of FILE.

When you define or update the FILE device class, you can specify the parameters described in the following sections.

Mount Limit

The mount limit value for FILE device classes is used to restrict the number of mount points (volumes or files) that can be concurrently opened for access by server storage and retrieval operations. Any attempts to access more volumes than indicated by the mount limit causes the requester to wait. The default value is 1. The maximum value for this parameter is 256.

Note: The MOUNTLIMIT=DRIVES parameter is not valid for the FILE device class.

When selecting a mount limit for this device class, consider how many TSM processes you want to run at the same time.

TSM automatically cancels some processes to run other, higher priority processes. If the server is using all available mount points in a device class to complete higher priority processes, lower priority processes must wait until a mount point becomes available. For example, TSM cancels the process for a client backup if the mount point being used is needed for a server migration or reclamation process. TSM cancels a reclamation process if the mount point being used is needed for a client restore operation.

If processes are often cancelled by other processes, consider whether you can make more mount points available for TSM use. Otherwise, review your scheduling of operations to reduce the contention for resources.

Maximum Capacity Value

You can specify a maximum capacity value that restricts the size of volumes (that is, files) associated with a FILE device class. Use the MAXCAPACITY parameter of the DEFINE DEVCLASS command. When the server detects that a volume has reached a size equal to the maximum capacity, it treats the volume as full and stores any new data on a different volume.

The default MAXCAPACITY value for a FILE device class is 4MB.

Directory

You can specify the directory location of the files used in the FILE device class. The default is the current working directory of the server at the time the command is issued, unless the DSMSEV_DIR environment variable is set. For more information on setting the environment variable, refer to *Quick Start*.

The directory name identifies the location where the server places the files that represent storage volumes for this device class. While processing the command, the server expands the specified directory name into its fully qualified form, starting from the root directory.

Later, if the server needs to allocate a scratch volume, it creates a new file in this directory. The following lists the file name extension created by the server for scratch volumes depending on the type of data that is stored.

For scratch volumes used to store this data:	The file extension is:
Client data	.BFS
Export	.EXP
Database backup	.DBB
Database dump and unload	.DMP

Defining and Updating SERVER Device Classes

The SERVER device type is used for special device classes whose storage volumes are not directly attached to this server. A volume with device type SERVER consists of one or more files archived in the server storage of another server, called a target server. You can define this device class by issuing a DEFINE DEVCLASS command with the DEVTYPE=SERVER parameter. For information about how to use a SERVER device class, see “Using Virtual Volumes to Store Data on Another Server” on page 348.

The following parameters specify how to manage data storage operations for the new device class:

- SERVERNAME
- MOUNTLIMIT
- MAXCAPACITY
- MOUNTRETENTION
- PREFIX
- RETRYPERIOD
- RETRYINTERVAL

You can update the device class information by issuing the UPDATE DEVCLASS command.

Server Name

The TSM server on which you define a SERVER device class is called a source server. The source server uses the SERVER device class to store data on another TSM server, called a target server.

When defining a SERVER device class, specify the name of the target server. The target server must already be defined by using the DEFINE SERVER command. See “Using Virtual Volumes to Store Data on Another Server” on page 348 for more information.

Mount Limit

Use the mount limit value for SERVER device classes to restrict the number of simultaneous sessions between the source server and the target server. Any attempts to access more sessions than indicated by the mount limit causes the requester to wait. The default mount limit value is 1. The maximum value for this parameter is 256.

Note: The MOUNTLIMIT=DRIVES parameter is not valid for the SERVER device class.

When selecting a mount limit, consider your network load balancing and how many TSM processes you want to run at the same time.

TSM automatically cancels some processes to run other, higher priority processes. If the server is using all available sessions in a device class to complete higher priority processes, lower priority processes must wait until a session becomes available. For example, TSM cancels the process for a client backup if a session is needed for a server migration or reclamation process. TSM cancels a reclamation process if the session being used is needed for a client restore operation.

Also consider the resources available on the target server when setting mount limits. Do not set a high mount limit value if the target cannot move enough data or access enough data to satisfy all of the requests.

If processes are often cancelled by other processes, consider whether you can make more sessions available for TSM use. Otherwise, review your scheduling of operations to reduce the contention for network resources.

Maximum Capacity Value

You can specify a maximum capacity value that restricts the size of files that are created on the target server to store data for the source server. The default MAXCAPACITY value is 500MB. The storage pool volumes of this device type are explicitly set to full when the volume is closed and dismounted.

Mount Retention

You can specify the amount of time, in minutes, to retain an idle sequential access volume before dismounting it. The default value is 60. The maximum value you can specify for this parameter is 9999. A value of 1 to 5 minutes is recommended. This parameter can improve response time for sequential access media mounts by leaving previously mounted volumes online.

Prefix

You can specify a prefix that the source server will use as the beginning portion of the high-level archive file name on the target server.

Retry Period

You can specify a retry period for communications with the target server. When there is a communications failure, this period determines the amount of time during which the source server continues to attempt to connect to the target server.

Retry Interval

You can specify how often the source server tries to connect to the target server when there is a communications failure. During the retry period, the source server tries to connect again as often as indicated by the retry interval.

Requesting Information about a Device Class

You can choose to view a standard or the default detailed report for a device class.

Task	Required Privilege Class
Request information about device classes	Any administrator

To display a standard report on device classes, enter:

```
query devclass
```

Figure 15 is an example of a standard report for device classes.

Device Class Name	Device Access Strategy	Storage Pool Count	Device Type	Format	Est/Max Capacity (MB)	Mount Limit
DISK	Random	9				
TAPE8MM	Sequential	1	8MM	8200	2,472.0	2

Figure 15. Example of a Standard Device Class Report

To display a detailed report on the TAPE8MM device class, enter:

```
query devclass tape8mm format=detailed
```

Figure 16 on page 115 shows an example of a detailed report for a device class.


```

Device Class Name: TAPE8MM
Device Access Strategy: Sequential
Storage Pool Count: 1
Device Type: 8MM
Format: 8200
Est/Max Capacity (MB): 2,472.0
Mount Limit: 2
Mount Wait (min): 10
Mount Retention (min): 30
Label Prefix: ADSM
Library: TAPELIB
Directory:
Last Update by (administrator): TSMADMIN
Last Update Date/Time: 01/05/2001 16:02:13

```

Figure 16. Example of a Detailed Device Class Report

Deleting a Device Class

Task	Required Privilege Class
Delete a device classes	System or unrestricted storage

You can delete a device class with the DELETE DEVCLASS command when:

- No storage pools are assigned to the device class. For information on deleting storage pools, see “Deleting a Storage Pool” on page 183.
- The device class is not being used by an export or import process.

Note: You cannot delete the DISK device class from the server.

How TSM Fills Volumes

The DEFINE DEVCLASS command has an optional ESTCAPACITY parameter that indicates the estimated capacity for sequential volumes associated with the device class. If the ESTCAPACITY parameter is not specified, TSM uses a default value based on the DEVTYPE parameter of the device class.

If you specify an estimated capacity that exceeds the actual capacity of the volume in the device class, TSM updates the estimated capacity of the volume when the volume becomes full. When TSM reaches the end of the volume, it updates the capacity for the amount that is written to the volume.

You can either accept the default estimated capacity for a given device class, or explicitly specify an estimated capacity. An accurate estimated capacity value is not required, but is useful. TSM uses the estimated capacity of volumes to determine the estimated capacity of a storage pool, and the estimated percent utilized. You may want to change the estimated capacity if:

- The default estimated capacity is inaccurate because data compression is being performed by the drives

-
- You have volumes of nonstandard size

Using Data Compression

Client files can be compressed to decrease the amount of data sent over networks and the space occupied by the data in TSM storage. With TSM, files can be compressed by the TSM client before the data is sent to the TSM server, or by the device where the file is finally stored.

Use either client compression or device compression, but not both. The following table summarizes the advantages and disadvantages of each type of compression.

Type of Compression	Advantages	Disadvantages
TSM client compression	Reduced load on the network	Higher CPU usage by the client Longer elapsed time for client operations such as backup
Drive compression	Amount of compression can be better than TSM client compression on some drives	Files that have already been compressed by the TSM client can become larger

Either type of compression can affect tape drive performance, because compression affects data rate. When the rate of data going to a tape drive is slower than the drive can write, the drive starts and stops while data is written, meaning relatively poorer performance. When the rate of data is fast enough, the tape drive can reach streaming mode, meaning better performance. If tape drive performance is more important than the space savings that compression can mean, you may want to perform timed test backups using different approaches to determine what is best for your system.

Drive compression is specified with the `FORMAT` parameter for the drive's device class, and the hardware device must be able to support the compression format. For information about how to set up compression on the client, see "Node Compression Considerations" on page 191 and "Registering Nodes with the Server" on page 190.

Tape Volume Capacity and Data Compression

How TSM views the capacity of the volume where the data is stored depends on whether files are compressed by the TSM client or by the storage device. It may wrongly appear that you are not getting the full use of the capacity of your tapes, for the following reasons:

- A tape device manufacturer often reports the capacity of a tape based on an assumption of compression by the device. If a client compresses a file before it is sent, the device may not be able to compress it any further before storing it.
- TSM records the size of a file as it goes to a storage pool. If the client compresses the file, TSM records this smaller size in the database. If the drive compresses the file, TSM is not aware of this compression.

Figure 17 on page 117 compares what TSM sees as the amount of data stored on tape when compression is done by the device and by the client. For this example, the tape has a physical capacity of 1.2GB; however, the manufacturer reports the capacity of the tape as 2.4GB by assuming the device compresses the data by a factor of two.

Suppose a client backs up a 2.4GB file:

- When the client does *not* compress the file, the server records the file size as 2.4GB, the file is compressed by the drive to 1.2GB, and the file fills up one tape.
- When the client compresses the file, the server records the file size as 1.2GB, the file cannot be compressed any further by the drive, and the file still fills one tape.

In both cases, TSM considers the volume to be full. However, TSM considers the capacity of the volume in the two cases to be different: 2.4GB when the drive compresses the file, and 1.2GB when the client compresses the file. Use the `QUERY VOLUME` command to see the capacity of volumes from TSM's viewpoint. See "Monitoring the Use of Storage Pool Volumes" on page 162.




Figure 17. Comparing Compression at the Client and Compression at the Device

For how to set up compression on the client, see "Node Compression Considerations" on page 191 and "Registering Nodes with the Server" on page 190.

9

Managing Storage Pools and Volumes

When you configure devices so that the Tivoli Storage Manager server can use them to store client data, you create storage pools and storage volumes. This section gives you overviews and details on storage pools and storage volumes.

The procedures in “Using Magnetic Disk Devices” on page 43 and “Configuring Storage Devices” on page 57 show you how to set up and use devices to provide TSM with server storage. The procedures use the set of defaults that TSM provides for storage pools and volumes. The defaults can work well, but you may have specific requirements not met by the defaults. Three common reasons to change the defaults are the following:

- Optimize and control storage device usage — Arrange the storage hierarchy and tune migration through the hierarchy (next storage pool, migration thresholds)
- Reuse tape volumes (reclamation) (Reuse is also related to policy and expiration.)
- Keep a client’s files on a minimum number of volumes (collocation)

You can also make other adjustments to tune the server for your systems. See the following sections to learn more. For some quick tips, see Table 10 on page 126.

Concepts:
“Overview: Storage Pools” on page 120
“Overview: Volumes in Storage Pools” on page 127
“Access Modes for Storage Pool Volumes” on page 131
“Overview: The Storage Pool Hierarchy” on page 133
“Migration of Files in a Storage Pool Hierarchy” on page 138
“Using Cache on Disk Storage Pools” on page 146
“Keeping a Client’s Files Together: Collocation” on page 147
“Reclaiming Space in Sequential Access Storage Pools” on page 152
“Estimating Space Needs for Storage Pools” on page 159

Tasks:
“Defining or Updating Primary Storage Pools” on page 123
“Preparing Volumes for Random Access Storage Pools” on page 128
“Preparing Volumes for Sequential Access Storage Pools” on page 129
“Defining Storage Pool Volumes” on page 130
“Updating Storage Pool Volumes” on page 130
“Setting Up a Storage Pool Hierarchy” on page 133
“Monitoring Storage Pools and Volumes” on page 161

Tasks:
“Monitoring the Use of Storage Pool Volumes” on page 162
“Moving Files from One Volume to Another Volume” on page 176
“Deleting a Storage Pool” on page 183
“Deleting Storage Pool Volumes” on page 184

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Overview: Storage Pools

A storage volume is the basic unit of storage, such as allocated space on a disk or a single tape cartridge. A storage pool is a collection of storage volumes. The server uses the storage volumes to store backed-up, archived, or space-managed files. The group of storage pools that you set up for the TSM server to use is called *server storage*. Storage pools can be arranged in a storage hierarchy.

The server has two types of storage pools that serve different purposes: primary storage pools and copy storage pools.

Primary Storage Pool

When a client node backs up, archives, or migrates data, the data is stored in a primary storage pool. The specific storage pool is identified as the destination in the management class associated with the data.

When a user tries to restore, retrieve, recall, or export file data, the requested file is obtained from a primary storage pool if possible. Primary storage pool volumes are always located onsite.

A primary storage pool can use random access storage (DISK device class) or sequential access storage (for example, tape or FILE device classes).

The server has three default, random access, primary storage pools:

ARCHIVEPOOL

In default STANDARD policy, the destination for files that are archived from client nodes

BACKUPPOOL

In default STANDARD policy, the destination for files that are backed up from client nodes

SPACEMGPOOL

For space-managed files that are migrated from Tivoli Space Manager client nodes (HSM clients)

The server does not require separate storage pools for archived, backed-up, or space-managed files. However, you may want to have a separate storage pool for

space-managed files. Clients are likely to require fast access to their space-managed files. Therefore, you may want to have those files stored in a separate storage pool that uses your fastest disk storage.

Copy Storage Pool

When an administrator backs up a primary storage pool, the data is stored in a copy storage pool. See “Backing Up Storage Pools” on page 465 for details.

A copy storage pool can use only sequential access storage (for example, a tape device class or FILE device class).

The copy storage pool provides a means of recovering from disasters or media failures. For example, when a client attempts to retrieve a file and the server detects an error in the file copy in the primary storage pool, the server marks the file as damaged. At the next attempt to access the file, the server obtains the file from a copy storage pool. For details, see “Restoring Storage Pools” on page 483, “Using Copy Storage Pools to Improve Data Availability” on page 468, “Recovering a Lost or Damaged Storage Pool Volume” on page 495, and “Maintaining the Integrity of Files” on page 491.

You can move copy storage pool volumes offsite and still have the server track the volumes. Moving copy storage pool volumes offsite provides a means of recovering from an onsite disaster.

An Example of Server Storage

Figure 18 on page 122 shows one way to set up server storage. In this example, the storage defined for the server includes:

- Three disk storage pools, which are primary storage pools: ARCHIVE, BACKUP, and HSM
- One primary storage pool that consists of tape cartridges
- One copy storage pool that consists of tape cartridges

Policies defined in management classes direct the server to store files from clients in the ARCHIVE, BACKUP, or HSM disk storage pools. For each of the three disk storage pools, the tape primary storage pool is next in the hierarchy. As the disk storage pools fill, the server migrates files to tape to make room for new files. Large files may go directly to tape. For more information about setting up a storage hierarchy, see “Overview: The Storage Pool Hierarchy” on page 133.

You can back up all four of the primary storage pools to the one copy storage pool. For more information on backing up primary storage pools, see “Backing Up Storage Pools” on page 465.




Figure 18. Example of Server Storage

To set up this server storage hierarchy, do the following:

1. Define the three disk storage pools, or use the three default storage pools that are defined when you install the server. Add volumes to the disk storage pools if you have not already done so.

See “Configuring Random Access Volumes on Disk Devices” on page 44.

2. Define policies that direct the server to initially store files from clients in the disk storage pools. To do this, you define or change management classes and copy groups so that they point to the storage pools as destinations. Then activate the changed policy. See “Overview: Changing Policy” on page 237 for details.

3. Attach one or more tape devices, or a tape library, to your server system.

To enable the server to use the device, you must enter a series of the following commands:

```
DEFINE LIBRARY
DEFINE DRIVE
DEFINE DEVCLASS
DEFINE STGPOOL
```

See “Configuring Storage Devices” on page 57 for more information. For detailed information on defining a storage pool, see “Defining or Updating Primary Storage Pools” on page 123.

4. Update the disk storage pools so that they point to the tape storage pool as the next storage pool in the hierarchy. See “Example: Updating Storage Pools” on page 126.
5. Define a copy storage pool. This storage pool can use the same tape device or a different tape device as the primary tape storage pool. See “Defining a Copy Storage Pool” on page 180
6. Set up administrative schedules or a script to back up the disk storage pools and the tape storage pool to the copy storage pool. Send the volumes offsite for safekeeping. See “Backing Up Storage Pools” on page 465.

Defining or Updating Primary Storage Pools

This section provides a summary of parameters you can set and change for storage pools using the administrative command-line or the administrative Web interface. The section also provides examples of defining and updating storage pools.

Task	Required Privilege Class
Define storage pools	System
Update storage pools	System or unrestricted storage

When you define a primary storage pool, be prepared to provide some or all of the information that is shown in Table 9. Most of the information is optional. Some information applies only to random access storage pools or only to sequential access storage pools. Required parameters are marked.

Table 9. Information for Defining a Storage Pool

Information	Explanation	Type of Storage Pool
Storage pool name <i>(Required)</i>	The name of the storage pool.	random, sequential
Device class <i>(Required)</i>	The name of the device class assigned for the storage pool.	random, sequential
Pool type	The type of storage pool (primary or copy). The default is to define a primary storage pool. Once you define a storage pool, you cannot change whether it is a primary or a copy storage pool.	random, sequential
Maximum number of scratch volumes <i>(Required for sequential access)</i>	When you specify a value greater than zero, the server dynamically acquires scratch volumes when needed, up to this maximum number. For automated libraries, set this value equal to the physical capacity of the library. See “Maintaining a Supply of Scratch Volumes in an Automated Library” on page 96.	sequential
Access mode	Defines access to volumes in the storage pool for user operations (such as backup and restore) and system operations (such as reclamation and server migration). Possible values are: Read/Write User and system operations can read from or write to the volumes. Read-Only User operations can read from the volumes, but not write. Server processes can move files within the volumes in the storage pool. However, no new writes are permitted to volumes in the storage pool from volumes outside the storage pool. Unavailable User operations cannot get access to volumes in the storage pool. No new writes are permitted to volumes in the storage pool from other volumes outside the storage pool. However, system processes (like reclamation) are permitted to move files within the volumes in the storage pool.	random, sequential

Table 9. Information for Defining a Storage Pool (continued)

Information	Explanation	Type of Storage Pool
Maximum file size	To exclude large files from a storage pool, set a maximum file size. The maximum file size applies to the size of a physical file (a single client file or an aggregate of client files). Do not set a maximum file size for the last storage pool in the hierarchy unless you want to exclude very large files from being stored in server storage.	random, sequential
Name of the next storage pool	Specifies the name of the next storage pool in the storage pool hierarchy, where files can be migrated or stored. See “Overview: The Storage Pool Hierarchy” on page 133.	random, sequential
Migration thresholds	Specifies a percentage of storage pool occupancy at which the server begins migrating files to the next storage pool (high threshold) and the percentage when migration stops (low threshold). See “Migration of Files in a Storage Pool Hierarchy” on page 138.	random, sequential
Migration processes	Specifies the number of processes that are used for migrating files from this storage pool. See “Migration for Disk Storage Pools” on page 139.	random
Migration delay	Specifies whether migration of files should be delayed for a minimum number of days. See “Keeping Files in a Storage Pool” on page 142 and “How Tivoli Storage Manager Migrates Data from Sequential Access Storage Pools” on page 144.	random, sequential
Continue migration process	Specifies whether migration of files should continue even if files do not meet the requirement for migration delay. This setting is used only when the storage pool cannot go below the low migration threshold without moving additional files. See “Keeping Files in a Storage Pool” on page 142 and “How Tivoli Storage Manager Migrates Data from Sequential Access Storage Pools” on page 144.	random, sequential
Cache	Enables or disables cache. When cache is enabled, copies of files migrated by the server to the next storage pool are left on disk after the migration. In this way, a retrieval request can be satisfied quickly. See “Using Cache on Disk Storage Pools” on page 146.	random
Collocation	With collocation enabled, the server attempts to keep all files belonging to a client node or a client file space on a minimal number of sequential access storage volumes. See “Keeping a Client’s Files Together: Collocation” on page 147.	sequential
Reclamation threshold	Specifies what percentage of reclaimable space can accumulate on a volume before the server initiates a space reclamation process for the volume. See “Choosing a Reclamation Threshold” on page 154.	sequential
Reclamation storage pool	Specifies the name of the storage pool to be used for storing data from volumes being reclaimed in this storage pool. Use for storage pools whose device class only has one drive or mount point. See “Reclaiming Volumes in a Storage Pool with One Drive” on page 155.	sequential
Reuse delay period	Specifies the number of days that must elapse after all of the files have been deleted from a volume, before the volume can be rewritten or returned to the scratch pool. See “Delaying Reuse of Sequential Access Volumes” on page 467.	sequential

Table 9. Information for Defining a Storage Pool (continued)

Information	Explanation	Type of Storage Pool
Overflow location	Specifies the name of a location where volumes are stored when they are ejected from an automated library by the MOVE MEDIA command. Use for a storage pool that is associated with an automated library or an external library. See “Managing a Full Library” on page 94.	sequential

Example: Defining Storage Pools

For this example, suppose you have determined that an engineering department requires a separate storage hierarchy. You want the department’s backed-up files to go to a disk storage pool. When that pool fills, you want the files to migrate to a tape storage pool. You want the pools to have the following characteristics:

- Disk primary storage pool
 - The pool named ENGBACK1 is the storage pool for the engineering department.
 - The size of the largest file that can be stored is 5MB. Files larger than 5MB are stored in the tape storage pool.
 - Files migrate from the disk storage pool to the tape storage pool when the disk storage pool is 85% full. File migration to the tape storage pool stops when the disk storage pool is down to 40% full.
 - The access mode is the default, read/write.
 - Cache is used.
- Tape primary storage pool
 - The name of the pool is BACKTAPE.
 - The pool uses the device class TAPE, which has already been defined.
 - No limit is set for the maximum file size, because this is the last storage pool in the hierarchy.
 - To group files from the same client on a small number of volumes, use collocation at the client node level.
 - Use scratch volumes for this pool, with a maximum number of 100 volumes.
 - The access mode is the default, read/write.
 - Use the default for reclamation: Reclaim a partially full volume (to allow tape reuse) when 60% of the volume’s space can be reclaimed.

You can define the storage pools in a storage pool hierarchy from the top down or from the bottom up. Defining the hierarchy from the bottom up requires fewer steps. To define the hierarchy from the bottom up, perform the following steps:

1. Define the storage pool named BACKTAPE with the following command:


```
define stgpool backtape tape
description='tape storage pool for engineering backups'
maxsize=nolimit collocate=yes maxscratch=100
```
2. Define the storage pool named ENGBACK1 with the following command:

```
define stgpool engback1 disk
description='disk storage pool for engineering backups'
maxsize=5m nextstgpool=backtape highmig=85 lowmig=40
```

Restrictions:

1. You cannot establish a chain of storage pools that leads to an endless loop. For example, you cannot define StorageB as the *next* storage pool for StorageA, and then define StorageA as the *next* storage pool for StorageB.
2. The storage pool hierarchy includes only primary storage pools, not copy storage pools.

Example: Updating Storage Pools

You can update storage pools to change the storage hierarchy and other characteristics.

For example, suppose you had already defined the ENGBACK1 disk storage pool according to the previous example. Now you have decided to increase the maximum size of a physical file that may be stored in the storage pool. Use the following command:

```
update stgpool engback1 maxsize=100m
```

Task Tips for Storage Pools

Table 10 gives tips on how to accomplish some tasks that are related to storage pools.

Table 10. Task Tips for Storage Pools

For this Goal	Do This	For More Information
Keep the data for a client on as few volumes as possible	Enable collocation for the storage pool	“Keeping a Client’s Files Together: Collocation” on page 147
Reduce the number of volume mounts needed to back up multiple clients	Disable collocation for the storage pool	“Keeping a Client’s Files Together: Collocation” on page 147
Specify how the server reuses tapes	Set a reclamation threshold for the storage pool Optional: Identify a reclamation storage pool	“Reclaiming Space in Sequential Access Storage Pools” on page 152
Move data from disk to tape automatically when needed	Set a migration threshold for the storage pool Identify the next storage pool	“Migration for Disk Storage Pools” on page 139
Move data from disk to tape automatically based on how frequently users access the data or how long the data has been in the storage pool	Set a migration threshold for the storage pool Identify the next storage pool Set the migration delay period	“Migration for Disk Storage Pools” on page 139
Back up your storage pools	Define a copy storage pool Set up a backup schedule	“Defining a Copy Storage Pool” on page 180 “Automating a Basic Administrative Command Schedule” on page 371
Have clients back up directly to a tape storage pool	Define a sequential access storage pool that uses a tape device class Change the policy that the clients use, so that the backup copy group points to the tape storage pool as the destination.	“Defining or Updating Primary Storage Pools” on page 123 “Overview: Changing Policy” on page 237

Overview: Volumes in Storage Pools

Storage pool volumes are the physical media that are assigned to a storage pool. Some examples of volumes are:

- Space allocated on a disk drive
- A tape cartridge
- An optical disk

Storage pools and their volumes are either random access or sequential access, depending on the device type of the device class to which the pool is assigned.

Random Access Storage Pool Volumes

Random access storage pools consist of volumes on disk. Random access storage pools are always associated with the DISK device class, and all volumes are one of the following:

- Fixed-size files on a disk. The files are created when you define volumes.
- Raw logical volumes that must be defined, typically by using SMIT, before the server can access them.

Attention: It is recommended that you use journal file system (JFS) files rather than raw logical volumes for storage pool volumes. See “The Advantages of Using Journal File System Files” on page 390 for details.

See “Preparing Volumes for Random Access Storage Pools” on page 128 for details.

Sequential Access Storage Pool Volumes

Volumes in sequential access storage pools include any supported device type to which the server writes data sequentially. Some examples of sequential access volumes are:

- Tape cartridge
- Optical disk
- File

Each volume defined in a sequential access storage pool must be of the same type as the device type of the associated device class. See Table 11 for the type of volumes associated with each device type.

For preparing sequential access volumes, see “Preparing Volumes for Sequential Access Storage Pools” on page 129.

Table 11. Volume Types

Device Type	Volume Description	Label Required
3570	IBM 3570 tape cartridge	Yes
3590	IBM 3590 tape cartridge	Yes
4MM	4mm tape cartridge	Yes
8MM	8mm tape cartridge	Yes
CARTRIDGE	IBM 3480 or 3490 cartridge system tape	Yes
DLT	A digital linear tape	Yes
DTF	A digital tape format (DTF) tape	Yes

Table 11. Volume Types (continued)

Device Type	Volume Description	Label Required
ECARTRIDGE	A cartridge tape that is used by a tape drive such as the StorageTek SD-3 or 9490 tape drive	Yes
FILE	A file in the file system of the server machine	No
GENERICTAPE	A tape that is compatible with the drives that are defined to the device class	Yes
OPTICAL	A two-sided 5.25-inch rewritable optical cartridge	Yes
QIC	A 1/4-inch tape cartridge	Yes
REMOVABLEFILE	A file on a removable medium. If the medium has two sides, each side is a separate volume.	Yes
SERVER	One or more objects that are archived in the server storage of another server	No
WORM	A two-sided 5.25-inch write-once optical cartridge	Yes
WORM12	A two-sided 12-inch write-once optical cartridge	Yes
WORM14	A two-sided 14-inch write-once optical cartridge	Yes

Scratch Volumes Versus Defined Volumes

You can define volumes in a sequential access storage pool or you can specify that the server dynamically acquire scratch volumes. You can also use a combination of defined and scratch volumes. What you choose depends on the amount of control you need over individual volumes.

Use defined volumes when you want to control precisely which volumes are used in the storage pool. Using defined volumes may be useful when you want to establish a naming scheme for volumes.

Use scratch volumes to enable the server to define a volume when needed and delete the volume when it becomes empty. Using scratch volumes frees you from the burden of explicitly defining all of the volumes in a storage pool.

The server tracks whether a volume being used was originally a scratch volume. Scratch volumes that the server acquired for a primary storage pool are deleted from the server database when they become empty. The volumes are then available for reuse by the server or other applications. For scratch volumes that were acquired in a FILE device class, the space that the volumes occupied is freed by the server and returned to the file system.

Scratch volumes in a copy storage pool are handled in the same way as scratch volumes in a primary storage pool, except for volumes with the access value of offsite. If an offsite volume becomes empty, the server does not immediately return the volume to the scratch pool. The delay prevents the empty volumes from being deleted from the database, making it easier to determine which volumes should be returned to the onsite location. The administrator can query the server for empty offsite copy storage pool volumes and return them to the onsite location. The volume is returned to the scratch pool only when the access value is changed to READWRITE, READONLY, or UNAVAILABLE.

Preparing Volumes for Random Access Storage Pools

For a random access storage pool, you must define volumes.

Task	Required Privilege Class
Define volumes in any storage pool	System or unrestricted storage

Task	Required Privilege Class
Define volumes in specific storage pools	System, unrestricted storage, or restricted storage for those pools

Prepare a volume for use in a random access storage pool by defining the volume. For example, suppose you want to define a 21MB volume for the BACKUPPOOL storage pool. You want the volume to be located in the path `/usr/lpp/admserv/bin` and named `stgvol.001`. Enter the following command:

```
define volume backuppool /usr/lpp/admserv/bin/stgvol.001 formatsize=21
```

If you do not specify a full path name for the volume name, the command uses the current path.

Tip: Define storage pool volumes on disk drives that reside on the TSM server machine, not on remotely mounted file systems.

Note: This one-step process replaces the former two-step process of first formatting a volume (using DSMFMT) and then defining the volume. If you choose to use the two-step process, the DSMFMT utility is available from the operating system command line. See *Administrator's Reference* for details.

Another option for preparing a volume is to create a raw logical volume by using SMIT.

Preparing Volumes for Sequential Access Storage Pools

For sequential access storage pools with a FILE or SERVER device type, no labeling or other preparation of volumes is necessary.

For sequential access storage pools with other than a FILE or SERVER device type, you must prepare volumes for use. When the server accesses a sequential access volume, it checks the volume name in the header to ensure that the correct volume is being accessed. To prepare a volume:

1. Label the volume. Table 11 on page 127 shows the types of volumes that require labels. You must label those types of volumes before the server can use them.
See "Labeling Removable Media Volumes" on page 84.

Tip: When you use the LABEL LIBVOLUME command with drives in an automated library, you can label and check in the volumes with one command.

2. For storage pools in automated libraries, use the CHECKIN LIBVOLUME command to check the volume into the library. See "Checking New Volumes into a Library" on page 87.
3. If you have not allowed scratch volumes in the storage pool, you must identify the volume, by name, to the server. For details, see "Defining Storage Pool Volumes" on page 130.

If you allowed scratch volumes in the storage pool by specifying a value greater than zero for the MAXSCRATCH parameter, you can let the server use scratch volumes, identify volumes by name, or do both. See "Using Scratch Volumes" on page 130 for information about scratch volumes.

Defining Storage Pool Volumes

Task	Required Privilege Class
Define volumes in any storage pool	System or unrestricted storage
Define volumes in specific storage pools	System, unrestricted storage, or restricted storage for those pools

When you define a storage pool volume, you inform the server that the volume is available for storing backup, archive, or space-managed data.

For a sequential access storage pool, the server can use dynamically acquired scratch volumes, volumes that you define, or a combination.

To define a volume named VOL1 in the ENGBACK3 tape storage pool, enter:

```
define volume engback3 vol1
```

Using Scratch Volumes

You do not have to define volumes in sequential access storage pools if you allow storage pools to use scratch volumes. Use the MAXSCRATCH parameter when you define or update the storage pool. Setting the MAXSCRATCH parameter to a value greater than zero lets the storage pool dynamically acquire volumes as needed. The server automatically defines the volumes as they are acquired. The server also automatically deletes scratch volumes from the storage pool when the server no longer needs them.

Before the server can use a scratch volume with a device type other than FILE or SERVER, the volume must have a standard label. See “Preparing Volumes for Sequential Access Storage Pools” on page 129.

Updating Storage Pool Volumes

Task	Required Privilege Class
Update volumes	System or operator

You can update the attributes of a storage pool volume assigned to a primary or copy storage pool. Update a volume to:

- Reset any error state for a volume, by updating the volume to an access mode of read/write.
- Change the access mode of a volume, for example if a tape cartridge is moved offsite (offsite access mode) or damaged (destroyed access mode). See “Access Modes for Storage Pool Volumes” on page 131.
- Change the location for a volume in a sequential access storage pool.

An example of when to use the UPDATE VOLUME command is if you accidentally damage a volume. You can change the access mode to unavailable so that the server does not try to write or read data from the volume. For example, if the volume name is VOL1, enter the following command:

```
update volume vol1 access=unavailable
```


When using the UPDATE VOLUME command, be prepared to supply some or all of the information shown in Table 12.

Table 12. Information for Updating a Storage Pool Volume

Information	Explanation
Volume name (Required)	Specifies the name of the storage pool volume to be updated. You can specify a group of volumes to update by using wildcard characters in the volume name. You can also specify a group of volumes by specifying the storage pool, device class, current access mode, or status of the volumes you want to update. See the parameters that follow.
New access mode	Specifies the new access mode for the volume (how users and server processes such as migration can access files in the storage pool volume). See “Access Modes for Storage Pool Volumes” for descriptions of access modes. A random access volume must be varied offline before you can change its access mode to <i>unavailable</i> or <i>destroyed</i> . To vary a volume offline, use the VARY command. See “Varying Disk Volumes Online or Offline” on page 45. If a scratch volume that is empty and has an access mode of offsite is updated so that the access mode is read/write, read-only, or unavailable, the volume is deleted from the database.
Location	Specifies the location of the volume. This parameter can be specified only for volumes in sequential access storage pools.
Storage pool	Restricts the update to volumes in the specified storage pool.
Device class	Restricts the update to volumes in the specified device class.
Current access mode	Restricts the update to volumes that currently have the specified access mode.
Status	Restricts the update to volumes with the specified status (online, offline, empty, pending, filling, or full).
Preview	Specifies whether you want to preview the update operation without actually performing the update.

Access Modes for Storage Pool Volumes

Access to any volume in a storage pool is determined by the access mode assigned to that volume. You can change the access mode of a volume. The server can also change the access mode based on what happens when it tries to access a volume. For example, if the server cannot write to a volume having read/write access mode, the server automatically changes the access mode to read-only.

The access modes are:

Read/write

Allows files to be read from or written to a volume in the storage pool.

If the server cannot write to a read/write access volume, the server automatically changes the access mode to read-only.

If a scratch volume that is empty and has an access mode of offsite is updated so that the access mode is read/write, the volume is deleted from the database.

Read-only

Allows files to be read from but not written to a disk or tape volume.

If a scratch volume that is empty and has an access mode of offsite is updated so that the access mode is read-only, the volume is deleted from the database.

Unavailable

Specifies that the volume is not available for any type of access by the server.

You must vary offline a random access volume before you can change its access mode to *unavailable*. To vary a volume offline, use the VARY command. See “Varying Disk Volumes Online or Offline” on page 45.

If a scratch volume that is empty and has an access mode of offsite is updated so that the access mode is unavailable, the volume is deleted from the database.

Destroyed

Specifies that a primary storage pool volume has been permanently damaged. Neither users nor system processes (like migration) can access files stored on the volume.

This access mode is used to indicate an entire volume that should be restored using the RESTORE STGPOOL or RESTORE VOLUME command. After all files on a destroyed volume are restored to other volumes, the destroyed volume is automatically deleted from the database. See “How Restore Processing Works” on page 458 for more information.

Only volumes in primary storage pools can be updated to an access mode of destroyed.

You must vary offline a random access volume before you can change its access mode to *destroyed*. To vary a volume offline, use the VARY command. See “Varying Disk Volumes Online or Offline” on page 45. Once you update a random access storage pool volume to destroyed, you cannot vary the volume online without first changing the access mode.

If you update a sequential access storage pool volume to destroyed, the server does not attempt to mount the volume.

If a volume contains no files and the UPDATE VOLUME command is used to change the access mode to destroyed, the volume is deleted from the database.

Offsite

Specifies that a copy storage pool volume is at an offsite location and therefore cannot be mounted. Use this mode to help you track volumes that are offsite. The server treats offsite volumes differently, as follows:

- Mount requests are not generated for offsite volumes
- Data can be reclaimed or moved from offsite volumes by retrieving files from other storage pools
- Empty, offsite scratch volumes are not deleted from the copy storage pool

You can only update volumes in a copy storage pool to offsite access mode. Volumes that have the device type of SERVER (volumes that are actually archived objects stored on another TSM server) cannot have an access mode of offsite.

Overview: The Storage Pool Hierarchy

You can set up your devices so that the server automatically moves data from one device to another, or one media type to another. The selection can be based on characteristics such as file size or storage capacity. To do this, you set up different primary storage pools to form a storage pool hierarchy. A typical implementation may have a disk storage pool with a subordinate tape storage pool. When a client backs up a file, the server may initially store the file on disk according to the policy for that file. Later, the server may move the file to tape when the disk becomes full. This action by the server is called migration. You can also place a size limit on files that are stored on disk, so that large files are stored initially on tape instead of on disk.

For example, your fastest devices are disks, but you do not have enough space on these devices to store all data that needs to be backed up over the long term. You have tape drives, which are slower to access, but have much greater capacity. You can define a hierarchy so that files are initially stored on the fast disk volumes in one storage pool. This provides clients with quick response to backup requests and some recall requests. As the disk storage pool becomes full, the server migrates, or moves, data to volumes in the tape storage pool.

Migration of files from disk to sequential storage pool volumes is particularly useful because the server migrates all the files for a single node together. This gives you partial collocation for clients. Migration of files is especially helpful if you decide not to enable collocation for sequential storage pools. See “Keeping a Client’s Files Together: Collocation” on page 147 for details.

Setting Up a Storage Pool Hierarchy

You can set up a storage pool hierarchy when you first define storage pools. You can also change the storage pool hierarchy later.

You establish a hierarchy by identifying the *next* storage pool, sometimes called the subordinate storage pool. The server migrates data to the next storage pool if the original storage pool is full or unavailable. See “Migration of Files in a Storage Pool Hierarchy” on page 138 for detailed information on how migration between storage pools works.

Restrictions:

1. You cannot establish a chain of storage pools that leads to an endless loop. For example, you cannot define StorageB as the *next* storage pool for StorageA, and then define StorageA as the *next* storage pool for StorageB.
2. The storage pool hierarchy includes only primary storage pools, not copy storage pools. See “Using Copy Storage Pools to Back Up a Storage Hierarchy” on page 137.

Example: Defining a Storage Pool Hierarchy

For this example, suppose that you have determined that an engineering department requires a separate storage hierarchy. You set up policy so that the server initially stores backed up files for this department to a disk storage pool. When that pool fills, you want the server to migrate files to a tape storage pool. You want the pools to have the following characteristics:

- Primary storage pool on disk
 - Name the storage pool ENGBACK1.
 - Limit the size of the largest file that can be stored to 5MB. The server stores files that are larger than 5MB in the tape storage pool.

- Files migrate from the disk storage pool to the tape storage pool when the disk storage pool is 85% full. File migration to the tape storage pool stops when the disk storage pool is down to 40% full.
- Use caching, so that migrated files stay on disk until the space is needed for other files.
- Primary storage pool on tape
 - Name the storage pool BACKTAPE.
 - Use the device class TAPE, which has already been defined, for this storage pool.
 - Do not set a limit for the maximum file size, because this is the last storage pool in the hierarchy.
 - Use scratch volumes for this pool, with a maximum number of 100 volumes.

You can define the storage pools in a storage pool hierarchy from the top down or from the bottom up. Defining the hierarchy from the bottom up requires fewer steps. To define the hierarchy from the bottom up, perform the following steps:

1. Define the storage pool named BACKTAPE with the following command:

```
define stgpool backtape tape
description='tape storage pool for engineering backups'
maxsize=nolimit collocate=yes maxscratch=100
```

2. Define the storage pool named ENGBACK1 with the following command:

```
define stgpool engback1 disk
description='disk storage pool for engineering backups'
maxsize=5M nextstgpool=backtape highmig=85 lowmig=40
```

Example: Updating a Storage Pool Hierarchy

If you have already defined the storage pool at the top of the hierarchy, you can update the storage hierarchy to include a new storage pool.

For example, suppose that you had already defined the ENGBACK1 disk storage pool. Now you have decided to set up a tape storage pool to which files from ENGBACK1 can migrate. Perform the following steps to define the new tape storage pool and update the hierarchy:

1. Define the storage pool named BACKTAPE with the following command:

```
define stgpool backtape tape
description='tape storage pool for engineering backups'
maxsize=nolimit collocate=yes maxscratch=100
```

2. Specify that BACKTAPE is the next storage pool defined in the storage hierarchy for ENGBACK1. To update ENGBACK1, enter:

```
update stgpool engback1 nextstgpool=backtape
```

How the Server Groups Files before Storing

When a user backs up or archives files from a client node, the server may group multiple client files into an *aggregate* (a single physical file). The size of the aggregate depends on the sizes of the client files being stored, and the number of bytes and files allowed for a single transaction. Two options, one in the server options file and one in the client options file, affect the number of bytes and files allowed for a single transaction:

- The TXNGROUPMAX option in the server options file indicates the maximum number of logical files (client files) that a client may send to the server in a single transaction.

The server can tune this option automatically if you set the SELFTUNETXNSIZE option to YES. The server then uses the value that is specified for TXNGROUPMAX in the server options file and adjusts it for each node until it obtains the best performance. It is recommended that the client specify the maximum transaction byte limit in the client options and rely on the automatic tuning.

Note: Although the values of TXNGROUPMAX, MOVEBATCHSIZE, and MOVESIZETHRESH may be changed, the settings in the server options file are not changed. Issuing a QUERY OPTION command displays only what is set in the server options file.

- The TXNBYTELIMIT option in the client options file indicates the total number of bytes that the client can send to the server in a single transaction. This option sets a target size for the aggregate file. An aggregate file will usually be smaller than the value specified by the TXNBYTELIMIT option. A logical file (a single user's file) that is larger than the value specified by TXNBYTELIMIT option will not become part of an aggregate, but will be stored as a single physical file.

The recommended value is 25600.

Together these options allow you to control the size of aggregate files stored by the server. For more information on using options to tune performance, look for the performance tuning guide on the product Web site (http://www.tivoli.com/support/storage_mgr/tivolimain.html).

When a Tivoli Space Manager client (HSM client) migrates files to the server, the files are not grouped into an aggregate.

Where the Files Are Stored

When a user backs up, archives, or migrates a file from a client node, the server looks at the management class that is bound to the file. The management class specifies the destination, the storage pool in which to store the file. The server then checks that storage pool to determine the following:

- If it is possible to write file data to the storage pool (access mode).
- If the size of the physical file exceeds the maximum file size allowed in the storage pool. For backup and archive operations, the physical file may be an aggregate file or a single client file.
- Whether sufficient space is available on the available volumes in the storage pool.
- What the next storage pool is, if any of the previous conditions prevent the file from being stored in the storage pool that is being checked.

Using these factors, the server determines if the file can be written to that storage pool or the next storage pool in the hierarchy.

Subfile backups: When the client backs up a subfile, it still reports the size of the entire file. Therefore, allocation requests against server storage and placement in the storage hierarchy are based on the full size of the file. The server does not aggregate a subfile with other files if the size of the entire file is too large to aggregate. For example, the entire file is 8MB, but the subfile is only 10KB. The server does not typically aggregate a large file, so the server begins to store this file as a standalone file. However, the client sends only 10KB, and it is now too late for the server to aggregate other files with this 10KB file. As a result, the benefits of aggregation are not always realized when clients back up subfiles.

ADSM Version 2 Clients: When an ADSM Version 2 client backs up or archives files, the server must estimate the size of the aggregate file that the client will send. The server bases the estimate on earlier transactions with the client. The server uses the estimated size to check whether the storage pool has enough space to store the file. Because the server uses the estimated size rather than the actual size for ADSM Version 2 clients, the server may not always store files in the storage pool that you expect.

How the Server Stores Files in a Storage Hierarchy

As an example of how the server stores files in a storage hierarchy, assume a company has a storage pool hierarchy as shown in Figure 19.




Figure 19. Storage Hierarchy Example

The storage pool hierarchy consists of two storage pools:

DISKPOOL

The top of the storage hierarchy. It contains fast disk volumes for storing data.

TAPEPOOL

The next storage pool in the hierarchy. It contains tape volumes accessed by high-performance tape drives.

Assume a user wants to archive a 5MB file that is named *FileX*. FileX is bound to a management class that contains an archive copy group whose storage destination is DISKPOOL, see Figure 19.

When the user archives the file, the server determines where to store the file based on the following process:

1. The server selects DISKPOOL because it is the storage destination specified in the archive copy group.
2. Because the access mode for DISKPOOL is read/write, the server checks the maximum file size allowed in the storage pool.

The maximum file size applies to the physical file being stored, which may be a single client file or an aggregate file. The maximum file size allowed in DISKPOOL is 3MB. FileX is a 5MB file and therefore cannot be stored in DISKPOOL.

3. The server searches for the next storage pool in the storage hierarchy.

If the DISKPOOL storage pool has no maximum file size specified, the server checks for enough space in the pool to store the physical file. If there is not enough space for the physical file, the server uses the next storage pool in the storage hierarchy to store the file.

4. The server checks the access mode of TAPEPOOL, which is the next storage pool in the storage hierarchy. The access mode for TAPEPOOL is read/write.
5. The server then checks the maximum file size allowed in the TAPEPOOL storage pool. Because TAPEPOOL is the last storage pool in the storage hierarchy, no maximum file size is specified. Therefore, if there is available space in TAPEPOOL, FileX can be stored in it.

Using Copy Storage Pools to Back Up a Storage Hierarchy

Copy storage pools enable you to back up your primary storage pools for an additional level of data protection for clients. See “Backing Up Storage Pools” on page 465 for details. Copy storage pools are not part of a storage hierarchy.

For efficiency, it is strongly recommended that you use one copy storage pool to back up all primary storage pools that are linked to form a storage hierarchy. By backing up all primary storage pools to one copy storage pool, you do not need to recopy a file when the file migrates from its original primary storage pool to another primary storage pool in the storage hierarchy.

In most cases, a single copy storage pool can be used for backup of all primary storage pools. The number of copy storage pools you need depends on whether you have more than one primary storage pool hierarchy and on what type of disaster recovery protection you want to implement.

Multiple copy storage pools may be needed to handle particular situations, including:

- Special processing of certain primary storage hierarchies (for example, archive storage pools or storage pools dedicated to priority clients)
- Creation of multiple copies for multiple locations (for example, to keep one copy onsite and one copy offsite)
- Rotation of full storage pool backups (see “Backing Up Storage Pools” on page 465 for more information)

Using the Hierarchy to Stage Client Data from Disk to Tape

A common way to use the storage hierarchy is to initially store client data on disk, then let the server migrate the data to tape. Typically you would need to ensure that you have enough disk storage to handle one night’s worth of the clients’ incremental backups. While not always possible, this guideline proves to be valuable when considering storage pool backups.

For example, if you have enough disk space for nightly incremental backups for clients and have tape devices, you can set up the following pools:

- A primary storage pool on disk, with enough volumes assigned to contain the nightly incremental backups for clients
- A primary storage pool on tape, which is identified as the next storage pool in the hierarchy for the disk storage pool
- A copy storage pool on tape

You can then schedule the following steps every night:

1. Perform an incremental backup of the clients to the disk storage pool.
2. After clients complete their backups, back up the disk primary storage pool (now containing the incremental backups) to the copy storage pool.
Backing up disk storage pools before migration processing allows you to copy as many files as possible while they are still on disk. This saves mount requests while performing your storage pool backups.
3. Start the migration of the files in the disk primary storage pool to the tape primary storage pool (the next pool in the hierarchy) by lowering the high migration threshold. For example, lower the threshold to 40%.
When this migration completes, raise the high migration threshold back to 100%.
4. Back up the tape primary storage pool to the copy storage pool to ensure that all files have been backed up.
The tape primary storage pool must still be backed up to catch any files that might have been missed in the backup of the disk storage pools (for example, large files that went directly to sequential media).

See “Estimating Space Needs for Storage Pools” on page 159 for more information about storage pool space.

Migration of Files in a Storage Pool Hierarchy

The server provides automatic migration to maintain free space in a primary storage pool. The server can migrate data from one storage pool to the next storage pool in the hierarchy. This process helps to ensure that there is sufficient free space in the storage pools at the top of the hierarchy, where faster devices can provide the most benefit to clients. For example, the server can migrate data stored in a random access disk storage pool to a slower but less expensive sequential access storage pool.

You can control:

When migration begins and ends

You use migration thresholds to control when migration begins and ends. Thresholds are set as levels of the space that is used in a storage pool, expressed as a percent of total space available in the storage pool. For a disk storage pool, the server compares the threshold with a calculation of the amount of data stored in the pool as a percent of the actual data capacity of the volumes in the pool. For a sequential access storage pool, the server compares the threshold with a calculation of the number of volumes containing data as a percent of the total number of volumes available to the pool.

How the server chooses files to migrate

By default, the server does not consider how long a file has been in a storage pool or how long since a file was accessed before choosing files to migrate. Optional parameters allow you to change the default. You can ensure that files remain in a storage pool for a minimum amount of time before the server migrates them to another pool. To do this, you set a migration delay period for a storage pool. Before the server can migrate a file, the file must be stored in the storage pool at least as long as the migration delay period. For disk storage pools, the last time the file was accessed is also considered for migration delay.

Migration processing differs for disk storage pools versus sequential access storage pools. If you plan to modify the default migration parameter settings for storage pools or want to understand how migration works, you should read the following sections:

“Migration for Disk Storage Pools”

“Migration for Sequential Access Storage Pools” on page 144

Migration for Disk Storage Pools

When you define or update a storage pool, you can set migration thresholds to specify when the server should begin and stop migrating data to the next storage pool in the storage hierarchy. Migration thresholds are defined in terms of a percentage of total data capacity for the disk storage pool. You can use the defaults for the migration thresholds, or you can change the threshold values to identify the maximum and minimum amount of space for a storage pool. See “How the Server Selects Files to Migrate” and “Choosing Appropriate Migration Threshold Values” on page 141 for more information about migration thresholds.

You can control how long files must stay in a storage pool before they are eligible for migration by setting a migration delay for a storage pool. See “Keeping Files in a Storage Pool” on page 142.

If you decide to enable cache for disk storage pools, files can temporarily remain on disks even after migration. You may want to set migration thresholds lower when you use cache. See “Minimizing Access Time to Migrated Files” on page 143 and “Using Cache on Disk Storage Pools” on page 146 for information about using the cache.

How the Server Selects Files to Migrate

When data in a storage pool uses a percentage of the pool’s capacity that is equal to the high migration threshold, the server migrates files from the pool to the next storage pool. The server selects the files to migrate as follows:

1. The server checks for the client node that has backed up or migrated the largest single file space or has archived files that occupy the most space.
2. For *all* files from *every* file space belonging to the client node that was identified, the server examines the number of days since the files were stored in the storage pool and last retrieved from the storage pool. The server compares the number (whichever is less) to the migration delay that is set for the storage pool. The server migrates any of these files for which the number is more than the migration delay set for the storage pool.
3. After the server migrates the files for the first client node to the next storage pool, the server checks the low migration threshold for the storage pool. If the amount of space that is used in the storage pool is now below the low migration threshold, migration ends. If not, the server chooses another client node by using the same criteria as described above, and the migration process continues.

The server may not be able to reach the low migration threshold for the pool by migrating only files that have been stored longer than the migration delay period. When this happens, the server checks the storage pool characteristic that determines whether migration should stop even if the pool is still above the low migration threshold. See “Keeping Files in a Storage Pool” on page 142 for more information.

If multiple migration processes are running (controlled by the MIGPROCESS parameter of the DEFINE STGPOOL command), the server may choose the files from more than one node for migration at the same time.

For example, Table 13 displays information that is contained in the database that is used by the server to determine which files to migrate. This example assumes that the storage pool contains no space-managed files. This example also assumes that the migration delay period for the storage pool is set to zero, meaning any files can be migrated regardless of time stored in the pool or the last time of access.

Table 13. Database Information on Files Stored in DISKPOOL

Client Node	Backed-Up File Spaces and Sizes		Archived Files (All Client File Spaces)
TOMC	TOMC/C	200MB	55MB
	TOMC/D	100MB	
CAROL	CAROL	50MB	5MB
PEASE	PEASE/home	150MB	40MB
	PEASE/temp	175MB	




Figure 20. The Migration Process and Migration Thresholds

Figure 20 shows what happens when the high migration threshold defined for the disk storage pool DISKPOOL is exceeded. When the amount of migratable data in DISKPOOL reaches 80%, the server performs the following tasks:

1. Determines that the TOMC/C file space is taking up the most space in the DISKPOOL storage pool, more than any other single backed-up or space-managed file space and more than any client node's archived files.
2. Locates all data belonging to node TOMC stored in DISKPOOL. In this example, node TOMC has backed up or archived files from file spaces TOMC/C and TOMC/D stored in the DISKPOOL storage pool.
3. Migrates all data from TOMC/C and TOMC/D to the next available storage pool. In this example, the data is migrated to the tape storage pool, TAPEPOOL.

The server migrates all of the data from both file spaces belonging to node TOMC, even if the occupancy of the storage pool drops below the low migration threshold before the second file space has been migrated.

If the cache option is enabled, files that are migrated remain on disk storage (that is, the files are *cached*) until space is needed for new files. For more information about using cache, see “Using Cache on Disk Storage Pools” on page 146.

4. After all files that belong to TOMC are migrated to the next storage pool, the server checks the low migration threshold. If the low migration threshold has not been reached, then the server again determines which client node has backed up or migrated the largest single file space or has archived files that occupy the most space. The server begins migrating files belonging to that node.

In this example, the server migrates *all* files that belong to the client node named PEASE to the TAPEPOOL storage pool.

5. After all the files that belong to PEASE are migrated to the next storage pool, the server checks the low migration threshold again. If the low migration threshold has been reached or passed, then migration ends.

Choosing Appropriate Migration Threshold Values

Setting migration thresholds for disk storage pools ensures sufficient free space on faster speed devices, which can lead to better performance. Choosing thresholds appropriate for your situation takes some experimenting, and you can start by using the default values. You need to ensure that migration occurs frequently enough to maintain some free space but not so frequently that the device is unavailable for other use.

Choosing the High-Migration Threshold

To choose the high-migration threshold, consider:

- The amount of storage capacity provided for each storage pool
- The amount of free storage needed for users to store additional files, without having migration occur

If you set the high-migration threshold too high, the pool may be just under the high threshold, but not have enough space to store an additional, typical client file. Or, with a high threshold of 100%, the pool may become full and a migration process must start before clients can back up any additional data to the disk storage pool. In either case, the server stores client files directly to tape until migration completes, resulting in slower performance.

If you set the high-migration threshold too low, migration runs more frequently and can interfere with other operations.

Keeping the high-migration threshold at a single value means that migration processing could start at any time of day, whenever that threshold is exceeded. You can control when migration occurs by using administrative command schedules to change the threshold. For example, set the high-migration threshold to 95% during the night when clients run their backup operations. Lower the high-migration threshold to 50% during the time of day when you want migration to occur. By scheduling when migration occurs, you can choose a time when your tape drives and mount operators are available for the operation.

Choosing the Low-Migration Threshold

To choose the low-migration threshold, consider:

-
- The amount of free disk storage space needed for normal daily processing. If you have disk space to spare, you can keep more data on the disk (a larger low threshold). If clients' daily backups are enough to fill the disk space every day, you may need to empty the disk (a smaller low threshold).

If your disk space is limited, try setting the threshold so that migration frees enough space for the pool to handle the amount of client data that is typically stored every day. Migration then runs about every day, or you can force it to run every day by lowering the high-migration threshold at a time you choose.

You may also want to identify clients that are transferring large amounts of data daily. For these clients, you may want to set up policy (a new copy group or a new policy domain) so that their data is stored directly to tape. Using a separate policy in this way can optimize the use of disk for the majority of clients.

- Whether you use cache on disk storage pools to improve how quickly some files are retrieved. If you use cache, you can set the low threshold lower, yet still maintain faster retrieval for some data. Migrated data remains cached on the disk until new client data pushes the data off the disk. Using cache requires more disk space for the database, however, and can slow backup and archive operations that use the storage pool.

If you do not use cache, you may want to keep the low threshold at a higher number so that more data stays on the disk.

- How frequently you want migration to occur, based on the availability of sequential access storage devices and mount operators. The larger the low threshold, the shorter time that a migration process runs (because there is less data to migrate). But if the pool refills quickly, then migration occurs more frequently. The smaller the low threshold, the longer time that a migration process runs, but the process runs less frequently.

You may need to balance the costs of larger disk storage pools with the costs of running migration (drives, tapes, and either operators or automated libraries).

- Whether you are using collocation on the next storage pool. When you use collocation, the server attempts to store data for different clients or client file spaces on separate tapes, even for clients with small amounts of data. You may want to set the low threshold to keep more data on disk, to avoid having many tapes used by clients with only small amounts of data.

Keeping Files in a Storage Pool

For some applications, you may want to ensure that files remain in the storage pool where they were initially stored by the server for a certain period of time. For example, you may have backups of monthly summary data that you want to keep in your disk storage pool for quicker access until the data is 30 days old. After the 30 days, the server can then move the file off into a tape storage pool.

You can delay migration of files for a specified number of days. The number of days is counted from the day that a file was stored in the storage pool or retrieved by a client, whichever is more recent. You can set the migration delay separately for each storage pool. When you set the delay to zero, the server can migrate any file from the storage pool, regardless of how short a time the file has been in the storage pool. When you set the delay to greater than zero, the server checks whether the file has been in the storage pool for at least the migration delay period before migrating the file.

Note: If you want the number of days for migration delay to be counted based only on when a file was stored and not when it was retrieved, use the `NORETRIEVEDATE` server option. See *Administrator's Reference* for more information on the server option.

If you set migration delay for a pool, you need to decide what is more important: either ensuring that files stay in the storage pool for the migration delay period, or ensuring that there is enough space in the storage pool for new files. For each storage pool that has a migration delay set, you can choose what happens as the server tries to move enough data out of the storage pool to reach the low migration threshold. If the server cannot reach the low migration threshold by moving only files that have been stored longer than the migration delay, you can choose one of the following:

- Allow the server to move files out of the storage pool even if they have not been in the pool for the migration delay (`MIGCONTINUE=YES`). This is the default. Allowing migration to continue ensures that space is made available in the storage pool for new files that need to be stored there.
- Have the server stop migration without reaching the low migration threshold (`MIGCONTINUE=NO`). Stopping migration ensures that files remain in the storage pool for the time you specified with the migration delay. The administrator must ensure that there is always enough space available in the storage pool to hold the data for the required number of days.

If you allow more than one migration process for the storage pool and allow the server to move files that do not satisfy the migration delay time (`MIGCONTINUE=YES`), some files that do not satisfy the migration delay time may be migrated unnecessarily. As one process migrates files that satisfy the migration delay time, a second process could begin migrating files that do not satisfy the migration delay time to meet the low migration threshold. The first process that is still migrating files that satisfy the migration delay time might have, by itself, caused the storage pool to meet the low migration threshold.

Minimizing Access Time to Migrated Files

Caching is a method of minimizing access time to files on disk storage, even if the server has migrated files to a tape storage pool. However, cached files are removed from disk when the space they occupy is required. The file then must be obtained from the storage pool to which it was migrated.

Note: The use of cache has some disadvantages. See “Using Cache on Disk Storage Pools” on page 146.

To ensure that files remain on disk storage and do not migrate to other storage pools, use one of the following methods:

- Do not define the *next* storage pool.
A disadvantage of using this method is that if the file exceeds the space available in the storage pool, the operation to store the file fails.
- Set the high-migration threshold to 100%.
When you set the high migration threshold to 100%, files will not migrate at all. You can still define the *next* storage pool in the storage hierarchy, and set the maximum file size so that large files are stored in the next storage pool in the hierarchy.

A disadvantage of setting the high threshold to 100% is that once the pool becomes full, client files are stored directly to tape instead of to disk. Performance may be affected as a result.

Migration for Sequential Access Storage Pools

You can set up migration thresholds for sequential access storage pools. However, you probably will not want the server to perform this type of migration on a regular basis. An operation such as tape-to-tape migration has limited benefits compared to disk-to-tape migration, and requires at least two tape drives. Migrating data from one sequential access storage pool to another may be appropriate in some cases, for example, when you install a tape drive that uses a different type of tape and want to move data to that tape.

To control the migration process, you can set migration thresholds and a migration delay for each storage pool.

Note: You can migrate data from a sequential access storage pool only to another sequential access storage pool. You cannot migrate data from a sequential access storage pool to a disk storage pool. If you need to move data from a sequential access storage pool to a disk storage pool, use the MOVE DATA command. See “Moving Files from One Volume to Another Volume” on page 176.

How Tivoli Storage Manager Migrates Data from Sequential Access Storage Pools

The server begins the migration process when the number of volumes containing data as a percentage of the total volumes in the storage pool reaches the high migration threshold. The server migrates data from sequential storage pools by volume, to minimize the number of mounts for volumes. The server performs the following processing for migration:

1. The server first reclaims volumes that have exceeded the reclamation threshold. Reclamation is a server process of consolidating data from several volumes onto one volume. (See “Reclaiming Space in Sequential Access Storage Pools” on page 152.)
2. After reclamation processing, the server compares the space used in the storage pool to the low migration threshold.
3. If the space used is now below the low migration threshold, the server stops processing. If the space used is still above the low migration threshold, the server determines which volume is the least recently referenced volume.
4. If the number of days since data was written is greater than the migration delay, the server migrates the volume. Otherwise, the server does not migrate this volume.
5. The server repeats steps 3 and 4 until the storage pool reaches the low migration threshold.

Because migration delay can prevent volumes from being migrated, the server can migrate data from all eligible volumes yet still find that the storage pool is above the low migration threshold. If you set migration delay for a pool, you need to decide what is more important: either ensuring that data stays in the storage pool for as long as the migration delay, or ensuring there is enough space in the storage pool for new data. For each storage pool that has a migration delay set, you can choose what happens as the server tries to move enough data out of the storage pool to reach the low migration threshold. If the server cannot reach the low migration threshold by migrating only volumes that meet the migration delay requirement, you can choose one of the following:

- Allow the server to migrate volumes from the storage pool even if they do not meet the migration delay criteria (MIGCONTINUE=YES). This is the default. Allowing migration to continue ensures that space is made available in the storage pool for new files that need to be stored there.
- Have the server stop migration without reaching the low migration threshold (MIGCONTINUE=NO). Stopping migration ensures that volumes are not migrated for the time you specified with the migration delay. The administrator must ensure that there is always enough space available in the storage pool to hold the data for the required number of days.

Selecting Migration Criteria for Sequential Access Storage Pools

When defining migration criteria for sequential access storage pools, consider:

- The capacity of the volumes in the storage pool
- The time required to migrate data to the next storage pool
- The speed of the devices that the storage pool uses
- The time required to mount media, such as tape volumes, into drives
- Whether operator presence is required

If you decide to migrate data from one sequential access storage pool to another, ensure that:

- Two drives (mount points) are available, one in each storage pool.
- The access mode for the next storage pool in the storage hierarchy is set to read/write. For information about setting an access mode for sequential access storage pools, see “Defining or Updating Primary Storage Pools” on page 123.
- Collocation is set the same in both storage pools. For example, if collocation is set to *yes* in the first storage pool, then collocation should be set to *yes* in the next storage pool.

When you enable collocation for a storage pool, the server attempts to keep all files belonging to a client node or a client file space on a minimal number of volumes. For information about collocation for sequential access storage pools, see “Keeping a Client’s Files Together: Collocation” on page 147.

- You have sufficient staff available to handle any necessary media mount and dismount operations. More mount operations occur because the server attempts to reclaim space from sequential access storage pool volumes before it migrates files to the next storage pool.

If you want to limit migration from a sequential access storage pool to another storage pool, set the high-migration threshold to a high percentage, such as 95%.

For information about setting a reclamation threshold for tape storage pools, see “Reclaiming Space in Sequential Access Storage Pools” on page 152.

There is no straightforward way to selectively migrate data for a specific node from one sequential storage pool to another. If you know the volumes on which a particular node’s data is stored, you can use the MOVE DATA command to move all files from selected volumes to the new storage pool. See “Moving Files from One Volume to Another Volume” on page 176.

Migration and Copy Storage Pools

Copy storage pools are not part of the hierarchy for migration. Files are not migrated to or from copy storage pools. The only way to store files in copy storage pools is by backing up primary storage pools (the `BACKUP STGPOOL` command).

Migration of files between primary storage pools does not affect copy storage pool files. Copy storage pool files do not move when primary storage pool files move.

For example, suppose a copy of a file is made while it is in a disk storage pool. The file then migrates to a primary tape storage pool. If you then back up the primary tape storage pool to the same copy storage pool, a new copy of the file is not needed. The server knows it already has a valid copy of the file.

Using Cache on Disk Storage Pools

When defining or updating disk storage pools, you can enable or disable cache.

When cache is disabled and migration occurs, the server migrates the files to the next storage pool and erases the files from the disk storage pool. By default, the system disables caching for each disk storage pool because of the potential effects of cache on backup performance.

You can enable cache by specifying `CACHE=YES` when you define or update a storage pool. When cache is enabled, the migration process leaves behind duplicate copies of files on disk after the server migrates these files to the next storage pool in the storage hierarchy. The copies remain in the disk storage pool, but in a *cached* state, so that subsequent retrieval requests can be satisfied quickly. However, if space is needed to store new data in the disk storage pool, cached files are erased and the space they occupied is used for the new data.

The advantage of using cache for a disk storage pool is that cache can improve how quickly the server retrieves some files. When you use cache, a copy of the file remains on disk storage after the server migrates the primary file to another storage pool. You may want to consider using a disk storage pool with cache enabled for storing space-managed files that are frequently accessed by clients.

However, using cache has some important disadvantages:

- Using cache can increase the time required for client backup operations to complete. Performance is affected because, as part of the backup operation, the server must erase cached files to make room for storing new files. The effect can be severe when the server is storing a very large file and must erase cached files.
For the best performance for client backup operations to disk storage pools, do not use cache.
- Using cache can require more space for the server database. When you use cache, more database space is needed because the server has to keep track of both the cached copy of the file and the new copy in the next storage pool.

If you leave cache disabled, you may want to consider higher migration thresholds for the disk storage pool. A higher migration threshold keeps files on disk longer because migration occurs less frequently.

How the Server Removes Cached Files

When space is needed, the server reclaims space occupied by cached files. Files that have the oldest retrieval date and occupy the largest amount of disk space are overwritten first. For example, assume that two files, File A and File B, are cached files that are the same size. If File A was last retrieved on 05/16/99 and File B was last retrieved on 06/19/99, then File A is deleted to reclaim space first.

You can change whether the server tracks the retrieval date for a file with the server option, `NORETRIEVEDATE`. When you include this option in the server options file, the server does not update the retrieval date for files. As a result, the server may remove copies of files in cache even though clients retrieved the files recently.

Effect of Caching on Storage Pool Statistics

The space utilization statistic for the pool (Pct Util) includes the space used by any cached copies of files in the storage pool. The migratable data statistic (Pct Migr) does *not* include space occupied by cached copies of files. The server uses the statistic on migratable data (Pct Migr) to compare with migration threshold parameters to determine when migration should begin or end. For more information on storage pool statistics, see “Monitoring Storage Pools and Volumes” on page 161.

Keeping a Client’s Files Together: Collocation

With *collocation* enabled, the server attempts to keep files belonging to a single client node or to a single file space of a client node on a minimal number of sequential access storage volumes. You can set collocation for each sequential access storage pool when you define or update the pool.

To have the server collocate data in a storage pool by client node, set collocation to `YES`. To have the server collocate data in a storage pool by client file space, set collocation to `FILESPACE`. By using collocation, you reduce the number of volume mount operations required when users restore, retrieve, or recall many files from the storage pool. Collocation thus improves access time for these operations. Figure 21 shows an example of collocation by client node with three clients, each having a separate volume containing that client’s data.




Figure 21. Example of Collocation Enabled

When collocation is disabled, the server attempts to use all available space on each volume before selecting a new volume. While this process provides better utilization of individual volumes, user files can become scattered across many volumes. Figure 22 on page 148 shows an example of collocation disabled, with three clients sharing space on a volume.




Figure 22. Example of Collocation Disabled

With collocation disabled, when users restore, retrieve, or recall a large number of files, media mount operators may be required to mount more volumes. The system default is to not use collocation.

The following sections give more detail on collocation:

“The Effects of Collocation on Operations”

“How the Server Selects Volumes with Collocation Enabled” on page 149

“How the Server Selects Volumes with Collocation Disabled” on page 150

“Turning Collocation On or Off” on page 151

“Collocation on Copy Storage Pools” on page 151

The Effects of Collocation on Operations

Table 14 summarizes the effects of collocation on operations.

Table 14. Effect of Collocation on Operations

Operation	Collocation Enabled	Collocation Disabled
Backing up, archiving, or migrating client files	More media mounts to collocate files.	Usually fewer media mounts are required.
Restoring, retrieving or recalling client files	Large numbers of files can be restored, retrieved, or recalled more quickly because files are located on fewer volumes.	<p>Multiple mounts of media may be required for a single user because files may be spread across multiple volumes.</p> <p>More than one user’s files can be stored on the same sequential access storage volume. For example, if two users attempt to recover a file that resides on the same volume, the second user will be forced to wait until the first user’s files are recovered.</p>

Table 14. Effect of Collocation on Operations (continued)

Operation	Collocation Enabled	Collocation Disabled
Storing data on tape	The server attempts to use all available tape volumes to separate user files before it uses all available space on every tape volume.	The server attempts to use all available space on each tape volume before using another tape volume.
Media mount operations	<p>More mount operations when user files are backed up, archived, or migrated from client nodes directly to sequential access volumes.</p> <p>More mount operations during reclamation and storage pool migration.</p> <p>More volumes to handle because volumes are not fully used.</p>	More mount operations required during restore, retrieve, and recall of client files.

Tip: If you use collocation, but want to reduce the number of media mounts and use space on sequential volumes more efficiently, you can do the following:

- Define a storage pool hierarchy and policy to require that backed-up, archived, or space-managed files are stored initially in disk storage pools.

When files are migrated from a disk storage pool, the server attempts to migrate all files belonging to the client node that is using the most disk space in the storage pool. This process works well with the collocation option because the server tries to place all of the files from a given client on the same sequential access storage volume.

- Use scratch volumes for sequential access storage pools to allow the server to select new volumes for collocation.

How the Server Selects Volumes with Collocation Enabled

When collocation at the client node level is enabled for a storage pool (COLLOCATION=YES) and a client node backs up, archives, or migrates files to the storage pool, the server attempts to select a volume using the following selection order:

1. A volume that already contains files from the same client node
2. An empty predefined volume
3. An empty scratch volume
4. A volume with the most available free space among volumes that already contain data

When collocation at the file space level is enabled for a storage pool (COLLOCATION=FILESPEC) and a client node backs up, archives, or migrates files to the storage pool, the server attempts to select a volume using the following selection order:

1. A volume that already contains files from the same file space of that client node
2. An empty predefined volume
3. An empty scratch volume
4. A volume containing data from the same client node

5. A volume with the most available free space among volumes that already contain data

When the server needs to continue to store data on a second volume, it uses the following selection order to acquire additional space:

1. An empty predefined volume
2. An empty scratch volume
3. A volume with the most available free space among volumes that already contain data
4. Any available volume in the storage pool

Through this selection process, the server attempts to provide the best use of individual volumes while minimizing the mixing of files from different clients or file spaces on volumes. For example, Figure 23 shows that volume selection is *horizontal*, where all available volumes are used before all available space on each volume is used. A, B, C, and D represent files from four different client nodes.




Figure 23. Using All Available Sequential Access Storage Volumes with Collocation Enabled

How the Server Selects Volumes with Collocation Disabled

When collocation is disabled, the server attempts to use all available space in a storage volume before it accesses another volume. When storing client files in a sequential access storage pool where collocation is disabled, the server selects a volume using the following selection order:

1. A previously used sequential volume with available space (a volume with the most amount of data is selected first)
2. An empty volume

When the server needs to continue to store data on a second volume, it attempts to select an empty volume. If none exists, the server attempts to select any remaining available volume in the storage pool.

Figure 24 on page 151 shows that volume utilization is *vertical* when collocation is disabled. In this example, fewer volumes are used because the server attempts to use all available space by mixing client files on individual volumes. A, B, C, and D represent files from four different client nodes.




Figure 24. Using All Available Space on Sequential Volumes with Collocation Disabled

Turning Collocation On or Off

After you define a storage pool, you can change the collocation setting by updating the storage pool. The change in collocation for the pool does not affect files that are already stored in the pool.

For example, if collocation had been off for a storage pool and you turn it on, *from then on* client files stored in the pool are collocated. Files that had previously been stored in the pool are *not* moved to collocate them. As volumes are reclaimed, however, the data in the pool tends to become more collocated. You can also use the MOVE DATA command to move data to new volumes to increase collocation, if you are able to afford the processing time and the volume mount activity this would cause.

Collocation on Copy Storage Pools

Using collocation on copy storage pools requires special consideration.

Primary and copy storage pools perform different recovery roles. Normally you use primary storage pools to recover data to clients directly. You use copy storage pools to recover data to the primary storage pools. In a disaster where both clients and the server are lost, the copy storage pool volumes will probably be used directly to recover clients. The types of recovery scenarios that concern you the most will help you to determine whether to use collocation on your copy storage pools.

You may also want to consider that collocation on copy storage pools will result in more partially filled volumes and potentially unnecessary offsite reclamation activity. Collocation typically results in a partially filled sequential volume for each client or client file space. This may be acceptable for primary storage pools because these partially filled volumes remain available and can be filled during the next migration process. However, for copy storage pools this may be unacceptable because the storage pool backups are usually made to be taken offsite immediately. If you use collocation for copy storage pools, you will have to decide between:

- Taking more partially filled volumes offsite, thereby increasing the reclamation activity when the reclamation threshold is lowered or reached.
- or
- Leaving these partially filled volumes onsite until they fill and risk not having an offsite copy of the data on these volumes.

With collocation disabled for a copy storage pool, typically there will be only a few partially filled volumes after storage pool backups to the copy storage pool are complete.

Consider carefully before using collocation for copy storage pools. Even if you use collocation for your primary storage pools, you may want to disable collocation for copy storage pools. Collocation on copy storage pools may be desirable when you have few clients, but each of them has large amounts of incremental backup data each day.

See “Keeping a Client’s Files Together: Collocation” on page 147 for more information about collocation.

Reclaiming Space in Sequential Access Storage Pools

Space on a sequential volume becomes reclaimable as files expire or are deleted from the volume. For example, files become obsolete because of aging or limits on the number of versions of a file. In reclamation processing, the server rewrites files on the volume being reclaimed to other volumes in the storage pool, making the reclaimed volume available for reuse.

The server reclaims the space in storage pools based on a *reclamation threshold* that you can set for each sequential access storage pool. When the percentage of space that can be reclaimed on a volume rises above the reclamation threshold, the server reclaims the volume. See the following sections:

- “How Tivoli Storage Manager Reclamation Works”
- “Choosing a Reclamation Threshold” on page 154
- “Reclaiming Volumes in a Storage Pool with One Drive” on page 155
- “Reclamation for WORM Optical Media” on page 155
- “Reclamation of Volumes with the Device Type of SERVER” on page 155
- “Reclamation for Copy Storage Pools” on page 156
- “How Collocation Affects Reclamation” on page 158

How Tivoli Storage Manager Reclamation Works

When the percentage of reclaimable space on a volume exceeds the reclamation threshold set for the storage pool, the volume is eligible for reclamation. The server checks whether reclamation is needed at least once per hour and begins space reclamation for eligible volumes. You can set a reclamation threshold for each sequential access storage pool when you define or update the pool.

During space reclamation, the server copies files that remain on eligible volumes to other volumes. For example, Figure 25 on page 153 shows that the server consolidates the files from tapes 1, 2, and 3 on tape 4. During reclamation, the server copies the files to volumes in the same storage pool unless you have specified a reclamation storage pool. Use a reclamation storage pool to allow automatic reclamation for a storage pool with only one drive.

The server also reclaims space within an aggregate file. An aggregate is a physical file that contains multiple logical files that are backed up or archived from a client in a single transaction. Space within the file becomes reclaimable space as logical files in the aggregate expire or are deleted by the client. The server removes unused space from expired or deleted

logical files as the server copies the aggregate file to another volume during reclamation processing. However, reclamation does not aggregate files that were originally stored in non-aggregated form. Reclamation also does not combine aggregates to make new aggregates. You can also reclaim space in an aggregate by issuing the MOVE DATA command. See “Reclaiming Space in Aggregates During Data Movement” on page 179 for details.




Figure 25. Tape Reclamation

After the server moves all readable files to other volumes, one of the following occurs for the reclaimed volume:

- If you have explicitly defined the volume to the storage pool, the volume becomes available for reuse by that storage pool
- If the server acquired the volume as a scratch volume, the server deletes the volume from the TSM database

Volumes that have a device type of SERVER are reclaimed in the same way as other sequential access volumes. However, because the volumes are actually data stored in the storage of another TSM server, the reclamation process can consume network resources. See “Reclamation of Volumes with the Device Type of SERVER” on page 155 for details of how the server reclaims these types of volumes.

Volumes in a copy storage pool are reclaimed in the same manner as a primary storage pool except for the following:

-
- *Offsite* volumes are handled differently.
 - The server copies active files from the candidate volume only to other volumes in the *same* storage pool.

See “Reclamation for Copy Storage Pools” on page 156 for details.

Choosing a Reclamation Threshold

The reclamation threshold indicates how much reclaimable space a volume must have before the server reclaims the volume. Space is reclaimable because it is occupied by files that have been expired or deleted from the TSM database, or because the space has never been used.

The server checks whether reclamation is needed at least once per hour. The lower the reclamation threshold, the more frequently the server tries to reclaim space. Frequent reclamation optimizes the use of a sequential access storage pool’s space, but can interfere with other processes, such as backups from clients.

If the reclamation threshold is high, reclamation occurs less frequently. A high reclamation threshold is useful if mounting a volume is a manual operation and the operations staff is at a minimum.

Each reclamation process requires at least two simultaneous volume mounts, that is, at least two mount points (drives). The two drives must be in the same device class to allow the server to move the data from reclaimed volumes to other volumes in the same storage pool. A sufficient number of volumes, drives (if appropriate), and mount operators (if appropriate) must be available to handle frequent reclamation requests. For more information about mount limit, see “Mount Limit” on page 107. If the device class for the storage pool does not have two drives, you can specify a reclamation storage pool. For information about how to use a reclamation storage pool for storage pools with only one mount point, see “Reclaiming Volumes in a Storage Pool with One Drive” on page 155.

If you set the reclamation threshold to 50% or greater, the server can combine the usable files from two or more volumes onto a single new volume.

Setting the reclamation threshold to 100% prevents reclamation from occurring. You might want to do this to control when reclamation occurs, to prevent interfering with other server processes. When it is convenient for you and your users, you can lower the reclamation threshold to cause reclamation to begin.

Lowering the Migration Threshold

If you have been running with a high migration threshold and decide you now need to reclaim volumes, you may want to lower the threshold in several steps. Lowering the threshold in steps ensures that volumes with the most reclaimable space are reclaimed first. For example, if you had set the high migration threshold to 100%, first lower the threshold to 98%. Volumes that have reclaimable space of 98% or greater are reclaimed by the server. Lower the threshold again to reclaim more volumes.

If you lower the reclamation threshold while a reclamation process is active, the reclamation process does not immediately stop. If an onsite volume is being reclaimed, the server uses the new threshold setting when the process begins to reclaim the next volume. If offsite volumes are being reclaimed, the server does not use the new threshold setting during the process that is running (because all eligible offsite volumes are reclaimed at the same time).

Use the CANCEL PROCESS command to stop a reclamation process.

Reclaiming Volumes in a Storage Pool with One Drive

When a storage pool has only one mount point (that is, just one drive) available to it through the device class, data cannot be reclaimed from one volume to another within that same storage pool.

To enable volume reclamation for a storage pool that has only one mount point, you can define a *reclamation storage pool* for the server to use when reclaiming volumes. When the server reclaims volumes, the server moves the data from volumes in the original storage pool to volumes in the reclamation storage pool. The server always uses the reclamation storage pool when one is defined, even when the mount limit is greater than one.

If the reclamation storage pool does not have enough space to hold all of the data being reclaimed, the server moves as much of the data as possible into the reclamation storage pool. Any data that could not be moved to volumes in the reclamation storage pool still remains on volumes in the original storage pool.

The pool identified as the reclamation storage pool must be a primary sequential storage pool. The primary purpose of the reclamation storage pool is for temporary storage of reclaimed data. To ensure that data moved to the reclamation storage pool eventually moves back into the original storage pool, specify the original storage pool as the next pool in the storage hierarchy for the reclamation storage pool. For example, if you have a tape library with one drive, you can define a storage pool to be used for reclamation using a device class with a device type of FILE:

```
define stgpool reclaimpool fileclass maxscratch=100
```

Define the storage pool for the tape drive as follows:

```
define stgpool tapepool1 tapeclass maxscratch=100
reclaimstgpool=reclaimpool
```

Finally, update the reclamation storage pool so that data migrates back to the tape storage pool:

```
update stgpool reclaimpool nextstgpool=tapepool1
```

Reclamation for WORM Optical Media

Reclamation for WORM volumes does not mean that you can reuse this write-once media. However, reclamation for WORM volumes does allow you to free library space. Reclamation consolidates data from almost empty volumes to other volumes. You can then eject the empty, used WORM volumes and add new volumes.

Storage pools that are assigned to device classes with a device type of WORM, WORM12, or WORM14 have a default reclamation value of 100. This prevents reclamation of WORM optical media. To allow reclamation, you can set the reclamation value to something lower when defining or updating the storage pool.

Reclamation of Volumes with the Device Type of SERVER

When virtual volumes (volumes with the device type of SERVER) in a primary storage pool are reclaimed, the client data stored on those volumes is sent across the network between the source server and the target server. As a result, the reclamation process can tie up your network resources. To control when reclamation starts for these volumes, consider setting the reclamation threshold to 100% for any primary storage pool that uses virtual volumes. Lower the reclamation threshold at a time when your network is less busy, so that the server can reclaim volumes.

For virtual volumes in a copy storage pool, the server reclaims a volume as follows:

1. The source server determines which files on the volume are still valid.
2. The source server obtains these valid files from a primary storage pool, or if necessary, from an onsite volume (not a virtual volume) in another copy storage pool.
3. The source server writes the files to one or more new virtual volumes in the copy storage pool and updates its database.
4. The server issues a message indicating that the volume was reclaimed.

For information about using the SERVER device type, see “Using Virtual Volumes to Store Data on Another Server” on page 348.

Reclamation for Copy Storage Pools

Reclamation of primary storage pool volumes does not affect copy storage pool files.

Reclamation of volumes in copy storage pools is similar to that of primary storage pools. However, most volumes in copy storage pools may be set to an access mode of offsite, making them ineligible to be mounted. When reclamation occurs and how reclamation processing is done depends on whether the volumes are marked as offsite.

For volumes that are not offsite, reclamation usually occurs after the volume is full and then begins to empty because of file deletion. When the percentage of reclaimable space on a volume rises above the reclamation threshold, the server reclaims the volume. Active files on the volume are rewritten to other volumes in the storage pool, making the original volume available for new files.

For offsite volumes, reclamation can occur when the percentage of unused space on the volume is greater than the reclaim parameter value. The unused space includes both space that has never been used on the volume and space that has become empty because of file deletion. During reclamation, the server copies valid files on offsite volumes from the original files in the primary storage pools. In this way, the server copies valid files on offsite volumes without having to mount these volumes. For more information, see “Reclamation of Offsite Volumes”.

Reclamation of copy storage pool volumes should be done periodically to allow reuse of partially filled volumes that are offsite. Reclamation can be done automatically by setting the reclamation threshold for the copy storage pool to less than 100%. However, you need to consider controlling when reclamation occurs because of how offsite volumes are treated. For more information, see “Controlling When Reclamation Occurs for Offsite Volumes” on page 157.

Virtual Volumes: Virtual volumes (volumes that are stored on another TSM server through the use of a device type of SERVER) cannot be set to the offsite access mode.

Reclamation of Offsite Volumes

As for volumes with other access values, volumes with the access value of offsite are eligible for reclamation if the amount of empty space on a volume exceeds the reclamation threshold for the copy storage pool. The default reclamation threshold for copy storage pools is 100%, which means that reclamation is not performed.

When an offsite volume is reclaimed, the files on the volume are rewritten to a *read/write* volume. Effectively, these files are moved back to the onsite location. The files may be obtained from the offsite volume after a disaster, if the volume has not been reused and the database backup that you use for recovery references the files on the offsite volume.

The server reclaims an offsite volume as follows:

1. The server determines which files on the volume are still valid.
 2. The server obtains these valid files from a primary storage pool, or if necessary, from an onsite volume of a copy storage pool.
 3. The server writes the files to one or more volumes in the copy storage pool and updates the database. If a file is an aggregate file with unused space, the unused space is removed during this process.
 4. A message is issued indicating that the offsite volume was reclaimed.
- For a single storage pool, the server reclaims all offsite volumes that are eligible for reclamation at the same time. Reclaiming all the eligible volumes at the same time minimizes the tape mounts for primary storage pool volumes.

If you have the Tivoli Disaster Recovery Manager product, see “Moving Backup Volumes Onsite” on page 513.

Controlling When Reclamation Occurs for Offsite Volumes

Suppose you plan to make daily storage pool backups to a copy storage pool, then mark all new volumes in the copy storage pool as *offsite* and send them to the offsite storage location. This strategy works well with one consideration if you are using automatic reclamation (the reclamation threshold is less than 100%).

Each day’s storage pool backups will create a number of new copy storage pool volumes, the last one being only partially filled. If the percentage of empty space on this partially filled volume is higher than the reclaim percentage, this volume becomes eligible for reclamation as soon as you mark it offsite. The reclamation process would cause a new volume to be created with the same files on it. The volume you take offsite would then be empty according to the TSM database. If you do not recognize what is happening, you could perpetuate this process by marking the new partially filled volume offsite.

One way to resolve this situation is to keep partially filled volumes onsite until they fill up. However, this would mean a small amount of your data would be without an offsite copy for another day.

If you send copy storage pool volumes offsite, it is recommended you control copy storage pool reclamation by using the default value of 100. This turns reclamation off for the copy storage pool. You can start reclamation processing at desired times by changing the reclamation threshold for the storage pool. To monitor offsite volume utilization and help you decide what reclamation threshold to use, enter the following command:

```
query volume * access=offsite format=detailed
```

Depending on your data expiration patterns, you may not need to do reclamation of offsite volumes each day. You may choose to perform offsite reclamation on a less frequent basis. For example, suppose you ship copy storage pool volumes to and from your offsite storage location once a week. You can run reclamation for the copy storage pool weekly, so that as offsite volumes become empty they are sent back for reuse.

When you do perform reclamation for offsite volumes, the following sequence is recommended:

1. Back up your primary storage pools to copy storage pools.
2. Turn on reclamation for copy storage pools by lowering the reclamation threshold below 100%.
3. When reclamation processing completes, turn off reclamation for copy storage pools by raising the reclamation threshold to 100%.
4. Mark any newly created copy storage pool volumes as offsite and then move them to the offsite location.

This sequence ensures that the files on the new copy storage pool volumes are sent offsite, and are not inadvertently kept onsite because of reclamation.

Using Storage on Another Server for Copy Storage Pools

Another resolution to this problem of partially filled volumes is to use storage on another TSM server (device type of SERVER) for storage pool backups. If the other server is at a different site, the copy storage pool volumes are already offsite, with no moving of physical volumes between the sites. See “Using Virtual Volumes to Store Data on Another Server” on page 348 for more information.

Delaying Reuse of Reclaimed Volumes

You should delay the reuse of any reclaimed volumes in copy storage pools for as long as you keep your oldest database backup. Delaying reuse may help you to recover data under certain conditions during recovery from a disaster. For more information on delaying volume reuse, see “Delaying Reuse of Sequential Access Volumes” on page 467.

How Collocation Affects Reclamation

If collocation is enabled and reclamation occurs, the server tries to reclaim the files for each client node or client file space onto a minimal number of volumes. Therefore, if the volumes are manually mounted, the mount operators must:

- Be aware that a tape volume may be rewound more than once if the server completes a separate pass to move the data for each client node or client file space.
- Mount and dismount multiple volumes to allow the server to select the most appropriate volume on which to move data for each client node or client file space. The server tries to select a volume in the following order:
 1. A volume that already contains files belonging to the client file space or client node
 2. An empty volume
 3. The volume with the most available space
 4. Any available volume

If collocation is disabled and reclamation occurs, the server tries to move usable data to new volumes by using the following volume selection criteria, in the order shown:

1. The volume that contains the most data
2. Any partially full volume
3. An empty predefined volume
4. An empty scratch volume

Estimating Space Needs for Storage Pools

This section provides guidelines for estimating the initial storage space required for your installation. You have the following default random access (disk) storage pools available at installation:

- BACKUPPOOL for backed-up files
- ARCHIVEPOOL for archived files
- SPACEMGPOOL for files migrated from client nodes (space-managed files)

You can add space to these storage pools by adding volumes, or you can define additional storage pools.

As your storage environment grows, you may want to consider how policy and storage pool definitions affect where workstation files are stored. Then you can define and maintain multiple storage pools in a hierarchy that allows you to control storage costs by using sequential access storage pools in addition to disk storage pools, and still provide appropriate levels of service to users.

To help you determine how to adjust your policies and storage pools, get information about how much storage is being used (by client node) and for what purposes in your existing storage pools. For more information on how to do this, see “Requesting Information on the Use of Storage Space” on page 173.

Estimating Space Needs in Random Access Storage Pools

To estimate the amount of storage space required for each random access (disk) storage pool:

- Determine the amount of disk space needed for different purposes:
 - For backup storage pools, provide enough disk space to support efficient daily incremental backups.
 - For archive storage pools, provide sufficient space for a user to archive a moderate size file system without causing migration from the disk storage pool to occur.
 - For storage pools for space-managed files, provide enough disk space to support the daily space-management load from HSM clients, without causing migration from the disk storage pool to occur.
- Decide what percentage of this data you want to keep on disk storage space. Establish migration thresholds to have the server automatically migrate the remainder of the data to less expensive storage media in sequential access storage pools.

See “Choosing Appropriate Migration Threshold Values” on page 141 for recommendations on setting migration thresholds.

Estimating Space for Backed-Up Files in a Random Access Storage Pool

To estimate the total amount of space needed for all backed-up files stored in a single random access (disk) storage pool, use the following formula:

$$\text{Backup space} = \text{WkstSize} * \text{Utilization} * \text{VersionExpansion} * \text{NumWkst}$$

where:

Backup Space

The total amount of storage pool disk space needed.

WkstSize

The average data storage capacity of a workstation. For example, if the typical workstation at your installation has a 4GB hard drive, then the average workstation storage capacity is 4GB.

Utilization

An estimate of the fraction of each workstation disk space used, in the range 0 to 1. For example, if you expect that disks on workstations are 75% full, then use 0.75.

VersionExpansion

An expansion factor (greater than 1) that takes into account the additional backup versions, as defined in the copy group. A rough estimate allows 5% additional files for each backup copy. For example, for a version limit of 2, use 1.05, and for a version limit of 3, use 1.10.

NumWkst

The estimated total number of workstations that the server supports.

If clients use compression, the amount of space required may be less than the amount calculated, depending on whether the data is compressible.

Estimating Space for Archived Files in a Random Access Storage Pool

Estimating the amount of storage space for archived files is more difficult, because the number of archived files generated by users is not necessarily related to the amount of data stored on their workstations.

To estimate the total amount of space needed for all archived files in a single random access (disk) storage pool, determine what percentage of user files are typically archived.

Work with policy administrators to calculate this percentage based on the number and type of archive copy groups defined. For example, if policy administrators have defined archive copy groups for only half of the policy domains in your enterprise, then estimate that you need less than 50% of the amount of space you have defined for backed-up files.

Because additional storage space can be added at any time, you can start with a modest amount of storage space and increase the space by adding storage volumes to the archive storage pool, as required.

Estimating Space Needs in Sequential Access Storage Pools

To estimate the amount of space required for sequential access storage pools, consider:

- The amount of data being migrated from disk storage pools
- The length of time backed-up files are retained, as defined in backup copy groups
- The length of time archived files are retained, as defined in archive copy groups
- How frequently you reclaim unused space on sequential volumes
See “Reclaiming Space in Sequential Access Storage Pools” on page 152 for information about setting a reclamation threshold.
- Whether or not you use collocation to reduce the number of volume mounts required when restoring or retrieving large numbers of files from sequential volumes
If you use collocation, you may need additional tape drives and volumes.
See “Keeping a Client’s Files Together: Collocation” on page 147 for information about using collocation for your storage pools.

- The type of storage devices and sequential volumes supported at your installation

Monitoring Storage Pools and Volumes

Any administrator can query for information about a storage pool by viewing a standard or a detailed report. Use these reports to monitor storage pool usage, including:

- Whether you need to add space to your disk and sequential access storage pools
- The status of the process of migrating data from one to storage pool to the next storage pool in the storage hierarchy
- The use of disk space by cached copies of files that have been migrated to the next storage pool

Monitoring Space Available in a Storage Pool

Monitoring the space available in storage pools is important to ensure that client operations such as backup can complete successfully. To make more space available, you may need to define more volumes for disk storage pools, or add more volumes for sequential access storage pools such as tape. For more information on maintaining a supply of volumes in libraries, see “Managing the Volume Inventory” on page 90.

To request a standard report that shows all storage pools defined to the system, enter:

```
query stgpool
```

Figure 26 shows a standard report with all storage pools defined to the system. To monitor the use of storage pool space, review the *Estimated Capacity* and *Pct Util* columns.

Storage Pool Name	Device Class Name	Estimated Capacity (MB)	Pct Util	Pct Migr	High Mig Pct	Low Mig Pct	Next Storage Pool
ARCHIVEPOOL	DISK	0.0	0.0	0.0	90	70	
BACKTAPE	TAPE	180.0	85.0	100.0	90	70	
BACKUPPOOL	DISK	80.0	51.6	51.6	50	30	BACKTAPE
COPYPOOL	TAPE	300.0	42.0				
ENGBACK1	DISK	0.0	0.0	0.0	85	40	BACKTAPE

Figure 26. Information about Storage Pools

Estimated Capacity

Specifies the space available in the storage pool in megabytes.

For a disk storage pool, this value reflects the total amount of available space in the storage pool, including any volumes that are varied offline.

For a sequential access storage pool, this value is an estimate of the total amount of available space on all volumes in the storage pool. The total includes volumes with any access mode (read-write, unavailable, read-only, offsite, or destroyed). The total includes scratch volumes that the storage pool can acquire only when the storage pool is using at least one scratch volume for data.

Volumes in a sequential access storage pool, unlike those in a disk storage pool, do not contain a precisely known amount of space. Data is written to a volume as

necessary until the end of the volume is reached. For this reason, the estimated capacity is truly an *estimate* of the amount of available space in a sequential access storage pool.

Pct Util

Specifies, as a percentage, the space used in each storage pool.

For disk storage pools, this value reflects the total number of disk blocks currently allocated by TSM. Space is allocated for backed-up, archived, or space-managed files that are eligible for server migration, cached files that are copies of server-migrated files, and files that reside on any volumes that are varied offline.

Note: The value for Pct Util can be higher than the value for Pct Migr if you query for storage pool information while a client transaction (such as a backup) is in progress. The value for Pct Util is determined by the amount of space actually allocated (while the transaction is in progress). The value for Pct Migr represents only the space occupied by *committed* files. At the end of the transaction, Pct Util and Pct Migr become synchronized.

For sequential access storage pools, this value is the percentage of the total bytes of storage available that are currently being used to store active data (data that is not expired). Because the server can only estimate the available capacity of a sequential access storage pool, this percentage also reflects an estimate of the actual utilization of the storage pool.

Example: Monitoring the Capacity of a Backup Storage Pool

Figure 26 on page 161 shows that the estimated capacity for a disk storage pool named BACKUPPOOL is 80MB, which is the amount of available space on disk storage. More than half (51.6%) of the available space is occupied by either backup files or cached copies of backup files.

The estimated capacity for the tape storage pool named BACKTAPE is 180MB, which is the total estimated space available on all tape volumes in the storage pool. This report shows that 85% of the estimated space is currently being used to store workstation files.

Note: This report also shows that volumes have not yet been defined to the ARCHIVEPOOL and ENGBACK1 storage pools, because the storage pools show an estimated capacity of 0.0MB.

Monitoring the Use of Storage Pool Volumes

Task	Required Privilege Class
Display information about volumes	Any administrator

You can query the server for information about storage pool volumes:

- General information about a volume, such as the following:
 - Current access mode and status of the volume
 - Amount of available space on the volume
 - Location
- Contents of a storage pool volume (user files on the volume)

- The volumes that are used by a client node

Getting General Information about Storage Pool Volumes

To request general information about all volumes defined to the server, enter:

```
query volume
```

Figure 27 shows an example of the output of this standard query. The example illustrates that data is being stored on the 8mm tape volume named WREN01, as well as on several other volumes in various storage pools.

Volume Name	Storage Pool Name	Device Class Name	Estimated Capacity (MB)	Pct Util	Volume Status
/dev/raixvol1	AIXPOOL1	DISK	240.0	26.3	On-Line
/dev/raixvol2	AIXPOOL2	DISK	240.0	36.9	On-Line
/dev/rdosvol1	DOSPOOL1	DISK	240.0	72.2	On-Line
/dev/rdosvol2	DOSPOOL2	DISK	240.0	74.1	On-Line
/dev/ros2vol1	OS2POOL1	DISK	240.0	55.7	On-Line
/dev/ros2vol2	OS2POOL2	DISK	240.0	51.0	On-Line
WREN00	TAPEPOOL	TAPE8MM	2,472.0	0.0	Filling
WREN01	TAPEPOOL	TAPE8MM	2,472.0	2.2	Filling

Figure 27. Information about Storage Pool Volumes

To query the server for a detailed report on volume WREN01 in the storage pool named TAPEPOOL, enter:

```
query volume wren01 format=detailed
```

Figure 28 on page 164 shows the output of this detailed query. Table 15 on page 164 gives some suggestions on how you can use the information.

```

Volume Name: WREN01
Storage Pool Name: TAPEPOOL
Device Class Name: TAPE8MM
Estimated Capacity (MB): 2,472.0
Pct Util: 26.3
Volume Status: Filling
Access: Read/Write
Pct. Reclaimable Space: 5.3
Scratch Volume?: No
In Error State?: No
Number of Writable Sides: 1
Number of Times Mounted: 4
Write Pass Number: 2
Approx. Date Last Written: 12/04/1996 11:33:26
Approx. Date Last Read: 12/03/1996 16:42:55
Date Became Pending:
Number of Write Errors: 0
Number of Read Errors: 0
Volume Location:
Last Update by (administrator): TANAGER
Last Update Date/Time: 12/02/1996 13:20:14

```

Figure 28. Detailed Information for a Storage Pool Volume

Table 15. Using the Detailed Report for a Volume

Task	Fields and Description
Ensure the volume is available	<p><i>Volume Status</i></p> <p><i>Access</i></p> <hr/> <p>Check the <i>Volume Status</i> to see if a disk volume has been varied offline, or if a sequential access volume is currently being filled with data.</p> <p>Check the <i>Access</i> to determine whether files can be read from or written to this volume.</p>
Monitor the use of storage space	<p><i>Estimated Capacity</i></p> <p><i>Pct Util</i></p> <hr/> <p>The <i>Estimated Capacity</i> is determined by the device class associated with the storage pool to which this volume belongs. Based on the estimated capacity, the system tracks the percentage of space occupied by client files (<i>Pct Util</i>). In this example, 26.3% of the estimated capacity is currently in use.</p>
Monitor the error status of the volume.	<p><i>Number of Write Errors</i></p> <p><i>Number of Read Errors</i></p> <hr/> <p>The server reports when the volume is in an error state and automatically updates the access mode of the volume to read-only. The <i>Number of Write Errors</i> and <i>Number of Read Errors</i> indicate the type and severity of the problem. Audit a volume when it is placed in error state. See “Auditing a Storage Pool Volume” on page 487 for information about auditing a volume.</p>

Table 15. Using the Detailed Report for a Volume (continued)

Task	Fields and Description
Monitor the life of sequential access volumes that you have defined to the storage pool.	<p data-bbox="565 264 873 422"><i>Scratch Volume?</i> <i>Write Pass Number</i> <i>Number of Times Mounted</i> <i>Approx. Date Last Written</i> <i>Approx. Date Last Read</i></p> <p data-bbox="565 432 1471 653">The server maintains usage statistics on volumes that are defined to storage pools. Statistics on a volume explicitly defined by an administrator remain for as long as the volume is defined to the storage pool. The server continues to maintain the statistics on defined volumes even as the volume is reclaimed and reused. However, the server deletes the statistics on the usage of a scratch volume when the volume returns to scratch status (after reclamation or after all files are deleted from the volume).</p> <p data-bbox="565 674 1471 737">In this example, WREN01 is a volume defined to the server by an administrator, not a scratch volume (<i>Scratch Volume?</i> is <i>No</i>).</p> <p data-bbox="565 758 1471 1104">The <i>Write Pass Number</i> indicates the number of times the volume has been written to, starting from the beginning of the volume. A value of one indicates that a volume is being used for the first time. In this example, WREN01 has a write pass number of two, which indicates space on this volume may have been reclaimed or deleted once before. Compare this value to the specifications provided with the media that you are using. The manufacturer may recommend a maximum number of write passes for some types of tape media. You may need to retire your tape volumes after reaching the maximum passes to better ensure the integrity of your data. To retire a volume, move the data off the volume by using the MOVE DATA command. See “Moving Files from One Volume to Another Volume” on page 176.</p> <p data-bbox="565 1136 1471 1325">Use the <i>Number of Times Mounted</i>, the <i>Approx. Date Last Written</i>, and the <i>Approx. Date Last Read</i> to help you estimate the life of the volume. For example, if more than six months have passed since the last time this volume has been written to or read from, audit the volume to ensure that files can still be accessed. See “Auditing a Storage Pool Volume” on page 487 for information about auditing a volume.</p>
Determine the location of a volume in a sequential access storage pool.	<p data-bbox="565 1335 667 1367"><i>Location</i></p> <p data-bbox="565 1377 1471 1503">When you define or update a sequential access volume, you can give location information for the volume. The detailed query displays this location name. The location information can be useful to help you track volumes, for example, offsite volumes in copy storage pools.</p>
Determine if a volume in a sequential access storage pool is waiting for the reuse delay period to expire.	<p data-bbox="565 1514 813 1545"><i>Date Became Pending</i></p> <p data-bbox="565 1556 1471 1713">A sequential access volume is placed in the pending state after the last file is deleted or moved from the volume. All the files that the pending volume had contained were expired or deleted, or were moved from the volume. Volumes remain in the pending state for as long as specified with the REUSEDELAY parameter for the storage pool to which the volume belongs.</p>

Whether or not a volume is full, at times the Pct Util (percent of the volume utilized) plus the Pct Reclaimable Space (percent of the volume that can be reclaimed) may add up to more than 100 percent. This can happen when a volume contains aggregates that have empty space because of files in the aggregates that have expired or been deleted. The Pct Util field shows all space occupied by both non-aggregated files and aggregates, including empty

space within aggregates. The Pct Reclaimable Space field includes any space that is reclaimable on the volume, also including empty space within aggregates. Because both fields include the empty space within aggregates, these values may add up to more than 100 percent. For more information about aggregates, see “How the Server Groups Files before Storing” on page 134 and “Requesting Information on the Use of Storage Space” on page 173.

Getting Information about the Contents of a Storage Pool Volume

Any administrator can request information about the contents of a storage pool volume. Viewing the contents of a storage volume is useful when a volume is damaged or before you do the following:

- Request the server to correct any inconsistencies (AUDIT VOLUME command)
- Move files from one volume to other volumes
- Delete a volume from a storage pool

Because the server tracks the contents of a storage volume through its database, the server does not need to access the requested volume to determine its contents.

The report generated by a QUERY CONTENT command shows the contents of a volume. This report can be extremely large and may take a long time to produce. To reduce the size of this report, narrow your search by selecting one or all of the following search criteria:

Node name

Name of the node whose files you want to include in the query.

File space name

Names of file spaces to include in the query. File space names are case-sensitive and must be entered exactly as they are known to the server. Use the QUERY FILESPACE command to find the correct capitalization.

Number of files to be displayed

Enter a positive integer, such as 10, to list the first ten files stored on the volume. Enter a negative integer, such as -15, to list the last fifteen files stored on the volume.

Filetype

Specifies which types of files, that is, backup versions, archive copies, or space-managed files, or a combination of these.

Format of how the information is displayed

Standard or detailed information for the specified volume.

Damaged

Specifies whether to restrict the query output either to files that are known to be damaged, or to files that are not known to be damaged.

Copied

Specifies whether to restrict the query output to either files that are backed up to a copy storage pool, or to files that are not backed up to a copy storage pool.

Viewing a Standard Report on the Contents of a Volume

To view the first seven backup files on volume WREN01 from file space /usr on client node TOMC, for example, enter:

```
query content wren01 node=tomc filespace=/usr count=7 type=backup
```

Figure 29 displays a standard report which shows the first seven files from file space /usr on TOMC stored in WREN01.

Node Name	Type	Filespace Name	Client's Name for File
TOMC	Bkup	/usr	/bin/ acctcom
TOMC	Bkup	/usr	/bin/ acledit
TOMC	Bkup	/usr	/bin/ aclput
TOMC	Bkup	/usr	/bin/ admin
TOMC	Bkup	/usr	/bin/ ar
TOMC	Bkup	/usr	/bin/ arcv
TOMC	Bkup	/usr	/bin/ banner

Figure 29. A Standard Report on the Contents of a Volume

The report lists logical files on the volume. If a file on the volume is an aggregate of logical files (backed-up or archived client files), all logical files that are part of the aggregate are included in the report. An aggregate file can be stored on more than one volume, and therefore not all of the logical files in the report may actually be stored on the volume being queried.

Viewing a Detailed Report on the Contents of a Volume

To display detailed information about the files stored on volume VOL1, enter:

```
query content vol1 format=detailed
```

Figure 30 on page 168 displays a detailed report that shows the files stored on VOL1. The report lists logical files and shows whether each file is part of an aggregate file. If a logical file is stored as part of an aggregate file, the information in the **Segment Number**, **Stored Size**, and **Cached Copy?** fields apply to the aggregate, not to the individual logical file.

If a logical file is part of an aggregate file, the **Aggregated?** field shows the sequence number of the logical file within the aggregate file. For example, the **Aggregated?** field contains the value 2/4 for the file AB0CTGLO.IDE, meaning that this file is the second of four files in the aggregate. All logical files that are part of an aggregate are included in the report. An aggregate file can be stored on more than one volume, and therefore not all of the logical files in the report may actually be stored on the volume being queried.

For disk volumes, the **Cached Copy?** field identifies whether the file is a cached copy of a file that has been migrated to the next storage pool in the hierarchy.

```

Node Name: DWE
Type: Bkup
Filespace Name: OS2
Client's Name for File: \ README
Aggregated?: No
Stored Size: 27,089
Segment Number: 1/1
Cached Copy?: No

Node Name: DWE
Type: Bkup
Filespace Name: DRIVE_L_K:
Client's Name for File: \COMMON\DSMCOMM\ AB0CTCOM.ENT
Aggregated?: 1/4
Stored Size: 202,927
Segment Number: 1/1
Cached Copy?: No

Node Name: DWE
Type: Bkup
Filespace Name: DRIVE_L_K:
Client's Name for File: \COMMON\DSMCOMM\ AB0CTGLO.IDE
Aggregated?: 2/4
Stored Size: 202,927
Segment Number: 1/1
Cached Copy?: No

Node Name: DWE
Type: Bkup
Filespace Name: DRIVE_L_K:
Client's Name for File: \COMMON\DSMCOMM\ AB0CTTRD.IDE
Aggregated?: 3/4
Stored Size: 202,927
Segment Number: 1/1
Cached Copy?: No

Node Name: DWE
Type: Bkup
Filespace Name: DRIVE_L_K:
Client's Name for File: \COMMON\DSMCOMM\ AB0CTSYM.ENT
Aggregated?: 4/4
Stored Size: 202,927
Segment Number: 1/1
Cached Copy?: No

```

Figure 30. Viewing a Detailed Report of the Contents of a Volume

Finding the Volumes Used by a Client Node

You can use the server's SELECT command to find the sequential volumes used by a client node. Use SELECT to perform an SQL query of the VOLUMEUSAGE table in the TSM database. For example, to get a list of volumes used by the EXCH1 client node in the TAPEPOOL storage pool, enter the following command:

```
select volume_name from volumeusage where node_name='EXCH1' and
stgpool_name='TAPEPOOL'
```

The results are something like the following:

```
VOLUME_NAME
-----
TAPE01
TAPE08
TAPE13
TAPE21
```

For more information about using the SELECT command, see *Administrator's Reference*.

Monitoring Migration Processes

Four fields on the standard storage pool report provide you with information about the migration process. They include:

Pct Migr

Specifies the percentage of data in each storage pool that can be migrated. This value is used to determine when to start or stop migration.

For disk storage pools, this value represents the amount of disk space occupied by backed-up, archived, or space-managed files that can be migrated to another storage pool, including files on volumes that are varied offline. Cached data are excluded in the Pct Migr value.

For sequential access storage pools, this value is the percentage of the total volumes in the storage pool that actually contain data at the moment. For example, assume a storage pool has four explicitly defined volumes, and a maximum scratch value of six volumes. If only two volumes actually contain data at the moment, then Pct Migr will be 20%.

This field is blank for copy storage pools.

High Mig Pct

Specifies when the server can begin migrating data from this storage pool. Migration can begin when the percentage of data that can be migrated reaches this threshold. (This field is blank for copy storage pools.)

Low Mig Pct

Specifies when the server can stop migrating data from this storage pool. Migration can end when the percentage of data that can be migrated falls below this threshold. (This field is blank for copy storage pools.)

Next Storage Pool

Specifies the primary storage pool destination to which data is migrated. (This field is blank for copy storage pools.)

Example: Monitoring the Migration of Data Between Storage Pools

Figure 26 on page 161 shows that the migration thresholds for BACKUPPOOL storage pool are set to 50% for the *high migration threshold* and 30% for the *low migration threshold*.

When the amount of migratable data stored in the BACKUPPOOL storage pool reaches 50%, the server can begin to migrate files to BACKTAPE.

To monitor the migration of files from BACKUPPOOL to BACKTAPE, enter:

```
query stgpool back*
```

See Figure 31 on page 170 for an example of the results of this command.

If caching is on for a disk storage pool and files are migrated, the Pct Util value does not change because the cached files still occupy space in the disk storage pool. However, the Pct Migr value decreases because the space occupied by cached files is no longer migratable.

Storage Pool Name	Device Class Name	Estimated Capacity (MB)	Pct Util	Pct Migr	High Mig Pct	Low Mig Pct	Next Storage Pool
BACKTAPE	TAPE	180.0	95.2	100.0	90	70	
BACKUPPOOL	DISK	80.0	51.6	28.8	50	30	BACKTAPE

Figure 31. Information on Backup Storage Pools

You can query the server to monitor the migration process by entering:
query process

A message similar to Figure 32 is displayed:

Process Number	Process Description	Status
2	Migration	Disk Storage Pool BACKUPPOOL, Moved Files: 1086, Moved Bytes: 25555579, Unreadable Files: 0, Unreadable Bytes: 0

Figure 32. Information on the Migration Process

When migration is finished, the server displays the following message:

```
ANR1101I Migration ended for storage pool BACKUPPOOL.
```

Handling Problems during the Migration Process

A problem can occur that causes the migration process to be suspended. For example, there may not be sufficient space in the storage pool to which data is being migrated. When migration is suspended, the process might be retried.

At this point, a system administrator can:

- Cancel the migration process. See “Canceling the Migration Process” on page 171 for additional information.
- End the migration process by changing the attributes of the storage pool from which data is being migrated. See “Ending the Migration Process by Changing Storage Pool Characteristics” on page 171 for additional information.
- Provide additional space. See “Providing Additional Space for the Migration Process” on page 171 for additional information.

The server attempts to restart the migration process every 60 seconds for several minutes and if not successful will terminate the migration process.

Canceling the Migration Process

To stop server migration when a problem occurs or when you need the resources the process is using, you can cancel the migration.

First determine the identification number of the migration process by entering:
query process

A message similar to Figure 33 is displayed:

Process Number	Process Description	Status
1	Migration	ANR1113W Migration suspended for storage pool BACKUPPOOL - insufficient space in subordinate storage pool.

Figure 33. Getting the Identification Number of the Migration Process

Then you can cancel the migration process by entering:
cancel process 1

Ending the Migration Process by Changing Storage Pool Characteristics

Some errors cause the server to continue attempting to restart the migration process after 60 seconds. (If the problem still exists after several minutes, the migration process will end.) To stop the repeated attempts at restart, you can change some characteristics of the storage pool from which data is being migrated. Depending on your environment, you can:

- Set higher migration thresholds for the storage pool from which data is being migrated. The higher threshold means the storage pool must have more migratable data before migration starts. This change delays migration.
In the example in “Example: Monitoring the Migration of Data Between Storage Pools” on page 169, you could update the disk storage pool BACKUPPOOL.
- Add volumes to the pool from which data is being migrated. Adding volumes decreases the percentage of data that is migratable (Pct Migr).
In the example in “Example: Monitoring the Migration of Data Between Storage Pools” on page 169, you could add volumes to the disk storage pool BACKUPPOOL to increase its storage capacity.

Note: Do this only if you received an out-of-space message for the storage pool to which data is being migrated.

Providing Additional Space for the Migration Process

A migration process can be suspended because of insufficient space in the storage pool to which data is being migrated. To allow the migration process to complete, you can provide additional storage volumes for that storage pool.

In the example in “Example: Monitoring the Migration of Data Between Storage Pools” on page 169 , you could add volumes to the BACKTAPE storage pool or increase the maximum number of scratch tapes allowed for it. Either way, you increase the storage capacity of BACKTAPE.

Monitoring the Use of Cache Space on Disk Storage

The Pct Util value includes cached data on a volume (when cache is enabled) and the Pct Migr value excludes cached data. Therefore, when cache is enabled and migration occurs, the Pct Migr value decreases while the Pct Util value remains the same. The Pct Util value remains the same because the migrated data remains on the volume as cached data. In this case, the Pct Util value only decreases when the cached data expires.

If you update a storage pool from CACHE=YES to CACHE=NO, the cached files will not disappear immediately. The Pct Util value will be unchanged. The cache space will be reclaimed over time as the server needs the space, and no additional cached files will be created.

To determine whether cache is being used on disk storage and to monitor how much space is being used by cached copies, query the server for a detailed storage pool report. For example, to request a detailed report for BACKUPPOOL, enter:

```
query stgpool backuppool format=detailed
```

Figure 34 displays a detailed report for the storage pool.

```
Storage Pool Name: BACKUPPOOL
Storage Pool Type: PRIMARY
Device Class Name: DISK
Estimated Capacity (MB): 80.0
    Pct Util: 42.0
    Pct Migr: 29.6
    Pct Logical: 82.1
    High Mig Pct: 50
    Low Mig Pct: 30
Migration Processes:
    Next Storage Pool: BACKTAPE
Reclaim Storage Pool:
Maximum Size Threshold: No Limit
    Access: Read/Write
Description:
    Overflow Location:
Cache Migrated Files?: Yes
    Collocate?:
Reclamation Threshold:
Maximum Scratch Volumes Allowed:
    Delay Period for Volume Reuse: 0 Day(s)
    Migration in Progress?: Yes
    Amount Migrated (MB): 0.10
Elapsed Migration Time (seconds): 5
    Reclamation in Progress?:
Volume Being Migrated/Reclaimed:
    Last Update by (administrator): SERVER_CONSOLE
    Last Update Date/Time: 04/07/1997 16:47:49
```

Figure 34. Detailed Storage Pool Report

When **Cache Migrated Files?** is set to **Yes**, the value for Pct Util should not change because of migration, because cached copies of files migrated to the next storage pool remain in disk storage.

This example shows that utilization remains at 42%, even after files have been migrated to the BACKTAPE storage pool, and the current amount of data eligible for migration is 29.6%.

When **Cache Migrated Files?** is set to **No**, the value for Pct Util more closely matches the value for Pct Migr because cached copies are not retained in disk storage.

Requesting Information on the Use of Storage Space

Task	Required Privilege Class
Query the server for information about server storage	Any administrator

Any administrator can request information about server storage occupancy. Use the QUERY OCCUPANCY command for reports with information broken out by node or file space. Use this report to determine the amount of space used by:

- Client node and file space
- Storage pool or device class
- Type of data (backup, archive, or space-managed)

Each report gives two measures of the space in use by a storage pool:

- Logical space occupied
The amount of space used for logical files. A logical file is a client file. A logical file is stored either as a single physical file, or in an aggregate with other logical files.
- Physical space occupied
The amount of space used for physical files. A physical file is either a single logical file, or an aggregate file composed of logical files.
An aggregate file may contain empty space that had been used by logical files that are now expired or deleted. Therefore, the amount of space used by physical files is equal to or greater than the space used by logical files. The difference gives you a measure of how much unused space any aggregate files may have. The unused space can be reclaimed in sequential storage pools.

You can also use this report to evaluate the average size of workstation files stored in server storage.

Amount of Space Used by Client Node

Any administrator can request information about the space used by each client node and file space:

- How much data has been backed up, archived, or migrated to server storage
- How many of the files that are in server storage have been backed up to a copy storage pool
- The amount of storage space being used

To determine the amount of server storage space used by the /home file space belonging to the client node MIKE, for example, enter:

```
query occupancy mike /home
```

Remember that file space names are case-sensitive and must be entered exactly as they are known to the server. Use the QUERY FILESPACE command to determine the correct capitalization. For more information, see “Managing File Spaces” on page 204.

Figure 35 shows the results of the query. The report shows the number of files backed up, archived, or migrated from the /home file space belonging to MIKE. The report also shows how much space is occupied in each storage pool.

If you back up the ENGBACK1 storage pool to a copy storage pool, the copy storage pool would also be listed in the report. To determine how many of the client node’s files in the primary storage pool have been backed up to a copy storage pool, compare the number of files in each pool type for the client node.

Node Name	Type	Filespace Name	Storage Pool Name	Number of Files	Physical Space Occupied (MB)	Logical Space Occupied (MB)
MIKE	Bkup	/home	ENGBACK1	513	3.52	3.01

Figure 35. A Report of the Occupancy of Storage Pools by Client Node

Amount of Space Used by Storage Pool or Device Class

You can monitor the amount of space being used by an individual storage pool, a group of storage pools, or storage pools categorized by a particular device class. Creating occupancy reports on a regular basis can help you with capacity planning.

To query the server for the amount of data stored in backup tape storage pools belonging to the TAPECLASS device class, for example, enter:

```
query occupancy devclass=tapeclass
```

Figure 36 on page 175 displays a report on the occupancy of tape storage pools assigned to the TAPECLASS device class.

Node Name	Type	Filespace Name	Storage Pool Name	Number of Files	Physical Space Occupied (MB)	Logical Space Occupied (MB)
CAROL	Arch	OS2C	ARCHTAPE	5	.92	.89
CAROL	Bkup	OS2C	BACKTAPE	21	1.02	1.02
PEASE	Arch	/home/pease/dir	ARCHTAPE	492	18.40	18.40
PEASE	Bkup	/home/pease/dir	BACKTAPE	33	7.60	7.38
PEASE	Bkup	/home/pease/dir1	BACKTAPE	2	.80	.80
TOMC	Arch	/home/tomc/driver5	ARCHTAPE	573	20.85	19.27
TOMC	Bkup	/home	BACKTAPE	13	2.02	1.88

Figure 36. A Report on the Occupancy of Storage Pools by Device Class

Note: For archived data, you may see “(archive)” in the Filespace Name column instead of a file space name. This means that the data was archived before collocation by file space was supported by the server.

Amount of Space Used by Backed-Up, Archived, or Space-Managed Files

You can query the server for the amount of space used by backed-up, archived, and space-managed files. By determining the average size of workstation files stored in server storage, you can estimate how much storage capacity you might need when registering new client nodes to the server. See “Estimating Space Needs for Storage Pools” on page 159 and “Estimating Space for Archived Files in a Random Access Storage Pool” on page 160 for information about planning storage space.

To request a report about backup versions stored in the disk storage pool named `BACKUPPOOL`, for example, enter:

```
query occupancy stgpool=backuppool type=backup
```

Figure 37 displays a report on the amount of server storage used for backed-up files.

Node Name	Type	Filespace Name	Storage Pool Name	Number of Files	Physical Space Occupied (MB)	Logical Space Occupied (MB)
CAROL	Bkup	OS2C	BACKUPPOOL	513	23.52	23.52
CAROL	Bkup	OS2D	BACKUPPOOL	573	20.85	20.85
PEASE	Bkup	/marketing	BACKUPPOOL	132	12.90	9.01
PEASE	Bkup	/business	BACKUPPOOL	365	13.68	6.18
TOMC	Bkup	/	BACKUPPOOL	177	21.27	21.27

Figure 37. A Report of the Occupancy of Backed-Up Files in Storage Pools

To determine the average size of backup versions stored in `BACKUPPOOL`, complete the following steps using the data provided in Figure 37:

1. Add the number of megabytes of space occupied by backup versions.

In this example, backup versions occupy 92.22MB of space in `BACKUPPOOL`.

2. Add the number of files stored in the storage pool.
In this example, 1760 backup versions reside in BACKUPPOOL.
3. Divide the space occupied by the number of files to determine the average size of each file backed up to the BACKUPPOOL.
In this example, the average size of each workstation file backed up to BACKUPPOOL is about 0.05MB, or approximately 50KB.

You can use this average to estimate the capacity required for additional storage pools that are defined to the server.

Moving Files from One Volume to Another Volume

You can move files from one volume to another volume in the same or a different storage pool. The volumes can be onsite volumes or offsite volumes. During normal operations, you do not need to move data. You might need to move data in some situations, for example, when you need to salvage any readable data from a damaged TSM volume.

During the data movement process, the server:

- Moves any readable files to available volumes in the specified destination storage pool
- Deletes any cached copies from a disk volume
- Attempts to bypass any files that previously were marked as damaged

During the data movement process, users cannot access the volume to restore or retrieve files, and no new files can be written to the volume.

Note: Files in a copy storage pool do not move when primary files are moved.

Task	Required Privilege Class
Move files from a volume in any storage pool to an available volume in any storage pool	System or unrestricted storage
Move files from one volume to an available volume in any storage pool to which you are authorized	Restricted storage

Moving Data to Other Volumes in the Same Storage Pool

Moving files from one volume to other volumes in the same storage pool is useful:

- When you want to free up all space on a volume so that it can be deleted from the TSM server
See “Deleting Storage Pool Volumes” on page 184 for information about deleting backed-up, archived, or space-managed data before you delete a volume from a storage pool.
- When you need to salvage readable files from a volume that has been damaged
- When you want to delete cached files from disk volumes
If you want to force the removal of cached files, you can delete them by moving data from one volume to another volume. During the move process, the server deletes cached files remaining on disk volumes.

If you move data between volumes within the same storage pool and you run out of space in the storage pool before all data is moved from the target volume, then you cannot move all the data from the target volume. In this case, consider moving data to available space in another storage pool as described in “Moving Data to Another Storage Pool”.

Moving Data to Another Storage Pool

You can move all data from a volume in one storage pool to volumes in another storage pool. When you specify a target storage pool that is different than the source storage pool, the server uses the storage hierarchy to move data if more space is required.

Note: Data cannot be moved from a primary storage pool to a copy storage pool. Data in a copy storage pool cannot be moved to any other storage pool.

You can move data from random access storage pools to sequential access storage pools. For example, if you have a damaged disk volume and you have a limited amount of disk storage space, you could move all files from the disk volume to a tape storage pool. Moving files from a disk volume to a sequential storage pool may require many volume mount operations if the target storage pool is collocated. Ensure that you have sufficient personnel and media to move files from disk to sequential storage.

Moving Data from an Offsite Volume in a Copy Storage Pool

You can move data from offsite volumes without bringing the volumes onsite. Processing of the MOVE DATA command for primary storage pool volumes does not affect copy storage pool files.

Processing of the MOVE DATA command for volumes in copy storage pools is similar to that of primary storage pools, with the following exceptions:

- Most volumes in copy storage pools may be set to an access mode of *offsite*, making them ineligible to be mounted. During processing of the MOVE DATA command, valid files on offsite volumes are copied from the original files in the primary storage pools. In this way, valid files on offsite volumes are copied without having to mount these volumes. These new copies of the files are written to another volume in the copy storage pool.
- With the MOVE DATA command, you can move data from any primary storage pool volume to any primary storage pool. However, you can move data from a copy storage pool volume *only* to another volume within the same copy storage pool.

When you move files from a volume marked as offsite, the server does the following:

1. Determines which files are still active on the volume from which you are moving data
2. Obtains these files from a primary storage pool or from another copy storage pool
3. Copies the files to one or more volumes in the destination copy storage pool

Procedure for Moving Data

1. Before you move files from a volume, complete the following steps:
 - If you want to ensure that no new files are written to a volume after you move data from it, change the volume’s access mode to read-only. This prevents the server from filling the volume with data again as soon as data is moved. You might want to do this if you want to delete the volume.

See “Updating Storage Pool Volumes” on page 130 for information about updating the access mode of a storage pool volume.

- Ensure sufficient space is available on volumes within the specified destination storage pool by:
 - a. Querying the source storage volume to determine how much space is required on other volumes. See “Monitoring the Use of Storage Pool Volumes” on page 162 for information about requesting information about a storage volume.
 - b. Querying the specified destination storage pool to ensure there is sufficient capacity to store the files being moved. See “Monitoring Space Available in a Storage Pool” on page 161 for information about querying a storage pool.

If you need more storage space, define volumes or increase the maximum number of scratch volumes in the specified destination storage pool. See “Defining Storage Pool Volumes” on page 130 for preparing volumes to be used for server storage.

- If you are moving files from a volume in a sequential storage pool to another volume in the same storage pool, ensure that the mount limit of the device class associated with the storage pool is greater than one.

See “Requesting Information about a Device Class” on page 114 for requesting information about the mount limit value for the device class.

- If you are moving files from a tape volume to a tape storage pool, ensure that the two tape drives required are available.

2. Move the data using the MOVE DATA command.

For example, to move the files stored in the /dev/vol3 volume to any available volume in the STGTMP1 storage pool, enter:

```
move data /dev/vol3 stgpool=stgtmp1
```

When you move data from a volume, the server starts a background process and sends informational messages, such as:

```
ANR1140I Move Data process started for volume /dev/vol3  
(process ID 32).
```

The command may be run in the foreground on an administrative client by issuing the command with the WAIT=YES parameter.

Note: A volume may not be totally empty after a move data operation completes. For example, the server may be unable to relocate one or more files to another volume because of input/output errors on the device or because errors were found in the file. You can delete the volume with DISCARDATA=YES to delete the volume and any remaining files. The server then deletes the remaining files that had I/O or other errors.

Requesting Information about the Data Movement Process

To request information on the data movement process, enter:

```
query process
```


Figure 38 shows an example of the report that you receive about the data movement process.

Process Number	Process Description	Status
32	Move Data	Volume /dev/vol3, (storage pool BACKUPPOOL), Target Pool STGTMP1, Moved Files: 49, Moved Bytes: 9,121,792, Unreadable Files: 0, Unreadable Bytes: 0. Current File (bytes): 3,522,560 Current output volume: VOL1.

Figure 38. Information on the Data Movement Process

Reclaiming Space in Aggregates During Data Movement

Empty space accumulates in a file aggregate as logical files in that aggregate are deleted. During reclamation processing, the aggregate is reconstructed and this empty space is removed. However, you cannot start reclamation processing only for specific volumes. To reconstruct an aggregate for a specific volume, you can issue the MOVE DATA command with the RECONSTRUCT parameter. In this way, you can move data within a sequential-access storage pool without moving any expired files in the aggregates. You may want to do this if the expired files contain sensitive data and must be purged for legal reasons.

For example, to move the files stored in volume /dev/vol3 to any available volume in the STGTMP1 storage pool and reconstruct the aggregates in that volume, enter:

```
move data /dev/vol3 stgpool=stgtmp1 reconstruct=yes
```

Monitoring the Movement of Data between Volumes

You can query the server for volume information to monitor the movement of data between volumes. For example, to see how much data has moved from the source volume in the move operation example, enter:

```
query volume /dev/vol3 stgpool=backuppool
```

Near the beginning of the move process, querying the volume from which data is being moved gives the following results:

Volume Name	Storage Pool Name	Device Class Name	Estimated Capacity (MB)	Pct Util	Volume Status
/dev/vol3	BACKUPPOOL	DISK	15.0	59.9	On-Line

Querying the volume to which data is being moved (VOL1, according to the process query output) gives the following results:

Volume Name	Storage Pool Name	Device Class Name	Estimated Capacity (MB)	Pct Util	Volume Status
-----	-----	-----	-----	-----	-----
VOL1	STGTMP1	8500DEV	4,944.0	0.3	Filling

At the end of the move process, querying the volume from which data was moved gives the following results:

Volume Name	Storage Pool Name	Device Class Name	Estimated Capacity (MB)	Pct Util	Volume Status
-----	-----	-----	-----	-----	-----
/dev/vo13	BACKUPOOL	DISK	15.0	0.0	On-Line

Renaming a Storage Pool

You can rename a storage pool. You may need to do this when distributing policy using enterprise configuration. See “Setting Up a Managed Server” on page 324.

When you rename a storage pool, any administrators with restricted storage privilege for the storage pool automatically have restricted storage privilege to the storage pool under the new name. If the renamed storage pool is in a storage pool hierarchy, the hierarchy is preserved.

Copy groups and management classes may contain a storage pool name as a destination. If you rename a storage pool used as a destination, the destination in a copy group or management class is not changed to the new name of the storage pool. To continue to use the policy with the renamed storage pool as a destination, you need to change the destination in the copy groups and management classes. You then activate the policy set with the changed destinations.

Defining a Copy Storage Pool

Use a copy storage pool to back up one or more primary storage pools. See Table 17 on page 182 and “Backing Up Storage Pools” on page 465 for more information. When you define a copy storage pool, be prepared to provide some or all of the information in Table 16.

Table 16. Information for Defining a Copy Storage Pool

Information	Explanation
Device class	Specifies the name of the device class assigned for the storage pool. This is a required parameter.
Pool type	Specifies that you want to define a copy storage pool. This is a required parameter. Updating a storage pool cannot change whether the pool is a primary or copy storage pool.

Table 16. Information for Defining a Copy Storage Pool (continued)

Information	Explanation
Access mode	<p>Defines access to volumes in the storage pool for user operations (such as backup and restore) and system operations (such as reclamation). Possible values are:</p> <p>Read/Write User and system operations can read from or write to the volumes.</p> <p>Read-Only User operations can read from the volumes, but not write. However, system processes can move files within the volumes in the storage pool.</p> <p>Unavailable Specifies that users cannot access files stored on volumes in the copy storage pool. Files can be moved within the volumes of the copy storage pool, but no new writes are permitted to the volumes in the storage pool from volumes outside the storage pool.</p>
Maximum number of scratch volumes	<p>When you specify a value greater than zero, the server dynamically acquires scratch volumes when needed, up to this maximum number. This is a required parameter.</p> <p>For automated libraries, set this value equal to the physical capacity of the library. See “Maintaining a Supply of Scratch Volumes in an Automated Library” on page 96.</p>
Collocation	<p>When collocation is enabled, the server attempts to keep all files belonging to a client node or a client file space on a minimal number of sequential access storage volumes. See “Collocation on Copy Storage Pools” on page 151.</p>
Reclamation threshold	<p>Specifies when to initiate reclamation of volumes in the copy storage pool. Reclamation is a process that moves any remaining active, fragmented files from one volume to another volume, thus making the original volume available for reuse. A volume is eligible for reclamation when the percentage of unused space on the volume is greater than the reclaim parameter value.</p> <p>Reclamation processing works differently for offsite storage pool volumes and virtual volumes. When a copy storage pool volume that is offsite becomes eligible for reclamation, the reclamation process attempts to retrieve the active files on the reclaimable volume from a primary or copy storage pool volume that is onsite. The process then writes these files to an available volume in the original copy storage pool. See “Reclamation for Copy Storage Pools” on page 156 and “Reclamation of Volumes with the Device Type of SERVER” on page 155 for more details.</p>
Reuse delay period	<p>Specifies the number of days that must elapse after all of the files have been deleted from a volume before the volume can be rewritten or returned to the scratch pool. See “Delaying Reuse of Reclaimed Volumes” on page 158.</p>

Example: Defining a Copy Storage Pool

Assume you need to maintain copies of the files stored in BACKUPPOOL, ARCHIVEPOOL, and SPACEMGPOOL (default disk storage pools) for disaster recovery purposes. You want to create a copy storage pool named DISASTER-RECOVERY. You decide to use only scratch tapes in the new pool, setting the maximum number of scratch volumes to an appropriate value. You enter the following command:

```
define stgpool disaster-recovery tapeclass pooltype=copy
maxscratch=100
```

To store data in the new storage pool, you must back up the primary storage pools (BACKUPPOOL, ARCHIVEPOOL, and SPACEMGPOOL) to the DISASTER-RECOVERY pool. See “Backing Up Storage Pools” on page 465.

Comparing Primary and Copy Storage Pools

Table 17 compares the characteristics of primary and copy storage pools.

Table 17. Comparing Primary and Copy Storage Pools

Characteristic	Primary storage pool	Copy storage pool
Destination for backed-up or archived files (specified in backup or archive copy groups)	Yes	No
Destination for space-managed files (specified in the management class)	Yes	No
Offsite access mode for volumes	No	Yes, except for volumes with device type SERVER
Destroyed access mode for volumes	Yes	No
Random access storage volumes	Yes	No
Sequential access storage volumes	Yes	Yes
Contents	Client files (backup versions, archived files, space-managed files)	Copies of files that are stored in primary storage pools
Moving data allowed	Within the same primary storage pool, or to any primary storage pool	Within the same pool only. If volumes are offsite, data is copied from the original files in primary storage pools.
Collocation	Yes (sequential access storage pools only)	Yes
Reclamation	Yes (sequential access storage pools only)	Yes Virtual volumes (volumes with device type SERVER) and offsite volumes are handled differently. For details, see “Reclamation of Volumes with the Device Type of SERVER” on page 155 and “Reclamation of Offsite Volumes” on page 156.

Table 17. Comparing Primary and Copy Storage Pools (continued)

Characteristic	Primary storage pool	Copy storage pool
File deletion	Files are deleted: <ul style="list-style-type: none"> ■ During inventory expiration processing, if the files have expired ■ When a file space is deleted ■ When a volume is deleted with the option to discard the data ■ When a primary storage pool volume is audited with the FIX=YES option, if the files on the volume are damaged and no other copies of the file exist 	Files are deleted: <ul style="list-style-type: none"> ■ Whenever the primary copy of the file is deleted from the primary storage pool (because of expiration, file space deletion, or volume deletion) ■ When a volume is deleted with the option to discard the data ■ When a copy storage pool volume is audited with the FIX=YES option, if the files on the volume are damaged

Deleting a Storage Pool

Task	Required Privilege Class
Delete storage pools	System

Before you delete a storage pool, ensure that:

- All volumes within the storage pool have been deleted

Ensure that you have saved any readable data that you want to preserve by issuing the MOVE DATA command. Moving all of the data that you want to preserve may require you to issue the MOVE DATA command several times.

Before you begin deleting all volumes that belong to the storage pool, change the access mode of the storage pool to unavailable so that no files can be written to or read from volumes in the storage pool.

See “Deleting a Storage Pool Volume with Data” on page 185 for information about deleting volumes.

- The storage pool is not identified as the next storage pool within the storage hierarchy
To determine whether this storage pool is referenced as the next storage pool within the storage hierarchy, query for storage pool information as described in “Monitoring Space Available in a Storage Pool” on page 161.

Update any storage pool definitions to remove this storage pool from the storage hierarchy by performing one of the following:

- Naming another storage pool as the next storage pool in the storage hierarchy
- Entering the value for the NEXTSTGPOOL parameter as "" (double quotes) to remove this storage pool from the storage hierarchy definition

See “Defining or Updating Primary Storage Pools” on page 123 for information about defining and updating storage pools.

- The storage pool to be deleted is not specified as the destination for any copy group in any management class within the active policy set of any domain. Also, a storage pool

to be deleted cannot be the destination for space-managed files (specified in any management class within the active policy set of any domain). If this pool is a destination and the pool is deleted, operations fail because there is no storage space to store the data.

Deleting Storage Pool Volumes

You can delete volumes, and optionally the client files they contain, from either primary or copy storage pools.

If files that are not cached are deleted from a primary storage pool volume, any copies of these files in copy storage pools will also be deleted.

Files in a copy storage pool are never deleted unless:

- The volume that contains the copy file is deleted by using the DISCARDDATA=YES option.
- A read error is detected by using AUDIT VOLUME with the FIX=YES option for a copy storage pool volume.
- The primary file is deleted because of:
 - Policy-based file expiration
 - File space deletion
 - Deletion of the primary storage pool volume

Tip: If you are deleting many volumes, delete the volumes one at a time. Concurrently deleting many volumes can adversely affect server performance.

Task	Required Privilege Class
Delete volumes from any storage pool	System or unrestricted storage
Delete volumes from storage pools over which they have authority	Restricted storage

Deleting an Empty Storage Pool Volume

You can delete empty storage pool volumes. For example, to delete an empty volume named WREN03, enter:

```
delete volume wren03
```

On an administrative client, you will receive the following confirmation messages, unless the client is running with the NOCONFIRM option:

```
ANR2200W This command will delete volume WREN03
from its storage pool after verifying that the volume
contains no data.
Do you wish to proceed? (Y/N)
```

After you respond yes, the server generates a background process to delete the volume.

The command may be run in the foreground on an administrative client by issuing the command with the WAIT=YES parameter.

Deleting a Storage Pool Volume with Data

To prevent you from accidentally deleting backed-up, archived, or space-managed files, the server does not allow you to delete a volume that contains user data unless you specify `DISCARDATA=YES` on the `DELETE VOLUME` command.

For example, to discard all data from volume `WREN03` and delete the volume from its storage pool, enter:

```
delete volume wren03 discarddata=yes
```

The server generates a background process and deletes data in a series of batch database transactions. After all files have been deleted from the volume, the server deletes the volume from the storage pool. If the volume deletion process is canceled or if a system failure occurs, the volume might still contain data. Reissue the `DELETE VOLUME` command and explicitly request the server to discard the remaining files on the volume.

To delete a volume but not the files it contains, move the files to another volume. See “Moving Files from One Volume to Another Volume” on page 176 for information about moving data from one volume to another volume.

Residual data: Even after you move data, residual data may remain on the volume because of I/O errors or because of files that were previously marked as damaged. (TSM does not move files that are marked as damaged.) To delete any volume that contains residual data that cannot be moved, you must explicitly specify that files should be discarded from the volume.

III — Managing Client Operations

10

Adding Client Nodes

When the Tivoli Storage Manager server is installed, the TSM backup-archive client and the TSM administrative client are installed on the same machine as the server by default. However, many installations of TSM include remote clients, application clients, and Tivoli Data Protection (TDP) host servers on other machines, often running on different operating systems.

The TSM server views its registered clients as nodes that require services and resources from the server. The term *nodes* in this chapter indicates the following type of clients and servers that you can register as client nodes:

- Tivoli Storage Manager backup-archive client
- Tivoli Data Protection application clients
- Tivoli Space Manager (HSM client)
- Tivoli Data Protection (TDP) host servers
- Tivoli Storage Manager source server registered as a node on a target server

Each node must be registered with the TSM server and requires an option file with a pointer to the server.

For details on many of the topics in this chapter, refer to *Tivoli Storage Manager Installing the Clients*. Administrators can perform the following activities when managing TSM nodes:

Tasks:
“Installing Client Node Software” on page 190
“Accepting Default Closed Registration or Enabling Open Registration” on page 190
“Registering Nodes with the Server” on page 190
“Connecting Nodes with the Server” on page 193
Concepts:
“Overview of Clients and Servers as Nodes” on page 190
“Comparing Network-Attached Nodes to Local Nodes” on page 194

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Overview of Clients and Servers as Nodes

Each backup-archive client, HSM client, TDP application client, TDP host server, and source server is given a node name when it is registered as a node with the TSM server. The server considers each as a node that requires services and resources from the server.

Typically, a node is equivalent to a machine as in the case of a backup-archive client that is installed on a user's computer for file system backups. However, multiple nodes can exist on a single machine. For example, a Structured Query Language (SQL) server machine can contain both a TDP for SQL server application client for database and transaction log backups, and a Tivoli Storage Manager backup-archive client for file system backups.

Installing Client Node Software

TSM administrators can install backup-archive clients, application clients, Tivoli Space Manager clients, or TDP host servers by using any of the following methods:

- Installing directly from the CD-ROM
- Installing by transferring installable files from the CD-ROM to a target machine
- Installing by creating client, application client, or host server images and installing the images

For more information about installing:

- TSM client software, refer to *Tivoli Storage Manager Installing the Clients*.
- Tivoli Data Protection application client software, refer to the Tivoli Data Protection application client documentation for your particular client.
- Tivoli Data Protection host server software, refer to *Tivoli Data Protection for Workgroups: User's Guide*.

Use the procedures in this chapter to configure a node after it has been installed.

Registering Nodes with the Server

TSM administrators can register TSM clients, Tivoli Data Protection application clients, HSM clients, and TDP host servers as client nodes.

When a node is registered, TSM automatically creates an administrative user ID with client owner authority over the node. You can use this administrative user ID to access the Web backup-archive client from remote locations through a Web browser. If an administrative user ID already exists with the same name, an administrative user ID is not automatically defined. For more information, see "Overview of Remote Access to Web Backup-Archive Clients" on page 200.

Note: To connect to a Web backup-archive client directly from a supported Web browser or from a hyperlink in the Web administrative Enterprise Console, you must specify the node's URL and port number during the registration process or later update the node with this information.

Accepting Default Closed Registration or Enabling Open Registration

Before a user can request TSM services the node must be registered with the server.

Closed registration is the default at installation. The administrator must register client nodes when registration is set to closed.

Open registration allows the client nodes to register their node names, passwords, and compression options. On UNIX systems, only the root user can register a client node with the TSM server.

With either registration mode, by default, an administrative user ID with client owner authority is created over the node.

Note: Changes to the registration process do not affect existing registered client nodes.

Closed Registration

To add a node with closed registration, an administrator uses the REGISTER NODE command to register the node and specify the initial password.

The administrator can also specify the following optional parameters:

- Contact information.
- The name of the policy domain to which the node is assigned.
- Whether the node compresses its files before sending them to the server for backup and archive.
- Whether the node can delete backups and archives from server storage.
- The name of a client option set to be used by the node.
- Whether to force a node to change or reset the password.
- Whether the client node keeps a mount point for an entire session.
- The maximum number of mount points the node can use.

To add a node with closed registration, an administrator registers the node, specifies the initial password, compression options, the policy domain to which the node belongs, and whether the user can delete backups and archives from server storage.

Open Registration

To add a node with open registration, the server prompts the user for a node name, password, and contact information the first time the user attempts to connect to the server. The server allows users to delete archive copies, but not backups for the server. The server automatically assigns the node to the STANDARD policy domain. TSM administrators can enable open registration by entering the following command from an administrative client command line:

```
set registration open
```

For examples and a list of open registration defaults, refer to the *Administrator's Reference*.

To change the defaults for a registered node, use the UPDATE NODE command.

Node Compression Considerations

When you enable compression, it reduces network utilization and saves server storage, but causes additional central processing unit (CPU) overhead to the node. Data compression is recommended only when there is insufficient network capacity. Server data compression has no effect on Tivoli Data Protection host server data.

Attention: Nodes should use either client compression or drive compression but not both. For details, see “Using Data Compression” on page 116.

To optimize performance or to ease memory constraints at the workstation, a TSM administrator can restrict file compression. You can select one of three options:

- Compress files
- Do not compress files
- Use the value set in the COMPRESSION option
Set the COMPRESSION option in the client system options file or in the application program interface (API) configuration file.
On a UNIX system, a root user can define the COMPRESSION option in the **dsm.opt** client options file.

Registering Nodes with Client Options Sets

Administrators can use client options sets in conjunction with the client options file to register nodes with the server. Client option sets are considered advanced implementation and are discussed in “Modifying Client Option Files” on page 214. You can specify an option set for a node when you register or update the node. For example:

```
register node mike pass2eng cloptset=engbackup
```

The client node MIKE is registered with the password pass2eng. When the client node MIKE performs a scheduling operation, the schedule log entries are kept for 5 days.

Registering a Source Server as a Node on a Target Server

A virtual volume is a volume that appears to be a sequential media volume on a source server. The volume is actually stored as an archive file on a target server.

To use virtual volumes, register the source server as a client node on the target server.

The REGISTER NODE and UPDATE NODE commands have a default parameter of TYPE=CLIENT. To register a source server as a node, you must specify the TYPE=SERVER parameter. For more information, see “Using Virtual Volumes to Store Data on Another Server” on page 348.

Registering an Application Programming Interface to the Server

Workstation users can request TSM services by using an application that uses the TSM application programming interface (API). An administrator uses the REGISTER NODE command to register the workstation as a node.

Understanding How to Set the Compression Option

For applications that use the TSM API, compression can be determined by:

- An administrator during registration who can:
 - Require that files are compressed
 - Restrict the client from compressing files
 - Allow the application user or the client user to determine the compression status
- The client options file. If an administrator does not set compression on or off, TSM checks the compression status that is set in the client options file. The client options file is required, but the API user configuration file is optional.

- One of the object attributes. When an application sends an object to the server, some object attributes can be specified. One of the object attributes is a flag that indicates whether or not the data has already been compressed. If the application turns this flag on during either a backup or an archive operation, then TSM does not compress the data a second time. This process overrides what the administrator sets during registration.

For more information on setting options for the API and on controlling compression, see *Tivoli Storage Manager Using the Application Programming Interface*.

Understanding How to Set the File Deletion Option

For applications that use the TSM API, the file deletion option can be set by:

- An administrator during registration
 - If an administrator does not allow file deletion, then a TSM administrator must delete objects or file spaces that are associated with the workstation from server storage.
 - If an administrator allows file deletion, then TSM checks the client options file.
- An application using the TSM API deletion program calls
 - If the application uses the **dsmDeleteObj** or **dsmDeleteFS** program call, then objects or files are marked for deletion when the application is executed.

Connecting Nodes with the Server

The client options file connects each node to the server. Administrators and users on all platforms can modify their client options file (*dsm.opt*) with a text editor. Client options files can be updated differently across platforms. On the Windows platform, you can use a wizard to work with the client options file.

Note: If any changes are made to the *dsm.opt* file, the client must be restarted for changes in the options file to have any affect.

The client options file *dsm.opt* is located in the client, application client, or host server directory. If the file does not exist, copy the *dsm.smp* file. Users and administrators can edit the client options file to specify:

- The network address of the server
- The communication protocol
- Backup and archive options
- Space management options
- Scheduling options

Required Client Options

Each node requires a client options file. Each client options file must contain the network address of the TSM server and other communication options that allow the node to communicate with the TSM server. Figure 39 on page 194 shows the contents of a client options file that is configured to connect to the TSM server by using TCP/IP. The communication options specified in the client options file satisfy the minimum requirements for the node to connect with the TSM server.




Figure 39. Client Node Options File

Non-Required Client Options

Many non-required options are available that can be set at any time. These options control the behavior of TSM processing. Refer to *Tivoli Storage Manager Installing the Clients* for more information about non-required TSM client options.

UNIX Client Options

For UNIX clients, TSM options are located in three options files: client systems options file, client user options file, and include-exclude options file. Clients and TDP host servers on other platforms use a single options file.

Methods for Creating or Updating a Client Options File

There are several methods for creating or updating TSM client options files. The available methods depend on the client platform.

Using a Text Editor

All TSM options files (*dsm.opt*) can be edited with a text editor. Anyone can edit the client options file if they have access to the directory where the node software is installed. Editing individual options files is the most direct method, but may not be suitable for sites with many client nodes.

Using the Client Configuration Wizard

When a local backup-archive client GUI starts initially and TSM does not find an options file, a setup wizard guides the client through the configuration process.

From the backup-archive client GUI, the client can also display the setup wizard by selecting **Utilities**→**Setup Wizard**. The client can follow the panels in the setup wizard to browse TSM server information in the Active Directory. The client can determine which server to connect to and what communication protocol to use.

Note: This wizard is not available for the web client.

Comparing Network-Attached Nodes to Local Nodes

A TSM environment can be either a server and client on the same machine (standalone environment) or a server and network-attached clients (network environment).

The standalone environment of TSM consists of a TSM client and a TSM administrative client on the same computer as the TSM server. There is nothing more to do to connect the client. This is shown in Figure 40.




Figure 40. Standalone Environment

Figure 41 shows that a network environment of TSM consists of a TSM client and a TSM administrative client on the same computer as the TSM server. However, network-attached client nodes can also connect to the TSM server.




Figure 41. Network Environment

Each client requires a client options file. A user can edit the client options file at the client node. The options file contains a default set of processing options that identify the server, communication method, backup and archive options, space management options, and scheduling options.

Adding Clients from the Administrative Command Line Client

The administrator can register nodes by using the REGISTER NODE command. For more information, refer to *Administrator's Reference*.

Enabling Open Registration

The default registration mode at installation is closed. To change the default to open so users can register their own client nodes, enter:

```
set registration open
```

Configuring the Client Options File to Connect with the Server

Edit the client options file (dsm.opt) in the client directory using a text editor.

Example: Register Three Client Nodes Using the Administrative Command Line

You want to register three workstations from the engineering department and assign them to the ENGPOLDOM policy domain. Before you can assign client nodes to a policy domain, the policy domain must exist. To define a policy domain, see “Implementing Policies for Client Data” on page 233.

You want to let users delete backed up or archived files from storage pools. From an administrative client, you can use the macro facility to register more than one client node at a time. For this example, you create a macro file named REGENG.MAC, that contains the following REGISTER NODE commands:

```
register node ssteiner choir contact='department 21'  
domain=engpoldom archdelete=yes backdelete=yes  
register node carolh skiing contact='department 21, second shift'  
domain=engpoldom archdelete=yes backdelete=yes  
register node mab guitar contact='department 21, third shift'  
domain=engpoldom archdelete=yes backdelete=yes
```

Next, issue the MACRO command:

```
macro regeng.mac
```

For information on the MACRO command, see *Administrator's Reference*.

11

Managing Client Nodes

This chapter contains information about managing client nodes, application clients, and Tivoli Data Protection (TDP) host servers that have been installed and configured. For information about installing and configuring client nodes, see “Adding Client Nodes” on page 189.

Note: The TSM server views its registered clients, application clients, host servers, and source servers as nodes. In a general sense, the TSM server considers all of these entities as a client. The term *nodes* in this chapter refers to the following type of clients and servers as client nodes:

- Tivoli Data Protection (TDP) host servers
- Tivoli Data Protection application clients
- Tivoli Storage Manager backup-archive client
- Tivoli Storage Manager source server registered as a node on a target server

Administrators can manage client nodes and control their access to the TSM server. See the following sections for more information:

Tasks:
“Managing Nodes” on page 198
“Managing Client Access Authority Levels” on page 202
“Managing File Spaces” on page 204
“Modifying Client Option Files” on page 214
“Managing Tivoli Storage Manager Sessions” on page 217
“Managing Tivoli Storage Manager Security” on page 222
Concepts:
“Overview of Client Nodes and File Spaces” on page 229
“Overview of Tivoli Storage Manager Privilege Classes” on page 230

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Managing Client Node Registration Techniques

By default, TSM provides closed registration as the technique for registering client nodes. Administrators can modify the default with the SET REGISTRATION command. For more information about open and closed registration, see “Accepting Default Closed Registration or Enabling Open Registration” on page 190.

Managing Nodes

From the perspective of the server, each client, application client, and Tivoli Data Protection host server is a node requiring TSM services. For information, see “Overview of Client Nodes and File Spaces” on page 229. Client nodes can be local or remote to the TSM server. For information, see “Comparing Network-Attached Nodes to Local Nodes” on page 194.

Administrators can perform the following activities when managing client nodes.

Task	Required Privilege Class
Updating, renaming, locking, or unlocking any client nodes	System or unrestricted policy
Updating, renaming, locking, or unlocking client nodes assigned to specific policy domains	System, unrestricted policy, or restricted policy for those domains
Displaying information about client nodes or file spaces	Any administrator
Deleting any client nodes	System or unrestricted policy
Removing client nodes assigned to specific policy domains	System, unrestricted policy, or restricted policy for those domains
Managing client access authority levels	System

Updating Client Node Information

You can use the UPDATE NODE command to update information such as the client’s assigned policy domain, the user’s password or contact information, and the client option set used by the node.

For example, update client node TOMC to prevent him from deleting archived files from storage pools by entering:

```
update node tomc archdelete=no
```

Renaming Client Nodes

You can rename a client node with the RENAME NODE command. You may need to rename a client node if the workstation network name or host name changes. For example, with UNIX clients, users define their node name based on the value returned by the HOSTNAME command. When users access the server, their TSM user IDs match the host name of their workstations. If the host name changes, you can update a client node user ID to match the new host name.

For example, to rename CAROLH to ENGNODE, enter:

```
rename node carolh engnode
```

ENGNODE retains the contact information and access to backup and archive data that belonged to CAROLH. All files backed up or archived by CAROLH now belong to ENGNODE.

Locking and Unlocking Client Nodes

You can prevent client nodes from accessing the server with the `LOCK NODE` command. This will prevent client nodes from performing functions such as either backup and restore or archive and retrieve.

You can restore a locked node's access to the server with the `UNLOCK NODE` command.

For example, to prevent client node MAB from accessing the server, enter:

```
lock node mab
```

To let client node MAB access the server again, enter:

```
unlock node mab
```

Deleting Client Nodes

You can delete a client node from the server with the `REMOVE NODE` command. All file spaces that belong to the client node must first be deleted from server storage. After all of the client node's file spaces have been deleted (see "Deleting File Spaces and Client Nodes" on page 213), you can delete the node.

For example, to remove client node DEBBYG, enter:

1. Delete the DEBBYG file space by entering:

```
delete filespace debbyg * type=any
```

2. Delete the DEBBYG node by entering:

```
remove node debbyg
```

Displaying Information about Client Nodes

You can display information about client nodes. For example, as a policy administrator, you might query the server about all client nodes assigned to the policy domains for which you have authority. Or you might query the server for detailed information about one client node.

Displaying Information about Client Nodes Assigned to Specific Policy Domains

You can display information about client nodes assigned to specific policy domains. For example, to view information about client nodes that are assigned to `STANDARD` and `ENGPOLDOM` policy domains, enter:

```
query node * domain=standard,engpoldom
```

The output from that command might look like this:

Node Name	Platform	Policy Domain Name	Days Since Last Access	Days Since Password Set	Locked?
DEBBYG	DOS	STANDARD	2	12	No
ENGNODE	AIX	ENGPOLDOM	<1	1	No
HTANG	OS/2	STANDARD	4	11	No
MAB	AIX	ENGPOLDOM	<1	1	No
PEASE	AIX	STANDARD	3	12	No
SSTEINER	(?)	ENGPOLDOM	<1	1	No

Displaying Information about a Specific Client Node

You can view information about specific client nodes. For example, to review the registration parameters defined for client node JOE, enter:

```
query node joe format=detailed
```

The resulting report would look like this:

```
Node Name: JOE
Platform: WinNT
Client OS Level: 4.00
Client Version: Version 3, Release 1, Level 3.0
Policy Domain Name: STANDARD
Last Access Date/Time: 05/19/1999 18:55:46
Days Since Last Access: 6
Password Set Date/Time: 05/19/1999 18:26:43
Days Since Password Set: 6
Invalid Sign-on Count: 0
Locked?: No
Contact:
Compression: Client's Choice
Archive Delete Allowed?: Yes
Backup Delete Allowed?: No
Registration Date/Time: 05/19/1999 18:26:43
Registering Administrator: SERVER_CONSOLE
Last Communication Method Used: Tcp/Ip
Bytes Received Last Session: 108,731
Bytes Sent Last Session: 698
Duration of Last Session (sec): 0.00
Pct. Idle Wait Last Session: 0.00
Pct. Comm. Wait Last Session: 0.00
Pct. Media Wait Last Session: 0.00
Optionset:
URL:http://joe.host.name:1581
Node Type: Client
Password Expiration Period: 60
Keep Mount Point?: No
Maximum Mount Points Allowed: 1
```

Overview of Remote Access to Web Backup-Archive Clients

With the introduction of the Web backup-archive client, when a client node is registered with a TSM 3.7.0 server or above, an identical administrative user ID is created at the same time. This user ID has client owner authority over the node by default.

Enterprise logon enables a user with the proper administrative user ID and password to access a Web backup-archive client from a Web browser. The Web backup-archive client can be used by the client node or a user ID with the proper authority to perform backup, archive, restore, and retrieve operations on any machine that is running the Web backup-archive client.

You can establish access to a Web backup-archive client for help desk personnel that do not have system or policy privileges by granting those users client access authority to the nodes they need to manage. Help desk personnel can then perform activities on behalf of the client node such as backup and restore operations.

A native backup-archive client can log on to TSM using their node name and password, or administrative user ID and password. The administrative user ID password is managed independently from the password that is generated with the *passwordaccess generate* client option. The client must have the option *passwordaccess generate* specified in their client option file to enable use of the Web backup-archive client.

To use the Web backup-archive client from your web browser, you specify the URL and port number of the TSM backup-archive client machine running the web client.

During node registration, you have the option of granting client owner or client access authority to an existing administrative user ID. You can also prevent the server from creating an administrative user ID at registration. If an administrative user ID already exists with the same name as the node being registered, the server registers the node but does not automatically create an administrative user ID. This process also applies if your site uses open registration.

For more information about installing and configuring the Web backup-archive client, refer to *Tivoli Storage Manager Installing the Clients*.

Description of Node Privilege Class with Client Access Authorities

Access to a Web backup-archive client requires either client *owner* authority or client *access* authority. Administrators with system or policy privileges over the client node's domain, have client owner authority by default. The administrative user ID created automatically at registration has *client owner* authority by default. This administrative user ID is displayed when an administrator issues a QUERY ADMIN command.

The following describes the difference between client *owner* and client *access* authority when defined for a user that has the node privilege class:

Client owner

You can access the client through the Web backup-archive client or native backup-archive client.

You own the data and have a right to physically gain access to the data remotely. You can backup and restore files on the same or different machine, you can delete file spaces or archive data.

The user ID with client owner authority can also access the data from another machine using the `-NODENAME` parameter.

The administrator can change the client node's password for which they have authority.

This is the default authority level for the client at registration. An administrator with system or policy privileges to a client's domain has client owner authority by default.

Client access

You can only access the client through the Web backup-archive client.

You can restore data only to the original client.

A user ID with client access authority cannot access the client from another machine using the `-NODENAME` parameter.

This privilege class authority is useful for help desk personnel so they can assist users in backing up or restoring data without having system or policy privileges. The

client data can only be restored to none other than the original client. A user ID with client access privilege cannot directly access client's data from a native backup-archive client.

Managing Client Access Authority Levels

By default, an administrator with system or policy privilege over a client's domain can remotely access clients and perform backup and restore operations.

You can grant client *access* or client *owner* authority to other administrators by specifying `CLASS=NODE` and `AUTHORITY=ACCESS` or `AUTHORITY=OWNER` parameters on the `GRANT AUTHORITY` command. You must have one of the following privileges to grant or revoke client access or client owner authority:

- System privilege
- Policy privilege in the client's domain
- Client owner privilege over the node
- Client access privilege over the node

You can grant an administrator client access authority to individual clients or to all clients in a specified policy domain. For example, you may want to grant client access privileges to users that staff help desk environments. See “Example: Setting up Help Desk Access to Client Machines in a Specific Policy Domain” on page 203 for more information.

Granting Client Authority

To grant client *access* authority to administrator FRED for the LABCLIENT node, issue:
`grant authority fred class=node node=labclient`

The administrator FRED can now access the LABCLIENT client, and perform backup and restore. The administrator can only restore data to the LABCLIENT node.

To grant client *owner* authority to ADMIN1 for the STUDENT1 node, issue:
`grant authority admin1 class=node authority=owner node=student1`

The user ID ADMIN1 can now perform backup and restore operations for the STUDENT1 client node. The user ID ADMIN1 can also restore files from the STUDENT1 client node to a different client node.

Automatically Creating an Administrative User ID with Client Owner Authority

When you use the `REGISTER NODE` command, by default, the server creates an administrative user ID in addition to the client node. The administrative user ID has client owner authority to the node when the node is defined to the server. For example, you want to register client node DESK2, issue:

```
register node desk2 pass2dsk
```

The following shows the output from this command.

```
ANR2060I Node DESK2 registered in policy domain STANDARD.  
ANR2099I Administrative userid DESK2 defined for OWNER access to node DESK2.
```

The DESK2 client node is registered, in addition to an administrative user ID with the same ID. The administrative user ID DESK2 has a password of pass2dsk with client owner

authority to the DESK2 node. When the `PASSWORDACCESS=GENERATE` option is used by the client to change the password, the administrative DESK2 ID can still access the client from a remote location.

Preventing Automatic Creation of an Administrative User ID with Client Owner Authority

You can prevent automatic creation of an administrative user ID with client owner authority by specifying `USERID=NONE` on the `REGISTER NODE` command. For example, you want to register DESK2 without creating an administrative user ID with client owner authority by default. Issue the following:

```
register node desk2 pass2dsk userid=none
```

Registering a Node and Granting an Existing Administrative ID Client Owner Authority

You can grant client owner authority to an existing administrative user ID. For example, to give client owner authority to the `HELPADMIN` user ID when registering the `NEWCLIENT` node, enter:

```
register node newclient pass2new userid=helpadmin
```

This command results in the `NEWCLIENT` node being registered with a password of `pass2new`, and also grants `HELPADMIN` client owner authority. This command would not create an administrator ID. The `HELPADMIN` client user ID is now able to access the `NEWCLIENT` node from a remote location.

Example: Setting up Help Desk Access to Client Machines in a Specific Policy Domain

You want to set up help desk access for user `HELP1` to the client nodes in the `FINANCE` domain. You want to grant `HELP1` client access authority to the `FINANCE` domain without having to grant system or policy privileges.

The client nodes have been previously set up as follows:

- Installed and configured. The URL and port numbers were specified during the `REGISTER NODE` process.
- Assigned to the `FINANCE` policy domain.
- Started the TSM Client Acceptor service.
- Specified *passwordaccess generate* option in their client option files.

The help desk person, using `HELP1` user ID, has a Java 1.1.6-capable Web browser.

1. Register an administrative user ID of `HELP1`.


```
register admin help1 05x23 contact="M. Smith, Help Desk x0001"
```
2. Grant the `HELP1` administrative user ID client access authority to all clients in the `FINANCE` domain. With client access authority, `HELP1` can perform backup and restore operations for clients in the `FINANCE` domain. Client nodes in the `FINANCE` domain are Dave, Sara, and Joe.


```
grant authority help1 class=node authority=access domains=finance
```

The following is output generated by this command:

```
ANR2126I GRANT AUTHORITY: Administrator HELP1 was granted ACCESS authority for client
DAVE.
ANR2126I GRANT AUTHORITY: Administrator HELP1 was granted ACCESS authority for client
JOE.
ANR2126I GRANT AUTHORITY: Administrator HELP1 was granted ACCESS authority for client
SARA.
```

3. The help desk person, HELP1, opens the Web browser and specifies the URL and port number for client machine Sara:

```
http://sara.machine.name:1581
```

A Java applet is started, and the client hub window is displayed in the main window of the Web browser. When HELP1 accesses the backup function from the client hub, the TSM login screen is displayed in a separate Java applet window. HELP1 authenticates with the administrative user ID and password. HELP1 can perform a backup for Sara.

For information about what functions are not supported on the Web backup-archive client, refer to *Tivoli Storage Manager Installing the Clients*.

Managing File Spaces

A *file space name* identifies a group of files that are stored as a logical unit in server storage. Administrators manage file spaces in which TSM stores each client node's data. See "Overview of Client Nodes and File Spaces" on page 229 for more information.

Administrators can perform the following activities when managing file spaces:

Task	Required Privilege Class
Determine when existing file spaces are renamed to allow for the creation of new Unicode-enabled file spaces	System, unrestricted policy privilege, or restricted policy privilege for the policy domain to which the client node is assigned.
Displaying information about file spaces	Any administrator
Deleting file spaces	System or unrestricted policy
Deleting file spaces assigned to specific policy domains	System, unrestricted policy, or restricted policy for those domains

Supporting Unicode-Enabled Clients (Windows NT and Windows 2000)

Unicode is a universal character encoding standard that supports the interchange, processing, and display of text that is written in any of the languages of the modern world. For Windows NT and Windows 2000 systems with the Unicode-enabled client, the server supports storing file spaces with Unicode file space names, directory names, and file names in server storage. The file spaces in server storage that have Unicode names are called *Unicode-enabled file spaces*. Support for Unicode names enables a client to successfully process a TSM operation even when the file spaces contain directory names or files in multiple languages, or when the client uses a different code page than the server.

New clients storing data on the server for the first time require no special set-up. If the client has the latest TSM client software installed, the server automatically stores Unicode-enabled file spaces for that client.

However, if you have clients that already have data stored on the server and the clients install the Unicode-enabled TSM client software, you need to plan for the migration to Unicode-enabled file spaces. To allow clients with existing data to begin to store data in Unicode-enabled file spaces, TSM provides a function for automatic renaming of existing file spaces. The file data itself is not affected; only the file space name is changed. Once the existing file space is renamed, the operation creates a new file space that is Unicode enabled. The creation of the new Unicode-enabled file space for clients can greatly increase the amount of space required for storage pools and the amount of space required for the server database. It can also increase the amount of time required for a client to run a full incremental backup, because the first incremental backup after the creation of the Unicode-enabled file space is a full backup.

When clients with existing file spaces migrate to Unicode-enabled file spaces, you need to ensure that sufficient storage space for the server database and storage pools is available. You also need to allow for potentially longer backup windows for the complete backups.

Note: Once the server is at the latest level of software that includes support for Unicode-enabled file spaces, you can only go back to a previous level of the server by restoring an earlier version of TSM and the database.

A Unicode-enabled TSM client is currently available only on Windows NT and Windows 2000. Data in a Unicode code page from any other source, including down-level clients and API clients, will not be identified or treated as Unicode enabled.

See the following sections:

“Deciding Whether Clients Need Unicode-Enabled File Spaces”

“Migrating Clients to Unicode-Enabled File Spaces” on page 206

“Querying Unicode-enabled File Spaces” on page 212

“Unicode-enabled Clients and Existing Backup Sets” on page 212

Deciding Whether Clients Need Unicode-Enabled File Spaces

Without the TSM support for storing Unicode-enabled file spaces, some Windows NT and Windows 2000 clients have experienced backup failures when file spaces contain names of directories or files in multiple languages, or have names that cannot be converted to the server’s code page. When TSM cannot convert the code page, the client may receive one or all of the following messages if they were using the command line: ANS1228E, ANS4042E, and ANS1803E. Clients that are using the GUI may see a “Path not found” message. If you have Windows NT and Windows 2000 clients that are experiencing such backup failures, then you need to migrate the file spaces for these clients to ensure that these systems are completely protected with backups. If you have a large number of clients, set the priority for migrating the clients based on how critical each client’s data is to your business. See “Migrating Clients to Unicode-Enabled File Spaces” on page 206.

If you have Windows NT and Windows 2000 clients that are not having problems backing up any files, you do not need to migrate the file spaces for these clients. You can choose whether to migrate their existing file spaces after these clients install the latest TSM client software. See “Migrating Clients to Unicode-Enabled File Spaces” on page 206 and “Choosing to Keep File Spaces that are Not Unicode Enabled” on page 212.

Any new file spaces that are backed up from Windows NT and Windows 2000 systems with the Unicode-enabled TSM client are automatically stored as Unicode-enabled file spaces in server storage.

Objects backed up or archived with a Unicode-enabled TSM client in any supported language environment can be restored or retrieved with a Unicode-enabled client in the same or any other supported language environment. This means, for example, that files backed up by a Japanese Unicode-enabled TSM client can be restored by a German Unicode-enabled TSM client.

Note: Objects backed up or archived by a Unicode-enabled TSM client, cannot be restored or retrieved by a TSM client that is not Unicode enabled.

Migrating Clients to Unicode-Enabled File Spaces

To allow clients with existing data to migrate to Unicode-enabled file spaces, TSM provides an automatic rename function for file spaces. When enabled, TSM uses the rename function when it recognizes that a file space that is not Unicode enabled in server storage matches the name of a file space on a client. The existing file space in server storage is renamed, so that the file space in the current operation is then treated as a new, Unicode-enabled file space. For example, if the operation is an incremental backup at the file space level, the entire file space is then backed up to the server as a Unicode-enabled file space.

The following example shows how this process works when automatic renaming is enabled from the server, for an existing client node that has file spaces in server storage.

1. The administrator updates a client node definition by issuing an UPDATE NODE command with the parameter, AUTOFSRENAME YES.
2. The client processes an incremental back up.
3. TSM processes the back up as follows:
 - a. Renames the existing file space (_OLD)
 - b. Creates a new Unicode-enabled file space
 - c. Processes the back up in the current operation to the new Unicode-enabled file space

Attention: If you force the file space renaming for all clients at the same time, backups can contend for network and storage resources, and storage pools can run out of storage space.

Before you allow automatic renaming of file spaces for Unicode-enabled TSM clients, read the following sections.

“The Rules for Automatically Renaming File Spaces” on page 208

“Options for Automatically Renaming File Spaces”

“Planning for Unicode Versions of Existing Client File Spaces” on page 208

“How Clients are Affected by the Migration to Unicode” on page 210

“Example of a Migration Process” on page 211

Options for Automatically Renaming File Spaces

As an administrator, you can control whether the file spaces of any existing clients are renamed to force the creation of new Unicode-enabled file spaces. By default, no automatic

renaming occurs. To control the automatic renaming, use the parameter `AUTOFSRENAME` when you register or update a node. You can also allow clients to make the choice. Clients can use the client option `AUTOFSRENAME`.

Note: The setting for `AUTOFSRENAME` affects only clients that are Unicode enabled.

You have these options:

- Do not allow existing file spaces to be renamed, so that Unicode-enabled file spaces are not created (`AUTOFSRENAME=NO`, the default).

TSM does not automatically rename client file spaces when the client system upgrades to the Unicode-enabled TSM client. This setting can help an administrator control how many clients' file spaces can be renamed at one time. The administrator can determine how many Unicode-enabled clients exist by using the `QUERY NODE FORMAT=DETAILED` command. The output displays the client level. A Unicode-enabled client is on a Windows NT or Windows 2000 system at TSM Version 4.2.0 or higher.

- Automatically rename existing file spaces, forcing the creation of Unicode-enabled file spaces in place of the renamed file spaces (`AUTOFSRENAME=YES`).

TSM automatically renames client file spaces in server storage when the client upgrades to the Unicode-enabled client and runs one of the following operations: archive, selective backup, full incremental backup, or partial incremental backup. TSM automatically renames the file spaces that are specified in the current operation and creates new, Unicode-enabled file spaces where files and directories are stored to complete the operation. Other file spaces that are not specified in the current operation are not affected by the rename. This means a client can have mixed file spaces. See "The Rules for Automatically Renaming File Spaces" on page 208 for how the new name is constructed.

Attention: If you force the file space renaming for all clients at the same time, client operations can contend for network and storage resources, and storage pools can run out of storage space.

- Allow clients to choose whether to rename files spaces, in effect choosing whether new Unicode-enabled file spaces are created (`AUTOFSRENAME=CLIENT`).

If you use this value for a client node, the client can set its `AUTOFSRENAME` option in its options file. The client option determines whether file spaces are renamed (YES or NO), or whether the user is prompted for renaming at the time of a TSM operation (PROMPT).

The default value for the client option is `PROMPT`. When the option is set for prompting, the client is presented with a choice about renaming file spaces. When a client that has existing file spaces on server storage upgrades to the Unicode-enabled client, and the client runs a TSM operation with the server, the user is asked to choose whether to rename the file spaces that are involved in the current operation.

The client is prompted only once about renaming a particular file space.

If the client does not choose to rename the file space, the administrator can later rename the file space so that a new Unicode-enabled file space is created the next time the client processes an archive, selective backup, full incremental backup, or partial incremental backup.

Attention: There is no prompt for operations that run with the client scheduler. If the client is running the scheduler and the client AUTOFSRENAME option is set to PROMPT, there is no prompt and the file space is not renamed. This allows a client session to run unattended. The prompt appears during the next interactive session on the client.

The following table summarizes what occurs with different parameter and option settings.

Table 18. Effects of AUTOFSRENAME Settings

Parameter on the server (for each client)	Option on the client	Result for file spaces	Is the file space renamed?
Yes	Yes, No, Prompt	Renamed	Yes
No	Yes, No, Prompt	Not renamed	No
Client	Yes	Renamed	Yes
	No	Not renamed	Yes
	Prompt	Command-line or GUI: The user receives a one-time only prompt about renaming	Depends on the response from the user (yes or no)
		Client Scheduler: Not renamed (prompt appears during the next command-line or GUI session)	No

The Rules for Automatically Renaming File Spaces

With its automatic renaming function, TSM renames a file space by adding the suffix `_OLD`. For example:

Original file space	<code>\\maria\c\$</code>
Renamed file space	<code>\\maria\c\$_OLD</code>

If the new name would conflict with the name of another file space, a number is added to the suffix. For example:

Original file space	<code>\\maria\c\$</code>	Other existing file spaces:
		<code>\\maria\c\$_OLD</code>
		<code>\\maria\c\$_OLD1</code>
Renamed file space	<code>\\maria\c\$_OLD2</code>	

If the new name for the file space exceeds the limit of 64 characters, the file space name is truncated on the right before the suffix `_OLD` is added.

Planning for Unicode Versions of Existing Client File Spaces

You need to consider the following factors in your planning:

- After clients with existing file spaces start to create Unicode-enabled file spaces, they will still need to have access to the renamed file spaces that are not Unicode-enabled for some period of time.
- Your storage pool and database space requirements can double if you allow all clients to create Unicode-enabled file spaces in addition to their existing file spaces that are not Unicode-enabled.

-
- Because the initial backups after migration are complete backups, it can also greatly increase the time required to finish backup operations.

To minimize problems, you need to plan the storage of Unicode-enabled file spaces for clients that already have existing file spaces in server storage.

1. Determine which clients need to migrate.

Clients that have had problems with backing up files because their file spaces contain names of directories or files that cannot be converted to the server's code page should have the highest priority. Balance that with clients that are most critical to your operations. If you have a large number of clients that need to become Unicode enabled, you can control the migration of the clients.

Change the rename option for a few clients at a time to keep control of storage space usage and processing time. Also consider staging migration for clients that have a large amount of data backed up.

2. Allow for increased backup time and network resource usage when the Unicode-enabled file spaces are first created in server storage.

Based on the number of clients and the amount of data those clients have, consider whether you need to stage the migration. Staging the migration means setting the AUTOFSRENAME parameter to YES or CLIENT for only a small number of clients every day.

Note: If you set the AUTOFSRENAME parameter to CLIENT, be sure to have the clients (that run the client scheduler) set their option to AUTOFSRENAME YES. This ensures the file spaces are renamed.

3. Check the current storage usage for the clients that need to become Unicode enabled.

You can use the QUERY OCCUPANCY command to display information on how much space each client is currently using. Initially, clients will need only the amount of space used by active files. Therefore, you need to estimate how much of the current space is used by copies (different versions of the same file). Migration will result in a complete backup at the next incremental backup, so clients will need space for that backup, plus for any other extra versions that they will keep. Therefore, the amount of storage required also depends on policy (see the next step). Your TSM policy specifies how files are backed up, archived, migrated from client node storage, and managed in server storage.

4. Understand how your TSM policies affect the storage that will be needed.

If your policies expire files based only on the number of versions (Versions Data Exists), storage space required for each client will eventually double, until you delete the old file spaces.

If your policies expire files based only on age (Retain Extra Versions), storage space required for each client will increase initially, but will not double.

If your policies use both the number of versions and their age, each client will need less than double their current usage.

5. Estimate the effect on the database size.

The database size depends on the number of files in server storage, as well as the number of versions of those files. As Unicode-enabled file spaces are backed up, the original file spaces that were renamed remain. Therefore, the server requires additional space in the database to store information about the increased number of file spaces and files.

See “Estimating and Monitoring Database and Recovery Log Space Requirements” on page 390 .

6. Arrange for the additional storage pool space, including space in copy storage pools, based on your estimate from step 3 on page 209 and 4 on page 209.
7. Check the server database space that is available and compare with your estimate from step 5 on page 209.
8. Ensure that you have a full database backup *before* you proceed with migration of Unicode-enabled file spaces. See “Backing Up the Database” on page 468.
9. Consider how you will manage the renamed file spaces as they age. The administrator can delete them, or the clients can be allowed to delete their own file spaces.

How Clients are Affected by the Migration to Unicode

The server manages a Unicode-enabled client and its file spaces as follows:

- When a client upgrades to a Unicode-enabled client and logs in to the server, the server identifies the client as Unicode-enabled.

Note: That same client (same node name) cannot log in to the server with a previous version of TSM or a client that is not Unicode-enabled.

- The original file space that was renamed (`_OLD`) remains with both its active and inactive file versions that the client can restore if needed. The original file space will no longer be updated. The server will not mark existing active files inactive when the same files are backed up in the corresponding Unicode-enabled file space.

Note: Before the Unicode-enabled client is installed, the client can back up files in a code page other than the current locale, but cannot restore those files. After the Unicode-enabled client is installed, if the same client continues to use file spaces that are not Unicode-enabled, the client skips files that are not in the same code page as the current locale during a backup. Because the files are skipped, they appear to have been deleted from the client. Active versions of the files in server storage are made inactive on the server. When a client in this situation is updated to a Unicode-enabled client, you should migrate the file spaces for that client to Unicode-enabled file spaces.

- The server does not allow a Unicode-enabled file space to be sent to a client that is not Unicode enabled during a restore or retrieve process.
- Clients should be aware that they will not see all their data on the Unicode-enabled file space until a full incremental backup has been processed.

When a client performs a selective backup of a file or directory and the original file space is renamed, the new Unicode-enabled file space will contain only the file or directory specified for that backup operation. All other directories and files are backed up on the next full incremental backup.

If a client needs to restore a file *before* the next full incremental backup, the client can perform a restore from the renamed file space instead of the new Unicode-enabled file space. For example:

1. Sue had been backing up her file space, `\\sue-node\d$`.
2. Sue upgrades the TSM client on her system to the Unicode-enabled client.
3. Sue performs a selective backup of the file `HILITE.TXT`.

4. The automatic file space renaming function is in effect and TSM renames \\sue-node\d\$ to \\sue-node\d\$_OLD. TSM then creates a new Unicode-enabled file space on the server with the name \\sue-node\d\$. This new Unicode-enabled file space contains only the HILITE.TXT file.
5. All other directories and files in Sue's file system will be backed up on the next full incremental backup. If Sue needs to restore a file before the next full incremental backup, she can restore the file from the \\sue-node\d\$_OLD file space.

Refer to the *Using the Backup-Archive Client* publication for more information.

Example of a Migration Process

This section gives one possible sequence for migrating clients. Assumptions for this scenario are:

- The TSM server database has been backed up.
- The latest server software has been installed. This installation has also performed an upgrade to the server database.
- Clients have installed the latest software.
- A few clients are file servers. Most clients are workstations used by individuals.
- Clients generally run scheduled incremental backups every night.

The following is a possible migration process:

1. Have all clients install the Unicode-enabled TSM client software.
2. Migrate the file servers first. For clients that are file servers, update the AUTOFSRENAME parameter to enable automatic renaming for the file spaces. For example, if the client node names for all file servers begin with FILE, enter the following command:


```
update node file* autofsrname=yes
```

This forces the file spaces to be renamed at the time of the next backup or archive operation on the file servers. If the file servers are large, consider changing the renaming parameter for one file server each day.
3. Allow backup and archive schedules to run as usual. Monitor the results.
 - a. Check for the renamed file spaces for the file server clients. Renamed file spaces have the suffix _OLD or _OLDn, where *n* is a number. (See "The Rules for Automatically Renaming File Spaces" on page 208.)
 - b. Check the capacity of the storage pools. Add tape or disk volumes to storage pools as needed.
 - c. Check database usage statistics to ensure you have enough space.
4. Migrate the workstation clients. For example, migrate all clients with names that start with the letter *a*.


```
update node a* autofsrname=yes
```
5. Allow backup and archive schedules to run as usual that night. Monitor the results.
6. After sufficient time passes, consider deleting the old, renamed file spaces. See "Managing the Renamed File Spaces" on page 212.

Managing the Renamed File Spaces

The file spaces that were automatically renamed (`_OLD`) to allow the creation of Unicode-enabled file spaces continue to exist on the server. Users can still access the file versions in these file spaces.

Because a renamed file space is not backed up again with its new name, the files that are active (the most recent backup version) in the renamed file space remain active and never expire. The inactive files in the file space expire according to the policy settings for how long versions are retained. To determine how long the files are retained, check the values for the parameters, Retain Extra Versions and Retain Only Versions, in the backup copy group of the management class to which the files are bound.

When users no longer have a need for their old, renamed file spaces, you can delete them. If possible, wait for the longest retention time for the only version (Retain Only Version) that any management class allows. If your system has storage constraints, you may need to delete these file spaces before that.

Querying Unicode-enabled File Spaces

You can determine which file spaces are Unicode-enabled by querying all of the file spaces:
`query filespace`

Node Name	Filespace Name	FSID	Platform	Filespace Type	Is Filespace Unicode?	Capacity (MB)	Pct Util
SUE	\\sue\c\$	1	WinNT	NTFS	Yes	2,502.3	75.2
SUE	\\sue\d\$	2	WinNT	NTFS	Yes	6,173.4	59.6
JOE	\\joe\c\$	1	WinNT	NTFS	No	12,299.7	31.7

To query a specific Unicode-enabled file space, it may be more convenient to use the file space identifier (FSID) than the file space name. File space names for Unicode-enabled file spaces may not be readable when displayed in the server's code page. Attempting to enter the name of a Unicode-enabled file space may not work because it depends on the server's code page and conversion routines that attempt to convert from the server's code page to Unicode. See "Displaying Information about File Spaces" on page 213 for details.

Unicode-enabled Clients and Existing Backup Sets

A client can have a backup set that contains both file spaces that are Unicode-enabled and file spaces that are not Unicode-enabled. The client must have the same level of TSM or higher to restore the data in the backup set. For example, a Version 4.1.0 client backs up file spaces, and then upgrades to Version 4.2.0 with support for Unicode-enabled file spaces. That same client can still restore the non-Unicode file spaces from the backup set.

Unicode-enabled file spaces in a backup set can only be accessed by a Unicode-enabled client, and not by an earlier version of the client. The server allows only Unicode-enabled clients to restore data from Unicode-enabled file spaces. For information about restoring backup sets, see "Restoring Backup Sets from a Backup-Archive Client" on page 280.

Choosing to Keep File Spaces that are Not Unicode Enabled

If a client that is using Windows NT or Windows 2000 does not want their file spaces Unicode enabled, the client can install the TSM client for Windows 95/98 on their workstation.

The administrator can also leave the AUTOFSRENAME parameter set to the default of NO for these clients.

Displaying Information about File Spaces

You can display file space information to:

- Identify file spaces defined to each client node, so that you can delete each file space from the server before removing the client node from the server
- Identify file spaces that are Unicode enabled and identify their file space ID (FSID)
- Monitor the space used on workstation's disks
- Monitor whether backups are completing successfully for the file space
- Determine the date and time of the last backup

You display file space information by identifying the client node name and file space name.

Note: File space names are case-sensitive and must be entered exactly as known to the server.

For example, to view information about file spaces defined for client node JOE, enter:

```
query filesystem joe *
```

The following figure shows the output from this command.

Node Name	Filespace Name	FSID	Platform	Filespace Type	Is Filespace Unicode?	Capacity (MB)	Pct Util
JOE	\\joe\c\$	1	WinNT	NTFS	Yes	2,502.3	75.2
JOE	\\joe\d\$	2	WinNT	NTFS	Yes	6,173.4	59.6

When you display file space information in detailed format, the Filespace Name field may display file space names as "...". This indicates to the administrator that a file space does exist but could not be converted to the server's code page. Conversion can fail if the string includes characters that are not available in the server code page, or if the server has a problem accessing system conversion routines.

File space names and file names that can be in a different code page or locale than the server do not display correctly on the administrator's Web interface or the administrative command-line interface. The data itself is backed up and can be restored properly, but the file space name or file name may display with a combination of invalid characters or blank spaces. Refer to *Administrator's Reference* for details.

Deleting File Spaces and Client Nodes

You can delete a client node from a server, but first you must delete all of that client's data from server storage by deleting any file spaces that belong to the node.

Deleting a File Space

Administrators may want to delete a file space when:

- Users are not authorized to delete backed up or archived files in storage pools.

The authority to delete backed up or archived files from server storage is set when a client node is registered. See “Accepting Default Closed Registration or Enabling Open Registration” on page 190 for information on allowing users to delete files in storage pools.

For example, client node PEASE no longer needs archived files in file space */home/pease/dir2*. However, he does not have the authority to delete those files. You can delete them by entering:

```
delete filespace pease /home/pease/dir2 type=archive
```

- You want to remove a client node from the server

You must delete a user’s files from storage pools before you can remove a client node. For example, to delete all file spaces belonging to client node ID DEBBYG, enter:

```
delete filespace debbyg * type=any
```

- You want to delete a specific user’s files

For client nodes that support multiple users, such as UNIX, a file owner name is associated with each file on the server. The owner name is the user ID of the operating system, such as the UNIX user ID. When you delete a file space belonging to a specific owner, only files that have the specified owner name in the file space are deleted.

When a node has more than one file space and you issue a DELETE FILESPACE command for only one file space, a QUERY FILESPACE command for the node during the delete process shows no file spaces. When the delete process ends, you can view the remaining file spaces with the QUERY FILESPACE command.

Note: After you delete all of a client node’s file spaces, you can delete the node with the REMOVE NODE command. See “Deleting Client Nodes” on page 199 for more details.

Modifying Client Option Files

TSM client nodes connect with the server through a client options file (*dsm.opt*). This file, located in the client directory, contains client options that control processing and connections with the server. The most important option is the network address of the server, but you can add many other client options at any time. See more information about client option files, see “Connecting Nodes with the Server” on page 193.

Administrators can also create client option sets to be used in conjunction with client option files. See “Creating Client Option Sets from the Server” on page 215 for more details.

All Nodes

All TSM client options files (*dsm.opt*) can be edited with a text editor. Anyone can edit the client options file if they have access to the directory where the node software is installed. Editing individual options files is the most direct method, but may not be suitable for sites with many client nodes.

Note: If any changes are made to the *dsm.opt* file, the client must be restarted for changes in the options file to have any affect.

Creating Client Option Sets from the Server

An administrator can create a set of client options to be used by a client node at TSM Version 3 or later. The client options specified in the set are used in conjunction with the client options file described in “Connecting Nodes with the Server” on page 193.

Client options sets allow the administrator to specify additional options that may not be included in the client’s option file (dsm.opt). Specify the option set with the REGISTER NODE or UPDATE NODE commands. The client can use these defined options during a backup, archive, restore, or retrieve process. See *Tivoli Storage Manager Installing the Clients* for detailed information about individual client options.

To create a client option set and have the clients use the option set, do the following:

1. Create the client option set with the DEFINE CLOPTSET command.
2. Add client options to the option set with the DEFINE CLIENTOPT command.
3. Specify which clients should use the option set with the REGISTER NODE or UPDATE NODE command.

Creating a Client Option Set

When you create a client option set, you define a name for the option set, and can optionally provide a description of the option set. For example:

```
define cloptset engbackup description='Backup options for eng. dept.'
```

Note: The option set is empty when it is first defined.

Adding Client Options in an Option Set

You can add client options in a defined client option set.

The following example shows how to add a client option in the ENGBACKUP option set.

```
define clientopt engbackup schedlogretention 5
```

For a list of valid client options you can specify, refer to *Administrator’s Reference*.

The server automatically assigns sequence numbers to the specified options, or you can choose to specify the sequence number for order of processing. This is helpful if you have defined more than one of the same option as in the following example.

```
define clientopt engbackup inclexcl "include d:\admin"
define clientopt engbackup inclexcl "include d:\payroll"
```

A sequence number of 0 is assigned to the option *include d:\admin*. A sequence number of 1 is assigned to the option *include d:\payroll*. If you want to specifically process one option before another, include the sequence parameter as follows:

```
define clientopt engbackup inclexcl "include d:\admin sequence=2"
define clientopt engbackup inclexcl "include d:\payroll sequence=1"
```

The FORCE parameter allows an administrator to specify whether a client node can override an option value. The default value is NO. If FORCE=YES, the client cannot override the value.

Registering Client Nodes and Assigning Them to an Option Set

You can register or update a client node and specify an option set for the client to use as follows:

```
register node mike pass2eng cloptset=engbackup
```

The client node MIKE is registered with the password pass2eng. When the client node MIKE performs a scheduling operation, his schedule log entries are kept for 5 days.

Managing Client Options from the Server Using Client Option Sets

Administrators can perform the following activities when managing client option sets:

Task	Required Privilege Class
Updating the sequence number for a client option	System or unrestricted policy
Deleting an option from a client option set	System, unrestricted policy, or restricted policy
Copying a client option set	System, unrestricted policy, or restricted policy
Displaying client option set information	Any administrator
Updating the client option set description	System, unrestricted policy, or restricted policy
Deleting a client option set	System, unrestricted policy, or restricted policy

Updating the Sequence Number for a Client Option

You can update the sequence number for a client option to change its processing order. This is helpful if you have more than one of the same option, for example several INCLUDE options.

The following example shows how to change the sequence number for the DATEFORMAT option from 0 to 9:

```
update clientopt engbackup dateformat 0 9
```

Deleting an Option from a Client Option Set

You can remove an option that is defined in a client option set. The following example shows how to remove the SCHEDMODE polling option from the financeschd option set:

```
delete clientopt financeschd schedmode
```

Copying a Client Option Set

You can copy an existing client option to another option set. The following example shows how to copy the engbackup option set to financeschd option set:

```
copy cloptset engbackup financeschd
```

Requesting Information about a Client Option Set

To display information about the contents of a client option set, issue the following command:

```
query cloptset financeschd
```

Updating the Description for a Client Option Set

You can update the description for a client option set. The following example shows how to update the description for the engbackup option set:

```
update cloptset engbackup description='Scheduling information'
```

Deleting a Client Option Set

When you delete a client option set, client node references to the option set are null. The clients continue to use their existing client options file. The following example shows how to delete the engbackup client option set:

```
delete cloptset engbackup
```

Managing Tivoli Storage Manager Sessions

Each time an administrator or client node connects with the server, an administrative or client session is established. TSM tracks its sessions in the server database. Backup-archive clients are eligible for client restartable restore sessions, however, application clients are not. See “Managing Client Restartable Restore Sessions” on page 220 for more information.

Administrators can perform the following activities when managing TSM sessions:

Task	Required Privilege Class
Displaying information about client sessions	Any administrator
Canceling a client session	System or operator
Disabling or enabling a client session	System or operator
Freeing links for client connections	Administrator with root authority

Displaying Information about Tivoli Storage Manager Sessions

Each client session is assigned a unique session number. To display information about client sessions, enter:

```
query session
```

Figure 42 shows a sample client session report.

Sess Number	Comm. Method	Sess State	Wait Time	Bytes Sent	Bytes Recvd	Sess Type	Platform	Client Name
471	Tcp/Ip	IdleW	36 S	592	186	Node	WinNT	JOEUSER
472	Tcp/Ip	RecvW	0 S	730	838.2 K	Node	WinNT	STATION1
475	HTTP	Run	0 S	0	0	Admin	WebBrow- ser	ADMIN

Figure 42. Information about Client Sessions

You can determine the state of the server by examining the *session state* and *wait time* to determine how long (in seconds, minutes, or hours) the session has been in the current state.

Server Session States

The server session state can be one of the following:

Start Connecting with a client session.

Run Executing a client request.

End Ending a client session.

RecvW

Waiting to receive an expected message from the client while a database transaction is in progress. A session in this state is subject to the COMMTIMEOUT limit.

SendW

Waiting for acknowledgment that the client has received a message sent by the server.

MediaW

Waiting for removable media to become available.

Aggregation can cause multiple media waits within a transaction and is indicated by one client message. For more information, see “Reclaiming Space in Sequential Access Storage Pools” on page 152.

Note: If `QUERY SESSION FORMAT=DETAILED` is specified, the Media Access Status field displays the type of media wait state.

IdleW Waiting for communication from the client, and a database transaction is NOT in progress. A session in this state is subject to the `IDLETIMEOUT` limit as specified in the server options file.

If a client does not initiate communication within the specified time limit set by the `IDLETIMEOUT` option in the server options file, then the server cancels the client session.

For example, if the `IDLETIMEOUT` option is set to 30 minutes, and a user does not initiate any operations within those 30 minutes, then the server cancels the client session. The client session is automatically reconnected to the server when it starts to send data again.

Canceling a Tivoli Storage Manager Session

You can cancel a client session with the `CANCEL SESSION` command and the associated session number. Canceling sessions may be necessary when a user’s machine is not responding or as a prerequisite to halting the server. Administrators can display a session number with the `QUERY SESSION` command as described in “Displaying Information about Tivoli Storage Manager Sessions” on page 217.

Users and administrators whose sessions have been canceled must reissue their last command to access the server again.

If an operation, such as a backup or an archive process, is interrupted when you cancel the session, the server rolls back the results of the current transaction. That is, any changes made by the operation that are not yet committed to the database are undone. If necessary, the cancellation process may be delayed.

If the session is in the Run state when it is canceled, the cancel process does not take place until the session enters the SendW, RecvW, or IdleW state. For details, see “Server Session States” on page 217.

If the session you cancel is currently waiting for a media mount, the mount request is automatically canceled. If a volume associated with the client session is currently being mounted by an *automated* library, the cancel may not take effect until the mount is complete.

For example, to cancel a session for client MARIE:

1. Query client sessions to determine the session number as shown Figure 42 on page 217. The example report displays MARIE’s session number 6.
2. Cancel node MARIE’s session by entering:
`cancel session 6`

If you want to cancel all backup and archive sessions, enter:

```
cancel session all
```

When a Client Session is Automatically Canceled

Client sessions can be automatically canceled based on the settings of the following server options:

COMMTIMEOUT

Specifies how many seconds the server waits for an expected client message during a transaction that causes a database update. If the length of time exceeds this time-out, the server rolls back the transaction that was in progress and ends the client session. The amount of time it takes for a client to respond depends on the speed and processor load for the client and the network load.

IDLETIMEOUT

Specifies how many minutes the server waits for a client to initiate communication. If the client does not initiate communication with the server within the time specified, the server ends the client session. For example, the server prompts the client for a scheduled backup operation but the client node is not started. Another example can be that the client program is idle while waiting for the user to choose an action to perform (for example, backup archive, restore, or retrieve files). If a user starts the client session and does not choose an action to perform, the session will time out. The client program automatically reconnects to the server when the user chooses an action that requires server processing. A large number of idle sessions can inadvertently prevent other users from connecting to the server.

THROUGHPUTDATATHRESHOLD

Specifies a throughput threshold, in kilobytes per second, a client session must achieve to prevent being cancelled after the time threshold is reached. Throughput is computed by adding send and receive byte counts and dividing by the length of the session. The length does not include time spent waiting for media mounts and starts at the time a client sends data to the server for storage. This option is used in conjunction with the THROUGHPUTTIMETHRESHOLD server option.

THROUGHPUTTIMETHRESHOLD

Specifies the time threshold, in minutes, for a session after which it may be canceled for low throughput. The server ends a client session when it has been active for more minutes than specified and the data transfer rate is less than the amount specified in the THROUGHPUTDATATHRESHOLD server option.

Refer to the *Administrator's Reference* for more information.

Freeing Links for SNA LU6.2 Client Connections

When a client node initially logs on to an TSM server by using SNA LU6.2, a SNASVCMG session link is established between the client and the server. This link remains in session even after the user logs off from TSM. If enough sessions are left connected, new clients can be prevented from connecting to the server.

Because only SNA LU6.2 links must be recycled only after the first time a client logs on and off the system, administrators must deactivate the SNASVCMG link once for each new user. Initially, you may want to recycle links daily until most users have registered with TSM. After most users have been registered with TSM, you may want to recycle SNA LU6.2 links less frequently; monthly, for example.

To free unused SNA LU6.2 links, an administrator with root authority must recycle the links as described below.

The server cannot stop the SNASVCMG mode sessions because it does not create them. It is the task of the administrator with root authority to manually deactivate SNASVCMG mode sessions between the server and clients. Because only one SNASVCMG mode session is created for each client, you only need to deactivate the client once. You should deactivate the SNASVCMG sessions on a regular basis to reduce the number of active sessions to zero so that link stations can be recycled.

The administrator with root authority can remove the SNASVCMG sessions by doing the following:

1. On the command line, type **smit sna**.
 2. On the first window, click on **Manage SNA Resources**.
 3. On the next window, click on **Stop SNA Resources**.
 4. On the next window, click on **Stop a SNA Session**.
 5. On the next window, select from the list of the conversation group ID, the entry with SNASVCMG mode and the partner LU name.
 6. Click on **Do**.
- Repeat the last 2 steps as necessary to deactivate the SNASVCMG mode sessions with other clients.

Disabling or Enabling Access to the Server

Task	Required Privilege Class
Disabling and enabling client node access to the server	System or operator
Displaying server status	Any administrator

You can prevent clients from establishing sessions with the server by using the **DISABLE SESSIONS** command. This command does not cancel sessions currently in progress or system processes like migration and reclamation. For example, to disable client node access to the server, enter:

```
disable sessions
```

You continue to access the server and current client activities complete unless a user logs off or an administrator cancels a client session. After the client sessions have been disabled, you can enable client sessions and resume normal operations by entering:

```
enable sessions
```

You can issue the **QUERY STATUS** command to determine if the server is enabled or disabled.

Managing Client Restartable Restore Sessions

Some large restore operations may invoke a special type of restore operation called client restartable restore sessions. These special sessions allow users to restart the restore session from where it left off if the session was interrupted. TSM identifies client restartable restore sessions by displaying message **ANS1247I** on the client machine when the sessions start. These restore sessions can be restarted as long as the restore interval has not expired.

When a restartable restore session is saved in the server database the file space is locked. The following is in effect during the file space lock:

- Files residing on sequential volumes associated with the file space cannot be moved.
- Files associated with the restore cannot be backed up. However, files not associated with the restartable restore session that are in the same file space are eligible for backup. For example, if you are restoring all files in directory A, you can still backup files in directory B from the same file space.

The `RESTOREINTERVAL` server option allows administrators to specify how long client restartable restore sessions are saved in the server database. Consider scheduled backup operations when setting this option. For more information, refer to the `RESTOREINTERVAL` server option in *TSM Administrator's Reference*.

Administrators can perform the following activities when managing client restartable restore sessions:

Task	Required Privilege Class
Displaying information about client restartable restore sessions	Any administrator
Canceling client restartable restore sessions	System or operator
Interrupting client restartable restore sessions	System or operator

Displaying Information about a Client Restartable Restore Session

You can display information about client restartable restore sessions with the `QUERY RESTORE` command. For example, to determine which client nodes have eligible restartable restore sessions, enter:

```
query restore
```

Restartable restore sessions have a negative session number.

Canceling a Client Restartable Restore Session

When a client restore session is in a restartable state, the file space is locked and no files can be moved from sequential volumes. This prevents the data from being migrated, moved, reclaimed, or backed up by another operation. These sessions will automatically expire when the specified restore interval has passed.

An administrator can cancel a restartable restore session that is in an active or restartable state. If the restore session is active, any outstanding mount requests related to the active session are automatically canceled. When a restartable restore session is canceled with the `CANCEL RESTORE` command, it cannot be restarted from the point of interruption. A restartable restore session always has a negative session number.

To cancel a restartable restore session, you must specify the session number. For example:

```
cancel restore -1
```

Interrupting an Active Client Restartable Restore Session

An administrator can interrupt an active restartable restore session and have the option to later restart the session from its point of interruption by canceling the session.

```
cancel session -2
```

Managing Tivoli Storage Manager Security

Administrators can perform the following activities when managing TSM security.

Task
Managing administrators
Managing levels of administrative authority
Managing administrator access to the server and clients
Managing passwords
Managing the server console

Managing Tivoli Storage Manager Administrators

The administrator is responsible for registering other administrators, granting levels of authority, renaming or removing administrators, or for locking and unlocking administrators from the server.

Task	Required Privilege Class
Registering an administrator	System
Granting administrative authority	System
Updating information about other administrators	System
Updating information about yourself	Any administrator
Displaying information about administrators	Any administrator
Renaming an administrator user ID	System
Removing administrators	System
Locking or unlocking administrators from the server	System

Registering Administrators

The administrator registers other administrators with the REGISTER ADMIN command.

To register the administrator with a user ID of DAVEHIL and the password of *birds*, and a password expiration period of 120 days, enter the REGISTER ADMIN command:

```
register admin davehil birds passexp=120 contact='backup team'
```

Granting Administrative Authority

After administrators are registered, they can make queries and request command-line help. To perform other server functions, they must be granted authority by being assigned one or more administrative privilege classes.

This section describes the privilege classes, which are illustrated in Figure 43 on page 223. An administrator with system privilege can perform any server function. Administrators with policy, storage, operator, analyst, or node privileges can perform subsets of server functions. For details, see “Overview of Tivoli Storage Manager Privilege Classes” on page 230.




Figure 43. Administrative Privilege Classes

Privilege classes can be summarized as follows:

Privilege Class	Responsibilities
System Example: grant authority rocko classes=system	<ul style="list-style-type: none"> ■ System-wide responsibilities ■ Manage the enterprise ■ Manage TSM security
Unrestricted Policy Example: grant authority smith classes=policy	<ul style="list-style-type: none"> ■ Manage nodes ■ Manage policy ■ Manage schedules
Restricted Policy Example: grant authority jones domains=engpoldom	Same responsibilities as unrestricted policy except authority is limited to specific policy domains.
Unrestricted Storage Example: grant authority coyote classes=storage An administrator with unrestricted storage privilege cannot define or delete storage pools.	<ul style="list-style-type: none"> ■ Manage the TSM database and recovery log ■ Manage TSM devices ■ Manage TSM storage
Restricted Storage Example: grant authority holland stgpools=tape*	Same responsibilities as unrestricted storage except authority is limited to specific storage pools
Operator Example: grant authority bill classes=operator	<ul style="list-style-type: none"> ■ Manage the TSM server ■ Manage client sessions ■ Manage tape operations
Analyst Example: grant authority marysmith classes=analyst	Reset the counters that track TSM server statistics

Privilege Class	Responsibilities
Node Example: grant authority help1 classes=node node=labclient	Perform backup and restore operations for a Web backup-archive client

Updating Information about Other Administrators

An administrator can reset another administrator's password with the UPDATE ADMINISTRATOR command. For example, administrator DAVEHIL changes his password to *ganymede*, by issuing the following command:

```
update admin davehil ganymede
```

Renaming an Administrator

You can rename an administrator ID when an employee wants to be identified by a new ID, or you want to assign an existing administrator ID to another person. You cannot rename an administrator ID to one that already exists on the system.

For example, if administrator HOLLAND leaves your organization, you can assign administrative privilege classes to another user by completing the following steps:

1. Assign HOLLAND's user ID to WAYNESMITH by issuing the RENAME ADMIN command:

```
rename admin holland waynesmith
```

By renaming the administrator's ID, you remove HOLLAND as a registered administrator from the server. In addition, you register WAYNESMITH as an administrator with the password, contact information, and administrative privilege classes previously assigned to HOLLAND.

2. Change the password to prevent the previous administrator from accessing the server by entering:

```
update admin waynesmith new_password contact="development"
```

Note: The administrator SERVER_CONSOLE cannot be renamed. See “Managing the Server Console” on page 229.

Removing Administrators

You can remove administrators from the server so that they no longer have access to administrator functions. For example, to remove registered administrator ID SMITH, enter:

```
remove admin smith
```

Notes:

1. You cannot remove the last system administrator from the system.
2. You cannot remove the administrator SERVER_CONSOLE. See “Managing the Server Console” on page 229 for more information.

Displaying Information about Administrators

Any administrator can query the server to display administrator information. You can also query all administrators authorized with a specific privilege class.

For example, to query the system for a detailed report on administrator ID DAVEHIL, issue the QUERY ADMIN command:

```
query admin davehil format=detailed
```

Figure 44 displays a detailed report.

```

Administrator Name: DAVEHIL
Last Access Date/Time: 1998.06.04 17.10.52
Days Since Last Access: <1
Password Set Date/Time: 1998.06.04 17.10.52
Days Since Password Set: 26
Invalid Sign-on Count: 0
  Locked?: No
  Contact:
System Privilege: Yes
Policy Privilege: **Included with system privilege**
Storage Privilege: **Included with system privilege**
Analyst Privilege: **Included with system privilege**
Operator Privilege: **Included with system privilege**
Client Access Privilege: **Included with system privilege**
Client Owner Privilege: **Included with system privilege**
Registration Date/Time: 05/09/1998 23:54:20
Registering Administrator: SERVER_CONSOLE
  Managing profile:
Password Expiration Period: 90 Day (s)

```

Figure 44. A Detailed Administrator Report

Locking and Unlocking Administrators from the Server

Administrators can prevent other administrators from accessing the server by locking and unlocking their administrative privilege classes. For details, see “Locking and Unlocking Administrators from the Server” on page 226.

Managing Levels of Administrative Authority

A privilege class is a level of authority granted to a TSM administrator. The privilege class determines which TSM administrative tasks the administrator can perform. See “Overview of Tivoli Storage Manager Privilege Classes” on page 230 about the activities that administrators can perform with each privilege class.

You can perform the following activities when managing other administrators’ levels of TSM authority:

Task	Required Privilege Class
Modifying administrators level of authority	System
Locking and unlocking administrators from the server	System

Modifying Administrator Levels of Authority

You may need to modify other administrators levels of authority as more clients and administrators are added to the TSM environment. If a person already has some level of TSM authority, granting additional authority adds to any existing privilege classes; it does not override those classes.

Extending Authority for Administrators

You can grant and extend authority with the GRANT AUTHORITY command. For example, JONES has restricted policy privilege for policy domain ENGPOLDOM. Enter the following command to extend JONES' authority to policy domain MKTPOLDOM and add operator privilege:

```
grant authority jones domains=mktpoldom classes=operator
```

As an additional example, assume that three tape storage pools exist: TAPEPOOL1, TAPEPOOL2, and TAPEPOOL3. To grant restricted storage privilege for these storage pools to administrator HOLLAND, you can enter the previous command:

```
grant authority holland stgpools=tape*
```

HOLLAND is restricted to managing storage pools beginning with TAPE that existed when the authority was granted. HOLLAND is not authorized to manage any storage pools that are defined after authority has been granted.

To add a new storage pool, TAPEPOOL4, to HOLLAND's authority, enter:

```
grant authority holland stgpools=tapepool4
```

Reducing Authority for Administrators

You can revoke part of an administrator's authority with the REVOKE AUTHORITY command and specifying the administrator's ID and one or more privilege classes.

Assume that rather than revoking all of the privilege classes for administrator JONES you wished only to revoke his operator authority and his policy authorization to policy domain MKTPOLDOM. You would enter:

```
revoke authority jones classes=operator domains=mktpoldom
```

JONES still has policy privilege to the ENGPOLDOM policy domain.

Reducing Privilege Classes

You can reduce an administrator's authority simply by revoking one or more privilege classes and granting one or more other classes.

For example, administrator HOGAN has system authority. To reduce HOGAN to the operator privilege class do the following:

1. Revoke the system privilege class by entering:

```
revoke authority hogan classes=system
```

2. Grant operator privilege class by entering:

```
grant authority hogan classes=operator
```

Revoking Authority for Administrators

You can revoke an administrator's authority with the REVOKE AUTHORITY command. To revoke all administrative privilege classes, do not specify any privilege classes, policy domains, or storage pools. For example, to revoke both the storage and operator privilege classes from administrator JONES enter:

```
revoke authority jones
```

Locking and Unlocking Administrators from the Server

You can lock out other administrators to temporarily prevent them from accessing TSM with the LOCK ADMIN command.

For example, administrator MARYSMITH takes a leave of absence from your business. You can lock her out by entering:

```
lock admin marysmith
```

When she returns, any system administrator can unlock her administrator ID by entering:

```
unlock admin marysmith
```

MARYSMITH can now access the server to complete administrative tasks.

You cannot lock or unlock the SERVER_CONSOLE ID from the server. See “Managing the Server Console” on page 229 for details.

Managing Access to the Server and Clients

An administrator can control access to the server by registering and granting authority to administrators, renaming or removing an administrator, or by locking and unlocking an administrator from the server.

By default, a system or policy administrator over a specified client’s domain can create a backup set from a client node’s latest active files. For more information, see “Managing Schedules for Client Nodes” on page 293.

When an administrator accesses the administrative Web interface, only the tasks that correspond to the administrator’s privilege class are displayed.

Preventing Clients from Accessing the Server

You can prevent clients from establishing administrative sessions with the server. For details, see “Locking and Unlocking Client Nodes” on page 199.

Preventing Administrators from Accessing the Server

You can prevent other administrators from establishing administrative sessions with the server. For details, see “Locking and Unlocking Administrators from the Server” on page 226.

Disabling or Enabling Client Sessions

You can prevent clients from establishing sessions with the server. This effectively locks the nodes from the server. For details, see “Disabling or Enabling Access to the Server” on page 220.

Managing Passwords

By default, TSM requires authorized administrators and nodes to identify themselves to the TSM server with a password.

Administrators can perform the following activities when managing passwords

Task	Required Privilege Class
Modifying the default timeout period for the administrative Web interface	System
Modifying the default password expiration period	
Setting the limit for invalid password attempts	
Setting the minimum limit for passwords	
Disabling the default password authentication	

Modifying the Default Timeout Period for the Administrative Web Interface

At installation, the timeout default value for the administrative Web interface is 10 minutes. When the timeout period expires, the user of the Web interface is required to reauthenticate by logging on and specifying a password. The following example shows how to set the timeout value to 20 minutes:

```
set webauthtimeout 20
```

You can specify a value from 0 to 9999 minutes. If the minimum value is 0, there is no timeout period for the administrative Web interface. To help ensure the security of an unattended browser, it is recommended that you set the timeout value higher than zero.

Modifying the Default Password Expiration Period

By default, the server sets a password expiration of 90 days. The expiration period begins when an administrator or client node is first registered to the server. If a user password is not changed within this period, the server prompts the user to change the password the next time the user tries to access the server.

To set the password expiration period for selected administrators or client nodes, you must specify the administrator or node names with the ADMIN or NODE parameter with the SET PASSEXP command. If you set the expiration period only for selected users, you may set the expiration period from 0–9999 days. A value of 0 means that user’s password never expires. For example, to set the expiration period of client node LARRY to 120 days, issue the following command:

```
set passexp 120 node=larry
```

Note: Once you have explicitly set a password expiration for a node or administrator, it is not modified if you later set a password expiration for all users.

Setting a Limit for Invalid Password Attempts

By default, TSM does not check the number of times a user attempts to login to TSM with an invalid password. You can set a limit on consecutive invalid password attempts for all client nodes. When the limit is exceeded, the server locks the node. The following example sets a system-wide limit of three consecutive invalid password attempts:

```
set invalidpwlimit 3
```

The default value at installation is 0. A value of 0 means that invalid password attempts are not checked. You can set the value from 0 to 9999 attempts.

If you initially set a limit of 4 and then change the limit to a lower number, some clients may fail verification during the next login attempt.

After a client node has been locked, only a storage administrator with proper authority can unlock the node. For information about unlocking a client or administrator node, see “Locking and Unlocking Client Nodes” on page 199 and “Locking and Unlocking Administrators from the Server” on page 226.

An administrator can also force a client to change their password on the next login by specifying the `FORCEPWRESET=YES` parameter on the `UPDATE NODE` or `UPDATE ADMIN` command. For more information, refer to *Administrator's Reference*.

Setting a Minimum Length for a Password

By default, TSM does not check the minimum length of a password. The administrator can specify a minimum password length that is required for TSM passwords. The following example shows how to set the minimum password length to eight characters:

```
set minpwlength 8
```

The default value at installation is 0. A value of 0 means that password length is not checked. You can set the length value from 0 to 64.

Disabling the Default Password Authentication

By default, the server automatically sets password authentication on. With password authentication set to on, all users must enter a password when accessing the server. To allow administrators and client nodes to access the server without entering a password, issue the following command:

```
set authentication off
```

Attention: Setting password authentication off reduces data security.

Managing the Server Console

At installation, the server console is defined with a special user ID, which is named `SERVER_CONSOLE`. This name is reserved and cannot be used by another administrator.

An administrator with system privilege can revoke or grant new privileges to the `SERVER_CONSOLE` user ID. However, an administrator cannot update, lock, rename, or remove the `SERVER_CONSOLE` user ID. The `SERVER_CONSOLE` user ID does not have a password. Therefore, you cannot use the user ID from an administrative client unless you set authentication off.

Overview of Client Nodes and File Spaces

Each client is given a node name when it is registered with the server. The server views its registered nodes as clients that require services and resources from the server.

Typically, a node is equivalent to a machine as in the case of a backup-archive client installed on a user's computer for file system backups. However, multiple nodes can exist on a single machine as in the case of a SQL server machine containing both an application client for SQL database and transaction log backups, and a backup-archive client for file system backups.

Typically, each client file system is represented on the server as a unique file space that belongs to each client node. Therefore, the number of file spaces a node has depends on the number of file systems on the client machine. For example, a Windows desktop system may have multiple drives (file systems), such as C: and D:. In this case, the client's node has two file spaces on the server; one for the C: drive and a second for the D: drive. The file spaces can grow as a client stores more data on the server. The file spaces decrease as backup and archive file versions expire and the server reclaims the space. TSM does not allow an administrator to delete a node unless the node's file spaces have been deleted.

File Spaces for Clients

For client nodes running on Windows, file spaces map to logical partitions and shares. Each file space is named with the UNC name of the respective client partition or share.

For client nodes running on NetWare, file spaces map to NetWare volumes. Each file space is named with the corresponding NetWare volume name.

For clients running on Macintosh, file spaces map to Macintosh volumes. Each file space is named with the corresponding Macintosh volume name.

For clients running AIX or SunOS, a file space name identifies a file system or file space defined by a user with the VIRTUALMOUNTPOINT option. With this option, users can define a virtual mount point for a file system to back up or archive files beginning with a specific directory or subdirectory. For information on the VIRTUALMOUNTPOINT option, refer to the appropriate *Using the Backup-Archive Client*.

Overview of Tivoli Storage Manager Privilege Classes

After administrators are registered, they can make queries and request command-line help. To perform other server functions, they must be granted authority by being assigned one or more administrative privilege classes.

This section describes the privilege classes. An administrator with system privilege can perform any server function. Administrators with policy, storage, operator, or analyst privileges can perform subsets of server functions.

System Privilege

An administrator with *system privilege* can perform any of the following server administrative tasks.

System responsibilities

- Define or delete policy domains and storage pools
- Import or export data from the server
- Cancel administrative background processes
- Set operating parameters for the server
- Perform license audits
- Cancel client restartable restore sessions
- Move sequential access storage pool media
- Begin logging events to a receiver
- Create a full backup set from a client node's latest active files

Set up enterprise management

- Create or delete a target server to a source server
- Set and manage server configuration managers
- Define and manage server groups and group members
- Define and manage server profiles
- Test the connection between the local server and a specified remote server

Manage TSM security

- Register or remove administrators
- Manage administrators
- Grant or revoke all levels of administrative authority
- Lock or unlock administrators from the server
- Manage TSM passwords and logins

Unrestricted Policy Privilege

An administrator with *unrestricted policy privilege* can manage the backup and archive services for client nodes assigned to any policy domain. When new policy domains are defined to the server, an administrator with unrestricted policy privilege is automatically authorized to manage the new policy domains.

An administrator with unrestricted policy privilege can perform the following tasks:

Manage TSM nodes

- Register client nodes in any policy domain
- Manage any client node access to the server
- Delete any client node files from storage pools
- Create a full backup set from a client node's latest active files

Manage TSM policy

- Manage policy objects within any policy domain
- Note:** System privilege is required to copy, define, or delete the policy domains themselves.

Manage TSM schedules

- Manage schedules that automatically back up or archive files
- Associate client nodes to schedules defined in the same policy domain

Restricted Policy Privilege

An administrator with *restricted policy privilege* can perform the same operations as an administrator with unrestricted policy privilege **but only for specified policy domains**.

Unrestricted Storage Privilege

An administrator with *unrestricted storage privilege* has the authority to manage the database, recovery log, and all storage pools.

An administrator with unrestricted storage privilege can perform the following tasks:

Manage the TSM database and recovery logs

- Create database or recovery log volumes
- Extend or reduce the size of the database or recovery log
- Create mirrored copy sets of the database or recovery log
- Delete database or recovery log volumes

Manage TSM devices

- Manage disk and tape device classes

Manage TSM storage pool volumes

- Create volumes for any disk or tape storage pools
 - Move data from a storage pool to any other storage pool
 - Delete volumes from any storage pool
- Note:** However, an administrator with unrestricted storage privilege cannot define or delete storage pools.
- Audit volumes belonging to any storage pool
 - Move sequential access storage pool media

Restricted Storage Privilege

Administrators with *restricted storage privilege* can manage only those storage pools to which they are authorized. They cannot manage the database or recovery log.

For those authorized storage pools, administrators with restricted storage privilege can:

Manage storage pool volumes

- Create volumes to the storage pools
- Move data from one volume to another in a storage pool
- Delete volumes from the storage pools
- Audit volumes belonging to the storage pools

Operator Privilege

Administrators with *operator privilege* control the immediate operation of the server and the availability of storage media.

An administrator with operator privilege can perform the following tasks:

Manage the TSM server

- Disable the server to prevent clients from accessing the server
- Enable the server for access by clients
- Halt the server, when necessary

Manage TSM sessions

- Cancel client/server sessions
- Cancel client restartable restore sessions

Manage tape operations

- Vary disk volumes on or off line to perform maintenance
- Reset the error status for tape volumes
- Manage tape mounts

Analyst Privilege

An administrator with *analyst privilege* can issue commands that reset the counters that track server statistics.

Node Privilege

A user with *node privilege* can access a Web backup-archive client to perform backup and restore operations. An administrative user ID with the node privilege class has either client owner authority or client access authority.

12

Implementing Policies for Client Data

Policies are rules that you set at the Tivoli Storage Manager (TSM) server to help you manage client data. Policies control how and when client data is stored, for example:

- How and when files are backed up and archived to server storage
- How space-managed files are migrated to server storage
- The number of copies of a file and the length of time copies are kept in server storage

Tivoli Storage Manager provides a standard policy that sets rules to provide a basic amount of protection for data on workstations. If this standard policy meets your needs, you can begin using Tivoli Storage Manager immediately. See “Basic Policy Planning” on page 234 for information about the standard policy.

The server process of expiration is one way that the server enforces policies that you define. Expiration processing determines when files are no longer needed, that is, when the files are expired. For example, if you have a policy that requires only four copies of a file be kept, the fifth and oldest copy is expired. During expiration processing, the server removes entries for expired files from the database, effectively deleting the files from server storage. See “File Expiration and Expiration Processing” on page 237 and “Running Expiration Processing to Delete Expired Files” on page 264 for details.

You may need more flexibility in your policies than the standard policy provides. To accommodate individual user’s needs, you may fine tune the STANDARD policy (see “Getting Users Started” on page 236 for details), or create your own policies (see “Creating Your Own Policies” on page 251 for details). Some types of clients or situations require special policy. For example, you may want to enable clients to restore backed-up files to a specific point in time (see “Setting Policy to Enable Point-in-Time Restore for Clients” on page 270 for more information).

Policy can be distributed from a configuration manager to managed servers. See “Working with a Network of Tivoli Storage Manager Servers” on page 309 for more information on distributing configurations.

See the following sections:

Concepts:
“Basic Policy Planning” on page 234
“The Standard Policy” on page 235
“File Expiration and Expiration Processing” on page 237
“Client Operations Controlled by Policy” on page 238

Concepts:
“The Parts of a Policy” on page 240
“More on Management Classes” on page 241
“How Tivoli Storage Manager Selects Files for Policy Operations” on page 246
“How Client Migration Works with Backup and Archive” on page 250

Tasks:
“Getting Users Started” on page 236
“Overview: Changing Policy” on page 237
“Creating Your Own Policies” on page 251
“Defining and Updating a Policy Domain” on page 253
“Defining and Updating a Policy Set” on page 254
“Defining and Updating a Management Class” on page 254
“Defining and Updating a Backup Copy Group” on page 255
“Defining and Updating an Archive Copy Group” on page 261
“Assigning a Default Management Class” on page 262
“Validating and Activating a Policy Set” on page 263
“Assigning Client Nodes to a Policy Domain” on page 264
“Running Expiration Processing to Delete Expired Files” on page 264
“Setting Policy to Enable Point-in-Time Restore for Clients” on page 270
“Policy for Tivoli Storage Manager Servers as Clients” on page 270
“Configuring Policy for Tivoli Data Protection Application Clients” on page 267
“Policy for Logical Volume Backups” on page 267
“Configuring Policy for Managed System for SAN” on page 268
“Distributing Policy Using Enterprise Configuration” on page 270
“Querying Policy” on page 271
“Deleting Policy” on page 273

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Basic Policy Planning

Start out simply to plan your policy. You may be able to use the default policy that comes with the server. Ask the questions:

- How many backup versions do clients need?
- How long do clients need the backup versions?

Examine the default policy to see if it meets your needs:

- Up to two backup versions of a file on the client’s system are retained in server storage.

- The most recent backup version is retained for as long as the original file is on the client file system. All other versions are retained for up to 30 days after they become inactive.
- One backup version of a file that has been deleted from the client's system is retained in server storage for 60 days.
- An archive copy is kept for up to 365 days.

See “The Standard Policy” for more details about the standard policy.

The server manages files based on whether the files are active or inactive. The most current backup or archived copy of a file is the active version. All other versions are called inactive versions. An active version of a file becomes inactive when:

- A new backup is made
- A user deletes that file on the client node and then runs an incremental backup

Policy determines how many inactive versions of files the server keeps, and for how long. When files exceed the criteria, the files expire. Expiration processing can then remove the files from the server database. See “File Expiration and Expiration Processing” on page 237 and “Running Expiration Processing to Delete Expired Files” on page 264 for details.

The Standard Policy

The standard policy consists of a standard policy domain, policy set, management class, backup copy group, and archive copy group. Each of these parts is named STANDARD. See “The Parts of a Policy” on page 240 for details. The attributes of the default policy are as follows:

Table 19. Summary of Default Policy

Policy	Object where the policy is set
<i>Backup Policies</i>	
Files are backed up to the default disk storage pool, BACKUPPOOL.	STANDARD backup copy group, DESTINATION parameter
An incremental backup is performed only if the file has changed since the last backup.	STANDARD backup copy group, MODE parameter
Files cannot be backed up while they are being modified.	STANDARD backup copy group, SERIALIZATION parameter
Up to two backup versions of a file on the client's system are retained in server storage. The most recent backup version is retained for as long as the original file is on the client file system. All other versions are retained for up to 30 days after they become inactive.	STANDARD backup copy group, the following parameters: VEREXISTS RETEXTRA REONLY
One backup version of a file that has been deleted from the client's system is retained in server storage for 60 days.	STANDARD backup copy group, VERDELETED parameter
When a backed up file is no longer associated with a backup copy group, it remains in server storage for 30 days (backup retention grace period).	STANDARD policy domain, BACKRETENTION parameter
<i>Archive Policies</i>	

Table 19. Summary of Default Policy (continued)

Policy	Object where the policy is set
Files are archived in the default disk storage pool, ARCHIVEPOOL.	STANDARD archive copy group, DESTINATION parameter
Files cannot be archived while they are being modified.	STANDARD archive copy group, SERIALIZATION parameter
An archive copy is kept for up to 365 days.	STANDARD archive copy group, RETVER parameter
When an archived file is no longer associated with an archive copy group, it remains in server storage for 365 days (archive retention grace period).	STANDARD policy domain, ARCHRETENTION parameter
General	
The default management class is STANDARD.	STANDARD policy set (ACTIVE), ASSIGN DEFMGMTCLASS command
Space Management (HSM) Policy	
Client files are not space-managed (no HSM clients).	STANDARD management class, SPACEMGTECHNIQUE parameter

Getting Users Started

When you register a client node, the default is to assign the node to the STANDARD policy domain. If users register their own workstations during open registration, they are also assigned to the STANDARD policy domain.

To help users take advantage of TSM, you can further tune the policy environment by doing the following:

- Define sets of client options for the different groups of users. See “Creating Client Option Sets from the Server” on page 215 for details.
- Help users with creating the include-exclude list. For example:
 - Create include-exclude lists to help inexperienced users who have simple file management needs. One way to do this is to define a basic include-exclude list as part of a client option set. This also gives the administrator some control over client usage. See “Creating Client Option Sets from the Server” on page 215 for details.
 - Provide a sample include-exclude list to users who want to specify how TSM manages their files. You can show users who prefer to manage their own files how to:
 - Request information about management classes
 - Select a management class that meets backup and archive requirements
 - Use include-exclude options to select management classes for their files

For information on the include-exclude list, see the user’s guide for the appropriate client. See also “The Include-Exclude List” on page 243.

- Automate incremental backup procedures by defining schedules for each policy domain. Then associate schedules with client nodes in each policy domain. For information on schedules, see “Scheduling Operations for Client Nodes” on page 285.

Overview: Changing Policy

Some types of clients and situations require policy changes. For example, if you need to direct client data to storage pools different from the default storage pools, you need to change policy. Other situations may also require policy changes. See “Configuring Policy for Specific Cases” on page 266 for details.

To change policy that you have established in a policy domain, you must replace the ACTIVE policy set. You replace the ACTIVE policy set by activating another policy set. Do the following:

1. Create or modify a policy set so that it contains the policy that you want to implement.
 - Create a new policy set either by defining a new policy set or by copying a policy set.
 - Modify an existing policy set (it cannot be the ACTIVE policy set).
- Note:** You cannot directly modify the ACTIVE policy set. If you want to make a small change to the ACTIVE policy set, copy the policy to modify it and follow the steps here.
2. Make any changes that you need to make to the management classes, backup copy groups, and archive copy groups in the new policy set. For details, see “Defining and Updating a Management Class” on page 254, “Defining and Updating a Backup Copy Group” on page 255, and “Defining and Updating an Archive Copy Group” on page 261.
 3. Validate the policy set. See “Validating a Policy Set” on page 263 for details.
 4. Activate the policy set. The contents of your new policy set becomes the ACTIVE policy set. See “Activating a Policy Set” on page 264 for details.

File Expiration and Expiration Processing

An expired file is a file that the server no longer needs to keep, according to policy. Files expire under the following conditions:

- Users delete file spaces from client nodes
- Users expire files by using the EXPIRE command on the client (client software at Version 4.2 and later)
- A file that is a backup version exceeds the criteria in the backup copy group (how long a file is kept and how many inactive versions of a file are kept)
- An archived file exceeds the time criteria in the archive copy group (how long archived copies are kept)
- A backup set exceeds the retention time that is specified for it

Note: A base file is not eligible for expiration until all of its dependent subfiles have been expired. For details, see “Expiration Processing of Base Files and Subfiles” on page 284.

The server deletes expired files from the server database only during expiration processing. After expired files are deleted from the database, the server can reuse the space in the storage pools that was occupied by expired files. You should ensure that expiration processing runs periodically to allow the server to reuse space. See “Reclaiming Space in Sequential Access Storage Pools” on page 152 and “Running Expiration Processing to Delete Expired Files” on page 264 for more information.

Expiration processing also removes from the database any restartable restore sessions that exceed the time limit set for such sessions by the `RESTOREINTERVAL` server option. See “Managing Client Restartable Restore Sessions” on page 220 for information about restartable restore sessions.

Client Operations Controlled by Policy

Tivoli Storage Manager policies govern the following client operations, which are discussed in this section:

- “Backup and Restore” on page 238
- “Archive and Retrieve”
- “Client Migration and Recall” on page 239

Backup and Restore

Backup-archive clients can back up and restore files and directories. Backup-archive clients on UNIX systems can also back up and restore logical volumes. Backups allow users to preserve different versions of files as they change.

Backup

To guard against the loss of information, the backup-archive client can copy files, subdirectories, and directories to media controlled by the server. Backups can be controlled by administrator-defined policies and schedules, or users can request backups of their own data. The backup-archive client provides two types of backup:

Incremental backup

The backup of files according to policy defined in the backup copy group of the management class for the files. An incremental backup typically backs up all files that are new or that have changed since the last incremental backup.

Selective backup

Backs up only files that the user specifies. The files must also meet some of the policy requirements defined in the backup copy group.

The latest level of the UNIX backup-archive clients can also back up logical volumes. The logical volume must meet some of the policy requirements that are defined in the backup copy group. See *Using the Backup-Archive Client* for details of this function.

Restore

When a user restores a backup version of a file, the server sends a copy of the file to the client node. The backup version remains in server storage. Restoring a logical volume backup works the same way.

If more than one backup version exists, a user can restore the active backup version or any inactive backup versions.

If policy is properly set up, a user can restore backed-up files to a specific time. See “Setting Policy to Enable Point-in-Time Restore for Clients” on page 270 for details on the requirements.

Archive and Retrieve

To preserve files for later use or for records retention, a user with a backup-archive client can archive files, subdirectories, and directories on media controlled by the server. When users archive files, they can choose to have the backup-archive client erase the original files from their workstation after the client archives the files.

When a user retrieves a file, the server sends a copy of the file to the client node. The archived file remains in server storage.

Client Migration and Recall

When the Tivoli Space Manager product is on the workstation, a user can migrate files from workstation storage to server storage and recall those files as needed. Tivoli Space Manager frees space for new data and makes more efficient use of your storage resources. The installed Tivoli Space Manager product is also called the space manager client or the HSM client.

Files that are migrated and recalled with the HSM client are called *space-managed* files.

For details about using Tivoli Space Manager, see *Using the UNIX HSM Clients*.

Migration

When a file is migrated to the server, it is replaced on the client node with a small stub file of the same name as the original file. The stub file contains data needed to locate the migrated file on server storage.

Tivoli Space Manager provides selective and automatic migration. Selective migration lets users migrate files by name. The two types of automatic migration are:

Threshold

If space usage exceeds a high threshold set at the client node, migration begins and continues until usage drops to the low threshold also set at the client node.

Demand

If an out-of-space condition occurs for a client node, migration begins and continues until usage drops to the low threshold.

To prepare for efficient automatic migration, Tivoli Space Manager copies a percentage of user files from the client node to the Tivoli Storage Manager server. The *premigration* process occurs whenever Tivoli Space Manager completes an automatic migration. The next time free space is needed at the client node, the files that have been premigrated to the server can quickly be changed to stub files on the client. The default premigration percentage is the difference between the high and low thresholds.

Files are selected for automatic migration and premigration based on the number of days since the file was last accessed and also on other factors set at the client node.

Recall

Tivoli Space Manager provides selective and transparent recall. Selective recall lets users recall files by name. Transparent recall occurs automatically when a user accesses a migrated file.

Reconciliation

Migration and premigration can create inconsistencies between stub files on the client node and space-managed files in server storage. For example, if a user deletes a migrated file from the client node, the copy remains at the server. At regular intervals set at the client node, TSM compares client node and server storage and reconciles the two by deleting from the server any outdated files or files that do not exist at the client node.

The Parts of a Policy

Policy administrators use Tivoli Storage Manager policy to specify how files are backed up, archived, migrated from client node storage, and managed in server storage. Figure 45 shows the parts of a policy and the relationships among the parts. You may refer to “Example: Sample Policy Objects” on page 252.




Figure 45. Tivoli Storage Manager Policy

Backup copy group

Controls how TSM performs backup processing of files associated with the management class. A backup copy group determines the following:

- How frequently a file can be backed up
- How to handle files that are in use during a backup
- Where the server initially stores backup versions of files and directories
- How many backup versions the server keeps of files and directories
- How long the server keeps backup versions of files and directories, see “Running Expiration Processing to Delete Expired Files” on page 264 for details

Archive copy group

Controls how TSM performs archive processing of files associated with the management class. An archive copy group determines the following:

- How to handle files that are in use during archive
- Where the server stores archived copies of files
- How long the server keeps archived copies of files, see “Running Expiration Processing to Delete Expired Files” on page 264 for details

Management class

Associates backup and archive groups with files, and specifies if and how client node files are migrated to storage pools. A management class can contain one

backup or archive copy group, both a backup and archive copy group, or no copy groups. Users can *bind* (that is, associate) their files to a management class through the include-exclude list.

See “More on Management Classes” for details.

Policy set

Specifies the management classes that are available to groups of users. Policy sets contain one or more management classes. You must identify one management class as the *default management class*. Only one policy set, the ACTIVE policy set, controls policy operations.

Policy domain

Lets an administrator group client nodes by the policies that govern their files and by the administrators who manage their policies. A policy domain contains one or more policy sets, but only one policy set (named ACTIVE) can be active at a time. The server uses only the ACTIVE policy set to manage files for client nodes assigned to a policy domain.

You can use policy domains to:

- Group client nodes with similar file management requirements
- Provide different default policies for different groups of clients
- Direct files from different groups of clients to different storage hierarchies based on need (different file destinations with different storage characteristics)
- Restrict the number of management classes to which clients have access

More on Management Classes

Management classes are the key connection between client files and policy.

Each client node is assigned to a single policy domain, and the client node has access only to the management classes contained in the active policy set. The management classes specify whether client files are migrated to storage pools (hierarchical storage management). The copy groups in these management classes specify the number of backup versions retained in server storage and the length of time to retain backup versions and archive copies.

For example, if a group of users needs only one backup version of their files, you can create a policy domain that contains only one management class whose backup copy group allows only one backup version. Then you can assign the client nodes for these users to the policy domain. See “Registering Nodes with the Server” on page 190 for information on registering client nodes and assigning them to policy domains.

The following sections give you more information about management classes and how they work with other parts of Tivoli Storage Manager:

- “Contents of a Management Class” on page 242
- “Default Management Classes” on page 242
- “The Include-Exclude List” on page 243
- “How Files and Directories Are Associated with a Management Class” on page 244

Contents of a Management Class

A management class contains policy for backup, archive, and space management operations by clients. You can specify if and how a Tivoli Space Manager client can migrate files to server storage with parameters in the management class. For clients using the server for backup and archive, you can choose what a management class contains from the following options:

A backup copy group and an archive copy group

Typical end users need to back up and archive documents, spreadsheets, and graphics.

A backup copy group only

Some users only want to back up files (such as working documents, database, log, or history files that change daily). Some application clients (Tivoli Data Protection products) need only a backup copy group because they never archive files.

An archive copy group only

A management class that contains only an archive copy group is useful for users who create:

- Point-in-time files. For example, an engineer can archive the design of an electronic component and the software that created the design. Later, the engineer can use the design as a base for a new electronic component.
- Files that are rarely used but need to be retained for a long time. A client can erase the original file without affecting how long the archive copy is retained in server storage. Examples include legal records, patient records, and tax forms.

Attention: A management class that contains neither a backup nor an archive copy group prevents a file from ever being backed up or archived. This type of management class is not recommended for most users. Use such a management class carefully to prevent users from mistakenly selecting it. If users bind their files to a management class without copy groups, TSM issues warning messages.

Default Management Classes

Each policy set must include a default management class, which is used for the following purposes:

- To manage files that are not bound to a specific management class, as defined by the INCLUDE option in the include-exclude list.
- To manage existing backup versions when an administrator deletes a management class or a backup copy group from the server. See “How Files and Directories Are Associated with a Management Class” on page 244.
- To manage existing archive copies when an administrator deletes a management class or an archive copy group from the server. The server does not rebind archive copies, but does use the archive copy group (if one exists) in the default management class. See “How Files and Directories Are Associated with a Management Class” on page 244.
- To manage files when a client node is assigned to a new policy domain and the active policy set does not have management classes with the same names as that to which the node’s files are bound.

A typical default management class should do the following:

- Meet the needs of most users

- Contain both a backup copy group and an archive copy group
- Set serialization static or shared static to ensure the integrity of backed up and archived files
- Retain backup versions and archive copies for a sufficient amount of time
- Retain directories for at least as long as any files are associated with the directory

Other management classes can contain copy groups tailored either for the needs of special sets of users or for the needs of most users under special circumstances.

The Include-Exclude List

A user can define an include-exclude list to specify which files are eligible for the different processes that the client can run. Include and exclude options in the list determine which files are eligible for backup and archive services, which files can be migrated from the client (space-managed), and how the server manages backed-up, archived, and space-managed files.

If a user does not create an include-exclude list, the following default conditions apply:

- All files belonging to the user are eligible for backup and archive services.
- The default management class governs backup, archive, and space-management policies.

Figure 46 shows an example of an include-exclude list. The statements in this example list do the following:

- Excludes certain files or directories from backup, archive, and client migration operations
Line 1 in Figure 46 means that the SSTEINER node ID excludes all core files from being eligible for backup and client migration.
- Includes some previously excluded files
Line 2 in Figure 46 means that the files in the /home/ssteiner directory are excluded. The include statement that follows on line 3, however, means that the /home/ssteiner/options.scr file is eligible for backup and client migration.
- Binds a file to a specific management class
Line 4 in Figure 46 means that all files and subdirectories belonging to the /home/ssteiner/driver5 directory are managed by the policy defined in the MCENGBK2 management class.

```
exclude /.../core
exclude /home/ssteiner/*
include /home/ssteiner/options.scr
include /home/ssteiner/driver5/.../* mcengbk2
```

Figure 46. Example of an Include-Exclude List

TSM processes the include-exclude list from the bottom up, and stops when it finds an include or exclude statement that matches the file it is processing. Therefore, the order in

which the include and exclude options are listed affects which files are included and excluded. For example, suppose you switch the order of two lines in the example, as follows:

```
include /home/ssteiner/options.scr
exclude /home/ssteiner/*
```

The exclude statement comes last, and excludes all files in the /home/ssteiner directory. When TSM is processing the include-exclude list for the options.scr file, it finds the exclude statement first. This time, the options.scr file is *excluded*.

Some options are evaluated after the more basic include and exclude options. For example, options that exclude or include files for compression are evaluated after the program determines which files are eligible for the process being run.

You can create include-exclude lists as part of client options sets that you define for clients. For information on defining client option sets and assigning a client option set to a client, see “Creating Client Option Sets from the Server” on page 215.

For detailed information on the include and exclude options, see the user’s guide for the appropriate client.

How Files and Directories Are Associated with a Management Class

Binding is the process of associating a file with a management class. The policies defined in the management class then apply to the bound files. The server binds a file to a management class when a client backs up, archives, or migrates the file. A client chooses a management class as follows:

- For backing up a file, a client can specify a management class in the client’s include-exclude list (include-exclude options file for UNIX clients), or can accept the default management class.
- For backing up directories, the client can specify a management class by using the DIRMC option in the client options file.

Note: It is recommended that you define a default management class. If no management class is specified for a directory, the server chooses the management class with the longest retention period in the backup copy group (retention period for the only backup version).

- For backing up a file system or logical volume, a client can specify a management class in the client’s include-exclude list (include-exclude options file for UNIX clients), or can accept the default management class.
- For archiving a file, the client can do one of the following:
 - Specify a management class in the client’s include-exclude list (with either an include option or an include.archive option)
 - Specify a management class with the ARCHMC option on the archive command
 - Accept the default management class
- For archiving directories, the client can specify a management class with the archiving options, or the ARCHMC option. If the client does not specify any archiving options, the server assigns the default management class to the archived directory. If the default management class has no archive copy group, the server assigns the management class that currently has the archive copy group with the shortest retention time.

-
- For migrating a file, a client can specify a management class in the client's include-exclude options file, or can accept the default management class.

The default management class is the management class identified as the default in the active policy set.

A management class specified with a simple `include` option can apply to one or more processes on the client. More specific include options (such as `include.archive`) allow the user to specify different management classes. Some examples of how this works:

- If a client backs up, archives, and migrates a file to the same server, and uses only a single include option, the management class specified for the file applies to all three operations (backup, archive, and migrate).
- If a client backs up and archives a file to one server, and migrates the file to a different server, the client can specify one management class for the file for backup and archive operations, and a different management class for migrating.
- Clients at Version 4.2 or later can specify a management class for archiving that is different from the management class for backup.

See the user's guide for the appropriate client for details.

Effects of Changing a Management Class

A file remains bound to a management class even if the attributes of the management class or its copy groups change. The following scenario illustrates this process:

1. A file named `REPORT.TXT` is bound to the default management class that contains a backup copy group specifying that up to three backup versions can be retained in server storage.
2. During the next week, three backup versions of `REPORT.TXT` are stored in server storage. The active and two inactive backup versions are bound to the default management class.
3. The administrator assigns a new default management class that contains a backup copy group specifying only up to two backup versions.
4. The administrator then activates the policy set, and the new default management class takes effect.
5. `REPORT.TXT` is backed up again, bringing the number of versions to four. The server determines that according to the new backup copy group only two versions are to be retained. Therefore, the server marks the two oldest versions for deletion (expired).
6. Expiration processing occurs (see "Running Expiration Processing to Delete Expired Files" on page 264 for details). `REPORT.TXT` is still bound to the default management class, which now includes new retention criteria. Therefore, the two versions marked for deletion are purged, and one active and one inactive backup version remain in storage.

Rebinding Files to Management Classes

Rebinding is the process of associating a file or a logical volume image with a new management class.

Backup Versions

The server rebinds backup versions of files and logical volume images in the following cases:

-
- The user changes the management class specified in the include-exclude list and does a backup.
 - An administrator activates a policy set in the same policy domain as the client node, and the policy set does not contain a management class with the same name as the management class to which a file is currently bound.
 - An administrator assigns a client node to a different policy domain, and the active policy set in that policy domain does not have a management class with the same name.

Backup versions of a directory can be rebound when the user specifies a different management class using the DIRMC option in the client option file, and when the directory gets backed up.

If a file is bound to a management class that no longer exists, the server uses the default management class to manage the backup versions. When the user does another backup, the server rebinds the file and any backup versions to the default management class. If the default management class does not have a backup copy group, the server uses the backup retention grace period specified for the policy domain.

Archive Copies

Archive copies are never rebound because each archive operation creates a different archive copy. Archive copies remain bound to the management class name specified when the user archived them.

If the management class to which an archive copy is bound no longer exists or no longer contains an archive copy group, the server uses the default management class. If you later change or replace the default management class, the server uses the updated default management class to manage the archive copy.

If the default management class does not contain an archive copy group, the server uses the archive retention grace period specified for the policy domain.

How Tivoli Storage Manager Selects Files for Policy Operations

This section describes how TSM selects files for the following operations:

- Full and partial incremental backups
- Selective backup
- Logical volume backup
- Archive
- Automatic migration from an HSM client (Tivoli Space Manager)

Incremental Backup

Backup-archive clients can choose to back up their files using full or partial incremental backup. A full incremental backup ensures that clients' backed-up files are always managed according to policies. Clients should use full incremental backup whenever possible.

If the amount of time for backup is limited, clients may sometimes need to use partial incremental backup. A partial incremental backup should complete more quickly and require less memory. When a client uses partial incremental backup, only files that have changed since the last incremental backup are backed up. Attributes in the management class that would cause a file to be backed up when doing a full incremental backup are ignored. For

example, unchanged files are not backed up even when they are assigned to a management class that specifies absolute mode and the minimum days between backups (frequency) has passed.

The server also does less processing for a partial incremental backup. For example, the server does not expire files or rebind management classes to files during a partial incremental backup.

If clients must use partial incremental backups, they should periodically perform full incremental backups to ensure that complete backups are done and backup files are stored according to policies. For example, clients can do partial incremental backups every night during the week, and a full incremental backup on the weekend.

Performing full incremental backups is important if clients want the ability to restore files to a specific time. Only a full incremental backup can detect whether files have been deleted since the last backup. If full incremental backup is not done often enough, clients who restore to a specific time may find that many files that had actually been deleted from the workstation get restored. As a result, a client's file system may run out of space during a restore process. See "Setting Policy to Enable Point-in-Time Restore for Clients" on page 270 for more information.

Full Incremental Backup

When a user requests a full incremental backup, TSM performs the following steps to determine eligibility:

1. Checks each file against the user's include-exclude list:
 - Files that are excluded are not eligible for backup.
 - If files are not excluded and a management class is specified with the INCLUDE option, TSM uses that management class.
 - If files are not excluded but a management class is not specified with the INCLUDE option, TSM uses the default management class.
 - If no include-exclude list exists, all files in the client domain are eligible for backup, and TSM uses the default management class.
2. Checks the management class of each included file:
 - If there is a backup copy group, the process continues with step 3.
 - If there is no backup copy group, the file is not eligible for backup.
3. Checks the *mode*, *frequency*, and *serialization* defined in the backup copy group.

Mode Specifies whether the file is backed up only if it has changed since the last backup (*modified*) or whenever a backup is requested (*absolute*).

Frequency

Specifies the minimum number of days that must elapse between backups.

Serialization

Specifies how files are handled if they are modified while being backed up and what happens if modification occurs.

- If the mode is *modified* and the minimum number of days have elapsed since the file was last backed up, TSM determines if the file has been changed since it was last backed up:

-
- If the file has been changed and the serialization requirement is met, the file is backed up.
 - If the file has not been changed, it is not backed up.
 - If the mode is *modified* and the minimum number of days have not elapsed since the file was last backed up, the file is not eligible for backup.
 - If the mode is *absolute*, the minimum number of days have elapsed since the file was last backed up, and the serialization requirement is met, the file is backed up.
 - If the mode is *absolute* and the minimum number of days have not elapsed since the file was last backed up, the file is not eligible for backup.

Partial Incremental Backup

When a user requests a partial incremental backup, TSM performs the following steps to determine eligibility:

1. Checks each file against the user's include-exclude list:
 - Files that are excluded are not eligible for backup.
 - If files are not excluded and a management class is specified with the INCLUDE option, TSM uses that management class.
 - If files are not excluded but a management class is not specified with the INCLUDE option, TSM uses the default management class.
 - If no include-exclude list exists, all files in the client domain are eligible for backup, and TSM uses the default management class.
2. Checks the management class of each included file:
 - If there is a backup copy group, the process continues with step 3.
 - If there is no backup copy group, the file is not eligible for backup.
3. Checks the date and time of the last incremental backup by the client, and the *serialization* requirement defined in the backup copy group. (Serialization specifies how files are handled if they are modified while being backed up and what happens if modification occurs.)
 - If the file has not changed since the last incremental backup, the file is not backed up.
 - If the file has changed since the last incremental backup and the serialization requirement is met, the file is backed up.

Selective Backup

When a user requests a selective backup, TSM performs the following steps to determine eligibility:

1. Checks the file against any include or exclude statements contained in the user include-exclude list:
 - Files that are not excluded are eligible for backup. If a management class is specified with the INCLUDE option, TSM uses that management class.
 - If no include-exclude list exists, the files selected are eligible for backup, and TSM uses the default management class.
2. Checks the management class of each included file:

-
- If the management class contains a backup copy group and the serialization requirement is met, the file is backed up. Serialization specifies how files are handled if they are modified while being backed up and what happens if modification occurs.
 - If the management class does not contain a backup copy group, the file is not eligible for backup.

An important characteristic of selective backup is that a file is backed up without regard for whether the file has changed. This result may not always be what you want. For example, suppose a management class specifies to keep three backup versions of a file. If the client uses incremental backup, the file is backed up only when it changes, and the three versions in storage will be at different levels. If the client uses selective backup, the file is backed up regardless of whether it has changed. If the client uses selective backup on the file three times without changing the file, the three versions of the file in server storage are identical. Earlier, different versions are lost.

Logical Volume Backup

When a user requests a logical volume backup, TSM performs the following steps to determine eligibility:

1. Checks the specification of the logical volume against any include or exclude statements contained in the user include-exclude list:
 - If no include-exclude list exists, the logical volumes selected are eligible for backup, and TSM uses the default management class.
 - Logical volumes that are not excluded are eligible for backup. If the include-exclude list has an INCLUDE option for the volume with a management class specified, TSM uses that management class. Otherwise, TSM uses the default management class.
2. Checks the management class of each included logical volume:
 - If the management class contains a backup copy group and the logical volume meets the serialization requirement, the logical volume is backed up. Serialization specifies how logical volumes are handled if they are modified while being backed up and what happens if modification occurs.
 - If the management class does not contain a backup copy group, the logical volume is not eligible for backup.

Archive

When a user requests the archiving of a file or a group of files, TSM performs the following steps to determine eligibility:

1. Checks the files against the user's include-exclude list to see if any management classes are specified:
 - TSM uses the default management class for files that are not bound to a management class.
 - If no include-exclude list exists, TSM uses the default management class unless the user specifies another management class. See the user's guide for the appropriate client for details.
2. Checks the management class for each file to be archived.

-
- If the management class contains an archive copy group and the serialization requirement is met, the file is archived. Serialization specifies how files are handled if they are modified while being archived and what happens if modification occurs.
 - If the management class does not contain an archive copy group, the file is not archived.

Automatic Migration from a Client Node

A file is eligible for automatic migration from an HSM client if it meets all of the following criteria:

- It resides on a node on which the root user has added and activated hierarchical storage management. It must also reside in a local file system to which the root user has added space management, and not in the root (/) or /tmp file system.
- It is not excluded from migration in the include-exclude list.
- It meets management class requirements for migration:
 - The file is not a character special file, a block special file, a FIFO special file (that is, a named pipe file) or a directory.
 - The file is assigned to a management class that calls for space management.
 - The management class calls for automatic migration after a specified number of days, and that time has elapsed.
 - A backup version of the file exists if the management class requires it.
 - The file is larger than the stub file that would replace it (plus one byte) or the file system block size, whichever is larger.

How Client Migration Works with Backup and Archive

As an administrator, you can define a management class that specifies automatic migration from the client under certain conditions. For example, if the file has not been accessed for at least 30 days and a backup version exists, the file is migrated. You can also define a management class that allows users to selectively migrate whether or not a backup version exists. Users can also choose to archive files that have been migrated. TSM does the following:

- If the file is backed up or archived to the server to which it was migrated, the server copies the file from the migration storage pool to the backup or archive storage pool. For a tape-to-tape operation, each storage pool must have a tape drive.
- If the file is backed up or archived to a different server, TSM accesses the file by using the migrate-on-close recall mode. The file resides on the client node only until the server stores the backup version or the archived copy in a storage pool.

When a client restores a backup version of a migrated file, the server deletes the migrated copy of the file from server storage the next time reconciliation is run.

When a client archives a file that is migrated and does not specify that the file is to be erased after it is archived, the migrated copy of the file remains in server storage. When a client archives a file that is migrated and specifies that the file is to be erased, the server deletes the migrated file from server storage the next time reconciliation is run.

The default management class delivered with TSM specifies that a backup version of a file must exist before the file is eligible for migration.

Creating Your Own Policies

Task	Required Privilege Class
Define or copy a policy domain	System
Update a policy domain over which you have authority	Restricted policy
Define, update, or copy policy sets and management classes in any policy domain	System or unrestricted policy
Define, update, or copy policy sets and management classes in policy domains over which you have authority	Restricted policy
Define or update copy groups in any policy domain	System or unrestricted policy
Define or update copy groups that belong to policy domains over which you have authority	Restricted policy
Assign a default management class to a nonactive policy set in any policy domain	System or unrestricted policy
Assign a default management class to a nonactive policy set in policy domains over which you have authority	Restricted policy
Validate and activate policy sets in any policy domain	System or unrestricted policy
Validate and activate policy sets in policy domains over which you have authority	Restricted policy
Start inventory expiration processing	System

You can create your own policies in one of two ways:

- Define the parts of a policy and specify each attribute
- Copy existing policy parts and update only those attributes that you want to change

The following table shows that an advantage of copying existing policy parts is that some associated parts are copied in a single operation.

If you copy this...	Then you create this...
Policy Domain	A new policy domain with: <ul style="list-style-type: none"> ■ A copy of each policy set from the original domain ■ A copy of each management class in each original policy set ■ A copy of each copy group in each original management class
Policy Set	A new policy set <i>in the same policy domain</i> with: <ul style="list-style-type: none"> ■ A copy of each management class in the original policy set ■ A copy of each copy group in the original management class
Management Class	A new management class <i>in the same policy set</i> and a copy of each copy group in the management class

Example: Sample Policy Objects

Figure 47 shows the policies for an engineering department. This example is used throughout the rest of this chapter.

The domain contains two policy sets that are named STANDARD and TEST. The administrator activated the policy set that is named STANDARD. When you activate a policy set, the server makes a copy of the policy set and names it ACTIVE. Only one policy set can be active at a time.

The ACTIVE policy set contains two management classes: MCENG and STANDARD. The default management class is STANDARD.




Figure 47. An Example of Policy Objects Defined for an Engineering Department

The sections that follow describe the tasks involved in creating new policies for your installation. Do the tasks in the following order:

Tasks:
“Defining and Updating a Policy Domain” on page 253
“Defining and Updating a Policy Set” on page 254
“Defining and Updating a Management Class” on page 254
“Defining and Updating a Backup Copy Group” on page 255
“Defining and Updating an Archive Copy Group” on page 261
“Assigning a Default Management Class” on page 262
“Activating a Policy Set” on page 264
“Running Expiration Processing to Delete Expired Files” on page 264.

Defining and Updating a Policy Domain

When you update or define a policy domain, you specify:

Backup Retention Grace Period

Specifies the number of days to retain an inactive backup version when the server cannot rebind the file to an appropriate management class. The backup retention grace period protects backup versions from being immediately expired when the management class to which a file is bound no longer exists or no longer contains a backup copy group, and the default management class does not contain a backup copy group.

Backup versions of the file managed by the grace period are retained in server storage only for the backup retention grace period. This period starts from the day of the backup. For example, if the backup retention grace period for the STANDARD policy domain is used and set to 30 days, backup versions using the grace period expire in 30 days from the day of the backup.

Backup versions of the file continue to be managed by the grace period unless one of the following occurs:

- The client binds the file to a management class containing a backup copy group and then backs up the file
- A backup copy group is added to the file's management class
- A backup copy group is added to the default management class

Archive Retention Grace Period

Specifies the number of days to retain an archive copy when the management class for the file no longer contains an archive copy group and the default management class does not contain an archive copy group. The retention grace period protects archive copies from being immediately expired.

The archive copy of the file managed by the grace period is retained in server storage for the number of days specified by the archive retention grace period. This period starts from the day on which the file is first archived. For example, if the archive retention grace period for the policy domain STANDARD is used, an archive copy expires 365 days from the day the file is first archived.

The archive copy of the file continues to be managed by the grace period unless an archive copy group is added to the file's management class or to the default management class.

Example: Defining a Policy Domain

To create a new policy domain you can do one of the following:

- Copy an existing policy domain and update the new domain
- Define a new policy domain from scratch

Note: When you copy an existing domain, you also copy any associated policy sets, management classes, and copy groups.

For example, to copy and update, follow this procedure:

1. Copy the STANDARD policy domain to the ENGPOLDOM policy domain by entering:
copy domain standard engpoldom

ENGPOLDOM now contains the standard policy set, management class, backup copy group, and archive copy group.

2. Update the policy domain ENGPOLDOM so that the backup retention grace period is extended to 90 days and the archive retention grace period is extended to 2 years by entering:

```
update domain engpoldom description='Engineering Policy Domain'  
backretention=90 archretention=730
```

Defining and Updating a Policy Set

When you define or update a policy set, specify:

Policy domain name

Names the policy domain to which the policy set belongs

The policies in the new policy set do not take effect unless you make the new set the ACTIVE policy set. See “Activating a Policy Set” on page 264.

Example: Defining a Policy Set

An administrator needs to develop new policies based on the existing STANDARD policy set. To create the TEST policy set in the ENGPOLDOM policy domain, the administrator performs the following steps:

1. Copy the STANDARD policy set and name the new policy set TEST:

```
copy policyset engpoldom standard test
```

Note: When you copy an existing policy set, you also copy any associated management classes and copy groups.

2. Update the description of the policy set named TEST:

```
update policyset engpoldom test  
description='Policy set for testing'
```

Defining and Updating a Management Class

When you define or update a management class, specify:

Policy domain name

Names the policy domain to which the management class belongs.

Policy set name

Names the policy set to which the management class is assigned.

Description

Describes the management class. A clear description can help users to choose an appropriate management class for their use.

The following four parameters apply only to Tivoli Space Manager clients (HSM clients):

Whether space management is allowed

Specifies that the files are eligible for both automatic and selective migration, only selective migration, or no migration.

How frequently files can be migrated

Specifies the minimum number of days that must elapse since a file was last accessed before it is eligible for automatic migration.

Whether backup is required

Specifies whether a backup version of a file must exist before the file can be migrated.

Where migrated files are to be stored

Specifies the name of the storage pool in which migrated files are stored. Your choice could depend on factors such as:

- The number of client nodes migrating to the storage pool. When many user files are stored in the same storage pool, volume contention can occur as users try to migrate files to or recall files from the storage pool.
- How quickly the files must be recalled. If users need immediate access to migrated versions, you can specify a disk storage pool as the destination.

Note: You cannot specify a copy storage pool as a destination.

Example: Define a New Management Class

Create a new management class by following these steps:

1. Define a new management class MCENG by entering:


```
define mgmtclass engpoldom standard mceng
```
2. Update the description of the MCENG management class by entering:


```
update mgmtclass engpoldom standard mceng
description='Engineering Management Class for Backup and Archive'
```

Defining and Updating a Backup Copy Group

Tasks:
“Where to Store Backed-Up Files”
“Whether Files Can Be Modified During Backup” on page 256
“How Frequently Files Can Be Backed Up” on page 256
“How Many Backup Versions to Retain and For How Long” on page 257

Where to Store Backed-Up Files

Specify a storage pool where the server initially stores the files associated with this backup copy group. This is called the destination. Your choice can depend on factors such as the following:

- Whether the server and the client nodes have access to shared devices on a storage area network (SAN).
- The number of client nodes backing up to the storage pool. When many user files are stored in the same storage pool, volume contention can occur as users try to back up to or restore files from the storage pool.
- How quickly the files must be restored. If users need immediate access to backup versions, you may want to specify a disk storage pool as the destination.

Note: You cannot specify a copy storage pool.

Whether Files Can Be Modified During Backup

You can specify how files are handled if they are modified while being backed up. The attribute, called serialization, can be one of four values: static, shared static, dynamic, and shared dynamic. The value you choose depends on whether you want to allow modification during backup:

Prevent modification during backup

For most files, you will want to prevent the server from backing up a file while it is being modified. Use one of the following values:

Static Specifies that if the file or directory is modified during a backup, TSM does not back it up. TSM does not retry the backup.

Shared Static

Specifies that if the file or directory is modified during a backup, TSM does not back it up. However, TSM retries the backup as many times as specified by the CHANGINGRETRIES option in the client options file.

Allow modification during backup

You may want to define a copy group that allows modification during backup for files where log records are continuously added, such as an error log. If you only have copy groups that prevent modification (static or shared static), these files may never be backed up because they are constantly in use. To allow modification during backup, use one of the following values:

Dynamic

Specifies that a file or directory is backed up on the first attempt, even if the file or directory is being modified during the backup.

Shared Dynamic

Specifies that if a file or directory is modified during a backup attempt, TSM backs it up on its last try even if the file or directory is being modified. TSM retries the backup as many times as specified by the CHANGINGRETRIES option in the client options file.

Attention: If a file is backed up while it is in use (shared dynamic or dynamic serialization), the copy may not contain all the changes and may not be usable. For example, the backup version may contain a truncated record.

Note: When certain users or processes open files, they deny read access to the files for any other user or process. When this happens, even with serialization set to dynamic or shared dynamic, TSM does not back up the file.

How Frequently Files Can Be Backed Up

You can specify how frequently files can be backed up with two parameters:

Frequency

The frequency is the minimum number of days that must elapse between full incremental backups.

Mode The mode parameter specifies whether a file or directory must have been modified to be considered for backup during a full incremental backup process. TSM does not check this attribute when a user requests a partial incremental backup, a selective backup for a file, or a backup of a logical volume. You can select from two modes:

Modified

A file is considered for full incremental backup only if it has changed since the last backup. A file is considered changed if any of the following items is different:

- Date on which the file was last modified
- File size
- File owner
- File permissions

Absolute

A file is considered for full incremental backup regardless of whether it has changed since the last backup.

The server considers both parameters to determine how frequently files can be backed up. For example, if frequency is 3 and mode is Modified, a file or directory is backed up only if it has been changed and if three days have passed since the last backup. If frequency is 3 and mode is Absolute, a file or directory is backed up after three days have passed whether or not the file has changed.

Use the Modified mode when you want to ensure that the server retains multiple, *different* backup versions. If you set the mode to Absolute, users may find that they have three *identical* backup versions, rather than three *different* backup versions.

Absolute mode can be useful for forcing a full backup. It can also be useful for ensuring that extended attribute files are backed up, because TSM does not detect changes if the size of the extended attribute file remains the same.

When you set the mode to Absolute, set the frequency to 0 if you want to ensure that a file is backed up each time full incremental backups are scheduled for or initiated by a client.

How Many Backup Versions to Retain and For How Long

Multiple versions of files are useful when users continually update files and sometimes need to restore the original file from which they started. The most current backup version of a file is called the *active* version. All other versions are called *inactive* versions. You can specify the number of versions to keep by:

- Directly specifying the number of versions
 - You specify the number of backup versions with two parameters:
 - Versions Data Exists (number of versions to keep when the data still exists on the client node)
 - Versions Data Deleted (number of versions to keep when the data no longer exists on the client node)
- Specifying the number of days to keep each backup version
 - You specify the number of days to keep backup versions with two parameters:
 - Retain Extra Versions (how many days to keep inactive backup versions; the days are counted from the day that the version became inactive)
 - Retain Only Versions (how many days to keep the last backup version of a file that has been deleted)
- Specifying a combination of the number of versions and the days to keep them

Use a combination of the four parameters: Versions Data Exists, Versions Data Deleted, Retain Extra Versions, and Retain Only Versions.

These parameters interact to determine the backup versions that the server retains. When the number of inactive backup versions exceeds the number of versions allowed (Versions Data Exists and Versions Data Deleted), the oldest version expires and the server deletes the file from the database the next time expiration processing runs. How many inactive versions the server keeps is also related to the parameter for how long inactive versions are kept (Retain Extra Versions). Inactive versions expire when the number of days that they have been inactive exceeds the value specified for retaining extra versions, even when the number of versions is not exceeded.

Note: A base file is not eligible for expiration until all its dependent subfiles have been expired. For details, see “Enabling Clients to Use Subfile Backup” on page 282

For example, see Table 20 and Figure 48. A client node has backed up the file REPORT.TXT four times in one month, from March 23 to April 23. The settings in the backup copy group of the management class to which REPORT.TXT is bound determine how the server treats these backup versions. Table 21 on page 259 shows some examples of how different copy group settings would affect the versions. The examples show the effects as of April 24 (one day after the file was last backed up).

Table 20. Status of REPORT.TXT as of April 24

Version	Date Created	Days the Version Has Been Inactive
Active	April 23	(not applicable)
Inactive 1	April 13	1 (since April 23)
Inactive 2	March 31	11 (since April 13)
Inactive 3	March 23	24 (since March 31)




Figure 48. Active and Inactive Versions of REPORT.TXT

Table 21. Effects of Backup Copy Group Policy on Backup Versions for REPORT.TXT as of April 24. One day after the file was last backed up.

Versions Data Exists	Versions Data Deleted	Retain Extra Versions	Retain Only Version	Results
3 versions	2 versions	60 days	180 days	<p>Versions Data Exists and Retain Extra Versions control the expiration of the versions. The version created on March 23 is retained until the client node backs up the file again (creating a fourth inactive version), or until that version has been inactive for 60 days.</p> <p>If the user deletes the REPORT.TXT file from the client node, the server notes the deletion at the next full incremental backup of the client node. From that point, the Versions Data Deleted and Retain Only Version parameters also have an effect. All versions are now inactive. Two of the four versions expire immediately (the March 23 and March 31 versions expire). The April 13 version expires when it has been inactive for 60 days (on June 23). The server keeps the last remaining inactive version, the April 23 version, for 180 days after it becomes inactive.</p>
NOLIMIT	2 versions	60 days	180 days	<p>Retain Extra Versions controls expiration of the versions. The inactive versions (other than the last remaining version) are expired when they have been inactive for 60 days.</p> <p>If the user deletes the REPORT.TXT file from the client node, the server notes the deletion at the next full incremental backup of the client node. From that point, the Versions Data Deleted and Retain Only Version parameters also have an effect. All versions are now inactive. Two of the four versions expire immediately (the March 23 and March 31 versions expire) because only two versions are allowed. The April 13 version expires when it has been inactive for 60 days (on June 22). The server keeps the last remaining inactive version, the April 23 version, for 180 days after it becomes inactive.</p>
NOLIMIT	NOLIMIT	60 days	180 days	<p>Retain Extra Versions controls expiration of the versions. The server does not expire inactive versions based on the maximum number of backup copies. The inactive versions (other than the last remaining version) are expired when they have been inactive for 60 days.</p> <p>If the user deletes the REPORT.TXT file from the client node, the server notes the deletion at the next full incremental backup of the client node. From that point, the Retain Only Version parameter also has an effect. All versions are now inactive. The three of four versions will expire after each of them has been inactive for 60 days. The server keeps the last remaining inactive version, the April 23 version, for 180 days after it becomes inactive.</p>
3 versions	2 versions	NOLIMIT	NOLIMIT	<p>Versions Data Exists controls the expiration of the versions until a user deletes the file from the client node. The server does not expire inactive versions based on age.</p> <p>If the user deletes the REPORT.TXT file from the client node, the server notes the deletion at the next full incremental backup of the client node. From that point, the Versions Data Deleted parameter controls expiration. All versions are now inactive. Two of the four versions expire immediately (the March 23 and March 31 versions expire) because only two versions are allowed. The server keeps the two remaining inactive versions indefinitely.</p>

See *Administrator's Reference* for details about the parameters. The following list gives some tips on using the NOLIMIT value:

Versions Data Exists

Setting the value to NOLIMIT may require increased storage, but that value may be needed for some situations. For example, to enable client nodes to restore files to a specific point in time, set the value for Versions Data Exists to NOLIMIT. Setting the value this high ensures that the server retains versions according to the Retain Extra Versions parameter for the copy group. See “Setting Policy to Enable Point-in-Time Restore for Clients” on page 270 and “Policy for Logical Volume Backups” on page 267 for more information.

Versions Data Deleted

Setting the value to NOLIMIT may require increased storage, but that value may be needed for some situations. For example, set the value for Versions Data Deleted to NOLIMIT to enable client nodes to restore files to a specific point in time. Setting the value this high ensures that the server retains versions according to the Retain Extra Versions parameter for the copy group. See “Setting Policy to Enable Point-in-Time Restore for Clients” on page 270 and “Policy for Logical Volume Backups” on page 267 for more information.

Retain Extra Versions

If NOLIMIT is specified, inactive backup versions are deleted based on the Versions Data Exists or Versions Data Deleted parameters.

To enable client nodes to restore files to a specific point in time, set the parameters Versions Data Exists or Versions Data Deleted to NOLIMIT. Set the value for Retain Extra Versions to the number of days that you expect clients may need versions of files available for possible point-in-time restoration. For example, to enable clients to restore files from a point in time 60 days in the past, set Retain Extra Versions to 60. See “Setting Policy to Enable Point-in-Time Restore for Clients” on page 270 for more information.

Retain Only Version

If NOLIMIT is specified, the last version is retained forever unless a user or administrator deletes the file from server storage.

Example: Define a Backup Copy Group

Define a backup copy group belonging to the MCENG management class in the STANDARD policy set belonging to the ENGPOLDOM policy domain. This new copy group must do the following:

- Let users back up changed files, regardless of how much time has elapsed since the last backup, using the default value 0 for the Frequency parameter (frequency parameter not specified)
- Retain up to four inactive backup versions when the original file resides on the user workstation, using the Versions Data Exists parameter (verexists=5)
- Retain up to four inactive backup versions when the original file is deleted from the user workstation, using the Versions Data Deleted parameter (verdeleted=4)
- Retain inactive backup versions for no more than 90 days, using the Retain Extra Versions parameter (retextra=90)
- If there is only one backup version, retain it for 600 days after the original is deleted from the workstation, using the Retain Only Version parameter (reonly=600)

- Prevent files from being backed up if they are in use, using the Serialization parameter (serialization=static)
- Store files in the ENGBACK1 storage pool, using the Destination parameter (destination=engback1)

To define the backup copy group, enter:

```
define copygroup engpoldom standard mceng standard
destination=engback1 serialization=static
verexists=5 verdeleted=4 retextra=90 retonly=600
```

Defining and Updating an Archive Copy Group

To define or update an archive copy group on the Web interface or command line, specify:

Where archived files are to be stored

Specify a defined storage pool as the initial destination. Your choice can depend on factors such as:

- Whether the server and the client nodes have access to shared devices on a SAN
- The number of client nodes archiving files to the storage pool. When many user files are stored in the same storage pool, volume contention can occur as users archive files to and retrieve files from the storage pool.
- How quickly the files must be restored. If users need immediate access to archive copies, you could specify a disk storage pool as the destination.
- Whether the archive copy group is for a management class that is the default for a policy domain. The default management class is used by clients registered in the policy domain, when they do not specify a management class for a file. This includes TSM servers that are registered as clients to this server. See “Using Virtual Volumes to Store Data on Another Server” on page 348 for information about registering TSM servers as clients to another TSM server.

Note: You cannot specify a copy storage pool as a destination.

If files can be modified during archive

Specify how files are handled if they are modified while being archived. This attribute, called serialization, can be one of four values:

Static Specifies that if the file is modified during an archiving process, TSM does not archive it. TSM does not retry the archive.

Shared Static

Specifies that if the file is modified during an archive process, TSM does not archive it. However, TSM retries the archive process as many times as specified by the CHANGINGRETRIES option in the client options file.

Dynamic

Specifies that a file is archived on the first attempt, even if the file is being modified during the archive process.

Shared Dynamic

Specifies that if the file is modified during the archive attempt, TSM archives it on its last try even if the file is being modified. TSM retries the archive process as many times as specified by the CHANGINGRETRIES option in the client options file.

For most files, set serialization to either static or shared static to prevent the server from archiving a file while it is being modified.

However, you may want to define a copy group with a serialization of shared dynamic or dynamic for files where log records are continuously added, such as an error log. If you only have copy groups that use static or shared static, these files may never be archived because they are constantly in use. With shared dynamic or dynamic, the log files are archived. However, the archive copy may contain a truncated message.

Attention: If a file is archived while it is in use (shared dynamic or dynamic serialization), the copy may not contain all the changes and may not be usable.

Note: When certain users or processes open files, they deny read access to the files for any other user or process. When this happens, even with serialization set to dynamic or shared dynamic, TSM does not back up the file.

How long to retain an archived copy

Specifies the number of days to retain an archived copy in storage. When the time elapses, the archived copy expires and the server deletes the file the next time expiration processing runs.

When a user archives directories, the server uses the default management class unless the user specifies otherwise. If the default management class does not have an archive copy group, the server binds the directory to the management class that currently has the shortest retention time for archive. When you change the retention time for an archive copy group, you may also be changing the retention time for any directories that were archived using that copy group.

The user can change the archive characteristics by using Archive Options in the interface or by using the ARCHMC option on the command.

Example: Define an Archive Copy Group

Define an archive copy group belonging to the MCENG class that:

- Allows users to archive a file if it is not in use (`serialization=static`)
- Retains the archive copy for 730 days (`retver=730`)
- Stores files in the ENGARCH1 storage pool (`destination=engarch1`)

To define a STANDARD archive copy group to the MCENG management class in the STANDARD policy set belonging to the ENGPOLDOM policy domain, enter:

```
define copygroup engpoldom standard mceng standard
type=archive destination=engarch1 serialization=static
retver=730
```

Assigning a Default Management Class

After you have defined a policy set and the management classes that it contains, you must assign a default management class for the policy set. See “Default Management Classes” on page 242 for suggestions about the content of default management classes.

Example: Assign a Default Management Class

To assign the STANDARD management class as the default management class for the TEST policy set in the ENGPOLDOM policy domain, enter:

```
assign defgmtclass engpoldom standard standard
```

The STANDARD management class was copied from the STANDARD policy set to the TEST policy set (see “Example: Defining a Policy Set” on page 254). Before the new default management class takes effect, you must activate the policy set.

Validating and Activating a Policy Set

After you have defined a policy set and defined management classes to it, you can validate the policy set and activate the policy set for the policy domain. Only one policy set is active in a policy domain.

Validating a Policy Set

When you validate a policy set, the server examines the management class and copy group definitions in the policy set and reports on conditions that need to be considered if the policy set is activated.

Validation fails if the policy set does not contain a default management class. Validation results in warning messages if any of the following conditions exist.

Condition	Reason for warning
The storage destinations specified for backup, archive, or migration do not refer to defined storage pools.	A backup, archive, or migration operation will fail when the operation involves storing a file in a storage pool that does not exist.
A storage destination specified for backup, archive, or migration is a copy storage pool.	The storage destination must be a primary storage pool.
The default management class does not contain a backup or archive copy group.	When the default management class does not contain a backup or archive copy group, any user files bound to the default management class <i>are not</i> backed up or archived.
The current ACTIVE policy set names a management class that is not defined in the policy set being validated.	<p>When users back up files that were bound to a management class that no longer exists in the active policy set, backup versions are rebound to the default management class. See “How Files and Directories Are Associated with a Management Class” on page 244 for details.</p> <p>When the management class to which an archive copy is bound no longer exists and the default management class does not contain an archive copy group, the archive retention grace period is used to retain the archive copy. See “Defining and Updating a Policy Domain” on page 253 for details.</p>
The current ACTIVE policy set contains copy groups that are not defined in the policy set being validated.	When users perform a backup and the backup copy group no longer exists in the management class to which a file is bound, backup versions are managed by the default management class. If the default management class does not contain a backup copy group, backup versions are managed by the backup retention grace period, and the workstation file is not backed up. See “Defining and Updating a Policy Domain” on page 253

Condition	Reason for warning
A management class specifies that a backup version must exist before a file can be migrated from a client node, but the management class does not contain a backup copy group.	The contradictions between the management classes can cause problems for HSM users.

Activating a Policy Set

To activate a policy set, specify a policy domain and policy set name. When you activate a policy set, the server:

- Performs a final validation of the contents of the policy set
- Copies the original policy set to the ACTIVE policy set

You cannot update the ACTIVE policy set; the original and the ACTIVE policy sets are two separate objects. For example, updating the original policy set has no effect on the ACTIVE policy set. To change the contents of the ACTIVE policy set, you must create or change another policy set and then activate that policy set. See “Overview: Changing Policy” on page 237 for details.

Example: Validating and Activating a Policy Set

Validating and activating the STANDARD policy set in the ENGPOLDOM policy domain is a two-step process:

1. To validate the STANDARD policy set, enter:

```
validate policyset engpoldom standard
```

Examine any messages that result and correct the problems.

2. To activate the STANDARD policy set, enter:

```
activate policyset engpoldom standard
```

Assigning Client Nodes to a Policy Domain

At the server command line or the administrative Web interface, you can assign existing client nodes to a new policy domain, or create new client nodes to be associated with an existing policy domain.

For example, to assign the client node APPCLIENT1 to the ENGPOLDOM policy domain, enter the following command:

```
update node appclient1 domain=engpoldom
```

To create a new client node, NEWUSER, and assign it to the ENGPOLDOM policy domain, enter the following command:

```
register node newuser newuser domain=engpoldom
```

Running Expiration Processing to Delete Expired Files

Expiration processing deletes expired client files from the server storage. Expiration processing also removes from the database any restartable restore sessions that exceed the time limit for saving such sessions.

You can run expiration processing either automatically or by command. You should ensure that expiration processing runs periodically to allow the server to reuse storage pool space that is occupied by expired client files.

Note: A base file is not eligible for expiration until all of its dependent subfiles have been expired. For details, see “Expiration Processing of Base Files and Subfiles” on page 284.

Running Expiration Processing Automatically

You control automatic expiration processing by using the expiration interval option (EXPINTERVAL) in the server options file (dsmserv.opt). You can also control when restartable restore sessions expire with another server option, RESTOREINTERVAL. You can set the options by editing the dsmserv.opt file (see *Administrator's Reference*).

If you use the server options file to control automatic expiration, the server runs expiration processing each time you start the server. After that, the server runs expiration processing at the interval you specified with the option, measured from the start time of the server.

Using Commands and Scheduling to Control Expiration Processing

You can manually start expiration processing by issuing the following command:

```
expire inventory
```

Expiration processing then deletes expired files from the database. You can schedule this command by using the DEFINE SCHEDULE command. If you schedule the EXPIRE INVENTORY command, set the expiration interval to 0 (zero) in the server options so that the server does not run expiration processing when you start the server.

You can control how long the expiration process runs by using the DURATION parameter with the EXPIRE INVENTORY command.

When expiration processing runs, the server normally sends detailed messages about policy changes made since the last time expiration processing ran. You can reduce those messages by using the EXPQUIET server option, or by using the QUIET=YES parameter with the EXPIRE INVENTORY command. When you use the quiet option or parameter, the server issues messages about policy changes during expiration processing only when files are deleted, and either the default management class or retention grace period for the domain has been used to expire the files.

Additional Expiration Processing with Tivoli Disaster Recovery Manager



If you have Tivoli Disaster Recovery Manager (DRM), one or more database backup volumes may also be deleted during expiration processing if the following conditions are true:

- The volume has a device type of SERVER
- The volume is not part of the most recent database backup series
- The last volume of the database backup series has exceeded the expiration value specified with the SET DRMDBBACKUPEXPIREDDAYS command

See “Moving Backup Volumes Onsite” on page 513 for more information.

Configuring Policy for Specific Cases

This section includes recommendations for some cases for which policy changes may be needed.

- “Configuring Policy for Direct-to-Tape Backups”
- “Configuring Policy for Tivoli Data Protection Application Clients” on page 267
- “Policy for Logical Volume Backups” on page 267
- “Configuring Policy for Managed System for SAN” on page 268
- “Policy for Tivoli Storage Manager Servers as Clients” on page 270
- “Setting Policy to Enable Point-in-Time Restore for Clients” on page 270

Configuring Policy for Direct-to-Tape Backups

The server default policy enables client nodes to back up data to disk storage pools on the server. As an alternative, you may configure a policy to store client data directly in tape storage pools in order to reduce contention for disk resources. If you back up directly to tape, the number of clients that can back up data at the same time is equal to the number of drives available to the storage pool (through the mount limit of the device class). For example, if you have one drive, only one client at a time can back up data.

The direct-to-tape backup eliminates the need to migrate data from disk to tape. On the other hand, performance of tape drives is often lower when backing up directly to tape than when backing up to disk and then migrating to tape. Backing up data directly to tape usually means more starting and stopping of the tape drive. Backing up to disk then migrating to tape usually means the tape drive moves more continuously, meaning better performance.

At the server command line, you may define a new policy domain that enables client nodes to back up or archive data directly to tape storage pools. For example, you may define a policy domain named DIR2TAPE with the following steps:

1. Copy the default policy domain STANDARD as a template:

```
copy domain standard dir2tape
```

This command creates the DIR2TAPE policy domain that contains a default policy set, management class, backup and archive copy group, each named STANDARD.

2. Update the backup or archive copy group in the DIR2TAPE policy domain to specify the destination to be a tape storage pool. For example, to use a tape storage pool named TAPEPOOL for backup, enter the following command:

```
update copygroup dir2tape standard standard destination=tapepool
```

To use a tape storage pool named TAPEPOOL for archive, enter the following command:

```
update copygroup dir2tape standard standard type=archive  
destination=tapepool
```

3. Activate the changed policy set.

```
activate policysset dir2tape standard
```
4. Assign client nodes to the DIR2TAPE policy domain. For example, to assign a client node named TAPEUSER1 to the DIR2TAPE policy domain, enter the following command:

```
update node tapeuser1 domain=dir2tape
```

Configuring Policy for Tivoli Data Protection Application Clients

The Tivoli Data Protection application clients using the server to store data may require that you configure policy to make the most efficient use of server storage. See the user's guide for each application client for policy requirements.

Some of the application clients include a time stamp in each database backup. Because the default policy for the server keeps one backup version of each unique file, database backups managed by default policy are never deleted because each backup is uniquely named with its time stamp. To ensure that the server deletes backups as required, configure policy as recommended in the user's guide for the application client.

Policy for Logical Volume Backups

Consider defining a management class specifically for logical volume backups. To enable clients to restore a logical volume and then reconcile the results of any file backup operations since the logical volume backup was made, you must set up management classes with the backup copy group set up differently from the STANDARD. The Versions Data Exists, Versions Data Deleted, and Retain Extra Versions parameters work together to determine over what time period a client can restore a logical volume image and reconcile later file backups. Also, you may have server storage constraints that require you to control the number of backup versions allowed for logical volumes.

Backups of logical volumes are intended to help speed the restoration of a machine. One way to use the capability is to have users periodically (for example, once a month) perform a logical volume backup, and schedule daily full incremental backups. If a user restores a logical volume, the program first restores the logical volume backup and then any files that were changed since the backup (incremental or other file backup processes). The user can also specify that the restore process reconcile any discrepancies that can result when files are deleted.

For example, a user backs up a logical volume, and the following week deletes one or more files from the volume. At the next incremental backup, the server records in its database that the files were deleted from the client. When the user restores the logical volume, the program can recognize that files have been deleted since the backup was created. The program can delete the files as part of the restore process. To ensure that users can use the capability to reconcile later incremental backups with a restored logical volume, you need to ensure that you coordinate policy for incremental backups with policy for backups for logical volumes.

For example, you decide to ensure that clients can choose to restore files and logical volumes from any time in the previous 60 days. You can create two management classes, one for files and one for logical volumes. Table 22 on page 268 shows the relevant parameters. In the backup copy group of both management classes, set the Retain Extra Versions parameter to 60 days.

In the management class for files, set the parameters so that the server keeps versions based on age rather than how many versions exist. More than one backup version of a file may be stored per day if clients perform selective backups or if clients perform incremental backups more than once a day. The Versions Data Exists parameter and the Versions Data Deleted parameter control how many of these versions are kept by the server. To ensure that any number of backup versions are kept for the required 60 days, set both the Versions Data Exists parameter and the Versions Data Deleted parameter to NOLIMIT for the management

class for files. This means that the server retains backup versions based on how old the versions are, instead of how many backup versions of the same file exist.

For logical volume backups, the server ignores the frequency attribute in the backup copy group.

Table 22. Example of Backup Policy for Files and Logical Volumes

Parameter (backup copy group in the management class)	Management Class for Files	Management Class for Logical Volumes
Versions Data Exists	NOLIMIT	3 versions
Versions Data Deleted	NOLIMIT	1
Retain Extra Versions	60 days	60 days
Retain Only Version	120 days	120 days

Configuring Policy for Managed System for SAN

With the Managed System for SAN feature, you can set up a SAN configuration in which a TSM client directly accesses a storage device to read or write data. SAN data transfer requires setup on the server and on the client, and the installation of a storage agent on the client machine. The storage agent transfers data between the client and the storage device. See *TSM Managed System for SAN Storage Agent User's Guide* for details. See the Web site for details on clients that support the feature:

http://www.tivoli.com/support/storage_mgr/tivolimain.html.

One task in configuring your systems to use this feature is to set up policy for the clients. Copy groups for these clients must point to the storage pool that is associated with the SAN devices. (“Configuring TSM Clients to Directly Access SAN-Attached Devices” on page 79 describes how to configure the devices and define the storage pool.) Clients for which you have mapped the SAN drives in this storage pool can then use the SAN to send data directly to the device for backup, archive, restore, and retrieve.

To set up the required policy, either define a new, separate policy domain, or define a new management class in an existing policy domain:

- “Define a New Policy Domain” on page 268
- “Define a New Management Class in an Existing Policy Domain” on page 269

Define a New Policy Domain

One way to configure policy for clients is to define a separate policy domain in which the active policy set has a default management class with the required settings. Then register all clients using SAN data transfer to that domain. Do the following:

1. Create the policy domain for the clients. For example, to define a policy domain that is named SANCLIENTS, enter the following command:

```
define domain sanclients  
description='Policy domain for clients using SAN devices'
```
2. Create a policy set in that domain. For example, to define the policy set that is named BASE in the SANCLIENTS policy domain, enter the following command:

```
define policyset sanclients base
```
3. Create the default management class for the policy set. First define the management class, then assign the management class as the default for the policy set.

For example, to define the management class that is named SANCLIENTMC, enter the following command:

```
define mgmtclass sanclients base sanclientmc
```

Then assign the new management class as the default:

```
assign defmgmtclass sanclients base sanclientmc
```

4. Define the backup copy group in the default management class, as follows:
 - Specify the DESTINATION, the name of the storage pool that is associated with the SAN devices on the server.

The storage pool must already be set up. The storage pool must point to a device class that is associated with the library for the SAN devices. See “Configuring TSM Clients to Directly Access SAN-Attached Devices” on page 79 for details.

- Accept the default settings for all remaining parameters.

For example, to define the backup copy group for the SANCLIENTMC management class, enter the following command:

```
define copygroup sanclients base sanclientmc standard destination=sanpool
```

5. Define the archive copy group in the default management class, as follows:
 - Specify the DESTINATION, the name of the storage pool that is associated with the SAN devices on the server.

The storage pool must already be set up. The storage pool must point to a device class that is associated with the library for the SAN devices. See “Configuring TSM Clients to Directly Access SAN-Attached Devices” on page 79 for details.

- Accept the default settings for all remaining parameters.

For example, to define the archive copy group for the SANCLIENTMC management class, enter the following command:

```
define copygroup sanclients base sanclientmc standard
  type=archive destination=sanpool
```

6. Activate the policy set.

For example, to activate the BASE policy set in the SANCLIENTS policy domain, enter the following command:

```
activate policyset sanclients base
```

7. Register or update the application clients to associate them with the new policy domain.

For example, to update the node SANCLIENT1, enter the following command:

```
update node sanclient1 domain=sanclients
```

Define a New Management Class in an Existing Policy Domain

If you choose not to define a separate policy domain with the appropriate management class as the default, you must define a new management class within an existing policy domain and activate the policy set. Because the new management class is not the default for the policy domain, you must add an include statement to each client options file to bind objects to that management class.

For example, suppose sanclientmc is the name of the management class that you defined for clients that are using devices on a SAN. You want the client to be able to use the SAN for backing up any file on the *c* drive. Put the following line at the end of the client’s include-exclude list:

```
include c:* sanclientmc
```

For details on the include-exclude list, see *Tivoli Storage Manager Installing the Clients*.

Policy for Tivoli Storage Manager Servers as Clients

One TSM server (a source server) can be registered as a client to another TSM server (the target server). Data stored by the source server appears as archived files on the target server. The source server is registered to a policy domain on the target server, and uses the default management class for that policy domain. In the default management class, the destination for the archive copy group determines where the target server stores data for the source server. Other policy specifications, such as how long to retain the data, do not apply to data stored for a source server. See “Using Virtual Volumes to Store Data on Another Server” on page 348 for more information.

Setting Policy to Enable Point-in-Time Restore for Clients

To enable clients to restore backed-up files to a specific point in time, you must set up the backup copy group differently from the STANDARD. The Versions Data Exists, Versions Data Deleted, and Retain Extra Versions parameters work together to determine over what time period a client can perform a point-in-time restore operation.

For example, you decide to ensure that clients can choose to restore files from anytime in the previous 60 days. In the backup copy group, set the Retain Extra Versions parameter to 60 days. More than one backup version of a file may be stored per day if clients perform selective backups or if clients perform incremental backups more than once a day. The Versions Data Exists parameter and the Versions Data Deleted parameter control how many of these versions are kept by the server. To ensure that any number of backup versions are kept for the required 60 days, set both the Versions Data Exists parameter and the Versions Data Deleted parameter to NOLIMIT. This means that the server essentially determines the backup versions to keep based on how old the versions are, instead of how many backup versions of the same file exist.

Keeping backed-up versions of files long enough to allow clients to restore their data to a point in time can mean increased resource costs. Requirements for server storage increase because more file versions are kept, and the size of the server database increases to track all of the file versions. Because of these increased costs, you may want to choose carefully which clients can use the policy that allows for point-in-time restore operations.

Clients need to run full incremental backup operations frequently enough so that TSM can detect files that have been deleted on the client file system. Only a full incremental backup can detect whether files have been deleted since the last backup. If full incremental backup is not done often enough, clients who restore to a specific time may find that many files that had actually been deleted from the workstation get restored. As a result, a client’s file system may run out of space during a restore process.

Distributing Policy Using Enterprise Configuration



If you set up one TSM server as a configuration manager, you can distribute policy to other TSM servers. To distribute policy, you associate a policy domain with a profile. Managed servers that subscribe to the profile then receive the following definitions:

- The policy domain itself

- Policy sets in that domain, except for the ACTIVE policy set
- Management classes in the policy sets
- Backup and archive copy groups in the management classes
- Client schedules associated with the policy domain

The names of client nodes and client-schedule associations are not distributed. The ACTIVE policy set is also not distributed.

The distributed policy becomes managed objects (policy domain, policy sets, management classes, and so on) defined in the database of each managed server. To use the managed policy, you must activate a policy set on each managed server. If storage pools specified as destinations in the policy do not exist on the managed server, you receive messages pointing out the problem when you activate the policy set. You can create new storage pools to match the names in the policy set, or you can rename existing storage pools.

On the managed server you also must associate client nodes with the managed policy domain and associate client nodes with schedules.

See “Setting Up an Enterprise Configuration” on page 321 for details.

Querying Policy

Task	Required Privilege Class
Query any policy domain, policy set, management class, or copy group	Any administrator

You can request information about the contents of policy objects. You might want to do this before creating new objects or when helping users to choose policies that fit their needs.

You can specify the output of a query in either standard or detailed format. The examples in this section are in standard format.

On a managed server, you can see whether the definitions are managed objects. Request the detailed format in the query and check the contents of the Last update by (administrator) field. For managed objects, this field contains the string `$$CONFIG_MANAGER$$`.

Querying Copy Groups

To request information about backup copy groups (the default) in the ENGPOLDOM engineering policy domain, enter:

```
query copygroup engpoldom * *
```

The following shows the output from the query. It shows that the ACTIVE policy set contains two backup copy groups that belong to the MCENG and STANDARD management classes.

Policy Domain Name	Policy Set Name	Mgmt Class Name	Copy Group Name	Versions Data Exists	Versions Data Deleted	Retain Extra Versions	Retain Only Version
ENGPOLDOM	ACTIVE	MCENG	STANDARD	5	4	90	600
ENGPOLDOM	ACTIVE	STANDARD	STANDARD	2	1	30	60
ENGPOLDOM	STANDARD	MCENG	STANDARD	5	4	90	600
ENGPOLDOM	STANDARD	STANDARD	STANDARD	2	1	30	60
ENGPOLDOM	TEST	STANDARD	STANDARD	2	1	30	60

To request information about archive copy groups in the ENGPOLDOM engineering policy domain, enter:

```
query copygroup engpoldom * type=archive
```

The following shows the output from the query.

Policy Domain Name	Policy Set Name	Mgmt Class Name	Copy Group Name	Retain Version
ENGPOLDOM	ACTIVE	MCENG	STANDARD	730
ENGPOLDOM	ACTIVE	STANDARD	STANDARD	365
ENGPOLDOM	STANDARD	MCENG	STANDARD	730
ENGPOLDOM	STANDARD	STANDARD	STANDARD	365
ENGPOLDOM	TEST	STANDARD	STANDARD	365

Querying Management Classes

To request information about management classes in the ENGPOLDOM engineering policy domain, enter:

```
query mgmtclass engpoldom * *
```

The following figure is the output from the query. It shows that the ACTIVE policy set contains the MCENG and STANDARD management classes.

Policy Domain Name	Policy Set Name	Mgmt Class Name	Default Mgmt Class ?	Description
ENGPOLDOM	ACTIVE	MCENG	No	Engineering Management Class with Backup and Archive Copy Groups
ENGPOLDOM	ACTIVE	STANDARD	Yes	Installed default management class
ENGPOLDOM	STANDARD	MCENG	No	Engineering Management Class with Backup and Archive Copy Groups
ENGPOLDOM	STANDARD	STANDARD	Yes	Installed default management class
ENGPOLDOM	TEST	STANDARD	Yes	Installed default management class

Querying Policy Sets

To request information about policy sets in the ENGPOLDOM engineering policy domain, enter:

```
query policyset engpoldom *
```

The following figure is the output from the query. It shows an ACTIVE policy set and two inactive policy sets, STANDARD and TEST.

Policy Domain Name	Policy Set Name	Default Mgmt Class Name	Description
ENGPOLDOM	ACTIVE	STANDARD	Installed default policy set
ENGPOLDOM	STANDARD	STANDARD	Installed default policy set
ENGPOLDOM	TEST	STANDARD	Policy set for testing

Querying Policy Domains

To request information about a policy domain (for example, to determine if any client nodes are registered to that policy domain), enter:

```
query domain *
```

The following figure is the output from the query. It shows that both the ENGPOLDOM and STANDARD policy domains have client nodes assigned to them.

Policy Domain Name	Activated Policy Set	Activated Default Mgmt Class	Number of Registered Nodes	Description
APPCLIEN-TS	BASE	APPCLIEN-TMC	1	Policy domain for application clients
ENGPOLDOM	STANDARD	STANDARD	21	Engineering Policy Domain
STANDARD	STANDARD	STANDARD	18	Installed default policy domain.

Deleting Policy

When you delete a policy object, you also delete any objects belonging to it. For example, when you delete a management class, you also delete the copy groups in it.

You cannot delete the ACTIVE policy set or objects that are part of that policy set.

Task	Required Privilege Class
Delete policy domains	System

Task	Required Privilege Class
Delete any policy sets, management classes, or copy groups	System or unrestricted policy
Delete policy sets, management classes, or copy groups that belong to policy domains over which you have authority	Restricted policy

You can delete the policy objects named STANDARD that come with the server. However, all STANDARD policy objects are restored whenever you reinstall the server. If you reinstall the server after you delete the STANDARD policy objects, the server issues messages during processing of a subsequent DSMSERV AUDITDB command. The messages may include the following statement: “An instance count does not agree with actual data.” The DSMSERV AUDITDB command corrects this problem by restoring the STANDARD policy objects. If necessary, you can later delete the restored STANDARD policy objects.

Deleting Copy Groups

You can delete a backup or archive copy group if it does not belong to a management class in the ACTIVE policy set.

For example, to delete the backup and archive copy groups belonging to the MCENG and STANDARD management classes in the STANDARD policy set, enter:

```
delete copygroup engpoldom standard mceng type=backup
delete copygroup engpoldom standard standard type=backup
delete copygroup engpoldom standard mceng type=archive
delete copygroup engpoldom standard standard type=archive
```

Deleting Management Classes

You can delete a management class if it does not belong to the ACTIVE policy set.

For example, to delete the MCENG and STANDARD management classes from the STANDARD policy set, enter:

```
delete mgmtclass engpoldom standard mceng
delete mgmtclass engpoldom standard standard
```

When you delete a management class from a policy set, the server deletes the management class and all copy groups that belong to the management class in the specified policy domain.

Deleting Policy Sets

Authorized administrators can delete any policy set other than the ACTIVE policy set. For example, to delete the TEST policy set from the ENGPOLDOM policy domain, enter:

```
delete policysset engpoldom test
```

When you delete a policy set, the server deletes all management classes and copy groups that belong to the policy set within the specified policy domain.

The ACTIVE policy set in a policy domain cannot be deleted. You can replace the contents of the ACTIVE policy set by activating a different policy set. Otherwise, the only way to remove the ACTIVE policy set is to delete the policy domain that contains the policy set.

Deleting Policy Domains

You can delete a policy domain only if the domain has no client nodes registered to it. To determine if any client nodes are registered to a policy domain, issue the `QUERY DOMAIN` or the `QUERY NODE` command. Move any client nodes to another policy domain, or delete the nodes.

For example, to delete the `STANDARD` policy domain, perform the following steps:

1. Request a list of all client nodes assigned to the `STANDARD` policy domain by entering:

```
query node * domain=standard
```
2. If client nodes are assigned to the policy domain, remove them in one of the following ways:
 - Assign each client node to a new policy domain. For example, enter the following commands:

```
update node htang domain=engpoldom  
update node tomc domain=engpoldom  
update node pease domain=engpoldom
```

If the `ACTIVE` policy set in `ENGPOLDOM` does not have the same management class names as in the `ACTIVE` policy set of the `STANDARD` policy domain, then backup versions of files may be bound to a different management class name, as described in “How Files and Directories Are Associated with a Management Class” on page 244.
 - Delete each node from the `STANDARD` policy domain by first deleting all file spaces belonging to the nodes, then deleting the nodes.
3. Delete the policy domain by entering:

```
delete domain standard
```

When you delete a policy domain, the server deletes the policy domain and all policy sets (including the `ACTIVE` policy set), management classes, and copy groups that belong to the policy domain.

13

Managing Data for Client Nodes

This chapter contains information to help you generate backup sets and enable subfile backups for client nodes.

See the following sections for more information:

Tasks:
“Generating Client Backup Sets on the Server” on page 278
“Restoring Backup Sets from a Backup-Archive Client” on page 280
“Moving Backup Sets to Other Servers” on page 280
“Managing Client Backup Sets” on page 280
“Enabling Clients to Use Subfile Backup” on page 282
Concepts:
“Creating and Using Client Backup Sets”

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Creating and Using Client Backup Sets

A *backup set* is a collection of backed-up data from one client, stored and managed as a single object, on specific media, in server storage. The server creates copies of active versions of a client’s backed up objects that are within the one or more file spaces specified with the GENERATE BACKUPSET command, and consolidates them onto sequential media. Currently, the backup object types supported for backup sets include directories and files only.

The media may be directly readable by a device such as a CD-ROM, JAZ, or ZIP drive attached to a client’s machine.

Administrators can generate multiple copies of backup sets that correspond to some point-in-time. The backup sets can be retained for various time periods. This is an efficient way to create long-term storage of periodic backups, without requiring the data to be sent over the network again.

While an administrator can generate a backup set from any client's backed up files, backup sets can only be used by a backup-archive client.

See the following sections for details:

- “Generating Client Backup Sets on the Server”
- “Restoring Backup Sets from a Backup-Archive Client” on page 280
- “Moving Backup Sets to Other Servers” on page 280
- “Managing Client Backup Sets” on page 280

Generating Client Backup Sets on the Server

Task	Required Privilege Class
Generate a backup set	System or restricted policy over the domain to which the node is assigned

You can generate backup sets on the server for client nodes. The client node for which a backup set is generated must be registered to the server. An incremental backup must be completed for a client node before the server can generate a backup set for the client node.

The GENERATE BACKUPSET command runs as a background process on the server. If you cancel the background process created by this command, the media may not contain a complete backup set.

See the following sections:

- “Choosing Media for Generating the Backup Set”
- “Selecting a Name for the Backup Set” on page 279
- “Setting a Retention Period for the Backup Set” on page 279
- “Example: Generating a Client Backup Set” on page 279

Choosing Media for Generating the Backup Set

To generate a backup set, you must specify a device class that is associated with the media to which the backup set will be written.

Consider the following when you select a device class for writing the backup set:

- Generate the backup set on any sequential access devices whose device types are supported on **both** the client and server machines. If you do not have access to compatible devices, you will need to define a device class for a device type that is supported on both the client and server.
- Ensure that the media type and recording format used for generating the backup set is supported by the device that will be reading the backup set.

You can write backup sets to sequential media: sequential tape and device class FILE. The tape volumes containing the backup set are not associated with storage pools and, therefore, are not migrated through the storage pool hierarchy.

For device class FILE, the server creates each backup set with a file extension of OST. You can copy FILE device class volumes to removable media that is associated with CD-ROM,

JAZ, or ZIP devices, by using the REMOVABLEFILE device type. For more information, see “Configuring Removable File Devices” on page 61.

Using Scratch Media

You can determine whether to use scratch volumes when you generate a backup set. If you do not use specific volumes, the server uses scratch volumes for the backup set.

You can use specific volumes for the backup set. If there is not enough space to store the backup set on the volumes, the server uses scratch volumes to store the remainder of the backup set.

Selecting a Name for the Backup Set

The server adds a unique suffix to the name you specify for the backup set. For example, if you name the backup set *mybackupset*, the server adds a unique extension, such as 3099, to the name. This allows you to create backup sets with the same name without overwriting previous backup sets.

To later display information about this backup set, you can include a wildcard character with the name, such as *mybackupset**, or you can specify the fully qualified name, such as *mybackupset.3099*.

Setting a Retention Period for the Backup Set

You can set the retention period, specified as a number of days, to retain the backup set on the server. You can specify a number between zero and 9999 days. Backup sets are retained on the server for 365 days if you do not specify a value. The server uses the retention period to determine when to expire the volumes on which the backup set resides.

Example: Generating a Client Backup Set

Generate a backup set on portable media that the client can later use to restore the data. Use the following steps to generate a backup set on a CD-ROM:

1. Define a library whose type is MANUAL. Name the library MANUALLIB.

```
define library manuallib libtype=manual
```
2. Define a device class whose device type is REMOVABLEFILE. Name the device class BACKSET:

```
define devclass backset devtype=removablefile library=manuallib
```
3. Define a drive to associate with the library. Name the drive CDDRIVE and the device /cdrom

```
define drive manuallib cddrive device=/cdrom
```
4. Define a device class whose device type is FILE. Name the device class FILES:

```
define devclass files devtype=file maxcapacity=640M dir=/backupset
```
5. Generate the backup set to the FILE device class for client node JOHNSON. Name the backup set PROJECT and retain it for 90 days.

```
generate backupset johnson project devclass=file scratch=yes retention=90
```
6. Use your own software for writing CD-ROMs. For this example, the CD-ROM volume names are VOL1, VOL2, and VOL3. These names were put on the CD-ROM as they were created.

For an example of using the backup set on the CD-ROM, see “Moving Backup Sets to Other Servers” on page 280.

Restoring Backup Sets from a Backup-Archive Client

Backup-archive client nodes can restore their backup sets in either of two ways:

- Directly from the server.
- Using a device attached to the client's machine that will read the media in which the backup set is stored.

Backup sets can only be used by a backup-archive client, and only if the files in the backup set originated from a backup-archive client.

For more information about restoring backup sets, see *Using the Backup-Archive Client* guide for your particular platform.

Moving Backup Sets to Other Servers

Task	Required Privilege Class
Define a backup set	If the REQSYSAUTHOUTFILE server option is set to YES, system privilege is required. If the REQSYSAUTHOUTFILE server option is set to NO, system or restricted policy over the domain to which the node is assigned is required.

You can define (move) a backup set generated on one server to another TSM server. Any client backup set that you generate on one server can be defined to another server as long as the servers share a common device type. The level of the server defining the backup set must be equal to or greater than the level of the server that generated the backup set.

If you have multiple servers connecting to different clients, the DEFINE BACKUPSET command makes it possible for you to take a previously generated backup set and make it available to other servers. The purpose is to allow the user flexibility in moving backup sets to different servers, thus allowing the user the ability to restore their data from a server other than the one on which the backup set was created.

Using the example described in “Example: Generating a Client Backup Set” on page 279, you can make the backup set that was copied to the CD-ROM available to another server by entering:

```
define backupset johnson project devclass=cdrrom volumes=vol1,vol2,vol3  
description="backup set copied to a CD-ROM"
```

Managing Client Backup Sets

You can update, query, and delete backup sets.

Task	Required Privilege Class
Update the retention period assigned to a backup set	System or restricted policy over the domain to which the node is assigned
Display information about backup sets	Any administrator
Display information about backup set contents	System or restricted policy over the domain to which the node is assigned

Task	Required Privilege Class
Delete backup set	If the REQSYSAUTHOUTFILE server option is set to YES, system privilege is required. If the REQSYSAUTHOUTFILE server option is set to NO, system or restricted policy over the domain to which the node is assigned is required.

Updating the Retention Period of a Backup Set

When you want to change the number of days the server retains a backup set, update the retention period that is associated with the backup set. For example, to update the retention period assigned to backup set named ENGDATA.3099, belonging to client node JANE, to 120 days, enter:

```
update backupset jane engdata.3099 retention=120
```

Displaying Information about Backup Set Volumes

The server records the information about the volumes used for the backup set in the volume history file. Volume history includes information such as the date and time the backup set was generated, the device class to which the backup set was written, and the command used to generate the backup set. You can view this information when you use the QUERY VOLHISTORY command, with BACKUPSET specified as the volume type.

To view additional information about backup sets, you can use the QUERY BACKUPSET command. The output that is displayed lists information such as the name of the client node whose data is contained in the backup set as well as the description of the backup set, assuming one has been used.

The following figure shows the report that is displayed after you enter:

```
query backupset
```

```
Node Name: JANE
Backup Set Name: MYBACKUPSET.3099
Date/Time: 06/09/1999 16:17:47
Retention Period: 60
Device Class Name: DCFILE
Description:
```

Displaying Contents of Backup Sets

You can display information about the contents of backup sets by using the QUERY BACKUPSETCONTENTS command. When you issue the query, the server displays only one backup set at a time.

The server displays information about the files and directories that are contained in a backup set. The following figure shows the report that is displayed after you enter:

```
query backupsetcontents jane engdata.3099
```

Node Name	Filespace Name	Client's Name for File
JANE	/srvr	/deblock
JANE	/srvr	/deblock.c
JANE	/srvr	/dsmerror.log
JANE	/srvr	/dsmxxxxx.log
JANE

How File Space and File Names May be Displayed

File space names and file names that can be in a different code page or locale than the server do not display correctly on the administrator's Web interface or the administrative command-line interface. The data itself is backed up and can be restored properly, but the file space or file name may display with a combination of invalid characters or blank spaces.

If the file space name is Unicode enabled, the name is converted to the server's code page for display. The results of the conversion for characters not supported by the current code page depends on the operating system. For names that TSM is able to partially convert, you may see question marks (??), blanks, unprintable characters, or "...". These characters indicate to the administrator that files do exist. If the conversion is not successful, the name is displayed as "...". Conversion can fail if the string includes characters that are not available in the server code page, or if the server has a problem accessing system conversion routines.

Deleting Backup Sets

When the server creates a backup set, the retention period assigned to the backup set determines how long the backup set remains in the database. When that date passes, the server automatically deletes the backup set when expiration processing runs. However, you can also manually delete the client's backup set from the server before it is scheduled to expire by using the `DELETE BACKUPSET` command.

After a backup set is deleted, the volumes return to scratch status if TSM acquired them as scratch volumes. Scratch volumes associated with a device type of `FILE` are deleted.

To delete a backup set named `ENGDATA.3099`, belonging to client node `JANE`, created before 11:59 p.m. on March 18, 1999, enter:

```
delete backupset jane engdata.3099 begindate=03/18/1999 begintime=23:59
```

To delete all backup sets belonging to client node `JANE`, created before 11:59 p.m. on March 18, 1999, enter:

```
delete backupset jane * begindate=03/18/1999 begintime=23:59
```

Enabling Clients to Use Subfile Backup

A basic problem that remote and mobile users face today is connecting to storage management services by using modems with limited bandwidth or poor line quality. This creates a need for users to minimize the amount of data they send over the network, as well as the time that they are connected to the network.

To help address this problem, you can use subfile backups. When a client's file has been previously backed up, any subsequent backups are *typically* made of the portion of the client's file that has changed (*a subfile*), rather than the entire file. A *base* file is represented by a backup of the entire file and is the file on which subfiles are dependent. If the changes to a file are extensive, a user can request a backup on the entire file. A new base file is established on which subsequent subfile backups are dependent.

This type of backup makes it possible for mobile users to reduce connection time, network traffic, and the time it takes to do a backup. To enable this type of backup, see “Setting Up Clients to Use Subfile Backup”.

Example of Subfile Backups

Assume that on a Monday, a user requests an incremental backup of a file called *CUST.TXT*. The user makes daily updates to the *CUST.TXT* file and requests subsequent backups.

The following table describes how TSM handles backups of file *CUST.TXT*.

Version	Day of subsequent backup	What TSM backs up
One	Monday	The entire <i>CUST.TXT</i> file (the base file)
Two	Tuesday	A subfile of <i>CUST.TXT</i> . The server compares the file backed up on Monday with the file that needs to be backed up on Tuesday. A subfile containing the changes between the two files is sent to the server for the backup.
Three	Wednesday	A subfile of <i>CUST.TXT</i> . TSM compares the file backed up on Monday with the file that needs to be backed up on Wednesday. A subfile containing the changes between the two files is sent to TSM for the backup.

Setting Up Clients to Use Subfile Backup

To enable subfile backup, do the following:

- **On the server:** You must set up the server to allow clients to back up subfiles. Use the `SET SUBFILE` command.

```
set subfile client
```

- **On the clients:** The `SUBFILEBACKUP`, `SUBFILECACHEPATH`, and `SUBFILECACHESIZE` options must be set in the client's options file (`dsm.opt`).

You can control these options from the server by including them in client option sets. For example, you can disable subfile backup for individual client nodes by setting `SUBFILEBACKUP=NO` in the client option set associated with the client node. See “Creating Client Option Sets from the Server” on page 215 for how to set up and use client option sets.

See *Tivoli Storage Manager for Windows Using the Backup-Archive Clients* for more information about the options.

Managing Subfile Backups

The following sections describe how TSM manages subfiles that are restored, exported, imported, or added to a backup set.

Restoring Subfiles

When a client issues a request to restore subfiles, TSM restores subfiles along with the corresponding base file back to the client. This process is transparent to the client. That is, the client does not have to determine whether all subfiles and corresponding base file were restored during the restore operation.

You can define (move) a backup set that contains subfiles to an earlier version of a server that is not enabled for subfile backup. That server can restore the backup set containing the subfiles to a client not able to restore subfiles. However, this process is not recommended as it could result in a data integrity problem.

Exporting and Importing Subfiles

When subfiles are exported during an export operation, TSM also exports the corresponding base file to volumes you specify. When the base file and its dependent subfiles are imported from the volumes to a target server and import processing is canceled while the base file and subfiles are being imported, the server automatically deletes any incomplete base files and subfiles that were stored on the target server.

Expiration Processing of Base Files and Subfiles

Because subfiles are useless without the corresponding base file, the server processes base files eligible for expiration differently. For example, when expiration processing runs, TSM recognizes a base file as eligible for expiration but does not delete the file until all its dependent subfiles have expired. For more information on how the server manages file expiration, see “Running Expiration Processing to Delete Expired Files” on page 264.

Adding Subfiles to Backup Sets

When a subfile is added to a backup set, TSM includes its corresponding base file with the backup set. If the base file and dependent subfiles are stored on separate volumes when a backup set is created, additional volume mounts may be required to create the backup set.

Deleting Base Files

If a base file is deleted as a result of processing a `DELETE VOLUME` command, the server recognizes its dependent subfiles and deletes them from the server as well. Subfiles without the corresponding base file are incomplete and useless to the user.

14

Scheduling Operations for Client Nodes

This chapter contains information about scheduling the following operations:

- Backing up and restoring client data, Tivoli Data Protection application client data, and Tivoli Data Protection host server data.
- Archiving and retrieving client data.
- Running operating system commands.
- Running macro or command files that contain operating system commands, TSM commands, or both. A command file can be scheduled to run on clients, application clients, or Tivoli Data Protection host servers.

If you are planning to use Tivoli Decision Support products with TSM, you can define a schedule that will run the Decision Support Loader automatically. For information, see “Scheduling the Decision Support Loader with Tivoli Storage Manager” on page 431. For information about the Tivoli Decision Support Guide products, see this URL:
http://www.tivoli.com/support/storage_mgr/tivolimain.html

The following concepts are described in this chapter:

Concepts:
“Prerequisites to Scheduling Operations” on page 286
“Comparing Tivoli Storage Manager Scheduling Across Operating Systems and Components” on page 290
“Commands for Scheduling Client Operations” on page 291

Administrators perform the following activities to schedule TSM client operations:

Tasks:
“Scheduling a Client Operation” on page 286 (task overview)
“Defining Client Schedules” on page 286
“Associating Client Nodes with Schedules” on page 287
“Starting the Scheduler on the Clients” on page 287
“Displaying Schedule Information” on page 288
“Creating Schedules for Running Command Files” on page 289
“Updating the Client Options File to Automatically Generate a New Password” on page 289

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Prerequisites to Scheduling Operations

To interact with TSM for scheduling operations, a client machine must meet the following prerequisites:

- The client node must be registered with the server. For information, see “Adding Client Nodes” on page 189.
- The client options file (dsm.opt) must contain the network address of the server that the client will contact for services. See “Connecting Nodes with the Server” on page 193 for more information.
- The scheduler must be started on the client machine. See *Tivoli Storage Manager Installing the Clients* for details.

Scheduling a Client Operation

To automate client operations, you can define new schedules. To later modify, copy, and delete these schedules, see “Managing Schedules for Client Nodes” on page 293.

When you define a schedule, you assign it to a specific policy domain. You can define more than one schedule for each policy domain.

To set up a client schedule on the server, perform these steps:

1. Define a schedule (DEFINE SCHEDULE command). (“Defining Client Schedules” on page 286)
2. Associate client nodes with the schedule (DEFINE ASSOCIATION command). (“Associating Client Nodes with Schedules” on page 287)
3. Ensure that the clients start the client scheduler. (“Starting the Scheduler on the Clients” on page 287)
4. Display the schedule information and check that the schedule completed successfully (QUERY SCHEDULE and QUERY EVENT commands). (“Displaying Schedule Information” on page 288)

The following sections describe how to automate a basic client operation, incremental backup.

Defining Client Schedules

Task	Required Privilege Class
Define client schedules for any policy domain	System or unrestricted policy
Define client schedules for specific policy domains	System, unrestricted policy, or restricted policy for those domains

Key information to have when scheduling operations are:

- The operation that needs to be run
- The time and day when the operation needs to run

- How often the operation needs to be repeated

To define a schedule for daily incremental backups, use the `DEFINE SCHEDULE` command. You must specify the policy domain to which the schedule belongs and the name of the schedule (the policy domain must already be defined). For example:

```
define schedule engpoldom daily_backup starttime=21:00
duration=2 durunits=hours
```

This command results in the following:

- Schedule `DAILY_BACKUP` is defined for policy domain `ENGPOLDOM`.
- The scheduled action is an incremental backup; this is the default.
- The priority for the operation is 5; this is the default. If schedules conflict, the schedule with the highest priority (lowest number) is run first.
- The schedule window begins at 9:00 p.m. and the schedule itself has 2 hours to start.
- The start window is scheduled every day; this is the default.
- The schedule never expires; this is the default.

To change the defaults, see the `DEFINE SCHEDULE` command in the *Administrator's Reference*.

Associating Client Nodes with Schedules

Task	Required Privilege Class
Associate client nodes with schedules	System, unrestricted policy, or restricted policy for the policy domain to which the schedule belongs

Client nodes process operations according to the schedules associated with the nodes. To associate client nodes with a schedule, use the `DEFINE ASSOCIATION` command. A client node can be associated with more than one schedule. However, a node must be assigned to the policy domain to which a schedule belongs.

After a client schedule is defined, you can associate client nodes with it by identifying the following information:

- Policy domain to which the schedule belongs
- List of client nodes to be associated with the schedule

To associate the `ENGNODE` client node with the `WEEKLY_BACKUP` schedule, both of which belong to the `ENGPOLDOM` policy domain, enter:

```
define association engpoldom weekly_backup engnode
```

Starting the Scheduler on the Clients

The client scheduler must be started before work scheduled by the administrator can be initiated. Administrators must ensure that users start the TSM Scheduler on the client, application client, or Tivoli Data Protection host server directory, and that the scheduler is running at the schedule start time. After the client scheduler starts, it continues to run and initiates scheduled events until it is stopped.

The way that users start the TSM Scheduler varies, depending on the operating system that the machine is running. The user can choose to start the client scheduler automatically when the operating system is started, or can start it manually at any time. The user can also have the client acceptor manage the scheduler, starting the scheduler only when needed. For instructions on these tasks, see *Tivoli Storage Manager Installing the Clients* and the appropriate client user's guide.

Note: TSM does not recognize changes made to the client options file while the scheduler is running. If you make changes to this file while the scheduler is running, and you want TSM to use these new values immediately, stop the scheduler and restart it.

Displaying Schedule Information

Task	Required Privilege Class
Display information about scheduled operations	Any administrator

You can display information about schedules and whether the schedules ran successfully.

Displaying Schedule Details

When you request information about schedules, the server displays the following information:

- Schedule name
- Policy domain name
- Type of operation to be performed
- Start date and time for the initial startup window
- Duration of the startup window
- Time period between startup windows
- Day of the week on which scheduled operations can begin

The following output shows an example of a report that is displayed after you enter:

```
query schedule engpoldom
```

Domain	* Schedule Name	Action	Start Date/Time	Duration	Period	Day
ENGPOLDOM	MONTHLY_BACKUP	Inc Bk	07/21/1998 12:45:14	2 H	2 Mo	Sat
ENGPOLDOM	WEEKLY_BACKUP	Inc Bk	07/21/1998 12:46:21	4 H	1 W	Sat

Checking the Status of Scheduled Operations

For TSM, a schedule completes successfully as long as the command associated with the schedule is successfully issued. The success of the issued command is independent of the success of the schedule.

- To determine the success of a scheduled operation, query the server. Each scheduled client operation is called an *event*, and is tracked by the server. You can get information about projected and actual scheduled processes by using the QUERY EVENT command. You can get information about scheduled processes that did not complete successfully by using exception reporting with this command.

For example, you can issue the following command to find out which events were missed (did not start) in the ENGPOLDOM policy domain for the WEEKLY_BACKUP schedule in the previous week:

```
query event engpoldom weekly_backup begindate=-7 begintime=now
enddate=today endtime=now exceptiononly=yes
```

For more information about managing event records, see “Managing Event Records” on page 296.

- To determine the success of the commands issued as the result of a successful schedule, you can:

- Check the client’s schedule log.

The schedule log is a file that contains information such as the statistics about the backed-up objects, the name of the server backing up the objects, and the time and date of the next scheduled operation. By default, TSM stores the schedule log as a file called *dsmsched.log* and places the file in the directory where the TSM backup-archive client is installed. See the client user’s guide for more information.

- Check the server’s activity log.

Search or query the activity log for related messages. For example, search for messages that mention the client node name, within the time period that the schedule ran. For example:

```
query actlog begindate=02/23/2001 enddate=02/26/2001 originator=client
nodename=hermione
```

Creating Schedules for Running Command Files

For some clients, you may want to run a command for a different application before running a TSM backup. For example, you may want to stop a database application, back up files with TSM, and then restart the application. To do this, you can schedule the running of a command file. Application clients and Tivoli Data Protection host servers *require* schedules that run command files.

A command file (also known as a macro or batch file on different operating systems) is stored on the client and contains a sequence of commands that are intended to be run during a scheduled start date and time window. Commands can include operating system commands, the TSM client’s DSMC command, and commands for other applications.

To use command files, administrators must create schedules with the ACTION=MACRO parameter. For example, you can define a schedule called DAILY_INCR that will process a command file called *c:\incr.cmd* on the client:

```
define schedule standard daily_incr description="daily incremental file"
action=macro objects="c:\incr.cmd" starttime=18:00 duration=5
durunits=minutes period=1 perunits=day dayofweek=any
```

Associate the client with the schedule and ensure that the scheduler is started on the client, application client, or Tivoli Data Protection host server directory. The schedule runs the file called *c:\incr.cmd* once a day between 6:00 p.m. and 6:05 p.m., every day of the week.

Updating the Client Options File to Automatically Generate a New Password

If the server uses password authentication, clients must use passwords. Passwords are then also required for the server to process scheduled operations for client nodes. If the password expires and is not updated, scheduled operations fail. You can prevent failed operations by allowing TSM to generate a new password when the current password expires. By including

the PASSWORDACCESS GENERATE option in the TSM client options file, you can ensure that the client always gets a new password when the old one expires.

The PASSWORDACCESS GENERATE option is also required in other situations, such as when you want to use the Web backup-archive client to access a client node. See the client user's guide for more information.

Comparing Tivoli Storage Manager Scheduling Across Operating Systems and Components

The TSM Scheduler provides the capability for the server to process scheduled operations. For client nodes running on operating systems other than Windows, the scheduler is installed when the backup-archive client or application client software is installed. The scheduler can be started by using the DSMC SCHEDULE command on the client's machine. For Windows NT and Windows 2000 clients, the TSM Scheduler service must be configured separately.

For more information about installing, configuring, and starting the TSM Scheduler, see *Tivoli Storage Manager Installing the Clients*.

The following table compares the scheduling environment across operating systems and components:

Component Type	Operating System	Scheduling Environment
Backup-Archive Client	UNIX, platforms other than Windows	The scheduler is installed as part of the client installation
Backup-Archive Client	Windows	The scheduler is installed but configured separately
Tivoli Data Protection for Oracle (application client)	AIX	The scheduler is installed as part of the client installation
Tivoli Data Protection for Oracle (application client)	HP-UX	The API must be installed
Tivoli Data Protection for Oracle Agent (application client)	Sun Solaris	The scheduler is installed as part of the client installation
Tivoli Data Protection for Microsoft Exchange (application client)	Windows	The scheduler is installed and configured separately
Tivoli Data Protection for SQL (application client)		
Tivoli Data Protection for Domino (application client)		
Tivoli Data Protection for Oracle (application client)		
Tivoli Data Protection for Lotus Notes™ (application client)	Windows	Uses the Lotus Notes scheduler
Tivoli Data Protection for Workgroups Host Server	Windows	The scheduler is installed and configured separately

Commands for Scheduling Client Operations

This section summarizes example commands that can be used for the scheduling tasks that are discussed in this chapter. See *Administrator's Reference* for server command details.

Define a schedule for a client:

```
define schedule engpoldom daily_backup starttime=21:00  
duration=2 durunits=hours
```

Associate a client with a schedule:

```
define association engpoldom weekly_backup engnode
```

On the client workstation, start the scheduler:

On most clients:

```
> dsmc schedule
```

On Windows NT and Windows 2000 clients:

```
> net start "TSM Scheduler"
```

Check the *Tivoli Storage Manager Installing the Clients* for details about automatically starting the scheduler and running the scheduler in the background.

Display schedule information:

```
query schedule engpoldom
```

Check to see if the schedule ran successfully:

```
query event engpoldom weekly_backup begindate=-7 begintime=now  
enddate=today endtime=now
```


15

Managing Schedules for Client Nodes

This chapter contains information about managing and coordinating TSM schedules for registered client nodes. For a description of what TSM views as client nodes, see “Adding Client Nodes” on page 189. For information about the TSM scheduler and creating schedules, see “Scheduling Operations for Client Nodes” on page 285.

Administrators can perform the following tasks:

Tasks:
“Managing Tivoli Storage Manager Schedules” on page 293
“Managing Node Associations with Schedules” on page 295
“Managing Event Records” on page 296
“Managing the Throughput of Scheduled Operations” on page 298
“Specifying One-Time Actions for Client Nodes” on page 304

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Managing Tivoli Storage Manager Schedules

You can perform the following activities to manage schedules.

Task	Required Privilege Class
Verify that the schedule ran	Any administrator
Add, copy, modify, or delete client schedules in any policy domain	System or unrestricted policy
Add, copy, modify, or delete client schedules for specific policy domains	System, unrestricted policy, or restricted policy for those domains
Display information about scheduled operations	Any administrator

Verifying that the Schedule Ran

You will want to ensure that all defined nodes completed their scheduled operations. You can check whether the schedules ran successfully by using the QUERY EVENT command. For information, see “Displaying Information about Scheduled Events” on page 296.

You can also check the log file described in “Checking the Schedule Log”.

Checking the Schedule Log

The TSM client stores detailed information about each scheduled event in a file. This file contains information such as the statistics about the backed-up objects, the name of the server to which the objects are backed up, and the time and date of the next scheduled operation.

The default name for this file is *dsmsched.log*. The file is located in the directory where the TSM backup-archive client is installed. You can override this file name and location by specifying the SCHEDLOGNAME option in the client options file. See the client user’s guide for more information.

Adding New Schedules

You can add new TSM schedules by using the DEFINE SCHEDULE command. After you add a new schedule, associate the node with the schedule. For more information, see “Defining Client Schedules” on page 286.

Copying Existing Schedules

You can create new schedules by copying existing schedules to the same policy domain or a different policy domain. The schedule description and all schedule parameter values are copied to the new schedule. You can then modify the new schedule to meet site-specific requirements.

Client node associations are not copied to the new schedule. You must associate client nodes with the new schedule before it can be used. The associations for the old schedule are not changed. For information, see “Associating Client Nodes with Schedules” on page 287.

To copy the WINTER schedule from policy domain DOMAIN1 to DOMAIN2 and name the new schedule WINTERCOPY, enter:

```
copy schedule domain1 winter domain2 wintercopy
```

Modifying Schedules

You can modify existing schedules by using the UPDATE SCHEDULE command. For example, to modify the ENGWEEKLY client schedule in the ENGPOLDOM policy domain, enter:

```
update schedule engpoldom engweekly period=5 perunits=days
```

The ENGWEEKLY schedule is updated so that the incremental backup period is now every five days.

Deleting Schedules

When you delete a schedule, TSM deletes all client node associations for that schedule. See “Associating Client Nodes with Schedules” on page 287 for more information.

To delete the schedule WINTER in the ENGPOLDOM policy domain, enter:

```
delete schedule engpoldom winter
```

Rather than delete a schedule, you may want to remove all nodes from the schedule and save the schedule for future use. For information, see “Removing Nodes from Schedules” on page 296.

Displaying Information about Schedules

When you request information about schedules, the server displays the following information:

- Schedule name
- Policy domain name
- Type of operation to be performed
- Start date and time for the initial startup window
- Duration of the startup window
- Time period between startup windows
- Day of the week on which scheduled operations can begin

The following output shows an example of a report that is displayed after you enter:

```
query schedule engpoldom
```

Domain	* Schedule Name	Action	Start Date/Time	Duration	Period	Day
ENGPOLODOM	MONTHLY_BACKUP	Inc Bk	07/21/1998 12:45:14	2 H	2 Mo	Sat
ENGPOLODOM	WEEKLY_BACKUP	Inc Bk	07/21/1998 12:46:21	4 H	1 W	Sat

Managing Node Associations with Schedules

You can add and delete node associations from schedules. Nodes can be associated with more than one schedule.

You can perform the following activities to manage associations of client nodes with schedules.

Task	Required Privilege Class
Add new nodes to existing schedules	System or restricted policy over the domain to which the node is assigned
Move nodes to existing schedules	System or restricted policy over the domain to which the node is assigned
Delete nodes associated with a schedule	System or restricted policy over the domain to which the node is assigned
Display nodes associated with a specific schedule	Any administrator

Adding New Nodes to Existing Schedules

You can add new nodes to existing schedules by associating the node with the schedule. To associate client nodes with a schedule, you can use the administrative Web interface or you can issue the DEFINE ASSOCIATION command from the command line interface. For information, see “Associating Client Nodes with Schedules” on page 287.

Moving Nodes from One Schedule to Another

You can move a node from one schedule to another schedule by:

1. Associating the node to the new schedule. For information, see “Associating Client Nodes with Schedules” on page 287.
2. Deleting the association of that node from the original schedule. For information, see “Removing Nodes from Schedules” on page 296.

Displaying Nodes Associated with Schedules

You can display information about the nodes that are associated with a specific schedule. For example, you should query an association before deleting a client schedule.

Figure 49 shows the report that is displayed after you enter:
query association engpoldom

```
Policy Domain Name: ENGPOLDOM
Schedule Name: MONTHLY_BACKUP
Associated Nodes: MAB_SSTEINER

Policy Domain Name: ENGPOLDOM
Schedule Name: WEEKLY_BACKUP
Associated Nodes: MAB_SSTEINER
```

Figure 49. Query Association Output

Removing Nodes from Schedules

When you remove the association of a node to a client schedule, the client no longer runs operations specified by the schedule. However, the remaining client nodes still use the schedule.

To delete the association of the ENGNOD client with the ENGWEEKLY schedule, in the policy domain named ENGPOLDOM, enter:

```
delete association engpoldom engweekly engnod
```

Rather than delete a schedule, you may want to delete all associations to it and save the schedule for possible reuse in the future.

Managing Event Records

Each scheduled client operation is called an *event*. All scheduled events, including their status, are tracked by the server. An *event record* is created in the server database whenever a scheduled event is completed or missed.

You can perform the following activities to manage event records:

Task	Required Privilege Class
Display information about scheduled events	Any administrator
Set the retention period for event records	System
Delete event records	System or unrestricted policy

Displaying Information about Scheduled Events

To help manage schedules for client operations, you can request information about scheduled and completed events by using the QUERY EVENT command.

- To get information about past and projected scheduled processes, use a simple query for events. If the time range you specify includes the future, the results show which events should occur in the future based on current schedules.
- To get information about scheduled processes that did not complete successfully, use the exceptions-only option with the query.

To minimize the processing time when querying events:

- Minimize the time range
- For client schedules, restrict the query to those policy domains, schedules, and client node names for which information is required

Displaying All Client Schedule Events

You can display information about all client events by issuing the `QUERY EVENT` command. The information includes events for both successful and failed schedules. If the administrator specifies a time range that includes the future, TSM displays future events with a status of *future*.

Figure 50 shows an example of a report for client node `GOODELL` that is displayed after you enter:

```
query event standard weekly_backup node=goode11 enddate=today+7
```

Scheduled Start	Actual Start	Schedule Name	Node Name	Status
03/09/1998 06:40:00	03/09/1998 07:38:09	WEEKLY_BACKUP	GOODELL	Started
03/16/1998 06:40:00		WEEKLY_BACKUP	GOODELL	Future

Figure 50. Events for a Node

Displaying Events that Ended Unsuccessfully

You can display information about scheduled events that ended unsuccessfully by using exception reporting. For example, you can issue the following command to find out which events were missed in the previous 24 hours, for the `DAILY_BACKUP` schedule in the `STANDARD` policy domain:

```
query event standard daily_backup begindate=-1 begintime=now
enddate=today endtime=now exceptionsonly=yes
```

Figure 51 on page 298 shows an example of the results of this query. To find out why a schedule was missed or failed, you may need to check the schedule log on the client node itself. For example, a schedule can be missed because the scheduler was not started on the client node.

Scheduled Start	Actual Start	Schedule Name	Node Name	Status
03/06/1998 20:30:00		DAILY_BACKUP	ANDREA	Missed
03/06/1998 20:30:00		DAILY_BACKUP	EMILY	Missed

Figure 51. Exception Report of Events

Displaying Past Events

If you query the server for events, the server may display past events even if the event records have been deleted. Such events are displayed with a status of *Uncertain*, indicating that complete information is not available because the event records have been deleted. To determine if event records have been deleted, check the message that is issued after the DELETE EVENT command is processed.

Managing Event Records in the Server Database

By default, the server retains event records for 10 days before automatically removing them from the database. The server automatically deletes event records from the database after the event retention period has passed and after the startup window for the event has elapsed.

You can specify how long event records stay in the database before the server automatically deletes them by using the SET EVENTRETENTION command. You can also manually delete event records from the database, if database space is required.

Setting the Event Retention Period

You can modify the retention period for event records in the database. To change the retention period to 15 days, enter:

```
set eventretention 15
```

Manually Deleting Event Records

You may want to manually delete event records to increase available database space. For example, to delete all event records written prior to 11:59 p.m. on June 30, 2000, enter:

```
delete event 06/30/2000 23:59
```

Managing the Throughput of Scheduled Operations

In the Tivoli Storage Manager environment where many nodes attempt to initiate scheduled operations simultaneously, you may have to manage scheduling throughput. You can choose a scheduling mode and you can control how often client nodes contact the server to perform a scheduled operation.

Administrators can perform the following activities to manage the throughput of scheduled operations.

Task	Required Privilege Class
Modify the default scheduling mode	System
Modify the scheduling period for incremental backup operations	System
Balance the scheduled workload for the server	System

Task	Required Privilege Class
Set the frequency at which client nodes contact the server	System

Modifying the Default Scheduling Mode

TSM provides two scheduling modes: *client-polling* and *server-prompted*. The mode indicates how client nodes interact with the server for scheduling operations. With client-polling mode, client nodes poll the server for the next scheduled event. With server-prompted mode, the server contacts the nodes at the scheduled start time.

By default, the server permits both scheduling modes. The default (ANY) allows nodes to specify either scheduling mode in their client options files. You can modify this scheduling mode.

If you modify the default server setting to permit only one scheduling mode, *all* client nodes must specify the same scheduling mode in their client options file. Clients that do not have a matching scheduling mode will not process the scheduled operations. The default mode for client nodes is client-polling.

The scheduler must be started on the client node's machine before a schedule can run in either scheduling mode.

For more information about modes, see "Overview of Scheduling Modes".

Overview of Scheduling Modes

With client-polling mode, client nodes poll the server for the next scheduled event. With server-prompted mode, the server contacts the nodes at the scheduled start time. See Table 24 on page 300 and Table 23.

Table 23. Client-Polling Mode

How the mode works	Advantages and disadvantages
<ol style="list-style-type: none"> 1. A client node queries the server at prescribed time intervals to obtain a schedule. This interval is set with a client option, <code>QUERYSCHEDPERIOD</code>. For information about client options, refer to the appropriate <i>Using the Backup-Archive Client</i>. 2. At the scheduled start time, the client node performs the scheduled operation. 3. When the operation completes, the client sends the results to the server. 4. The client node queries the server for its next scheduled operation. 	<ul style="list-style-type: none"> ■ Useful when a high percentage of clients start the scheduler manually on a daily basis, for example when their workstations are powered off nightly. ■ Supports <i>randomization</i>, which is the random distribution of scheduled start times. The administrator can control randomization. By randomizing the start times, TSM prevents all clients from attempting to start the schedule at the same time, which could overwhelm server resources. ■ Valid with all communication methods.

Table 24. Server-Prompted Mode

How the mode works	Advantages and disadvantages
<ol style="list-style-type: none">1. The server contacts the client node when scheduled operations need to be performed and a server session is available.2. When contacted, the client node queries the server for the operation, performs the operation, and sends the results to the server.	<ul style="list-style-type: none">■ Useful if you change the schedule start time frequently. The new start time is implemented without any action required from the client node.■ Useful when a high percentage of clients are running the scheduler and are waiting for work.■ Does not allow for randomization of scheduled start times.■ Valid only with client nodes that use TCP/IP to communicate with the server.

Modifying the Scheduling Mode on the Server

If you modify the default so that the server permits only one scheduling mode for the server, all clients must specify the same scheduling mode in their client options file. Clients that do not have a matching scheduling mode do not process scheduled operations.

Client-Polling Scheduling Mode: To have clients poll the server for scheduled operations, enter:

```
set schedmodes polling
```

Ensure that client nodes specify the same mode in their client options files.

Server-Prompted Scheduling Mode: To have the server prompt clients for scheduled operations, enter:

```
set schedmodes prompted
```

Ensure that client nodes specify the same mode in their client options files.

Any Scheduling Mode: To return to the default scheduling mode so that the server supports both client-polling and server-prompted scheduling modes, enter:

```
set schedmodes any
```

Client nodes can then specify either polling or prompted mode.

Modifying the Default Scheduling Mode on Client Nodes

Users set the scheduling mode on client nodes. They specify either the client-polling or the server-prompted scheduling mode on the command line or in the client user options file. (On UNIX systems, root users set the scheduling mode in the client system options file.)

For more information, refer to the appropriate *Using the Backup-Archive Client*.

Specifying the Schedule Period for Incremental Backup Operations

When you define a backup copy group, you specify the copy frequency, which is the minimum interval between successive backups of a file. When you define a schedule, you specify the length of time between processing of the schedule. Consider how these interact to ensure that the clients get the backup coverage that you intend.

See “Defining and Updating a Backup Copy Group” on page 255.

Balancing the Scheduled Workload for the Server

You can control the server’s workload and ensure that the server can perform all scheduled operations within the specified window. To enable the server to complete all schedules for clients, you may need to use trial and error to control the workload. To estimate how long client operations take, test schedules on several representative client nodes. Keep in mind, for example, that the first incremental backup for a client node takes longer than subsequent incremental backups.

You can balance the server’s scheduled workload by:

- Adjusting the number of sessions that the server allocates to scheduled operations
- Randomizing scheduled start time for client operations (if clients use client-polling scheduling mode)
- Increasing the length of the startup window

Setting the Number of Sessions the Server Allocates to Scheduled Operations

The maximum number of concurrent client/server sessions is defined by the MAXSESSIONS server option. Of these sessions, you can set a maximum percentage to be available for processing scheduled operations. Limiting the number of sessions available for scheduled operations ensures that sessions are available when users initiate any unscheduled operations, such as restoring file or retrieving files.

If the number of sessions for scheduled operations is insufficient, you can increase either the total number of sessions or the maximum percentage of scheduled sessions. However, increasing the total number of sessions can adversely affect server performance. Increasing the maximum percentage of scheduled sessions can reduce the server availability to process unscheduled operations.

For example, assume that the maximum number of sessions between client nodes and the server is 80. If you want 25% of these sessions to be used by for scheduled operations, enter:

```
set maxschedsessions 25
```

The server then allows a maximum of 20 sessions to be used for scheduled operations.

The following table shows the tradeoffs of using either the SET MAXSCHEDESESSIONS command or the MAXSESSIONS server option.

An administrator can...	Using...	With the result
Increase the total number of sessions	MAXSESSIONS server option	May adversely affect the server’s performance
Increase the total number of sessions allocated to scheduled operations	SET MAXSCHEDESESSIONS command	May reduce the server’s ability to process unscheduled operations

For information about the MAXSESSIONS option and the SET MAXSCHEDESESSIONS command, refer to *Administrator’s Reference*.

Randomizing Schedule Start Times

To randomize start times for schedules means to scatter each schedule's start time across its startup window. A startup window is defined by the start time and duration during which a schedule must be initiated. For example, if the start time is 1:00 a.m. and the duration is 4 hours, the startup window is 1:00 a.m. to 5:00 a.m.

For the client-polling scheduling mode, you can specify the percentage of the startup window that the server can use to randomize start times for different client nodes associated with a schedule.

If you set randomization to 0, no randomization occurs. This process can result in communication errors if many client nodes try to contact the server at the same instant.

The settings for randomization and the maximum percentage of scheduled sessions can affect whether schedules are successfully completed for client nodes. Users receive a message if all sessions are in use when they attempt to process a schedule. If this happens, you can increase randomization and the percentage of scheduled sessions allowed to make sure the server can handle the workload. The maximum percentage of randomization allowed is 50%. This limit ensures that half of the startup window is available for retrying scheduled commands that have failed.

To set randomization to 50%, enter:

```
set randomize 50
```

It is possible, especially after a client node or the server has been restarted, that a client node may not poll the server until *after* the beginning of the startup window in which the next scheduled event is to start. In this case, the starting time is randomized over the specified percentage of the *remaining* duration of the startup window.

Consider the following situation:

- The schedule start time is 8:00 a.m. and its duration is 1 hour. Therefore the startup window for the event is from 8:00 to 9:00 a.m.
- Ten client nodes are associated with the schedule.
- Randomization is set to 50%.
- Nine client nodes poll the server before 8:00 a.m.
- One client node does not poll the server until 8:30 a.m.

The result is that the nine client nodes that polled the server *before* the beginning of the startup window are assigned randomly selected starting times between 8:00 and 8:30. The client node that polled at 8:30 receives a randomly selected starting time that is between 8:30 and 8:45.

Increasing the Length of the Schedule Startup Window

Increasing the size of the startup window (by increasing the schedule's duration) can also affect whether a schedule completes successfully. A larger startup window gives the client node more time to attempt initiation of a session with the server.

Controlling How Often Client Nodes Contact the Server

To control how often client nodes contact the server to perform a scheduled operation, an administrator can set:

- How often nodes query the server (see "Setting How Often Clients Query the Server" on page 303)

- The number of command retry attempts (see “Setting the Number of Command Retry Attempts”)
- The amount of time between retry attempts (see “Setting the Amount of Time between Retry Attempts” on page 304)

Users can also set these values in their client user options files. (Root users on UNIX systems set the values in client system options files.) However, user values are overridden by the values that the administrator specifies on the server.

The communication paths from client node to server can vary widely with regard to response time or the number of gateways. In such cases, you can choose *not* to set these values so that users can tailor them for their own needs.

Setting How Often Clients Query the Server

When scheduling client nodes with client-polling scheduling, you can specify how often the nodes query the server for a schedule. If nodes poll frequently for schedules, changes to scheduling information (through administrator commands) are propagated more quickly to the nodes. However, increased polling by client nodes also increases network traffic.

For the client-polling scheduling mode, you can specify the maximum number of hours that the scheduler on a client node waits between attempts to contact the server to obtain a schedule. You can set this period to correspond to the frequency with which the schedule changes are being made. If client nodes poll more frequently for schedules, changes to scheduling information (through administrator commands) are propagated more quickly to client nodes.

If you want to have all clients using polling mode contact the server every 24 hours, enter:

```
set queryschedperiod 24
```

| This setting has no effect on clients that use the server-prompted scheduling mode.

| The clients also have a QUERYSCHEDPERIOD option that can be set on each client. The
| server value overrides the client value once the client successfully contacts the server.

Setting the Number of Command Retry Attempts

You can specify the maximum number of times the scheduler on a client node can retry a scheduled command that fails.

The maximum number of command retry attempts does not limit the number of times that the client node can contact the server to obtain a schedule. The client node never gives up when trying to query the server for the next schedule.

Be sure not to specify so many retry attempts that the total retry time is longer than the average startup window.

If you want to have all client schedulers retry a failed attempt to process a scheduled command up to two times, enter:

```
set maxcmdretries 2
```

| Maximum command retries can also be set on each client with a client option,
| MAXCMDRETRIES. The server value overrides the client value once the client successfully
| contacts the server.

Setting the Amount of Time between Retry Attempts

You can specify the length of time that the scheduler waits between command retry attempts. Command retry attempts occur when a client node is unsuccessful in establishing a session with the server or when a scheduled command fails to process. Typically, this setting is effective when set to half of the estimated time it takes to process an average schedule.

If you want to have the client scheduler retry every 15 minutes any failed attempts to either contact the server or process scheduled commands, enter:

```
set retryperiod 15
```

You can use this setting in conjunction with the SET MAXCMDRETRIES command (number of command retry attempts) to control when a client node contacts the server to process a failed command. See “Setting the Number of Command Retry Attempts” on page 303.

The retry period can also be set on each client with a client option, RETRYPERIOD. The server value overrides the client value once the client successfully contacts the server.

Specifying One-Time Actions for Client Nodes

You can use the DEFINE CLIENTACTION command to specify that one or more client nodes perform a one-time action if the client schedulers are active. If the scheduling mode is set to prompted, the client performs the action within 3 to 10 minutes. If the scheduling mode is set to polling, the client processes the command at its prescribed time interval. The time interval is set by the QUERYSCHEDPERIOD client option.

The DEFINE CLIENTACTION command causes TSM to automatically define a schedule and associate client nodes with that schedule. The schedule name and association information is returned to the server console or the administrative client with messages ANR2500I and ANR2510I. With the schedule name provided, you can later query or delete the schedule and associated nodes. The names of one-time client action schedules can be identified by a special character followed by numerals, for example @1.

For example, you can issue a DEFINE CLIENTACTION command that specifies an incremental backup command for client node HERMIONE in domain ENGPOLDOM:

```
define clientaction hermione domain=engpoldom action=incremental
```

TSM defines a schedule and associates client node HERMIONE with the schedule. The server assigns the schedule priority 1, sets the period units (PERUNITS) to ONETIME, and determines the number of days to keep the schedule active based on the value set with SET CLIENTACTDURATION command.

For a list of valid actions, see the DEFINE CLIENTACTION command in *Administrator's Reference*. You can optionally include the OPTIONS and OBJECTS parameters.

Determining How Long the One-Time Schedule Remains Active

You can determine how long schedules that were defined via DEFINE CLIENTACTION commands remain active by using the SET CLIENTACTDURATION command. This command allows you to specify the number of days that schedules that were created with the DEFINE CLIENTACTION command are active. These schedules are automatically

removed from the database whether the associated nodes have processed the schedule or not, after the specified number of days. The following example specifies that schedules for client actions be active for 3 days:

```
set clientactduration 3
```

| If the duration of client actions is set to zero, the server sets the DURUNITS parameter
| (duration units) as indefinite for schedules defined with DEFINE CLIENTACTION
| command. The indefinite setting for DURUNITS means that the schedules are not deleted
| from the database.

IV — Maintaining the Server

16

Working with a Network of Tivoli Storage Manager Servers

You may have a number of TSM servers in your network, at the same or different locations. TSM provides functions to help you configure, manage, and monitor the servers connected to a network. An administrator working at one TSM server can work with TSM servers at other locations around the world.

See the following sections:

Concepts:
“Concepts for Working with a Network of Servers”
Tasks:
“Planning for Enterprise Administration” on page 313
“Setting Up Communications Among Servers” on page 314
“Setting Up an Enterprise Configuration” on page 321
“Performing Tasks on Multiple Servers” on page 342
“Using Virtual Volumes to Store Data on Another Server” on page 348

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Concepts for Working with a Network of Servers

To manage a network of servers, you can use the following capabilities of Tivoli Storage Manager:

- Configure and manage multiple servers with enterprise configuration.
Distribute a consistent configuration for TSM servers through a configuration manager to managed servers. By having consistent configurations, you can simplify the management of a large number of servers and clients.
- Perform tasks on multiple servers by using command routing, enterprise logon, and enterprise console.
- Send server and client events to another server for logging.
- Monitor many servers and clients from a single server.

-
- Store data on another server using virtual volumes.

In a network of TSM servers, a server can play a number of different roles. For example, a server may send volumes to be archived on another server and also receive routed commands from another server. In the following descriptions, when a server sends data it is sometimes referred to as a *source server*, and when a server receives data it is sometimes referred to as a *target server*. In other words, one TSM server may be both a source and a target server. At the same time, any TSM server can still provide backup, archive, and space management services to clients.

Configuring and Managing Servers: Enterprise Configuration

The enterprise configuration functions of the Tivoli Storage Manager make it easier to consistently set up and manage a network of TSM servers. You set up configurations on one server and distribute the configurations to the other servers. You can make changes to configurations and have the changes automatically distributed.

Figure 52 on page 311 illustrates a simple configuration. To use enterprise configuration, you first select the TSM server that is to act as the *configuration manager*. You may want to dedicate a new server for this purpose. At the configuration manager, you define the details of the server configurations that you want to distribute. For example:

- You set up backup and archive policies and client option sets
- You designate one or more administrators to have access to the servers, and control their authority levels
- You define the servers that you want the configuration manager to manage or communicate with, and you set up communications among the servers

In one or more *profiles*, you point to the definitions of the configuration information that you want to use to manage other servers.

On each server that is to receive the configuration information, you identify the server as a *managed server* by defining a *subscription* to one or more profiles owned by the configuration manager. All the definitions associated with the profiles are then copied into the managed server's database. Things defined to the managed server in this way are managed objects that cannot be changed by the managed server. From then on, the managed server gets any changes to the managed objects from the configuration manager via the profiles. Managed servers receive changes to configuration information at time intervals set by the servers, or by command.

See “Setting Up an Enterprise Configuration” on page 321 for details.




Figure 52. Enterprise Configuration

Performing Tasks on Multiple Servers

When you connect to the configuration manager via a Web browser, you are presented with the *enterprise console*. From the enterprise console you can perform tasks on the configuration manager and on one or more of the managed servers. You can also connect to another server to perform tasks directly on that server. As long as you are registered with the same administrator ID and password, you can do this work on many servers without having to log on each time. See “Using Tivoli Storage Manager Enterprise Logon” on page 343.

From the command line of the administrative Web interface or from the command-line administrative client, you can also route commands to other servers. The other servers must be defined to the server to which you are connected. You must also be registered on the other servers as an administrator with the administrative authority that is required for the command. See “Routing Commands” on page 343.

To make routing commands easier, you can define a server group that has servers as members. See “Setting Up Server Groups” on page 345. Commands that you route to a server group are sent to all servers in the group.

Central Monitoring

TSM provides you with several ways to centrally monitor the activities of a server network:

- Enterprise event logging, in which events are sent from one or more of servers to be logged at an event server. See “Enterprise Event Logging: Logging Events to Another Server” on page 428 for a description of the function and “Setting Up Communications for Enterprise Configuration and Enterprise Event Logging” on page 314 for communications set up.

-
- Allowing designated administrators to log in to any of the servers in the network with a single user ID and password. See “Using Tivoli Storage Manager Enterprise Logon” on page 343.
 - Routing query commands to one or more of the servers in the network. See “Routing Commands to One or More Servers” on page 344 for a description of the function and “Setting Up Communications for Enterprise Configuration and Enterprise Event Logging” on page 314 for communications set up.

Storing Data on Another Server

TSM lets one server store data in and retrieve data from the storage pool of another server. This data, stored as *virtual volumes*, can include database and storage pool backups, disaster recovery plan files, and data that is directly backed up, archived, or space managed from client nodes. The data can also be a recovery plan file created by using Tivoli Disaster Recovery Manager (DRM). The source server is a client of the target server, and the data for the source server is managed only by the source server. In other words, the source server controls the expiration and deletion of the files that comprise the virtual volumes on the target server.

To use virtual volumes to store database and storage pool backups and recovery plan files, you must have the Tivoli Disaster Recovery Manager product and register a license for its use. See “Licensing Tivoli Storage Manager” on page 355.

For information on using virtual volumes with DRM, see “Using Tivoli Disaster Recovery Manager” on page 497.

Example Scenarios

The functions for managing multiple servers can be applied in many ways. Here are just two scenarios to give you some ideas about how you can put the functions to work for you:

- Setting up and managing TSM servers primarily from one location. For example, an administrator at one location controls and monitors servers at several locations.
- Setting up a group of TSM servers from one location, and then managing the servers from any of the servers. For example, several administrators are responsible for maintaining a group of servers. One administrator defines the configuration information on one server for distributing to servers in the network. Administrators on the individual servers in the network manage and monitor the servers.

Managing Tivoli Storage Manager Servers from One Location

Enterprise management allows you to set up and manage the servers in your network from one location, the enterprise console. For example, suppose you are an administrator responsible for TSM servers at your own location plus servers at branch office locations. Servers at each location have similar storage resources and client requirements. You can set up the environment as follows:

- Set up an existing or new TSM server as a configuration manager.
- Set up communications so that a configuration manager can send commands to its managed servers.
- Define the configuration you want to distribute by defining policy domains, schedules, and so on. Associate the configuration information with profiles.
- Have the managed servers subscribe to profiles.
- Activate policies and set up storage pools as needed on the managed servers.

- Set up enterprise monitoring by setting up one server as an event server. The event server can be the same server as the configuration manager or a different server.

After you complete the setup, you can manage many servers as if there was just one. You can do any of the following tasks:

- Have administrators that can manage the group of servers from anywhere in the network by using the enterprise console, an interface available through a Web browser.
- Have consistent policies, schedules, and client option sets on all servers.
- Make changes to configurations and have the changes automatically distributed to all servers. Allow local administrators to monitor and tune their own servers.
- Perform tasks on any server or all servers by using command routing from the enterprise console.
- Back up the databases of the managed servers on the automated tape library that is attached to the server that is the configuration manager. You use virtual volumes to accomplish this.
- Log on to individual servers from the enterprise console without having to re-enter your password, if your administrator ID and password are the same on each server.

Managing Servers from Any Server

Enterprise management allows you to manage the servers in your network from many locations. For example, suppose you are an administrator responsible for servers located in different departments on a college campus. The servers have some requirements in common, but also have many unique client requirements. You can set up the environment as follows:

- Set up an existing or new TSM server as a configuration manager.
- Set up communications so that commands can be sent from any server to any other server.
- Define any configuration that you want to distribute by defining policy domains, schedules, and so on, on the configuration manager. Associate the configuration information with profiles.
- Have the managed servers subscribe to profiles as needed.
- Activate policies and set up storage pools as needed on the managed servers.
- Set up enterprise monitoring by setting up one server as an event server. The event server can be the same server as the configuration manager or a different server.

After setting up in this way, you can manage the servers from any server. You can do any of the following tasks:

- Use enterprise console to monitor all the servers in your network.
- Perform tasks on any or all servers using the enterprise console and command routing.
- Manage the group of servers from anywhere in the network. Allow local administrators to monitor and tune their own servers.

Planning for Enterprise Administration

To take full advantage of the functions of Enterprise Administration, you should decide on the following:

-
- The servers you want to include in the enterprise network. The servers must have unique names.
 - The server or servers from which you want to manage the network. Servers can have multiple roles. For example, one server can act as a server for backup-archive clients, as the configuration manager, and as the event server. You can also set up separate servers to fill each of these roles.
 - Whether you want administrators to have the ability to route commands to other servers. If you want administrators to route commands, decide on the servers from which and to which commands will be routed.
 - The administrator activities you want to be centrally managed.
 - The authority level of the administrators and the servers to which they should have access.

Setting Up Communications Among Servers

This section describes how to set up communications for enterprise configuration, enterprise event logging, and command routing. Communication set up for Server-to-server Virtual Volumes is described in “Setting Up Source and Target Servers for Virtual Volumes” on page 349.

When you set up communications among servers for any purpose, ensure that servers have unique names. At installation, a TSM server has the name “TSM”. Change the server name to a unique name before setting up communication with other servers. For example, enter this command to name the server TUCSON:

```
set servername tucson
```

Setting Up Communications for Enterprise Configuration and Enterprise Event Logging

The communication setup for enterprise configuration and enterprise event logging, which is through TCP/IP, is identical. The examples shown here apply to both functions. If you are set up for one, you are set up for the other. However, be aware that the configuration manager and event server are not defined simply by setting up communications. You must identify a server as a configuration manager (SET CONFIGMANAGER command) or an event server (DEFINE EVENTSERVER command). Furthermore, a configuration manager and an event server can be the same server or different servers.

Enterprise configuration

Each managed server must be defined to the configuration manager, and the configuration manager must be defined to each managed server.

Enterprise event logging

Each server sending events to an event server must be defined to the event server, and the event server must be defined to each source server.

The following examples of setting up communications could be used to create these configurations:

- A server named HEADQUARTERS as a configuration manager and two servers, MUNICH and STRASBOURG, as managed servers.
- HEADQUARTERS as an event server and MUNICH and STRASBOURG as source servers.

For a pair of servers to communicate with each other, each server must be defined to the other. For example, if a configuration manager manages three managed servers, there are three server pairs. You can issue separate definitions from each server in each pair, or you can “cross define” a pair in a single operation. Cross definition can be useful in large or complex networks. The following scenarios and accompanying figures illustrate the two methods.

Using separate definitions — Follow this sequence:

1. **On MUNICH:** Specify the server name and password of MUNICH.
On STRASBOURG: Specify the server name and password of STRASBOURG.
On HEADQUARTERS: Specify the server name and password of HEADQUARTERS.
2. **On HEADQUARTERS:** Define MUNICH (whose password is BERYL and whose address is 9.115.2.223:1919) and STRASBOURG (whose password is FLUORITE and whose address is 9.115.2.178:1715).
On MUNICH and STRASBOURG: Define HEADQUARTERS (whose password is AMETHYST and whose address is 9.115.4.177:1823).

Figure 53 shows the servers and the commands issued on each:




Figure 53. Communication Configuration with Separate Server Definitions

Using Cross Definitions — Follow this sequence:

1. **On MUNICH:** Specify the server name, password, and high and low level addresses of MUNICH. Specify that cross define is permitted.

On STRASBOURG: Specify the server name, password, and high and low level addresses of STRASBOURG. Specify that cross define is permitted.

On HEADQUARTERS: Specify the server name, password, and high and low level addresses of HEADQUARTERS.

2. **On HEADQUARTERS:** Define MUNICH and STRASBOURG, specifying that cross define should be done.

Figure 54 shows the servers and the commands issued on each:




Figure 54. Communication Configuration with Cross Definition

Communication Security

Security for this communication configuration is enforced through the exchange of passwords (which are encrypted) and, in the case of enterprise configuration only, verification keys. Communication among servers, which is through TCP/IP, requires that the servers verify server passwords (and verification keys). For example, assume that HEADQUARTERS begins a session with MUNICH:

1. HEADQUARTERS, the source server, identifies itself by sending its name to MUNICH.
2. The two servers exchange verification keys (enterprise configuration only).

-
3. HEADQUARTERS sends its password to MUNICH, which verifies it against the password stored in its database.
 4. If MUNICH verifies the password, it sends its password to HEADQUARTERS, which, in turn, performs password verification.

Note: If another server named MUNICH tries to contact HEADQUARTERS for enterprise configuration, the attempt will fail. This is because the verification key will not match. If MUNICH was moved or restored, you can issue the UPDATE SERVER command with the FORCERESYNC parameter to override the condition.

Setting Up Communications for Command Routing

This section describes how to set up communications for command routing. You must define the target servers to the source servers, and the same administrator must be registered on all servers. Using enterprise configuration, you can easily distribute the administrator information to all the servers.

Note: You must be registered as an administrator with the same name and password on the source server and all target servers. The privilege classes do not need to be the same on all servers. However, to successfully route a command to another server, an administrator must have the minimum required privilege class for that command on the server from which the command is being issued.

For command routing in which one server will always be the sender, you would only define the target servers to the source server. If commands can be routed from any server to any other server, each server must be defined to all the others.

Only One Source Server

The example in this section shows how to set up communications for administrator HQ on the server HEADQUARTERS who will route commands to the servers MUNICH and STRASBOURG. Administrator HQ has the password SECRET and has system privilege class. Here is the procedure:

- **On HEADQUARTERS:** register administrator HQ and specify the server names and addresses of MUNICH and STRASBOURG:

```
register admin hq secret
grant authority hq classes=system

define server munich haddress=9.115.2.223 laddress=1919
define server strasbourg haddress=9.115.2.178 laddress=1715
```

- **On MUNICH and STRASBOURG** Register administrator HQ with the required privilege class on each server:

```
register admin hq secret
grant authority hq classes=system
```

Note: If your server network is using enterprise configuration, you can automate the preceding operations. You can distribute the administrator and server lists to MUNICH and STRASBOURG. In addition, all server definitions and server groups are distributed by default to a managed server when it first subscribes to any profile on a configuration manager. Therefore, it receives all the server definitions that exist on the configuration manager, thus enabling command routing among the servers.

Multiple Source Servers

The examples in this section show how to set up communications if the administrator, HQ, can route commands from any of the three servers to any of the other servers. You must define all the servers to each other. You can separately define each server to each of the other servers, or you can “cross define” the servers. In cross definition, defining MUNICH to HEADQUARTERS also results in automatically defining HEADQUARTERS to MUNICH.

Separate Definitions

Follow this sequence:

1. **On MUNICH:** Specify the server name and password of MUNICH. Register administrator HQ and grant HQ system authority.
On STRASBOURG: Specify the server name and password of STRASBOURG. Register administrator HQ and grant HQ system authority.
On HEADQUARTERS: Specify the server name and password of HEADQUARTERS. Register administrator HQ and grant HQ system authority.
2. **On HEADQUARTERS:** Define MUNICH (whose password is BERYL and whose address is 9.115.2.223:1919) and STRASBOURG (whose password is FLUORITE and whose address is 9.115.2.178:1715).
On MUNICH: Define HEADQUARTERS (whose password is AMETHYST and whose address is 9.115.4.177:1823) and STRASBOURG.
On STRASBOURG: Define HEADQUARTERS and MUNICH.

Figure 55 on page 319 shows the servers and the commands issued on each:




Figure 55. Communication Configuration with Separate Server Definitions

Cross Definitions

Follow this sequence:

- On MUNICH:** Specify the server name, password, and high and low level addresses of MUNICH. Specify that cross define is permitted. Register administrator HQ and grant HQ system authority.

On STRASBOURG: Specify the server name, password, and high and low level addresses of STRASBOURG. Specify that cross define is permitted. Register administrator HQ and grant HQ system authority.

On HEADQUARTERS: Specify the server name, password, and high and low level addresses of HEADQUARTERS. Register administrator HQ and grant HQ system authority.
- On HEADQUARTERS:** Define MUNICH and STRASBOURG, specifying that cross define should be done.

3. **On MUNICH:** Define STRASBOURG, specifying that cross define should be done.

Note: If your server network is using enterprise configuration, you can automate the preceding operations. You can distribute the administrator lists and server lists to MUNICH and STRASBOURG. In addition, all server definitions and server groups are distributed by default to a managed server when it first subscribes to any profile on a configuration manager. Therefore, it receives all the server definitions that exist on the configuration manager, thus enabling command routing among the servers.

Figure 56 shows the servers and the commands issued on each:




Figure 56. Communication Configuration with Cross Definitions

Updating and Deleting Servers

You can update a server definition by issuing the UPDATE SERVER command.

- For Server-to-server Virtual Volumes:
 - If you update the node name, you must also update the password.
 - If you update the password but not the node name, the node name defaults to the server name specified by the SET SERVERNAME command.
- For enterprise configuration and enterprise event logging: If you update the server password, it must match the password specified by the SET SERVERPASSWORD command at the target server.
- For enterprise configuration: When a server is first defined at a managed server, that definition cannot be replaced by a server definition from a configuration manager. This prevents the definition at the managed server from being inadvertently replaced. Such a replacement could disrupt functions that require communication among servers, for example command routing or virtual volumes.

To allow replacement, update the definition at the managed server by issuing the UPDATE SERVER command with the ALLOWREPLACE=YES parameter. When a configuration manager distributes a server definition, the definition always includes the ALLOWREPLACE=YES parameter.

You can delete a server definition by issuing the DELETE SERVER command. For example, to delete the server named NEWYORK, enter the following:

```
delete server newyork
```

The deleted server is also deleted from any server groups of which it is a member. See “Setting Up Server Groups” on page 345 for information about server groups.

You cannot delete a server if either of the following conditions is true:

- The server is defined as an event server.

You must first issue the DELETE EVENTSERVER command.
- The server is a target server for virtual volumes.

A target server is named in a DEFINE DEVCLASS (DEVTYPE=SERVER) command. You must first change the server name in the device class or delete the device class.

Setting Up an Enterprise Configuration

After you set up server communication as described in “Setting Up Communications for Enterprise Configuration and Enterprise Event Logging” on page 314, you set up the configuration manager and its profiles. With the profiles, you designate the configuration information that can be distributed to managed servers. Then you can set up other servers as managed servers. The managed servers receive configuration information through subscriptions to profiles on the configuration manager. Each managed server stores the distributed information as managed objects in its database. Managed servers receive periodic updates of the configuration information from the configuration manager, or an administrator can trigger an update by command.

You can distribute the following configuration information from a configuration manager to managed servers:

- Administrators, including authorities for them
- Policy objects

Policy objects include policy domains, and the policy sets, management classes, copy groups and client schedules associated with them. However, a configuration manager does *not* distribute an active policy set and any of its associated objects. On each managed server, you must activate a policy set in each managed policy domain.

Note: The configuration manager does not distribute definitions for any storage pools identified as destinations in the policy. Definitions of storage pools and device classes are not distributed by a configuration manager.

- Administrative command schedules
- TSM server scripts
- Client option sets
- Server definitions
- Server groups

“Enterprise Configuration Scenario” gives you an overview of the steps to take for one possible implementation of enterprise configuration. Sections that follow give more details on each step.

Enterprise Configuration Scenario

To illustrate how you might use these functions, suppose your enterprise has offices around the world, with one or more TSM servers at each location. To make managing these servers easier, you want to control the configuration of all TSM servers from one TSM server in the headquarters office. Figure 57 shows the hierarchy that you want to set up.




Figure 57. A Scenario for Implementing Enterprise Configuration

You want to set up a configuration manager named HEADQUARTERS. Managed servers have the names of cities where they are located. You have three groups of managed servers, one in the Americas, one in Europe, and one in Asia. Each of the servers supports backup

and archive services for client machines in that office. For client backup operations, you want to use the default policy that stores backups on disk. Each server has an automated tape library configured to work with TSM, and you want to use the tape library at each location for client archive operations and for TSM server database backups. You want to be able to monitor activities on all servers. You also want to designate some other users as administrators who can work with these servers.

The following sections give you an overview of the steps to take to complete this setup. For details on each step, see the section referenced.

Setting up a Configuration Manager

Figure 58 shows the specific commands needed to set up one TSM server as a configuration manager. The following procedure gives you an overview of the steps required to set up a server as a configuration manager.




Figure 58. Setting Up a Configuration Manager

1. Decide whether to use the existing TSM server in the headquarters office as the configuration manager or to install a new TSM server on a system.
2. Set up the communications among the servers. See “Setting Up Communications Among Servers” on page 314 for details.
3. Identify the server as a configuration manager.

Use the following command:

```
set configmanager on
```

This command automatically creates a profile named `DEFAULT_PROFILE`. The default profile includes all the server and server group definitions on the configuration manager. As you define new servers and server groups, they are also associated with the default profile. For more information, see “Creating the Default Profile on a Configuration Manager” on page 326.

4. Create the configuration to distribute.

The tasks that might be involved include:

- Register administrators and grant authorities to those that you want to be able to work with all the servers.
- Define policy objects and client schedules
- Define administrative schedules
- Define TSM server scripts
- Define client option sets
- Define servers
- Define server groups

Example 1: You need a shorthand way to send commands to different groups of managed servers. You can define server groups. For example, you can define a server group named AMERICAS for the servers in the offices in North America and South America. See “Defining a Server Group and Members of a Server Group” on page 346 for details.

Example 2: You want each managed server to back up its database and storage pools regularly. One way to do this is to set up TSM server scripts and schedules to automatically run these scripts everyday. You can do the following:

- Verify or define server scripts that perform these operations.
- Verify or define administrative command schedules that run these scripts.

Example 3: You want clients to back up data to the default disk storage pool, BACKUPPOOL, on each server. But you want clients to archive data directly to the tape library attached to each server. You can do the following:

- In the policy domain that you will point to in the profile, update the archive copy group so that TAPEPOOL is the name of the destination storage pool.
- On each server that is to be a managed server, ensure that you have a tape storage pool named TAPEPOOL.

Note: You must set up the storage pool itself (and associated device class) on each managed server, either locally or by using command routing. If a managed server already has a storage pool associated with the automated tape library, you can rename the pool to TAPEPOOL.

Example 4: You want to ensure that client data is consistently backed up and managed on all servers. You want all clients to be able to store three backup versions of their files. You can do the following:

- Verify or define client schedules in the policy domain so that clients are backed up on a consistent schedule.
- In the policy domain that you will point to in the profile, update the backup copy group so that three versions of backups are allowed.
- Define client option sets so that basic settings are consistent for clients as they are added.

5. Define one or more profiles.

For example, you can define one profile named ALLOFFICES that points to all the configuration information (policy domain, administrators, scripts, and so on). You can also define profiles for each type of information, so that you have one profile that points to policy domains, and another profile that points to administrators, for example.

For details, see “Creating and Changing Configuration Profiles” on page 326.

Setting Up a Managed Server

Figure 59 on page 325 shows the specific commands needed to set up one TSM server as a managed server. The following procedure gives you an overview of the steps required to set up a server as a managed server.




Figure 59. Setting Up a Managed Server

Setting up the managed server can be done by an administrator working at a central location, or by administrators working at the servers that will be managed servers.

A server becomes a managed server when that server first subscribes to a profile on a configuration manager.

1. Query the server to look for potential conflicts.

See “Getting Information about Profiles” on page 333. Look for definitions of objects on the managed server that have the same name as those defined on the configuration manager. With some exceptions, these objects will be overwritten when the managed server first subscribes to the profile on the configuration manager. See “Associating Configuration Information with a Profile” on page 327 for details on the exceptions.

If the managed server is a new server and you have not defined anything, the only objects you will find are the defaults (for example, the STANDARD policy domain).

2. Subscribe to one or more profiles.

A managed server can only subscribe to profiles on one configuration manager. See “Subscribing to a Profile” on page 335.

If you receive error messages during the configuration refresh, such as a local object that could not be replaced, resolve the conflict and refresh the configuration again. You can either wait for the automatic refresh period to be reached, or kick off a refresh by issuing the SET CONFIGREFRESH command, setting or resetting the interval.

3. If the profile included policy domain information, activate a policy set in the policy domain, add or move clients to the domain, and associate any required schedules with the clients.

You may receive warning messages about storage pools that do not exist, but that are needed for the active policy set. Define any storage pools needed by the active policy set, or rename existing storage pools. See “Defining or Updating Primary Storage Pools” on page 123 or “Renaming a Storage Pool” on page 180.

4. If the profile included administrative schedules, make the schedules active.

Administrative schedules are not active when they are distributed by a configuration manager. The schedules do not run on the managed server until you make them active on the managed server. See “Tailoring Schedules” on page 373.

5. Set how often the managed server contacts the configuration manager to update the configuration information associated with the profiles.

The initial setting for refreshing the configuration information is 60 minutes. See “Refreshing Configuration Information” on page 339.

Creating the Default Profile on a Configuration Manager

Task	Required Privilege Class
Set up a server as a configuration manager	System

To set up one TSM server as the source for configuration information for other servers, you identify the server as a configuration manager. A configuration manager can be an existing TSM server that already provides services to clients, or can be a server dedicated to just providing configuration information to other TSM servers.

Enter the following command:

```
set configmanager on
```

When a server becomes a configuration manager, the server automatically creates a default profile named `DEFAULT_PROFILE`. The default profile contains any definitions of servers and server groups that exist on the configuration manager. You can change or delete the profile named `DEFAULT_PROFILE`.

When a managed server first subscribes to a profile on a configuration manager, the configuration manager automatically also subscribes the managed server to the profile named `DEFAULT_PROFILE`, if it exists. The information distributed via this profile gets refreshed in the same way as other profiles. This helps ensure that all servers have a consistent set of server and server group definitions for all servers in the network.

If you do not change the `DEFAULT_PROFILE`, whenever a managed server subscribed to the `DEFAULT_PROFILE` profile refreshes configuration information, the managed server receives definitions for all servers and server groups that exist on the configuration manager at the time of the refresh. As servers and server groups are added, deleted, or changed on the configuration manager, the changed definitions are distributed to subscribing managed servers.

Creating and Changing Configuration Profiles

You create configuration profiles on a configuration manager, which distributes the information associated with the profiles to any managed server that subscribes to those profiles. Creating a configuration profile includes these steps:

1. Defining the profile
2. Associating the configuration information with the profile

Once you define the profile and its associations, a managed server can subscribe to the profile and obtain the configuration information.

After you define a profile and associate information with the profile, you can change the information later. While you make changes, you can lock the profiles to prevent managed servers from refreshing their configuration information. To distribute the changed information associated with a profile, you can unlock the profile, and either wait for each managed server to refresh its configuration to get the changed information or notify each managed server to refresh its configuration. The following sections provide information on each of these tasks.

Defining the Profile

Task	Required Privilege Class
Define profiles	System

When you define the profile, you select the name and can include a description. For example, to define a profile named ALLOFFICES, enter the following command:

```
define profile alloffices  
description='Configuration to be used by all offices'
```

Associating Configuration Information with a Profile

Task	Required Privilege Class
Define profile associations	System

After you define a profile, you associate the configuration information that you want to distribute via that profile. You can associate the following configuration information with a profile:

- TSM administrators, including their authorities.

Note: Be careful if you are distributing definitions of administrators that have the same name as administrators already defined to managed servers. The configuration refresh overwrites the administrator definition and authority defined on the managed server. If the authority level of an administrator is less on the configuration manager than it was on the managed server, you could have problems with access to the managed server after distributing the administrator definition.

The configuration manager does not distribute information about whether an administrator is locked (preventing access to the server).

The administrator with the name SERVER_CONSOLE is never distributed from the configuration manager to a managed server.

- Servers and server groups.

The DEFAULT_PROFILE that is automatically created on a configuration manager already points to all servers and server groups defined to that server. If you leave the DEFAULT_PROFILE intact, you do not need to include servers or server groups in any other profile. Any servers and server groups that you define later are associated automatically with the default profile and the configuration manager distributes the definitions at the next refresh.

For a server definition, the following attributes are distributed:

- Communication method
- TCP/IP address (high-level address)
- Port number (low-level address)
- Server password
- Server URL
- The description

When server definitions are distributed, the attribute for allowing replacement is always set to YES. You can set other attributes, such as the server's node name, on the managed server by updating the server definition.

A managed server may already have a server defined with the same name as a server associated with the profile. The configuration refresh does not overwrite the local definition unless the managed server allows replacement of that definition. On a managed server, you allow a server definition to be replaced by updating the local definition. For example:

```
update server santiago allowreplace=yes
```

This safeguard prevents disruption of existing functions that require communication among servers (such as virtual volumes).

Table 25 summarizes what happens when servers or server groups being distributed have the same names as servers or server groups on the managed server.

Table 25. Results of Configuration Refresh with Duplicate Object Names

Local definition (on managed server)	Object with duplicate name to be distributed	Result of configuration refresh
Server	Server	The local server definition is replaced by the distributed server definition only if an administrator for the managed server updated the local definition to allow replacement.
Server	Server group	The local server definition remains. The server group definition is not distributed.
Server group	Server	The local server group is deleted. The server definition is distributed.
Server group	Server group	The local server group definition is replaced by the distributed server group definition.

■ Policy domains.

When you point to a policy domain in a profile, the configuration information that will be sent to the managed servers includes the policy domain itself, and all policy sets with their associated management classes, copy groups, and client schedules in the domain. However, the ACTIVE policy set and its associated management classes, copy groups, and client schedules are not included.

Policy domains can refer to storage pool names in the management classes, backup copy groups, and archive copy groups. As you set up the configuration information, consider whether managed servers already have or can set up or rename storage pools with these names.

Associations between clients and schedules are not distributed with the configuration information. For clients in a managed policy domain to run client schedules, you must associate the clients with the schedules on the managed server.

A subscribing managed server may already have a policy domain with the same name as the domain associated with the profile. The configuration refresh overwrites the domain

defined on the managed server unless client nodes are already assigned to the domain. Once the domain becomes a managed object on the managed server, you can associate clients with the managed domain. Future configuration refreshes can then update the managed domain.

If nodes are assigned to a domain with the same name as a domain being distributed, the domain is not replaced. This safeguard prevents inadvertent replacement of policy that could lead to loss of data. To replace an existing policy domain with a managed domain of the same name, you can do the following steps on the managed server:

1. Copy the domain.
 2. Move all clients assigned to the original domain to the copied domain.
 3. Trigger a configuration refresh.
 4. Activate the appropriate policy set in the new, managed policy domain.
 5. Move all clients back to the original domain, which is now managed.
- Administrative command schedules.
When the configuration manager distributes administrative schedules, the schedules are not active on the managed server. An administrator on the managed server must activate any managed schedules to have them run on the managed server.
A configuration refresh does not replace or remove any local schedules that are active on a managed server. However, a refresh can update an active schedule that is already managed by a configuration manager.
 - Client option sets.
 - TSM server scripts.

Before you can associate specific configuration information with a profile, the definitions must exist on the configuration manager. For example, to associate a policy domain named `ENGDOMAIN` with a profile, you must have already defined the `ENGDOMAIN` policy domain on the configuration manager.

Suppose you want the `ALLOFFICES` profile to distribute policy information from the `STANDARD` and `ENGDOMAIN` policy domains on the configuration manager. Enter the following command:

```
define profassociation alloffices domains=standard,engdomain
```

You can make the association more dynamic by specifying the special character, `*` (asterisk), by itself. When you specify the `*`, you can associate all existing objects with a profile without specifically naming them. If you later add more objects of the same type, the new objects are automatically distributed via the profile. For example, suppose you want the `ADMINISTRATORS` profile to distribute all administrators registered to the configuration manager. Enter the following commands on the configuration manager:

```
define profile administrators
  description='Profile to distribute administrators IDs'

define profassociation administrators admins=*
```

Whenever a managed server that is subscribed to the `ADMINISTRATORS` profile refreshes configuration information, it receives definitions for all administrators that exist on the

configuration manager at the time of the refresh. As administrators are added, deleted, or changed on the configuration manager, the changed definitions are distributed to subscribing managed servers.

Changing a Profile

Task	Required Privilege Class
Define profile associations	System
Update profiles	

You can change a profile and its associated configuration information. For example, if you want to add a policy domain named FILESERVERS to objects already associated with the ALLOFFICES profile, enter the following command:

```
define profassociation alloffices domains=fileservers
```

You can also delete associated configuration information, which results in removal of configuration from the managed server. Use the DELETE PROFASSOCIATION command. See “Removing Configuration Information from Managed Servers” on page 331 for details.

On a configuration manager, you cannot directly change the names of administrators, scripts, and server groups associated with a profile. To change the name of an administrator, script, or server group associated with a profile, delete the object then define it again with a new name and associate it with the profile again. During the next configuration refresh, each managed server makes the corresponding changes in their databases.

You can change the description of the profile. Enter the following command:

```
update profile alloffices  
description='Configuration for all offices with file servers'
```

Preventing Access to Profiles While You Make Changes

If you are making changes to a profile, you may want to prevent any subscribing managed server from refreshing its configuration information until you are done. You can lock the profile to prevent access to the profile by a managed server. Locking prevents a managed server from getting information that is incomplete because you are still making changes.

Task	Required Privilege Class
Lock and unlock profiles	System

For example, to lock the ALLOFFICES profile for two hours (120 minutes), enter the following command:

```
lock profile alloffices 120
```

You can let the lock expire after two hours, or unlock the profile with the following command:

```
unlock profile alloffices
```

Distributing Changed Configuration Information

To distribute the changed profile, you can wait for each managed server to refresh its configuration to get the changed information, or you can notify each managed server from the configuration manager. Managed servers refresh profile information on a configuration

refresh period. See “Refreshing Configuration Information” on page 339 for how to set this period.

Task	Required Privilege Class
Notify servers that subscribe to profiles to refresh configuration information	System

From the configuration manager, to notify all servers that are subscribers to the ALLOFFICES profile, enter the following command:

```
notify subscribers profile=alloffices
```

The managed servers then refresh their configuration information, even if the time period for refreshing the configuration has not passed.

Removing Configuration Information from Managed Servers

Task	Required Privilege Class
Delete profile associations	System

To remove configuration information from managed servers, you can do one of two things: delete the association of the object with the profile, or delete the object itself from the configuration manager.

Note: To remove all configuration information that is defined in the database of a managed server as a result of a profile subscription, you must delete the subscription using the option to discard all managed objects. See “Deleting Subscriptions” on page 338.

On the configuration manager, you can delete the association of objects with a profile. For example, you may want to remove some of the administrators that are associated with the ADMINISTRATORS profile. With an earlier command, you had included all administrators defined on the configuration manager (by specifying ADMINIS=*). To change the administrators included in the profile you must first delete the association of all administrators, then associate just the administrators that you want to include. Do the following:

1. Before you make these changes, you may want to prevent any servers from refreshing their configuration until you are done. Enter the following command:

```
lock profile administrators
```
2. Now make the change by entering the following commands:

```
delete profassociation administrators admins=*
```



```
define profassociation administrators  
admins=admin1,admin2,admin3,admin4
```
3. Unlock the profile:

```
unlock profile administrators
```
4. You may want to notify any managed server that subscribes to the profile so that servers refresh their configuration information:

```
notify subscribers profile=administrators
```

When you delete the association of an object with a profile, the configuration manager no longer distributes that object via the profile. Any managed server subscribing to the profile deletes the object from its database when it next contacts the configuration manager to refresh configuration information. However, a managed server does not delete the following objects:

- An object that is associated with another profile to which the server subscribes.
- A policy domain that has client nodes still assigned to it. To delete the domain, you must assign the affected client nodes to another policy domain on the managed server.
- An administrator that currently has a session open with the server.
- An administrator that is the last administrator with system authority on the managed server.

Also the managed server does not change the authority of an administrator if doing so would leave the managed server without any administrators having the system privilege class.

You can avoid both problems by ensuring that you have locally defined at least one administrator with system privilege on each managed server.

- An administrative schedule that is active. To remove an active schedule, you must first make the schedule inactive on the managed server.
- A server definition for a server that currently has an open connection from the managed server.
- A server definition that is specified in the definition of a device class that is a SERVER device type.
- A server definition that is the definition for the event server for the managed server.

If you no longer need an object defined on the configuration manager itself or on any managed server, you can delete the object itself. Deleting the object itself from the configuration manager has an effect similar to deleting the association of that object with the profile: the configuration manager no longer distributes that object, and a managed server attempts to delete the object from its database when it refreshes configuration information.

Deleting Profiles

Task	Required Privilege Class
Delete profiles	System

You can delete a profile from a configuration manager. Before deleting a profile, you should ensure that no managed server still has a subscription to the profile. If the profile still has some subscribers, you should first delete the subscriptions on each managed server. When you delete subscriptions, consider whether you want the managed objects to be deleted on the managed server at the same time. For example, to delete the subscription to profile ALLOFFICES from managed server SANTIAGO without deleting the managed objects, log on to the SANTIAGO server and enter the following command:

```
delete subscription alloffices
```

Then, on the configuration manager, enter the following command:

```
delete profile alloffices
```

See “Deleting Subscriptions” on page 338 for more details about deleting subscriptions on a managed server.

Note: You can use command routing to issue the DELETE SUBSCRIPTION command for all managed servers.

If you try to delete a profile that still has subscriptions, the command fails unless you force the operation:

```
delete profile alloffices force=yes
```

If you do force the operation, managed servers that still subscribe to the deleted profile will later contact the configuration manager to try to get updates to the deleted profile. The managed servers will continue to do this until their subscriptions to the profile are deleted. A message will be issued on the managed server alerting the administrator of this condition.

Getting Information about Profiles

Task	Required Privilege Class
Request information about profiles	Any administrator

You can get information about configuration profiles defined on any configuration manager, as long as that server is defined to the server with which you are working. For example, from a configuration manager, you can display information about profiles defined on that server or on another configuration manager. From a managed server, you can display information about any profiles on the configuration manager to which the server subscribes. You can also get profile information from any other configuration manager defined to the managed server, even though the managed server does not subscribe to any of the profiles.

For example, to get information about all profiles on the HEADQUARTERS configuration manager when logged on to another server, enter the following command:

```
query profile server=headquarters
```

The following shows what the results might look like:

Configuration manager	Profile name	Locked?
-----	-----	-----
HEADQUARTERS	ADMINISTRATORS	No
HEADQUARTERS	DEFAULT_PROFILE	No
HEADQUARTERS	ENGINEERING	No
HEADQUARTERS	MARKETING	No

You may need to get detailed information about profiles and the objects associated with them, especially before subscribing to a profile. You can get the names of the objects associated with a profile by entering the following command:

```
query profile server=headquarters format=detailed
```

The following shows what the results might look like:

```

Configuration manager: HEADQUARTERS
  Profile name: ADMINISTRATORS
  Locked?: No
  Description:
  Server administrators: ADMIN1 ADMIN2 ADMIN3 ADMIN4
  Policy domains:
Administrative command schedules: ** all objects **
  Server Command Scripts:
  Client Option Sets:
  Servers:
  Server Groups:

Configuration manager: HEADQUARTERS
  Profile name: DEFAULT_PROFILE
  Locked?: No
  Description:
  Server administrators:
  Policy domains:
Administrative command schedules:
  Server Command Scripts:
  Client Option Sets:
  Servers: ** all objects **
  Server Groups: ** all objects **

Configuration manager: HEADQUARTERS
  Profile name: ENGINEERING
  Locked?: No
  Description:
  Server administrators:
  Policy domains: ENGDOMAIN
Administrative command schedules:
  Server Command Scripts: QUERYALL
  Client Option Sets: DESIGNER PROGRAMMER
  Servers:
  Server Groups:

Configuration manager: HEADQUARTERS
  Profile name: MARKETING
  Locked?: Yes
  Description:
  Server administrators:
  Policy domains: MARKETDOM
Administrative command schedules:
  Server Command Scripts: QUERYALL
  Client Option Sets: BASIC
  Servers:
  Server Groups:

```

If the server from which you issue the query is already a managed server (subscribed to one or more profiles on the configuration manager being queried), by default the query returns profile information as it is known to the managed server. Therefore the information is accurate as of the last configuration refresh done by the managed server. You may want to ensure that you see the latest version of profiles as they currently exist on the configuration manager. Enter the following command:

```
query profile useLocal=no format=detailed
```

To get more than the names of the objects associated with a profile, you can do one of the following:

- If command routing is set up between servers, you can route query commands from the server to the configuration manager. For example, to get details on the ENGDOMAIN policy domain on the HEADQUARTERS server, enter this command:

```
headquarters: query domain engdomain format=detailed
```

You can also route commands from the configuration manager to another server to get details about definitions that already exist.

- If command routing is not set up, log on to the configuration manager and enter the query commands to get the information you need.

Subscribing to a Profile

Task	Required Privilege Class
Define subscriptions to profiles	System
Set the period for configuration refreshes	

After an administrator at a configuration manager has created profiles and associated objects with them, managed servers can subscribe to one or more of the profiles.

Notes:

Unless otherwise noted, the commands in this section would be run on a managed server:

1. An administrator at the managed server could issue the commands.
2. You could log in from the enterprise console and issue them.
3. If command routing is set up, you could route them from the server that you are logged in to.

After a managed server subscribes to a profile, the configuration manager sends the object definitions associated with the profile to the managed server where they are automatically stored in the database. Object definitions created this way in the database of a managed server are called managed objects. With a few exceptions, you cannot change managed objects on the managed server. The exceptions are that you can change:

- The active status of a schedule
- The lock status of an administrator
- Which policy set is active in a policy domain
- The default management class of a policy set
- The attributes of a server definition that are related to the use of virtual volumes (node name, password, and delete grace period)

Before a managed server subscribes to a profile, be aware that if you have defined any object with the same name and type as an object associated with the profile that you are subscribing to, those objects will be overwritten. You can check for such occurrences by querying the profile before subscribing to it.

When a managed server first subscribes to a profile on a configuration manager, it also automatically subscribes to DEFAULT_PROFILE, if a profile with this name is defined on the configuration manager. Unless DEFAULT_PROFILE is modified on the configuration

manager, it contains all the server definitions and server groups defined on the configuration manager. In this way, all the servers in your network receive a consistent set of server and server group definitions.

Note: Although a managed server can subscribe to more than one profile on a configuration manager, it cannot subscribe to profiles on more than one configuration manager at a time.

Changes may be made to a profile, after a managed server subscribes to it. An administrator on the configuration manager can notify your server of a change by issuing the NOTIFY SUBSCRIBERS command. The configuration manager contacts each managed server having a subscription to one of the specified profiles. When a managed server is contacted, it begins refresh processing to get the configuration updates from the configuration manager.

A Subscription Scenario

This section describes a typical scenario in which a server subscribes to a profile on a configuration manager, HEADQUARTERS. In this scenario an administrator for the HEADQUARTERS server has defined three profiles, ADMINISTRATORS, ENGINEERING, and MARKETING, each with its own set of associations. In addition, DEFAULT_PROFILE was automatically defined and contains only the server and server group definitions defined on the HEADQUARTERS server. An administrator for HEADQUARTERS has given you the names of the profiles that you should be using. To subscribe to the ADMINISTRATORS and ENGINEERING profiles and keep them current, perform the following steps:

1. Display the names of the objects in the profiles on HEADQUARTERS.

You might want to perform this step to see if the object names on the profiles are used on your server for any objects of the same type. Issue this command:

```
query profile * server=headquarters format=detailed
```

You might want to get detailed information on some of the objects by issuing specific query commands on either your server or the configuration manager.

Note: If any object name matches and you subscribe to a profile containing an object with the matching name, the object on your server will be replaced, with the following exceptions:

- A policy domain is not replaced if the domain has client nodes assigned to it.
- An administrator with system authority is not replaced by an administrator with a lower authority level if the replacement would leave the server without a system administrator.
- The definition of a server is not replaced unless the server definition on the managed server allows replacement.
- A server with the same name as a server group is not replaced.
- A locally defined, active administrative schedule is not replaced

2. Subscribe to the ADMINISTRATORS and ENGINEERING profiles.

After the initial subscription, you do not have to specify the server name on the DEFINE SUBSCRIPTION commands. If at least one profile subscription already exists, any additional subscriptions are automatically directed to the same configuration manager. Issue these commands:

```
define subscription administrators server=headquarters
define subscription engineering
```

The object definitions in these profiles are now stored on your database. In addition to ADMINISTRATORS and ENGINEERING, the server is also subscribed by default to DEFAULT_PROFILE. This means that all the server and server group definitions on HEADQUARTERS are now also stored in your database.

3. Set the time interval for obtaining refreshed configuration information from the configuration manager.

If you do not perform this step, your server checks for updates to the profiles at start up and every 60 minutes after that. Set up your server to check HEADQUARTERS for updates once a day (every 1440 minutes). If there is an update, HEADQUARTERS sends it to the managed server automatically when the server checks for updates.

```
set configrefresh 1440
```

Note: You can initiate a configuration refresh from a managed server at any time. To initiate a refresh, simply reissue the SET CONFIGREFRESH with any value greater than 0. The simplest approach is to use the current setting:

```
set configrefresh 1440
```

Querying Subscriptions

Task	Required Privilege Class
Request information about subscriptions	Any administrator
Request information about profiles	

From time to time, you may want to see what profiles a server is subscribed to. You may also want to see the last time that the configuration associated with that profile was successfully refreshed on your server. The QUERY SUBSCRIPTION command gives you this information. You can name a specific profile or use a wildcard character to display all or a subset of profiles to which the server is subscribed. For example, the following command displays ADMINISTRATORS and any other profiles that begin with the string "ADMIN":

```
query subscription admin*
```

Here is a sample of the output:

Configuration manager	Profile name	Last update date/time
-----	-----	-----
HEADQUARTERS	ADMINISTRATORS	06/04/1998 17:51:49
HEADQUARTERS	ADMINS_1	06/04/1998 17:51:49
HEADQUARTERS	ADMINS_2	06/04/1998 17:51:49

To see what objects the ADMINISTRATORS profile contains, use the following command:

```
query profile administrators uselocal=no format=detailed
```

You will see output similar to the following:

```

Configuration manager: HEADQUARTERS
Profile name: ADMINISTRATORS
Locked?: No
Description:
Server administrators: ADMIN1 ADMIN2 ADMIN3 ADMIN4
Policy domains:
Administrative command schedules: ** all objects **
Server Command Scripts:
Client Option Sets:
Servers:
Server Groups:

```

Managed objects are stored in the database of a managed server as a result of subscriptions to profiles on a configuration manager. Any object that was created or updated in the database of the managed server as a result of a subscription has the string `$$CONFIG_MANAGER$$` in place of the name of the administrator who last changed the object. For example, if the policy domain named `ENGDOMAIN` is a managed object and you enter this command on the managed server:

```
query domain engdomain format=detailed
```

You will see output similar to the following:

```

Policy Domain Name: ENGDOMAIN
Activated Policy Set:
Activation Date/Time:
Days Since Activation:
Activated Default Mgmt Class:
Number of Registered Nodes: 0
Description: Policy for design and software engineers
Backup Retention (Grace Period): 30
Archive Retention (Grace Period): 365
Last Update by (administrator): $$CONFIG_MANAGER$$
Last Update Date/Time: 06/04/1998 17:51:49
Managing profile: ENGINEERING

```

The field `Managing profile` shows the profile to which the managed server subscribes to get the definition of this object.

Deleting Subscriptions

Task	Required Privilege Class
Delete subscriptions to profiles	System

If you decide that a server no longer needs to subscribe to a profile, you can delete the subscription. When you delete a subscription to a profile, you can choose to discard the objects that came with the profile or keep them in your database. For example, to request that your subscription to `PROFILEC` be deleted and to keep the objects that came with that profile, issue the following command:

```
delete subscription profilec discardobjects=no
```

After the subscription is deleted on the managed server, the managed server issues a configuration refresh request to inform the configuration manager that the subscription is deleted. The configuration manager updates its database with the new information.

When you choose to delete objects when deleting the subscription, the server may not be able to delete some objects. For example, the server cannot delete a managed policy domain if the domain still has client nodes registered to it. The server skips objects it cannot delete, but does not delete the subscription itself. If you take no action after an unsuccessful subscription deletion, at the next configuration refresh the configuration manager will again send all the objects associated with the subscription. To successfully delete the subscription, do one of the following:

- Fix the reason that the objects were skipped. For example, reassign clients in the managed policy domain to another policy domain. After handling the skipped objects, delete the subscription again.
- Delete the subscription again, except this time do not discard the managed objects. The server can then successfully delete the subscription. However, the objects that were created because of the subscription remain.

Refreshing Configuration Information

Task	Required Privilege Class
Set the period for configuration refreshes	System (on the managed server)
Notify servers that subscribe to profiles to refresh configuration information	System (on the configuration manager)

On a configuration manager, an administrator can make changes to configuration information that is associated with a profile. How quickly the changes get distributed to a subscribing managed server depends on the configuration refresh period set on the managed server and whether the administrator on the configuration manager sent a notification.

By default, a managed server refreshes its configuration information every 60 minutes. To cause an immediate refresh, change this period. For example, to immediately refresh the configuration and change the frequency of future refreshes to once a day, enter the following command for the managed server:

```
set configrefresh 1440
```

By issuing this command with a value greater than zero, you cause the managed server to immediately start the refresh process.

At the configuration manager, you can cause managed servers to refresh their configuration information by notifying the servers. For example, to notify subscribers to all profiles, enter the following command:

```
notify subscribers profile=*
```

The managed servers then start to refresh configuration information to which they are subscribed through profiles.

A managed server automatically refreshes configuration information when it is restarted.

Handling Problems with Configuration Refresh

To monitor for any problems during a configuration refresh, you can watch the server console or activity log of the managed server. One problem that may occur is that the refresh process may skip objects. For example, a policy domain of the same name as an existing policy domain on the managed server is not distributed if the policy domain has

client nodes assigned to it. See “Associating Configuration Information with a Profile” on page 327 for details on when objects cannot be distributed.

The configuration manager sends the objects that it can distribute to the managed server. The configuration manager skips (does not send) objects that conflict with local objects. If the configuration manager cannot send all objects that are associated with the profile, the managed server does not record the configuration refresh as complete. The objects that the configuration manager successfully sent are left as local instead of managed objects in the database of the managed server. The local objects left as a result of an unsuccessful configuration refresh become managed objects at the next successful configuration refresh of the same profile subscription.

Returning Managed Objects to Local Control

You may want to return one or more managed objects (objects distributed by a configuration manager via profiles) to local control on the managed servers. You can do this from the configuration manager or from the managed servers.

To do this from the configuration manager, you do not simply delete the association of the object from the profile, because that would cause the object to be deleted from subscribing managed servers. To ensure the object remains in the databases of the managed servers as a locally managed object, you can copy the current profile, make the deletion, and change the subscriptions of the managed servers to the new profile.

For example, servers are currently subscribed to the ENGINEERING profile. The ENGDOMAIN policy domain is associated with this profile. You want to return control of the ENGDOMAIN policy domain to the managed servers. You can do the following:

1. Copy the ENGINEERING profile to a new profile, ENGINEERING_B:
`copy profile engineering engineering_b`
2. Delete the association of the ENGDOMAIN policy domain from ENGINEERING_B:
`delete profassociation engineering_b domains=engdomain`
3. Use command routing to delete subscriptions to the ENGINEERING profile:
`americas,europe,asia: delete subscription engineering
discardobjects=no`
4. Delete the ENGINEERING profile:
`delete profile engineering`
5. Use command routing to define subscriptions to the new ENGINEERING_B profile:
`americas,europe,asia: define subscription engineering_b`

To return objects to local control when working on a managed server, you can delete the subscription to one or more profiles. When you delete a subscription, you can choose whether to delete the objects associated with the profile. To return objects to local control, you do not delete the objects. For example, use the following command on a managed server:

```
delete subscription engineering discardobjects=no
```

Setting Up Administrators for the Servers

Include in your profiles any administrators that you want to give access to all servers in the network. These administrators must then maintain their passwords on the configuration manager. To ensure passwords stay valid for as long as expected on all servers, set the

password expiration period to the same time on all servers. One way to do this is to route a SET PASSEXP command from one server to all of the others.

Ensure that you have at least one administrator that is defined locally on each managed server with system authority. This avoids an error on configuration refresh when all administrators for a server would be removed as a result of a change to a profile on the configuration manager.

Handling Problems with Synchronization of Profiles

In rare situations, when a managed server contacts a configuration manager to refresh configuration information, the configuration manager may determine that the profile information on the two servers is not synchronized. It may appear that the configuration information is more recent on the managed server than on the configuration manager. This could occur in the following situations:

- The database on the configuration manager has been restored to an earlier time and now has configuration information from profiles that appear to be older than what the managed server has obtained.
- On the configuration manager, an administrator deleted a profile, forcing the deletion even though one or more managed servers still subscribed to the profile. The administrator redefined the profile (using the same name) before the managed server refreshed its configuration information.

If the configuration manager still has a record of the managed server's subscription to the profile, the configuration manager does not send its profile information at the next request for refreshed configuration information. The configuration manager informs the managed server that the profiles are not synchronized. The managed server then issues a message indicating this condition so that an administrator can take appropriate action. The administrator can perform the following steps:

1. If the configuration manager's database has been restored to an earlier point in time, the administrator may want to query the profile and associated objects on the managed server and then manually update the configuration manager with that information.
2. Use the DELETE SUBSCRIPTION command on the managed server to delete subscriptions to the profile that is not synchronized. If desired, you can also delete definitions of the associated objects, then define the subscription again.

It is possible that the configuration manager may not have a record of the managed server's subscription. In this case, no action is necessary. When the managed server requests a refresh of configuration information, the configuration manager sends current profile information and the managed server updates its database with that information.

Switching a Managed Server to a Different Configuration Manager

To switch a managed server from one configuration manager to another, perform the following steps:

1. Query profiles on the server that will be the new configuration manager to compare with current profiles to which the managed server subscribes.
2. On the managed server, delete all subscriptions to profiles on the current configuration manager. Remember to delete the subscription to the profile named DEFAULT_PROFILE. Consider whether to discard the managed objects in the database when you delete the subscriptions.

Verify that all subscriptions have been deleted by querying subscriptions.

3. Change server communications as needed. Define the server that will be the new configuration manager. You can delete the server that was formerly the configuration manager.
4. On the managed server, define subscriptions to profiles on the new configuration manager.

Deleting Subscribers from a Configuration Manager

Under normal circumstances, you do not need to delete subscribers from a configuration manager. You only need to delete a subscription to a profile on the managed server (by using the `DELETE SUBSCRIPTION` command). When you issue the `DELETE SUBSCRIPTION` command, the managed server automatically notifies the configuration manager of the deletion by refreshing its configuration information. As part of the refresh process, the configuration manager is informed of the profiles that the managed server subscribes to (and does not subscribe to). If the configuration manager cannot be contacted immediately for a refresh, the configuration manager will find out that the subscription was deleted the next time the managed server refreshes configuration information.

Deleting subscribers from a configuration manager is only necessary as a way to clean up in certain unusual situations. For example, you may need to delete subscribers if a managed server goes away completely or deletes its last subscription without being able to notify the configuration manager. You then use the `DELETE SUBSCRIBER` command to delete all subscriptions for that subscriber (the managed server) from the configuration manager's database.

Renaming a Managed Server

To rename a managed server, perform the following steps:

1. By using command routing or by logging on to the managed server, change the name of the managed server. Use the enterprise console or use the `SET SERVERNAME` command.
2. Change the communication setup.
 - a. On the configuration manager, delete the server definition with the old name.
 - b. On the configuration manager, define the server with its new name.
3. On the managed server, refresh the configuration information. You can wait for the configuration refresh period to pass, or you can reset the refresh period to cause an immediate refresh.

Performing Tasks on Multiple Servers

To make performing tasks with multiple servers easier, TSM provides the following functions:

- Enterprise logon
- Command routing
- Server group definitions that can be used to simplify command routing

Using Tivoli Storage Manager Enterprise Logon

Enterprise logon enables the administrator's logon credentials to be used for access to other servers for successfully linking to other servers and routing commands to other servers. The administrator must be defined on each server with the appropriate administrative authority for the action or command.

Enterprise logon, in conjunction with enterprise configuration, allows an administrator to log on to one TSM server and have access to all associated TSM servers and clients that the administrator is authorized to access. Enterprise logon is available from a Web browser. The client must be configured to access a server at TSM Version 3 or later.

An administrator no longer has to remember multiple user IDs and passwords for servers and clients, other than the initial user ID and password. The administrator enters the initial user ID and password from the sign-on screen displayed on the administrator's Web browser. A single set of logon credentials are then used to verify an administrator's identity across servers and clients in a Web browser environment. Encrypted credentials ensure password security.

Authentication time-out processing requires an administrator to re-authenticate after a specific amount of time has passed. You can set the amount of time by using the SET WEBAUTHTIMEOUT command. The time-out protects against unauthorized users indefinitely accessing an unattended Web browser that has credentials stored in a Web browser cache. A pop-up is displayed on the browser that requires an administrator's ID and password to proceed.

The following can use enterprise logon:

- An administrator who uses a Web browser to connect to a TSM server
- An administrator or a help-desk person who uses a Web browser to connect to a remote client with the Web backup-archive client
- An end user of TSM who uses the Web backup-archive client to connect to their own remote client

A client can optionally disable enterprise logon.

Routing Commands

If you have set up your servers as described in "Setting Up Communications for Command Routing" on page 317, you can route TSM administrative commands to one or more servers. Command routing enables an administrator to send commands for processing to one or more servers at the same time. The output is collected and displayed at the server that issued the routed commands. A system administrator can configure and monitor many different servers from a central server by using command routing.

You can route commands to one server, multiple servers, servers defined to a named group (see "Setting Up Server Groups" on page 345), or a combination of these servers. A routed command cannot be further routed to other servers; only one level of routing is allowed.

Each server that you identify as the target of a routed command must first be defined with the DEFINE SERVER command. If a server has not been defined, that server is skipped and the command routing proceeds to the next server in the route list.

TSM does not run a routed command on the server from which you issue the command unless you also specify that server. To be able to specify the server on a routed command, you must define the server just as you did any other server.

Commands cannot be routed from the SERVER_CONSOLE ID.

Routed commands run independently on each server to which you send them. The success or failure of the command on one server does not affect the outcome on any of the other servers to which the command was sent.

For more information on command routing and return codes generated by command processing, refer to *Administrator's Reference*.

Routing Commands to One or More Servers

The following sections describe how you can route commands to one or more servers, and to server groups.

To successfully route commands to other servers, you must have the proper administrative authority on all servers that receive the command for processing.

The return codes for command routing can be one of three severities: 0, ERROR, or WARNING. See *Administrator's Reference* for a list of valid return codes and severity levels.

Routing Commands to Single Servers

To route a command to a single server, enter the defined server's name, a colon, and then the command to be processed. For example, to route a QUERY STGPOOL command to the server that is named ADMIN1, enter:

```
admin1: query stgpool
```

The colon after the server name indicates the end of the routing information. This is also called the *server prefix*. Another way to indicate the server routing information is to use parentheses around the server name, as follows:

```
(admin1) query stgpool
```

Note: When writing scripts, you must use the parentheses for server routing information.

To route a command to more than one server, separate the server names with a comma. For example, to route a QUERY OCCUPANCY command to three servers named ADMIN1, GEO2, and TRADE5 enter:

```
admin1,geo2,trade5: query occupancy
```

Or

```
(admin1,geo2,trade5) query occupancy
```

The command QUERY OCCUPANCY is routed to servers ADMIN1, GEO2, and TRADE5. If a server has not been defined with the DEFINE SERVER command, that server is skipped and the command routing proceeds to the next server in the route list.

The routed command output of each server is displayed in its entirety at the server that initiated command routing. In the previous example, output for ADMIN1 would be displayed, followed by the output of GEO2, and then the output of TRADE5.

Processing of a command on one server does not depend upon completion of the command processing on any other servers in the route list. For example, if GEO2 server does not successfully complete the command, the TRADE5 server continues processing the command independently.

Routing Commands to Server Groups

A server group is a named group of servers. Once you set up the groups, you can route commands to the groups. See “Setting Up Server Groups” for how to set up a server group.

To route a QUERY STGPOOL command to the server group WEST_COMPLEX, enter:

```
west_complex: query stgpool
```

Or

```
(west_complex) query stgpool
```

The QUERY STGPOOL command is sent for processing to servers BLD12 and BLD13 which are members of group WEST_COMPLEX.

To route a QUERY STGPOOL command to two server groups WEST_COMPLEX and NORTH_COMPLEX, enter:

```
west_complex,north_complex: query stgpool
```

Or

```
(west_complex,north_complex) query stgpool
```

The QUERY STGPOOL command is sent for processing to servers BLD12 and BLD13 which are members of group WEST_COMPLEX, and servers NE12 and NW13 which are members of group NORTH_COMPLEX.

Routing Commands to Single Servers and Server Groups

You can route commands to multiple single servers and to server groups at the same time. For example, to route the QUERY DB command to servers HQSRV, REGSRV, and groups WEST_COMPLEX and NORTH_COMPLEX, enter:

```
hqsrv,regsrv,west_complex,north_complex: query db
```

Or

```
(hqsrv,regsrv,west_complex,north_complex) query db
```

The QUERY DB command is sent for processing to servers HQSRV, REGSRV, to BLD12 and BLD13 (both members of WEST_COMPLEX), and to NE12 and NW12 (both members of NORTH_COMPLEX).

Duplicate references to servers are removed in processing. For example, if you route a command to server BLD12 and to server group WEST_COMPLEX (which includes BLD12), the command is sent only once to server BLD12.

Setting Up Server Groups

You can make command routing more efficient by creating one or more server groups and adding servers to them. You can then route commands to server groups in addition to or in place of routing commands to single servers. This section describes how to set up server groups. To use server groups, you must do the following tasks:

1. Define the server groups.

-
2. Add the servers as members of the appropriate group.

After you have the server groups set up, you can manage the groups and group members.

Defining a Server Group and Members of a Server Group

Task	Required Privilege Class
Define a server group	System
Define a server group member	

You can define groups of servers to which you can then route commands. The commands are routed to all servers in the group. To route commands to a server group you must do the following:

1. Define the server with the DEFINE SERVER command if it is not already defined (see “Setting Up Communications for Command Routing” on page 317).
2. Define a new server group with the DEFINE SERVERGROUP command. Server group names must be unique because both groups and server names are allowed for the routing information.
3. Define servers as members of a server group with the DEFINE GRPMEMBER command.

The following example shows how to create a server group named WEST_COMPLEX, and define servers BLD12 and BLD13 as members of the WEST_COMPLEX group:

```
define servergroup west_complex
define grpmember west_complex bld12,bld13
```

Managing Server Groups

You can query, copy, rename, update, and delete server groups as necessary.

Task	Required Privilege Class
Query a server group	System
Copy a server group	
Rename a server group	
Update a server group description	
Delete a server group	

Querying a Server Group

To query server group WEST_COMPLEX, enter:

```
query servergroup west_complex
```

The following is sample output from a QUERY SERVERGROUP command:

Server Group	Members	Description	Managing profile
WEST_COMPLEX	BLD12, BLD13		

Copying a Server Group

To copy the entire server group contents of WEST_COMPLEX to a different server group named NEWWEST, enter:

```
copy servergroup west_complex newwest
```

This command creates the new group. If the new group already exists, the command fails.

Renaming a Server Group

To rename an existing server group NORTH_COMPLEX to NORTH, enter:

```
rename servergroup north_complex north
```

Updating a Server Group Description

To update the NORTH server group to modify its description, enter:

```
update servergroup north description="Northern marketing region"
```

Deleting a Server Group

To delete WEST_COMPLEX server group from the TSM server, enter:

```
delete servergroup west_complex
```

This command removes all members from the server group. The server definition for each group member is not affected. If the deleted server group is a member of other server groups, the deleted group is removed from the other groups.

Managing Group Members

You can move and delete group members from a previously defined group.

Task	Required Privilege Class
Move a group member to another group	System
Delete a group member	

Moving a Group Member to Another Group

To move group member TRADE5 from the NEWWEST group to the NORTH_COMPLEX group, enter:

```
move grpmember trade5 newwest north_complex
```

Deleting a Group Member from a Group

To delete group member BLD12 from the NEWWEST server group, enter:

```
delete grpmember newwest bld12
```

When you delete a server, the deleted server is removed from any server groups of which it was a member.

Querying Server Availability

You can test a connection from your local server to a specified server with the PING SERVER command. To ping the server GEO2, enter:

```
ping server geo2
```

The PING SERVER command uses the user ID and password of the administrative ID that issued the command. If the administrator is not defined on the server being pinged, the ping fails even if the server may be running.

Using Virtual Volumes to Store Data on Another Server

TSM lets a server (a *source server*) store the results of database backups, export operations, storage pool operations, and a DRM PREPARE command on another server (a *target server*). The data is stored as *virtual volumes*, which appear to be sequential media volumes on the source server but which are actually stored as archive files on a target server. Virtual volumes can be any of the following:

- Database backups
- Storage pool backups
- Data that is backed up, archived, or space managed from client nodes
- Client data migrated from storage pools on the source server
- Any data that can be moved by EXPORT and IMPORT commands
- DRM plan files

The source server is a client of the target server, and the data for the source server is managed only by the source server. In other words, the source server controls the expiration and deletion of the files that comprise the virtual volumes on the target server.

At the target server, the virtual volumes from the source server are seen as archive data. The source server is registered as a client node (of TYPE=SERVER) at the target server and is assigned to a policy domain. The archive copy group of the default management class of that domain specifies the storage pool for the data from the source server.

Note: If the default management class does not include an archive copy group, data cannot be stored on the target server.

Using virtual volumes can benefit you in the following ways:

- The source server can use the target server as an electronic vault for rapid recovery from a disaster.
- Smaller TSM source servers can use the storage pools and tape devices of larger TSM servers.
- For incremental database backups, it can decrease wasted space on volumes and under use of high-end tape drives.

Be aware of the following when you use virtual volumes:

- If you use virtual volumes for database backups, you might have the following situation: SERVER_A backs up its database to SERVER_B, and SERVER_B backs up its database to SERVER_A. If this is the only way databases are backed up, if both servers are at the same location, and if a disaster strikes that location, you may have no backups with which to restore your databases.
- Moving large amounts of data between the servers may slow down your communications significantly, depending on the network bandwidth and availability.
- You can specify in the device class definition (DEVTYPE=SERVER) how often and for how long a time the source server will try to contact the target server. Keep in mind that frequent attempts to contact the target server over an extended period can affect your communications.

- Under certain circumstances, inconsistencies may arise among virtual volume definitions on the source server and the archive files on the target server. You can use the `RECONCILE VOLUMES` command to reconcile these inconsistencies (see “Reconciling Virtual Volumes and Archive Files” on page 352 for details).
- Storage space limitations on the target server affect the amount of data that you can store on that server.
- To minimize mount wait times, the total mount limit for all server definitions that specify the target server should not exceed the mount total limit at the target server. For example, a source server has two device classes, each specifying a mount limit of 2. A target server has only two tape drives. In this case, the source server mount requests could exceed the target server’s tape drives.

Note: When you issue a `DEFINE SERVER` command, the source server sends a verification code to the target server. When the source server begins a session with the target server, it also sends the verification code. If the code matches what was previously stored on the target, the session is opened in read/write mode. If the verification code is lost at the source server (for example, after a database restore), the code can be reset by issuing an `UPDATE SERVER` command with the `FORCESYNC=YES` parameter.

Setting Up Source and Target Servers for Virtual Volumes

In the source/target relationship, the source server is defined as a client node of the target server. To set up this relationship, a number of steps must be performed at the two servers. In the following example (illustrated in Figure 60 on page 350), the source server is named `DELHI` and the target server is named `TOKYO`.

■ At `DELHI`:

1. Define the target server:
 - `TOKYO` has a TCP/IP address of `9.115.3.221:1845`
 - Assigns to `TOKYO` the password `CALCITE`.
 - Assigns `DELHI` as the node name by which the source server `DELHI` will be known at the target server. If no node name is assigned, the server name of the source server is used. To see the server name, you can issue the `QUERY STATUS` command.
2. Define a device class for the data to be sent to the target server. The device type for this device class must be `SERVER`, and the definition must include the name of the target server.

■ At `TOKYO`:

- Register the source server as a client node. The target server can use an existing policy domain and storage pool for the data from the source server. However, you can define a separate management policy and storage pool for the source server. Doing so can provide more control over storage pool resources.
1. Use the `REGISTER NODE` command to define the source server as a node of `TYPE=SERVER`. The policy domain to which the node is assigned determines where the data from the source server is stored. Data from the source server is stored in the storage pool specified in the archive copy group of the default management class of that domain.
 2. You can set up a separate policy and storage pool for the source server.

- a. Define a storage pool named SOURCEPOOL:

```
define stgpool sourcepool autotapeclass maxscratch=20
```
- b. Copy an existing policy domain STANDARD to a new domain named SOURCEDOMAIN:

```
copy domain standard sourcedomain
```
- c. Assign SOURCEPOOL as the archive copy group destination in the default management class of SOURCEDOMAIN:

```
update copygroup sourcedomain standard standard type=archive
destination=sourcepool
```

After issuing these commands, ensure that you assign the source server to the new policy domain (UPDATE NODE) and activate the policy. See “Overview: Changing Policy” on page 237 for details.




Figure 60. Communication configuration for virtual volumes

Performing Operations at the Source Server

You can perform certain operations at the source server that cause data to be stored in a storage pool at the target server. These operations are:

- Database backups
- Storage pool backups
- Client data backup, archive, or migration
- Data migration from one storage pool to another
- Export of server information
- DRM prepare

The following sections describe how to perform these operations. In the examples, the following is assumed:

- The definitions shown in the previous section have been done.
- An operational TCP/IP connection exists between both servers.
- Both servers are running.

Back Up the Database

You can back up the database of a source server to a target server. For example, to perform an incremental backup of the source server and send the volumes to the target server, issue the following command:

```
backup db type=incremental devclass=targetclass
```

Expiration Processing of Database Backup Volumes and Recovery Plan Files with the Tivoli Disaster Recovery Manager: If your server is licensed for DRM, expiration processing can delete volumes containing expired database backups and recovery plan files. One or more database backup volumes may be deleted from the volume history during expiration processing if the following conditions are true:

- The volume has a device type of SERVER
- The volume is not part of the most recent database backup series
- The last volume of the database backup series has exceeded the expiration value specified with the SET DRMDBBACKUPEXPIREDAYS command

See “Moving Backup Volumes Onsite” on page 513 for more information.

You can also do an automatic database backup to a target server. For example, if you have issued the following command, a database backup occurs automatically when more than 60 percent of recovery log space is used:

```
define dbbackuptrigger devclass=targetclass logfullpct=60
```

Back Up a Storage Pool

You can back up a storage pool of a source server to a target server. For example, a primary storage pool named TAPEPOOL is on the source server. You can define a copy storage pool named TARGETCOPYPOOL, also on the source server. TARGETCOPYPOOL must have an associated device class whose device type is SERVER. When you back up TAPEPOOL to TARGETCOPYPOOL, the backup is sent to the target server. To do so, issue the following commands:

```
define stgpool targetcopypool targetclass pooltype=copy
  maxscratch=20
backup stgpool tapepool targetcopypool
```

Store Client Data on a Target Server

You can configure your TSM system so that when client nodes registered to the source server back up, archive, or migrate their data, that data is sent to the target server. When clients restore, retrieve, or recall their data, the source server gets the data from the target server.

To configure your system, ensure that the management policy for those nodes specifies a storage pool that has a device class whose device type is SERVER. For example, the following command defines the storage pool named TARGETPOOL.

```
define stgpool targetpool targetclass maxscratch=20
  reclaim=100
```

Note: Reclamation of a storage pool automatically begins when the percentage of reclaimable space, which is specified by the RECLAIM parameter, is reached. Reclamation of a target storage pool can involve the movement of a great deal of data from the target server to the source server and back to the target. If this operation occurs automatically during peak operating periods, it could slow network performance significantly. If you set the value to 100, reclamation will not occur automatically. For details about storage pool reclamation and how to begin it manually, see “Reclaiming Space in Sequential Access Storage Pools” on page 152.

Migrate Data from a Source Server Storage Pool to a Target Server Storage Pool

You can set up your storage pool hierarchy so that client data is migrated from a storage pool on the source server to the target server. For example, storage pool TAPEPOOL is on the source server. The TAPEPOOL definition specifies NEXTSTGPOOL=TARGETPOOL. TARGETPOOL has been defined on the source server as a storage pool of device type SERVER. When data is migrated from TAPEPOOL, it is sent to the target server.

```
define stgpool tapepool tapeclass nextstgpool=targetpool  
maxscratch=20
```

Export Server Information to a Target Server

You can use any of the TSM EXPORT commands to export data from one TSM source server to sequential media on a target TSM server. You must specify a device class with a device type specified as SERVER. For example, to copy server information directly to a target server, issue the following command:

```
export server devclass=targetclass
```

Import Server Information from a Target Server

If data has been exported from a source server to a target server, you can import that data from the target server to a third server. The server that will import the data uses the node ID and password of the source server to open a session with the target server. That session is in read-only mode because the third server does not have the proper verification code.

For example, to import server information from a target server, issue the following command:

```
import server devclass=targetclass
```

Reconciling Virtual Volumes and Archive Files

If you have restored the database on the source or target server, you should perform reconciliation between the virtual volumes on the source server and the archive files on the target server. You should also perform reconciliation if you have any other reason to suspect inconsistencies. For example, frequent communication errors between target and source servers could introduce a problem.

To perform reconciliation, issue the RECONCILE VOLUMES command specifying a device class of the device type of SERVER. In the following example TARGETCLASS is a server device class:

```
reconcile volumes targetclass fix=yes
```

The reconciliation action is determined by the FIX parameter as shown in the following table:

FIX=	At the Source Server	At the Target Server	Action
NO	Volumes exist	No files exist	Report error
		Files exist but are marked for deletion	
		Active files exist but attributes do not match	
	Volumes do not exist	Active files exist	Report error
		Files exist but are marked for deletion	None
YES	Volumes exist	No files exist	Report error For storage pool volumes: Mark volumes as unavailable
		Files exist but marked for deletion	Report error For storage pool volumes: If attributes match, mark files on the target server as active again, mark volumes on the source server as unavailable, and recommend that an AUDIT VOLUME be done to further verify the data. If attributes do not match, mark volumes as unavailable.
		Active files exist but attributes do not match	Report error For storage pool volumes: Mark volumes as unavailable and recommend that an AUDIT VOLUME be done to further verify the data.
	Volumes do not exist	Active files exist	Mark files for deletion on the target server.
		Files exist but marked for deletion	None

17

Managing Server Operations

Administrators can perform such server operations as licensing purchased features, starting and halting the server, and monitoring server information. See the following sections:

Tasks:
“Licensing Tivoli Storage Manager”
“Starting and Halting the Server” on page 359
“Changing the Date and Time on the Server” on page 365
“Managing Server Processes” on page 365
“Preemption of Client or Server Operations” on page 367
“Setting the Server Name” on page 368
“Adding or Updating Server Options” on page 368
“Automatic Tuning of Server Options” on page 369
“Getting Help on Commands and Error Messages” on page 369

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Licensing Tivoli Storage Manager

This section describes the tasks involved when licensing a TSM system, including registering, saving and auditing.

Task	Required Privilege Class
Register licenses Audit licenses	System
Display license information	Any administrator

For current information about supported clients and devices, visit the TSM page on the World Wide Web at http://www.tivoli.com/support/storage_mgr/tivolimain.html.

The base Tivoli Storage Manager feature includes the following support:

- An unlimited number of administrative clients.

- Enterprise Administration, which includes: command routing, enterprise configuration, and enterprise logging (server-to-server).
- Server-to-server Virtual Volume capabilities (does not include database and storage pool backup).
- Network Enabler (network connections for clients).
- AFS/DFS Support, (the S/390 platform includes the S/390 UNIX client as part of Managed System for SAN).

Registering Licensed Features

You must register a new license if you want to add support for any of the following features that are not already in your existing license agreement. A license file and the REGISTER LICENSE command are used to complete this task. Licenses are stored in enrollment certificate files, which contain licensing information for the server product. The enrollment certificate files are on the TSM installation CD-ROM. When registered, the licenses are stored in a NODELOCK file within the current directory.

Table 26. Licensed Features

License File Name	Description
1mgsylan.lic 5mgsylan.lic 10mgsylan.lic 50mgsylan.lic	Managed System for LAN Not required if the managed system also needs the Managed System for SAN.
1mgsyssan.lic 5mgsyssan.lic 10mgsyssan.lic 50mgsyssan.lic	Managed System for SAN Required for each managed system that moves data to and from storage over a storage area network (SAN). The Tape Library Sharing feature is required on the TSM server.
1spacemgr.lic 5spacemgr.lic 10spacemgr.lic 50spacemgr.lic	Each managed system that uses Tivoli Space Manager Also required: Managed System for LAN or Managed System for SAN license. Only one Managed System for LAN license is required if an HSM client and backup-archive client are on the same system with the same node ID.
1domino.lic 5domino.lic 10domino.lic 50domino.lic	Each managed system that uses Tivoli Data Protection for Lotus Domino Also required: Managed System for LAN or Managed System for SAN license
1emcsymm.lic 5emcsymm.lic 10emcsymm.lic 50emcsymm.lic	Each managed each managed system that uses Tivoli Data Protection for EMC Symmetrix Also required: Managed System for LAN or Managed System for SAN license
1emcsymr3.lic 5emcsymr3.lic 10emcsymr3.lic 50emcsymr3.lic	Each managed system that uses Tivoli Data Protection for EMC Symmetrix R/3 Also required: Managed System for LAN or Managed System for SAN license
1ess.lic 5ess.lic 10ess.lic 50ess.lic	Each managed system that uses Tivoli Data Protection for ESS Also required: Managed System for LAN or Managed System for SAN license

Table 26. Licensed Features (continued)

License File Name	Description
1essr3.lic 5essr3.lic 10essr3.lic 50essr3.lic	Each managed system that uses Tivoli Data Protection for ESS R/3 Also required: a Managed System for LAN or Managed System for SAN license.
1informix.lic 5informix.lic 10informix.lic 50informix.lic	Each managed system that uses Tivoli Data Protection for Informix Also required: a Managed System for LAN or Managed System for SAN license
1lnotes.lic 5lnotes.lic 10lnotes.lic 50lnotes.lic	Each managed system that uses Tivoli Data Protection for Lotus Notes Also required: Managed System for LAN or Managed System for SAN license
1msexch.lic 5msexch.lic 10msexch.lic 50msexch.lic	Each managed system that uses Tivoli Data Protection for MS Exchange Also required: Managed System for LAN or Managed System for SAN license
1mssql.lic 5mssql.lic 10mssql.lic 50mssql.lic	Each managed system that uses Tivoli Data Protection for MS SQL Server Also required: Managed System for LAN or Managed System for SAN license.
1oracle.lic 5oracle.lic 10oracle.lic 50oracle.lic	Each managed system that uses Tivoli Data Protection for Oracle Also required: Managed System for LAN or Managed System for SAN license.
1r3.lic 5r3.lic 10r3.lic 50r3.lic	Each managed system that uses Tivoli Data Protection for R/3 Also required: Managed System for LAN or Managed System for SAN license.
1library.lic 5library.lic	Managed Library Required for each library in the Extended Device Category that is managed by a TSM server. For current information on supported devices, visit the TSM page on the World Wide Web at http://www.tivoli.com/support/storage_mgr/tivolimain.html .
drm.lic	Tivoli Disaster Recovery Manager (includes server-to-server virtual volumes for database and storage pool backup) Required on a source server but not on a target server.
libshare.lic	Tape Library Sharing Required on a TSM server that can access a shared library, including the library manager. The Managed Library license is required only on the library manager.

To register a license, you must issue the REGISTER LICENSE command as well as the license file associated with the license. For example, to use the Tivoli Disaster Recovery Manager and two Tivoli Space Manager (HSM clients), issue the following commands:

```
register license file=drm.lic
register license file=1spacemgr.lic number=2
register license file=1mgyslan.lic number=2
```

To register 20 managed systems that move data over a local area network, issue the following command:

```
register license file=10mgsyslan.lic number=2
```

To register 10 Tivoli Data Protection for Lotus Notes clients that move data over a LAN, issue the following commands:

```
register license file=10lnotes.lic  
register license file=10mgsyslan.lic
```

With the exception of the `drm.lic` and `libshare.lic`, you can specify license files in increments of 1, 5, 10, or 50. These increments minimize the number of license statements in the `nodelock` file of the current directory. For example, to register TSM for 510 managed systems that move data over a local area network, issue the following commands:

```
register license file=50mgsyslan.lic number=10  
register license file=10mgsyslan.lic
```

By using the license increments together with the `NUMBER` parameter, TSM creates only 11 entries in the `nodelock` file instead of 510 individual entries.

You can also register a license by specifying the product password that is included in the license certificate file. For example:

```
register license 5s3qydpnwx7njdxnafksqas4
```

Attention: TSM licenses are associated with the CPU chip of the machine on which TSM is installed. If you change that CPU chip, you must first erase the existing `nodelock` files and then reregister all your licenses.

Saving Your Licenses

Save the CD-ROM containing your enrollment certificate files if you need to register your licenses again for any of the following reasons:

- The server is corrupted.
- The server is moved to a different machine.
- The *Nodelock* file is destroyed or corrupted. TSM stores license information in the *Nodelock* file, which is located in the directory from which the server is started.

Monitoring Licenses

When license terms change (for example, a new license is specified for the server), the server conducts an audit to determine if the current server configuration conforms to the license terms. The server also periodically audits compliance with license terms. The results of an audit are used to check and enforce license terms. If 30 days have elapsed since the previous license audit, the administrator cannot cancel the audit.

If a TSM system exceeds the terms of its license agreement, one of the following occurs:

- The server issues a warning message indicating that it is not in compliance with the licensing terms.
- Operations fail because the server is not licensed for specific features.

You must contact your TSM account representative or authorized reseller to modify your agreement.

An administrator can monitor license compliance by:

Auditing licenses

Use the `AUDIT LICENSES` command to compare the current configuration with the current licenses.

Note: During a license audit, the server calculates, by node, the amount of backup, archive, and space management storage in use. This calculation can take a great deal of CPU time and can stall other server activity. Use the `AUDITSTORAGE` server option to specify that storage is not to be calculated as part of a license audit.

Displaying license information

Use the `QUERY LICENSE` command to display details of your current licenses and determine licensing compliance.

Scheduling automatic license audits

Use the `SET LICENSEAUDITPERIOD` command to specify the number of days between automatic audits.

Starting and Halting the Server

Task	Required Privilege Class
Start, halt, and restart the server	System or operator

Starting the Server

The following events occur when you start or restart the TSM server:

- The server invokes the communication methods specified in the server options file.
- The server uses the volumes specified in the `dsmserv.dsk` file for the database and recovery log to record activity. It also identifies storage pool volumes to be used.
- The server starts a TSM server console session that is used to operate and administer the server until administrative clients are registered to the server.

To start the server, complete the following steps:

1. Change to the `/usr/tivoli/tsm/server/bin` directory from an AIX session.

Enter:

```
cd /usr/tivoli/tsm/server/bin
```

2. Start the server by entering:

```
dsmserv
```

Note: If the server does not start, set the `ulimit` parameter to unlimited. For example,

```
ulimit -d unlimited
```

When the server is started, TSM displays the following information:

- Product licensing and copyright information
- Processing information about the server options file
- Communication protocol information
- Database and recovery log information
- Storage pool volume information
- Server generation date

-
- Progress messages and any errors encountered during server initialization

If TSM detects an invalid system date and time, the server is disabled, and expiration, migration, reclamation, and volume history deletion operations are not allowed. An error message (ANR0110E) is displayed. You may either change the system date if it is in error, or issue the ACCEPT DATE command to force the server to accept the current system date as valid. After the system date is resolved, you must issue the ENABLE SESSIONS command to re-enable the server for client sessions.

The date and time check occur when the server is started and once each hour thereafter. An invalid date is one that is:

- Earlier than the server installation date and time
- More than one hour earlier than the last time the date was checked
- More than 30 days later than the last time the date was checked

Running the Server in Background Mode

You may choose to run the server in the background. When the server runs in the background, you control the server through your administrative client.

Attention: Before running the server in the background, ensure the following conditions exist:

1. An administrative node has been registered and granted system authority. See “Registering Administrators” on page 222.
2. The administrative client options file has been updated with the correct SERVERNAME and TCPPOINT options.
3. The administrative client can access the TSM server.

If you do not follow these steps, you cannot control the server. When this occurs, you can only stop the server by canceling the process, using the process number displayed at startup. You may not be able to take down the server cleanly without this process number.

To start the server running in the background, enter the following:

```
nohup dsmserv -quiet &
```

You can check your directory for the output created in the nohup.out file to determine if the server has started. This file can grow considerably over time.

Capturing Server Console Messages to a User Log File

You can capture TSM server console messages to a user log file with the TSM dsmulog utility. You can invoke the utility with the ADSMSTART shell script which is provided as part of the TSM AIX server package. You can have the server messages written to one or more user log files. When the dsmulog utility detects that the server it is capturing messages from is stopped or halted, it closes the current log file and ends its processing.

When you specify more than one file, TSM manages the user logs as a circular list of files based on size or change of day. You can manage the amount of space the logs used in the file system by specifying a size parameter (in kilobytes) in the ADSMSTART shell script for the dsmulog utility. When the specified limit is reached, TSM closes the current user log and opens the next user log. When the specified limit is reached on the next user log, TSM

writes to the next user log and can overwrite the previous contents of the file. If a size parameter is not specified, the utility writes to the next user log file when it detects a change of day.

If the user log file names are not fully qualified in the ADSMSTART shell script, the user logs are created in the directory where ADSMSTART is invoked. The user logs should not be placed in the /usr/lpp file system because space constraints in the file system can prevent the TSM server from starting.

The following is an example of how to set up and invoke the dsmulog utility to rotate through the user logs on a daily basis:

1. Change to the server bin directory:

```
cd /usr/tivoli/tsm/server/bin
```
2. Copy ADSMSTART.SMP to ADSMSTART:

```
cp adsmstart.smp ./adsmstart
```
3. Edit ADSMSTART. Do NOT change the first line in the file. Specify the user log files to capture messages on a daily basis. For example:

```
dsmulog /u/admin/log1 /u/admin/log2 /u/admin/log3
```

The following steps automatically start the server with console logging when the system is rebooted:

4. If the server is running, halt the server.
5. Run the *dsm_rmv_itab autostart* script.
6. Run the *dsm_update_itab autotrace* script.
7. Restart the server in one of the following ways:
 - If you restart the server by running the ADSMSTART script, the server runs in the foreground and all console output is sent to the specified user logs.
 - If you restart the server by issuing *nohup adsmstart &*, the server runs in the background and all console output is sent to the specified user logs. You must then use an administrative client session to halt the server.

In the above example, if you invoke the utility on Friday, on Friday the server messages are captured to log1, on Saturday the messages are captured to log2, and on Sunday the messages are captured to log3. On Monday the messages are captured to log1 and the previous Friday messages are overwritten.

The following example shows how to invoke the dsmulog utility to rotate through the user logs based on size limit:

```
dsmulog /u/admin/log1 /u/admin/log2 /u/admin/log3 size=500
```

When the server is started, the utility captures the server messages to log1 until it reaches a file size of 500 kilobytes and then changes to log2.

Tip: If the TSM server goes down unexpectedly, copy the current user logs to other file names before you restart the server. This will prevent the dsmulog utility from overwriting the current logs. You can then view the user logs to try and determine the cause of the unavailability of the server.

To log console messages during the current session, do the following:

1. If the server is running, halt the server.
2. Issue the `dsmserv` command as specified in the `ADSMSTART` shell script. For example:
| `/usr/tivoli/tsm/server/bin/dsmserv 2>&1 | dsmu log /u/admin/log1 /u/admin/log2`

To stop console logging and have the server automatically start after a system reboot, complete the following steps:

1. If the server is running, halt the server.
2. Change to the server bin directory:
| `cd /usr/tivoli/tsm/server/bin`
3. Run the `dsm_rmv_itab autotrace` script.
4. Run the `dsm_update_itab autostart` script.
5. Restart the server by running the `rc.admserv` script. This script starts the server in the quiet mode.

Starting the Server in Other Modes

The following TSM command options specify how you can start the server in other modes as part of the `dsmserv` command. For example:

`dsmserv option`

Where *option* can be any one of the following:

quiet Starts the server as a daemon program. The server runs as a background process, and does not read commands from the server console. Output messages are directed to the `SERVER_CONSOLE`.

Note: Before issuing this command, you must have an administrative client registered and authorized with system authority. The administrative client must be started. Otherwise, the server will run in the quiet mode and you will not be able to access the server.

-o filename

Specifies an explicit options file name when running more than one server.

Defining Environment Variables

If you want to run the TSM server from a directory other than the default directory or to run multiple servers, you may have to define environment variables.

An *environment variable* describes the operating environment of a process, such as the home directory or the terminal in use. It provides the path that the server requires to find and create files.

For example, to define the `DSMSERV_DIR` environment variable to point to the `usr/lpp/admserv/bin` directory so that the server can find various files, such as `dsmreg.lic` or the message file (`dsmameng.txt`) enter:

| `export DSMSERV_DIR=/usr/tivoli/tsm/server/bin`

You can also define an environment variable to point to the server options file. For example, to define the `DSMSERV_CONFIG` environment variable to point to the server options file, enter:


```
| export DSMSERV_CONFIG=/usr/tivoli/tsm/server/bin/ filename.opt
```

where *filename* is the name you assigned your server options file (dsmserv.opt).

Notes:

1. The -o parameter of the DSMSERV command can also be used to specify an options file name.
2. The *set environment* command:


```
| setenv DSMSERV_DIR /usr/tivoli/tsm/server/bin
```

is issued if your shell is in the "csh" family.
3. If you want to save this environment, save these entries in the *.kshrc* or the *.cshrc* file of your \$HOME directory.
4. The dsmserv.dsk is always read from the directory in which the server is started.

Running Multiple Servers on a Single Machine

To have multiple servers running on a single machine, issue the DSMSERV FORMAT command from different directories to create multiple pairs of recovery log and database files. You do not have to install the server executable files in more than one directory.

However, if non-root users will be running servers, you must modify the access permission by adding read permission to the following files:

- dsmlicense
- dsmtli.drv

Use these commands as a root user to modify the permission for these files:

```
| chmod 755 /usr/tivoli/tsm/server/bin/dsmlicense
| chmod 755 /usr/tivoli/tsm/server/bin/dsmtli.drv
```

The following procedure shows how to set up an additional TSM server:

1. Determine the directory where you want the server files created, for example, /usr/tivoli/tsm/myserver, and make that directory:

```
| mkdir /usr/tivoli/tsm/myserver
```

2. Copy the dsmserv.opt file to your directory:

```
| cp /usr/tivoli/tsm/server/bin/dsmserv.opt
| dsmserv.opt /usr/tivoli/tsm/myserver/dsmserv.opt
```

Note: Ensure that the communication parameters are unique among all other TSM servers. The communication protocols are:

- TCPPOINT for TCP/IP
- HTTPPOINT for HTTP Access in the Web Administrative Client Browser

For example, if your first server is using the default TCPport of 1500, ensure that the new server is using a TCPport other than 1500 by providing a real value in the server options file.

3. Set your path on the server console or from an aixterm session. Define your environment variables, for example:

To define the DSMSERV_DIR, enter:

```
export DSMSERV_DIR=/usr/tivoli/tsm/server/bin
```

Ensure that you are in the target directory before continuing.

4. Format the database and recovery log files, for example:

```
/usr/tivoli/tsm/server/bin/dsmfmt -m -db dbvol2 5  
/usr/tivoli/tsm/server/bin/dsmfmt -m -log logvol2 9
```

In this example, db indicates the database log, -m indicates megabytes and log indicates the recovery log. Refer to *Administrator's Reference* for more information on these commands.

5. Create the database and recovery log in the desired directory for the new server, for example:

```
/usr/tivoli/tsm/server/bin/dsmserv format 1 logvol2 1 dbvol2
```

Note: You need additional license authorizations to run additional servers. You can use the register license file command to register these licenses. See “Registering Licensed Features” on page 356 for more information.

Halting the Server

You can halt the server without warning if an unplanned operating system problem requires the server to be stopped.

When you halt the server, all processes are abruptly stopped and client sessions are canceled, even if they are not complete. Any in-progress transactions are rolled back when the server is restarted. Administrator activity is not possible.

If possible, halt the server only after current administrative and client node sessions have completed or canceled. To shut down the server without severely impacting administrative and client node activity with the server, you must:

1. Disable the server to prevent new client node sessions from starting by issuing the DISABLE SESSIONS command. This command does not cancel sessions currently in progress or system processes like migration and reclamation.
2. Notify any existing administrative and client node sessions that you plan to shut down the server. The server does not provide a network notification facility; you must use external means to notify users.
3. Cancel any existing administrative or client node sessions by issuing the CANCEL SESSION command and the associated session number. To obtain session numbers and determine if any sessions are running, use the QUERY SESSION command. If a session is running, a table will appear showing the session number on the far left side of the screen.
4. Find out if any other processes are running, such as server migration or inventory expiration, by using the QUERY PROCESS command. If a database backup process is running, allow it to complete before halting the server. If other types of processes are running, cancel them by using the CANCEL PROCESS command.

Note: If the process you want to cancel is currently waiting for a tape volume to be mounted (for example, a process initiated by EXPORT, IMPORT, or MOVE DATA commands), the mount request is automatically cancelled. If a volume associated with the process is currently being mounted by an *automated* library, the cancel may not take effect until the mount is complete.

5. Halt the server to shut down all server operations by using the HALT command.

Note: The QUIESCE option on the HALT command is recommended *only* if you plan to do a database dump by using the DSMSEV DUMPDB command immediately after halting. Because TSM supports online database backup (BACKUP DB command), the DSMSEV DUMPDB command should be rarely, if ever, needed.

Stopping the Server When Running as a Background Process

If you started the server as a background process and want to stop the server, connect to the server as an administrative client and issue the HALT command. If you cannot connect to the server with an administrative client and you want to stop the server, you must cancel the process by using the **kill** command with the process ID number (pid) that is displayed at initialization.

Note: Before you issue the **kill** command, ensure that you know the correct process ID for the TSM server.

Changing the Date and Time on the Server

Every time the server is started and for each hour thereafter, a date and time check occurs. An invalid date can be one of the following:

- Earlier than the server installation date and time.
- More than one hour earlier than the last time the date was checked.
- More than 30 days later than the last time the date was checked.

If the server detects an invalid date or time, server sessions become disabled. An error message (ANR0110E) is displayed and expiration, migration, reclamation, and volume history deletion operations are not allowed. You may either change the system date if it is in error, or issue the ACCEPT DATE command to force the server to accept the current system date as valid. Use the ENABLE SESSIONS command after you issue the ACCEPT DATE command to re-enable the server for client node activity.

Managing Server Processes

Task	Required Privilege Class
Display information about a server background process	Any administrator
Cancel a server process	System

When a user or administrator issues a TSM command or uses a graphical user interface to perform an operation, the server starts a process. Some examples of an operation are registering a client node, deleting a management class, or canceling a client session.

Most processes occur quickly and are run in the foreground, but others that take longer to complete run as background processes.

The server runs the following operations as background processes:

- Auditing an automated library
- Auditing licenses

- Auditing a volume
- Backing up the database
- Backing up a storage pool
- Checking volumes in and out of an automated library
- Defining a database volume copy
- Defining a recovery log volume copy
- Deleting a database volume
- Deleting a file space
- Deleting a recovery log volume
- Deleting a storage volume
- Expiring the inventory
- Exporting or importing data
- Extending the database or recovery log
- Generating a backup set
- Migrating files from one storage pool to the next storage pool
- Moving data from a storage volume
- Reclaiming space from tape storage volumes
- Reducing the database or recovery log
- Restoring a storage pool
- Restoring a volume
- Varying a database or recovery log volume online

The server assigns each background process an ID number and displays the process ID when the operation starts. This process ID number is used for tracking purposes. For example, if you issue an EXPORT NODE command, the server displays a message similar to the following:

```
EXPORT NODE started as Process 10
```

Some of these processes can also be run in the foreground by using the WAIT=YES parameter when you issue the command from an administrative client. See *Administrator's Reference* for details.

Requesting Information about Server Processes

You can request information about server background processes. If you know the process ID number, you can use the number to limit the search. However, if you do not know the process ID, you can display information about all background processes by entering:

```
query process
```

The following figure shows a server background process report after a DELETE FILESPACE command was issued. The report displays a process ID number, a description and a completion status for each background process.

Process Number	Process Description	Status
2	DELETE FILESPACE	Deleting filesystem DRIVE_D for node CLIENT1: 172 files deleted.

Canceling Server Processes

You can cancel a server background process by specifying its ID number in the following command:

```
cancel process 2
```

You can issue the QUERY PROCESS command to find the process number. See “Requesting Information about Server Processes” on page 366 for details.

If the process you want to cancel is currently waiting for a tape volume to be mounted (for example, a process initiated by EXPORT, IMPORT, or MOVE DATA commands), the mount request is automatically canceled. If a volume associated with the process is currently being mounted by an *automated* library, the cancel may not take effect until the mount is complete.

Preemption of Client or Server Operations

The server can preempt server or client operations for a higher priority operation when a mount point is in use and no others are available, or access to a specific volume is required.

Mount Point Preemption

The following are high priority operations that can preempt operations for a mount point:

- Backup database
- Restore
- Retrieve
- HSM recall
- Export
- Import

The following lists operations that can be preempted and are listed in order of priority. The server selects the lowest priority operation to preempt, for example reclamation.

1. Move data
2. Migration from disk to sequential media
3. Backup, archive, or HSM migration
4. Migration from sequential media to sequential media
5. Reclamation

You can disable preemption by specifying NOPREEMPT in the server options file. When this option is specified, the BACKUP DB command is the only operation that can preempt other operations.

Volume Access Preemption

A high priority operation that requires access to a specific volume currently in use by a low priority operation can automatically preempt the operation. For example, if a restore request requires access to a volume in use by a reclamation process and a drive is available, the reclamation process is canceled and message ANR0494I or ANR1441I is issued.

The following are high priority operations that can preempt operations for access to a specific volume:

- Restore
- Retrieve
- HSM recall

The following lists operations that can be preempted, and are listed in order of priority. The server preempts the lowest priority operation, for example reclamation.

1. Move data
2. Migration from disk to sequential media
3. Backup, archive, or HSM migration
4. Migration from sequential media
5. Reclamation

You can disable preemption by specifying `NOPREEMPT` in the server options file. When this option is specified, no operation can preempt another operation for access to a volume.

Setting the Server Name

Task	Required Privilege Class
Specify the server name	System

At installation, the server name is set to `SERVER1`. After installation, you can use the `SET SERVERNAME` command to change the server name. You can use the `QUERY STATUS` command to see the name of the server.

To specify the server name as `WELLS_DESIGN_DEPT.`, for example, enter the following:
`set servername wells_design_dept.`

You must set unique names on servers that communicate with each other. See “Setting Up Communications Among Servers” on page 314 for details.

Adding or Updating Server Options

Task	Required Privilege Class
Add or update a server option	System

You can add or update server options by editing the `dsmserv.opt` file, using the `SETOPT` command. For information about editing the server options file, refer to *Administrator's Reference*.

Adding or Updating a Server Option without Restarting the Server

A system administrator can add or update a limited number of server options without stopping and restarting the server. The added or updated server option is appended to the end of the server options file.

The following example shows how to use the `SETOPT` command to update the existing server option for `MAXSESSIONS`:

```
setopt maxsessions 20
```

The following lists server options that can be added or updated:

```
BUFPOOLSIZE  
COMMTIMEOUT  
EXPINTERVAL
```

EXPQUIET
IDLETIMEOUT
MAXSESSIONS

| THROUGHPUTDATATHRESHOLD
| THROUGHPUTTIMETHRESHOLD

Note: SETOPT commands in a macro cannot be rolled back.

Automatic Tuning of Server Options

For optimal performance, the server can tune the following server options automatically:

- **MOVEBATCHSIZE and MOVESIZETHRESH**
To have the server automatically tune the MOVEBATCHSIZE and MOVESIZETHRESH options, set the SELFTUNETXNSIZE option to Yes. When the server performs an internal data movement operation, such as migration, reclamation, move data, storage pool backup or restore, it will adjust these values to achieve optimal performance. To prevent running out of log space during these operations, use the DEFINE SPACETRIGGER command to allow for expansion of the recovery log.
- **BUFPOOLSIZE**
To have the server automatically tune the BUFPOOLSIZE option, set the SELFTUNEBUFPOOLSIZE option to Yes. Before expiration processing, the server resets the database buffer pool and examines the database buffer pool cache hit ratio. The server accounts for the amount of available storage and adjusts the buffer pool size as needed.

| **Note:** Although the values of TXNGROUPMAX, MOVEBATCHSIZE, and
| MOVESIZETHRESH may be changed, the settings in the server options file are not
| changed. Issuing a QUERY OPTION command displays only what is set in the server
| options file.

For information about the SELFTUNEBUFPOOLSIZE and SELFTUNETXNSIZE server options, refer to *Administrator's Reference*.

Getting Help on Commands and Error Messages

Any administrator can issue the HELP command to display information about administrative commands and messages from the server and the administrative command-line client. You can issue the HELP command with no operands to display a menu of help selections. You also can issue the HELP command with operands that specify help menu numbers, commands, or message numbers.

To display the help menu, enter:

```
help
```

To display help information on the REMOVE commands, enter:

```
help remove
```

To display help information on a specific message, such as ANR0992I for example, enter:

```
help 0992
```

Additional information is also available in the online documentation.

18

Automating Server Operations

Administrative commands can be scheduled for use in tuning server operations and to start functions that require significant server or system resources during times of low usage. Automating these operations allows the administrator to ensure that server resources are available when needed by clients.

An administrator can automate the process of issuing a sequence of commands by storing the commands in a server script. From the command line, the administrator can immediately process the script or schedule the script for processing.

TSM includes a central scheduling component that allows the automatic processing of administrative commands during a specific time period when the schedule is activated.

Each scheduled administrative command is called an *event*. Each scheduled event is tracked by the server and recorded in the database. Event records can be deleted from the database as needed to recover database space.

See the following sections:

Tasks:
“Automating a Basic Administrative Command Schedule”
“Tailoring Schedules” on page 373
“Copying Schedules” on page 375
“Deleting Schedules” on page 375
“Managing Scheduled Event Records” on page 375
“Tivoli Storage Manager Server Scripts” on page 376
“Using Macros” on page 383

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Automating a Basic Administrative Command Schedule

This section describes how to set up a basic administrative command schedule using TSM defaults. To later update or tailor your schedules, see “Tailoring Schedules” on page 373.

Notes:

1. Scheduled administrative command output is directed to the activity log. This output cannot be redirected. For information about the length of time activity log information is retained in the database, see “Using the Tivoli Storage Manager Activity Log” on page 416.
2. You cannot schedule MACRO or QUERY ACTLOG commands.

Task	Required Privilege Class
Define, update, copy, or delete administrative schedules	System
Display information about scheduled operations	Any administrator

Defining the Schedule

Use the DEFINE SCHEDULE command to create a new schedule to process an administrative command. Include the following parameters:

- Specify the administrative command to be issued (CMD=).
- Specify whether the schedule is to be activated (ACTIVE=).

For example:

```
define schedule backup_archivepool type=administrative  
cmd='backup stgpool archivepool recoverypool' active=yes
```

This command results in the following:

- The schedule created is *BACKUP_ARCHIVEPOOL*.
- The schedule is to process the administrative command:
backup stgpool archivepool recoverypool

This command specifies that primary storage pool ARCHIVEPOOL is backed up to the copy storage pool RECOVERYPOOL.

- The schedule is currently active.
- Administrative command output is redirected to the activity log.
- The following defaults are in effect:
 - The start date and time defaults to the current date and time.
 - The length of the startup window is 1 hour.
 - The priority for the schedule is 5. If schedules conflict, the schedule with the highest priority (lowest number) is run first.
 - The schedule never expires.

To change the defaults, see “Tailoring Schedules” on page 373.

Verifying the Schedule

You can verify the details of what you have scheduled by using the QUERY SCHEDULE command. When you use the QUERY SCHEDULE command, you must specify the TYPE=ADMINISTRATIVE parameter to view an administrative command schedule. The following figure shows an example of a report that is displayed after you enter:

```
query schedule backup_archivepool type=administrative
```

* Schedule Name	Start Date/Time	Duration	Period	Day
-----	-----	-----	-----	---
BACKUP_ARCHIVE- OOL	03/15/1998 14:08:11	1 H	1 D	Any

Note: The asterisk (*) in the first column specifies whether the corresponding schedule has expired. If there is an asterisk in this column, the schedule has expired.

You can check when the schedule is projected to run and whether it ran successfully by using the QUERY EVENT command. For information about querying events, see “Querying Events” on page 375.

Tailoring Schedules

To control more precisely when and how your schedules run, you can specify values for schedule parameters instead of accepting the defaults when you define or update schedules.

Schedule name

All schedules must have a unique name, which can be up to 30 characters.

Initial start date, time, and day

You can specify a past date, the current date, or a future date for the initial start date for a schedule with the STARTDATE parameter.

You can specify a start time, such as 6 p.m. with the STARTTIME parameter.

You can also specify the day of the week on which the startup window begins with the DAYOFWEEK parameter. If the start date and start time fall on a day that does not correspond to your value for the day of the week, the start date and time are shifted forward in 24-hour increments until the day of the week is satisfied.

If you select a value for the day of the week other than ANY, then depending on the values for PERIOD and PERUNITS, schedules may not be processed when you expect. Use the QUERY EVENT command to project when schedules will be processed to ensure that you achieve the desired result.

Duration of a startup window

You can specify the duration of a startup window, such as 12 hours, with the DURATION and DURUNITS parameters. The server must start the scheduled service within the specified duration but does not necessarily complete it within that period of time. If the schedule needs to be retried for any reason, the retry attempt must begin before the startup window elapses or the operation does not restart.

If the schedule does not start during the startup window, the server records this as a *missed event* in the database. To identify any schedules that may have been missed, you can get an exception report from the server for events. For more information, see “Querying Events” on page 375.

How often to run the scheduled service

You can set the schedule frequency based on a period of hours, days, weeks, months, or years with the PERIOD and PERUNITS parameters. To have weekly backups, for example, set the period to one week with PERIOD=1 and PERUNITS=WEEKS.

Expiration date

You can specify an expiration date for a schedule with the EXPIRATION parameter if the services it initiates are required for only a specific period of time. If you set an expiration date, the schedule is not used after that date, but it still exists. You must delete the schedule to remove it from the database.

Priority

You can assign a priority to schedules with the PRIORITY parameter. For example, if you define two schedules and they have the same startup window or windows overlap, the server runs the schedule with the highest priority first. A schedule with a priority of 1 is started before a schedule with a priority of 3.

If two schedules try to use the same resources, the schedule that first initiated the process will be the one to continue processing. The second schedule will start but will not successfully complete. Be sure to check the activity log for details.

Administrative schedule name

If you are defining or updating an administrative command schedule, you **must** specify the schedule name.

Type of schedule

If you are updating an administrative command schedule, you **must** specify TYPE=ADMINISTRATIVE on the UPDATE command. If you are defining a new administrative command schedule, this parameter is assumed if the CMD parameter is specified.

Command

When you define an administrative command schedule, you **must** specify the complete command that is processed with the schedule with the CMD parameter. These commands are used to tune server operations or to start functions that require significant server or system resources. The functions include:

- Migration
- Reclamation
- Export and import
- Database backup

Whether or not the schedule is active

Administrative command schedules can be active or inactive when they are defined or updated. Active schedules are processed when the specified command window occurs. Inactive schedules are not processed until they are made active by an UPDATE SCHEDULE command with the ACTIVE parameter set to YES.

Example: Defining and Updating an Administrative Command Schedule

To schedule the backup of the ARCHIVEPOOL primary storage pool, enter:

```
define schedule backup_archivepool type=administrative
cmd='backup stgpool archivepool recoverypool'
active=yes starttime=20:00 period=2
```

This command specifies that, starting today, the ARCHIVEPOOL primary storage pool is to be backed up to the RECOVERYPOOL copy storage pool every two days at 8 p.m.

To update the BACKUP_ARCHIVEPOOL schedule, enter:

```
update schedule backup_archivepool type=administrative
starttime=22:00 period=3
```

Starting with today, the `BACKUP_ARCHIVEPOOL` schedule begins the backup every three days at 10 p.m.

Copying Schedules

You can create a new schedule by copying an existing administrative schedule. When you copy a schedule, TSM copies the following information:

- A description of the schedule
- All parameter values from the original schedule

You can then update the new schedule to meet your needs.

To copy the `BACKUP_ARCHIVEPOOL` administrative schedule and name the new schedule `BCKSCHED`, enter:

```
copy schedule backup_archivepool bcksched type=administrative
```

Deleting Schedules

To delete the administrative schedule `ENGBKUP`, enter:

```
delete schedule engbkup type=administrative
```

Managing Scheduled Event Records

Task	Required Privilege Class
Display information about events	Any administrator
Set the retention period for event records	System
Delete event records	System or unrestricted policy

Each scheduled administrative command operation is called an *event*. All scheduled events, including their status, are tracked by the server. An *event record* is created in the server database whenever processing of a scheduled command is created or missed.

Querying Events

To help manage schedules for administrative commands, you can request information about scheduled and completed events. You can request general or exception reporting queries.

- To get information about past and projected scheduled processes, use a general query. If the time range you specify includes the future, the query output shows which events should occur in the future based on current schedules.
- To get information about scheduled processes that did not complete successfully, use exception reporting.

To minimize the processing time when querying events, minimize the time range.

To query an event for an administrative command schedule, you must specify the `TYPE=ADMINISTRATIVE` parameter. Figure 61 on page 376 shows an example of the results of the following command:

```
query event * type=administrative
```

Scheduled Start	Actual Start	Schedule Name	Status
03/17/1998 14:08:11	03/17/1998 14:08:14	BACKUP_ARCHI-VEPOOL	Completed

Figure 61. Query Results for an Administrative Schedule

Removing Event Records from the Database

You can specify how long event records stay in the database before the server deletes them. You can also manually remove event records from the database.

If you issue a query for events, past events may be displayed even if the event records have been deleted. The events displayed with a status of *Uncertain* indicate that complete information is not available because the event records have been deleted. To determine if event records have been deleted, check the message that is issued after the DELETE EVENT command is processed.

Setting the Event Record Retention Period

You can specify the retention period for event records in the database. After the retention period passes, the server automatically removes the event records from the database. At installation, the retention period is set to 10 days.

To set the retention period to 15 days, enter:

```
set eventretention 15
```

Event records are automatically removed from the database after both of the following conditions are met:

- The specified retention period has passed
- The startup window for the event has elapsed

Deleting Event Records

Because event records are deleted automatically, you do not have to manually delete them from the database. However, you may want to manually delete event records to increase available database space.

To delete all event records written prior to 11:59 p.m. on June 30, 1998, enter:

```
delete event type=administrative 06/30/1998 23:59
```

Tivoli Storage Manager Server Scripts

TSM provides for automation of common administrative tasks with server scripts that are stored in the database. The scripts can be processed directly on the server console, the web interface, or included in an administrative command schedule. TSM provides sample scripts in *scripts.smp*. The sample scripts have an example order of execution for scheduling administrative commands. For more information, see “Using SELECT Commands in Tivoli Storage Manager Scripts” on page 414. The sample scripts can be loaded from the *scripts.smp* file by issuing the runfile command. See *Quick Start* for details.

The administrator can run the script by issuing the RUN command from the web administrative interface, or scheduling the script for processing using the administrative

command scheduler on the server. If one of the specified commands in the script does not process successfully, the remaining commands are not processed.

TSM scripts can include the following:

- Command parameter substitution.
- SQL SELECT statements that you specify when the script is processed.
- Conditional logic flow statements. These logic flow statements include:
 - The IF clause; this clause determines how processing should proceed based on the current return code value.
 - The EXIT statement; this statement ends script processing.
 - The GOTO and LABEL statement; this statement directs logic flow to continue processing with the line that starts with the label specified.
 - Comment lines

Defining a Server Script

Task	Required Privilege Class
Define a server script	System, policy, storage, and operator

You can define a server script line by line, create a file that contains the command lines, or copy an existing script.

The following examples use commands to define and update scripts. However, you can easily define and update scripts using the web administrative interface where you can also use local workstation cut and paste functions.

You can define a script with the DEFINE SCRIPT command. You can initially define the first line of the script with this command. For example:

```
define script qaixc "select node_name from nodes where platform='aix'"
desc='Display AIX clients'
```

This example defines the script as QAIXC. When you run the script, all AIX clients are displayed.

To define additional lines, use the UPDATE SCRIPT command. For example, you want to add a QUERY SESSION command, enter:

```
update script qaixc "query session *"
```

You can specify a WAIT parameter with the DEFINE CLIENTACTION command that allows the client action to complete before processing the next step in a command script or macro. See *Administrator's Reference* for information

You can use the ISSUE MESSAGE command to determine where a problem is within a command in a script. See *Administrator's Reference* for information on how to use the ISSUE MESSAGE command.

For additional information about updating server scripts, or updating a command line, see "Updating a Script" on page 380.

Defining a Server Script Using Contents of Another File

You can define a script whose command lines are read in from another file that contains statements for the script to be defined. For example, to define a script whose command lines are read in from the file BKUP12.MAC, issue:

```
define script admin1 file=bkup12.mac
```

The script is defined as ADMIN1 and the contents of the script have been read in from the file BKUP12.MAC.

Note: The file must reside on the server, and is read by the server.

Using Continuation Characters for Long Commands

You can continue long commands across multiple command lines by specifying the continuation character (-) as the last character for a command that is continued. The following example continues an SQL statement across multiple command lines:

```
/*-----*/  
/* Sample continuation example */  
SELECT-  
* FROM-  
NODE WHERE-  
PLATFORM='win32'
```

When this command is processed, it runs the following:

```
select * from nodes where platform='win32'
```

Using Substitution Variables

You can include substitution variables in a script. Substitution variables are specified with a \$ character followed by a number that represents the position of the parameter when the script is processed. The following example SQLSAMPLE script specifies substitution variables \$1 and \$2:

```
/*-----*/  
/* Sample substitution example */  
/* -----*/  
SELECT-  
$1 FROM-  
NODES WHERE-  
PLATFORM='$2'
```

When you run the script you must specify two values, one for \$1 and one for \$2. For example:

```
run sqlsample node_name aix
```

The command that is processed when the SQLSAMPLE script is run is:

```
select node_name from nodes where platform='aix'
```

Using Logic Flow Statements in a Script

You can use conditional logic flow statements based on return codes issued from previous command processing. These logic statements allow you to process your scripts based on the outcome of certain commands. You can use IF, EXIT, or GOTO (label) statements.

As each command is processed in a script, the return code is saved for possible evaluation before the next command is processed. The return code can be one of three severities: OK, WARNING, or ERROR. Refer to *Administrator's Reference* for a list of valid return codes and severity levels.

Specifying the IF Clause

You can use the IF clause at the beginning of a command line to determine how processing of the script should proceed based on the current return code value. In the IF clause you specify a return code symbolic value or severity.

The server initially sets the return code at the beginning of the script to RC_OK. The return code is updated by each processed command. If the current return code from the processed command is equal to any of the return codes or severities in the IF clause, the remainder of the line is processed. If the current return code is not equal to one of the listed values, the line is skipped.

The following script example backs up the BACKUPPOOL storage pool only if there are no sessions currently accessing the server. The backup proceeds only if a return code of RC_NOTFOUND is received:

```
/* Backup storage pools if clients are not accessing the server */
select * from sessions
/* There are no sessions if rc_notfound is received */
if(rc_notfound) backup stg backuppool copypool
```

The following script example backs up the BACKUPPOOL storage pool if a return code with a severity of warning is encountered:

```
/* Backup storage pools if clients are not accessing the server */
select * from sessions
/* There are no sessions if rc_notfound is received */
if(warning) backup stg backuppool copypool
```

Specifying the EXIT Statement

The EXIT statement ends script processing. The following example uses the IF clause together with RC_OK to determine if clients are accessing the server. If a RC_OK return code is received, this indicates that client sessions are accessing the server. The script proceeds with the exit statement and the backup is not started.

```
/* Back up storage pools if clients are not accessing the server */
select * from sessions
/* There are sessions if rc_ok is received */
if(rc_ok) exit
backup stg backuppool copypool
```

Specifying the GOTO Statement

The GOTO statement is used in conjunction with a label statement. The label statement is the target of the GOTO statement. The GOTO statement directs script processing to the line that contains the label statement to resume processing from that point. The label statement always has a colon (:) after it and may be blank after the colon.

The following example uses the GOTO statement to back up the storage pool only if there are no sessions currently accessing the server. In this example, the return code of RC_OK indicates that clients are accessing the server. The GOTO statement directs processing to the **done:** label which contains the EXIT statement that ends the script processing:

```
/* Back up storage pools if clients are not accessing the server */
select * from sessions
/* There are sessions if rc_ok is received */
if(rc_ok) goto done
backup stg backuppool copypool
done:exit
```

Managing Server Scripts

You can update, copy, rename, query, delete, and run server scripts.

Task	Required Privilege Class
Update, copy, rename, query, and delete a script	System, policy, storage, and operator
Run a script	

Updating a Script

You can update a script to change an existing command line or to add a new command line to a script.

To change an existing command line, specify the `LINE=` parameter.

To append a command line to an existing script issue the `UPDATE SCRIPT` command without the `LINE=` parameter. The appended command line is assigned a line number of five greater than the last command line number in the command line sequence. For example, if your script ends with line 010, the appended command line is assigned a line number of 015.

Appending a New Command

The following is an example of the `QSTATUS` script. The script has lines 001, 005, and 010 as follows:

```
001 /* This is the QSTATUS script */
005 QUERY STATUS
010 QUERY PROCESS
```

To append the `QUERY SESSION` command at the end of the script, issue the following:

```
update script qstatus "query session"
```

The `QUERY SESSION` command is assigned a command line number of 015 and the updated script is as follows:

```
001 /* This is the QSTATUS script */
005 QUERY STATUS
010 QUERY PROCESS
015 QUERY SESSION
```

Replacing an Existing Command

Line number 010 in the `QSTATUS` script contains a `QUERY PROCESS` command. To replace the `QUERY PROCESS` command with the `QUERY STGPPOOL` command, specify the `LINE=` parameter as follows:

```
update script qstatus "query stgpool" line=10
```

The `QSTATUS` script is updated to the following:

```
001 /* This is the QSTATUS script */
005 QUERY STATUS
010 QUERY STGPPOOL
015 QUERY SESSION
```

Adding a New Command and Line Number

To add the `SET REGISTRATION OPEN` command as the new line 007 in the `QSTATUS` script, issue the following:

```
update script qstatus "set registration open" line=7
```

The QSTATUS script is updated to the following:

```
001 /* This is the QSTATUS script */
005 QUERY STATUS
007 SET REGISTRATION OPEN
010 QUERY STGPOOL
015 QUERY SESSION
```

Copying a Server Script

You can copy an existing script to a new script with a different name. For example, to copy the QSTATUS script to QUERY1 script, issue:

```
copy script qstatus query1
```

The QUERY1 command script now contains the same command lines as the QSTATUS command script.

Querying a Server Script

You can query a script to display information about the script. You can specify wildcard characters to display all scripts with names that match a particular pattern. When you query a script, you have the option of directing the output to a file in a file system that the server is able to access. The various formats you can use to query scripts are as follows:

Format	Description
Standard	Displays the script name and description. This is the default.
Detailed	Displays commands in the script and their line numbers, date of last update, and update administrator for each command line in the script.
Lines	Displays the name of the script, the line numbers of the commands, comment lines, and the commands.
Raw	Outputs only the commands contained in the script without all other attributes. You can use this format to direct the script to a file so that it can be loaded into another server with the DEFINE script command specifying the FILE= parameter.

The following is an example for querying a script in the standard format.

```
query script *
```

The command gives results like the following:

Name	Description
QCOLS	Display columns for a specified SQL table
QSAMPLE	Sample SQL Query

For more information about querying a server script, refer to *Administrator's Reference*.

Querying a Server Script to Create Another Server Script

You can create additional server scripts by querying a script and specifying the FORMAT=RAW and OUTPUTFILE parameters. You can use the resulting output as input into another script without having to create a script line by line.

The following is an example of querying the SRTL2 script in the raw format, directing the output to newscript.script:

```
query script srt12 format=raw outputfile=newscript.script
```

You can then edit the newscript.script with an editor that is available to you on your system. To create a new script using the edited output from your query, issue:

```
define script srtnew file=newscript.script
```

Renaming a Server Script

You can rename a script to a different name. For example, to rename the QUERY1 script to QUERY5, issue:

```
rename script query1 query5
```

The QUERY1 script is now named QUERY5.

Deleting a Command from a Server Script

You can delete an individual command line from a script. When you specify a line number, only the corresponding command line is deleted from the script.

For example, to delete the 007 command line from the QSTATUS script, issue:

```
delete script qstatus line=7
```

Deleting a Server Script

To delete an entire script, issue the DELETE SCRIPT command.

To delete the QSTATUS script, issue:

```
delete script qstatus
```

Running a Server Script

To process a script, issue the RUN command. You can run a script that contains substitution variables by specifying them along with the RUN command.

You can preview the command lines of a script without actually executing the commands by using the PREVIEW=YES parameter with the RUN command. If the script contains substitution variables, the command lines are displayed with the substituted variables. This is useful for evaluating a script before you run it.

For example, to process the QAIXC script previously defined, issue:

```
run qaixc
```

To process the following script that contains substitution variables:

```
/*-----*/  
/* Sample continuation and substitution example */  
/* -----*/  
SELECT-  
$1 FROM-  
NODES WHERE-  
PLATFORM='$2'
```

Enter:

```
run qaixc node_name aix
```

Where \$1 is node_name and \$2 is aix.

Using Macros

TSM supports macros on the administrative client. A macro is a file that contains one or more administrative client commands. You can only run a macro from the administrative client in batch or interactive modes. Macros are stored as a file on the administrative client. Macros are not distributed across servers and cannot be scheduled on the server.

Macros can include the following:

- Administrative commands
For more information on administrative commands, see “Writing Commands in a Macro”.
- Comments
For more information on comments, see “Writing Comments in a Macro” on page 384.
- Continuation characters
For more information on continuation characters, see “Using Continuation Characters” on page 384.
- Variables
For more information on variables, see “Using Substitution Variables in a Macro” on page 385.

The name for a macro must follow the naming conventions of the administrative client running on your operating system. For more information about file naming conventions, refer to the *Administrator's Reference*.

In macros that contain several commands, use the COMMIT and ROLLBACK commands to control command processing within the macro. For more information about using these commands, see “Controlling Command Processing in a Macro” on page 386.

You can include the MACRO command within a macro file to invoke other macros up to ten levels deep. A macro invoked from the TSM administrative client command prompt is called a high-level macro. Any macros invoked from within the high-level macro are called *nested* macros.

Writing Commands in a Macro

Refer to the *Administrator's Reference* for more information on how commands are entered and the general rules for entering administrative commands. The administrative client ignores any blank lines included in your macro. However, a completely blank line terminates a command that is continued (with a continuation character).

The following is an example of a macro called REG.MAC that registers and grants authority to a new administrator:

```
register admin pease mypasswd -  
  contact='david pease, x1234'  
grant authority pease -  
  classes=policy,storage -  
  domains=domain1,domain2 -  
  stgpools=stgpool1,stgpool2
```

This example uses continuation characters in the macro file. For more information on continuation characters, see “Using Continuation Characters” on page 384.

After you create a macro file, you can update the information it contains and use it again, or you can copy the macro file, make changes to the copy, and then run the copy.

Writing Comments in a Macro

You can add comments to your macro file. To write a comment, write a slash and an asterisk (/*) to indicate the beginning of the comment, write the comment, and then write an asterisk and a slash (*/) to indicate the end of the comment. You can put a comment on a line by itself, or put it on a line that contains a command or part of a command.

For example, to use a comment to identify the purpose of a macro, write the following:

```
/* auth.mac-register new nodes */
```

Or, to write a comment to explain something about a command or part of a command, write:

```
domain=domain1          /*assign node to domain1 */
```

Comments cannot be nested and cannot span lines. Every line of a comment must contain the comment delimiters.

Using Continuation Characters

You can use continuation characters in a macro file. Continuation characters are useful when you want to execute a command that is longer than your screen or window width.

Attention: Without continuation characters, you can enter up to 256 characters. With continuation characters, you can enter up to 1500 characters. In the MACRO command, these maximums are *after* any substitution variables have been applied (see “Using Substitution Variables in a Macro” on page 385).

To use a continuation character, enter a dash or a back slash at the end of the line that you want to continue. With continuation characters, you can do the following:

- Continue a command. For example:

```
register admin pease mypasswd -  
contact="david, ext1234"
```

- Continue a list of values by entering a dash or a back slash, with no preceding blank spaces, after the last comma of the list that you enter on the first line. Then, enter the remaining items in the list on the next line with no preceding blank spaces. For example:

```
stgpools=stg1,stg2,stg3,-  
stg4,stg5,stg6
```

- Continue a string of values enclosed in quotation marks by entering the first part of the string enclosed in quotation marks, followed by a dash or a back slash at the end of the line. Then, enter the remainder of the string on the next line enclosed in the *same* type of quotation marks. For example:

```
contact="david pease, bldg. 100, room 2b, san jose,"-  
"ext. 1234, alternate contact-norm pass,ext 2345"
```

TSM concatenates the two strings with no intervening blanks. You must use *only* this method to continue a quoted string of values across more than one line.

Using Substitution Variables in a Macro

You can use substitution variables in a macro to supply values for commands when you run the macro. When you use substitution variables, you can use a macro again and again, whenever you need to perform the same task for different objects or with different parameter values.

A substitution variable consists of a percent sign (%), followed by a number that indicates the number of the substitution variable. When you run the file with the MACRO command, you must specify values for the variables.

For example, to create a macro named AUTH.MAC to register new nodes, write it as follows:

```
/* register new nodes */
register node %1 %2 -      /* userid password          */
contact=%3 -             /* 'name, phone number'    */
domain=%4                /* policy domain           */
```

Then, when you run the macro, you enter the values you want to pass to the server to process the command.

For example, to register the node named DAVID with a password of DAVIDPW, with his name and phone number included as contact information, and assign him to the DOMAIN1 policy domain, enter:

```
macro auth.mac david davidpw "david pease, x1234" domain1
```

If your system uses the percent sign as a wildcard character, a pattern-matching expression in a macro where the percent sign is immediately followed by a numeric digit is interpreted by the administrative client as a substitution variable.

You cannot enclose a substitution variable in quotation marks. However, a value you supply as a substitution for the variable can be a quoted string.

Running a Macro

Use the MACRO command when you want to run a macro. You can enter the MACRO command in batch or interactive mode.

If the macro does not contain substitution variables (such as the REG.MAC macro described in the “Writing Commands in a Macro” on page 383), run the macro by entering the MACRO command with the name of the macro file. For example:

```
macro reg.mac
```

If the macro contains substitution variables (such as the AUTH.MAC macro described in “Using Substitution Variables in a Macro”), include the values that you want to supply after the name of the macro. Each value is delimited by a space. For example:

```
macro auth.mac pease mypasswd "david pease, x1234" domain1
```

If you enter fewer values than there are substitution variables in the macro, the administrative client replaces the remaining variables with null strings.

If you want to omit one or more values between values, enter a null string ("") for each omitted value.

For example, if you omit the contact information in the previous example, you must enter:

```
macro auth.mac please mypasswd "" domain1
```

Controlling Command Processing in a Macro

When you issue a MACRO command, the server processes all commands in the macro file in order, including commands contained in any nested macros. The server commits all commands in a macro after successfully completing processing for the highest-level macro. If an error occurs in any command in the macro or in any nested macro, the server terminates processing and rolls back any changes caused by all previous commands.

If you specify the ITEMCOMMIT option when you enter the DSMADMC command, the server commits each command in a script or a macro individually, after successfully completing processing for each command. If an error occurs, the server continues processing and only rolls back changes caused by the failed command.

You can control precisely when commands are committed with the COMMIT command. If an error occurs while processing the commands in a macro, the server terminates processing of the macro and rolls back any uncommitted changes (commands that have been processed since the last COMMIT). Make sure your administrative client session is *not* running with the ITEMCOMMIT option if you want to control command processing with the COMMIT command.

Note: Commands that start background processes cannot be rolled back. For a list of commands that can generate background processes, see “Managing Server Processes” on page 365

You can test a macro before implementing it by using the ROLLBACK command. You can enter the commands (except the COMMIT command) you want to issue in the macro, and enter ROLLBACK as the last command. Then, you can run the macro to verify that all the commands process successfully. Any changes to the database caused by the commands are rolled back by the ROLLBACK command you have included at the end. Remember to remove the ROLLBACK command before you make the macro available for actual use. Also, make sure your administrative client session is not running with the ITEMCOMMIT option if you want to control command processing with the ROLLBACK command.

If you have a series of commands that process successfully via the command line, but are unsuccessful when issued within a macro, there are probably dependencies between commands. It is possible that a command issued within a macro cannot be processed successfully until a previous command that is issued within the same macro is committed. Either of the following actions allow successful processing of these commands within a macro:

- Insert a COMMIT command before the command dependent on a previous command. For example, if COMMAND C is dependent upon COMMAND B, you would insert a COMMIT command before COMMAND C. An example of this macro is:

```
command a
command b
commit
command c/
```

- Start the administrative client session using the ITEMCOMMIT option. This causes each command within a macro to be committed before the next command is processed.

19

Managing the Database and Recovery Log

The TSM database contains information needed for server operations and information about client data that has been backed up, archived, and space-managed. The database does not store client data. Instead, the database points to the locations of the client files in the TSM storage pools.

The database includes information about:

- Client nodes and administrators
- Policies and schedules
- Server settings
- Locations of client files on server storage
- Server operations (for example, activity logs and event records)

Note: If the database is unusable, the entire TSM server is unavailable. If a database is lost and cannot be recovered, the backup, archive and space-managed data for that server is lost. See “Protecting and Recovering Your Server” on page 457 for steps that you can take to protect your database.

The recovery log contains information about database updates that have not yet been committed. Updates can include activities such as defining a management class, backing up a client file, and registering a client node. Changes to the database are recorded in the recovery log to maintain a consistent database image.

The following shows authority requirements for tasks in this chapter:

Task	Required Privilege Class
Manage disk volumes used by the database and recovery log	System or unrestricted storage
Display information about the database and recovery log	Any administrator

See the following sections:

Concepts:
“How Tivoli Storage Manager Processes Transactions” on page 388
“How Space Is Managed by the Server” on page 388
“The Advantages of Using Journal File System Files” on page 390

Tasks:
“Estimating and Monitoring Database and Recovery Log Space Requirements” on page 390
“Increasing the Size of the Database or Recovery Log” on page 393
“Decreasing the Size of the Database or Recovery Log” on page 397
“Optimizing the Performance of the Database and Recovery Log” on page 399

Note: Mirroring of the database and recovery log is described in the chapter on data protection. See “Mirroring the Database and Recovery Log” on page 462.

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

How Tivoli Storage Manager Processes Transactions

To support multiple transactions from concurrent client sessions, the server holds transaction log records in the recovery log buffer pool until they can be written to the recovery log. These records remain in the buffer pool until the active buffer becomes full or TSM forces log records to the recovery log.

Changes resulting from transactions are held in the buffer pool temporarily and are not made to the database immediately. Therefore, the database and recovery log are not always consistent. When all records for a transaction are written to the recovery log, TSM updates the database. The transaction is then committed to the database. At some point after a transaction is committed, the server deletes the transaction record from the recovery log.

How Space Is Managed by the Server

TSM tracks all volumes defined to the database as one logical volume and all volumes defined to the recovery log as another logical volume. In Figure 62, the database consists of four volumes: VOL1 through VOL4, which TSM tracks as a single logical volume.



Figure 62. A Server Database

To manage the database and recovery log effectively, you must understand the following concepts:

- Available space
- Assigned capacity
- Utilization

Available Space

Not all of the space that is allocated for the database or recovery log volumes can be used for database and recovery log information. TSM subtracts 1MB from each physical volume for overhead. The remaining space is divided into 4MB partitions. For example, you allocate four 25MB volumes for the database. For the four volumes, TSM requires 4MB for overhead leaving 96MB of available space as shown in the following figure:




Figure 63. An Example of Available Space

Assigned Capacity

Assigned capacity is the available space that can be used for database or recovery log information. During installation, the database and recovery log assigned capacities match the available space.

If you add volumes after installation, you increase your available space. However, to increase the assigned capacity, you must also extend the database or recovery log. See “Step 2: Extending the Capacity of the Database or Recovery Log” on page 396 for details.

Utilization

Utilization is the percent of the assigned capacity in use at a specific time. *Maximum percent utilized* is the highest utilization since the statistics were reset. For example, an installation performs most backups after midnight. Figure 64 shows that utilization statistics for the recovery log were reset at 9 p.m. the previous evening and that the maximum utilization occurred at 12 a.m.




Figure 64. An Example of Recovery Log Utilization

Unless an unusually large number of objects are deleted, the database maximum percent utilized is usually close to the utilization percentage.

The Advantages of Using Journal File System Files

TSM supports both journaled file system (JFS) files and raw logical volumes as database, recovery log, and disk storage pool volumes. JFS files have the following advantages:

- When TSM has JFS files open, they are locked by JFS and other applications cannot write to them. However, raw volumes are not locked and any application can write to them. TSM tries to prevent starting more than one instance of the same server from the same directory, but it can be done. If you are using raw volumes, both servers' instances can simultaneously update the same information. This could cause errors in the database, recovery log, or storage pool raw volumes.
- After a database, recovery log, or storage pool volume is defined to TSM, you cannot change its size. TSM uses size information to determine where data is placed and whether volumes have been modified by other applications or utilities. However, if you use raw volumes, `smit` lets you increase their sizes. If the volume is defined to TSM before its size is increased, TSM cannot use the volume or its data.
- You should use TSM mirroring rather than AIX mirroring. If you use AIX mirroring, you may have a problem with raw volumes, but not with JFS files. AIX tracks mirroring activity by writing control information to the first 512 bytes of USER area in a raw volume. This is not a problem for database and recovery log volumes, but TSM control information is also written in this area. If AIX overwrites TSM control information when raw volumes are mirrored, TSM may not be able to vary the volume online.

The use of JFS files for database, recovery log, and storage pool volumes requires slightly more CPU than is required for raw volumes. However, JFS read-ahead caching improves performance.

Estimating and Monitoring Database and Recovery Log Space Requirements

The size of the database depends on the number of client files to be stored and how TSM manages them. If you can estimate the maximum number of files that might be in server storage at any time, you can use the following information to come up with a useful database size estimate:

- Each stored **version of a file** requires about 400 to 600 bytes of database space.
- Each **cached** or **copy storage pool** file requires about 100 to 200 bytes of database space.
- **Overhead** could require up to 25% in additional space.

In the example below, the computations are probable maximums. In addition, the numbers are not based on the use of file aggregation. In general, aggregation of small files reduces the required database space. For details about aggregation, see “How the Server Groups Files before Storing” on page 134. Assume the following numbers for a Tivoli Storage Manager system:

Versions of files

Backed up files

Up to 500 000 client files might be backed up. Storage policies call for keeping up to 3 copies of backed up files:

$$500\ 000\ \text{files} \times 3\ \text{copies} = 1\ 500\ 000\ \text{files}$$

Archived files

Up to 100 000 files might be archived copies of client files.

Space-managed files

Up to 200 000 files migrated from client workstations might be in server storage.

Note: File aggregation does not affect space-managed files.

At 600 bytes per file, the space required for these files is:

$$(1\ 500\ 000 + 100\ 000 + 200\ 000) \times 600 = 1.0\text{GB}$$

Cached and copy storage pool files**Cached copies**

Caching is enabled in a 5GB disk storage pool. The pool's high and low migration thresholds are 90% and 70% respectively. Thus, 20% of the disk pool, or 1GB, is occupied by cached files.

If the average file size is about 10KB, about 100 000 files are in cache at any one time.

$$100\ 000\ \text{files} \times 200\ \text{bytes} = 19\text{MB}$$

Copy storage pool files

All primary storage pools are backed up to the copy storage pool:

$$(1\ 500\ 000 + 100\ 000 + 200\ 000) \times 200\ \text{bytes} = 343\text{MB}$$

Therefore, cached and copy storage pool files require about 0.4GB of database space.

Overhead

About 1.4GB is required for file versions and cached and copy storage pool files. Up to 50% additional space (or 0.7GB) should be allowed for overhead.

The database should then be approximately 2.1GB.

It may not be practical for you to estimate the numbers of files managed by TSM policies. In that case, from 1% to 5% of the required server storage space can be used as a rough estimate of the database size. For example, if you need 100GB of server storage, your database should be between 1GB and 5GB. See “Estimating Space Needs for Storage Pools” on page 159 for details.

During SQL queries of the server, intermediate results are stored in temporary tables that require space in the free portion of the database. Therefore, the use of SQL queries requires additional database space. The more complicated the queries, the greater the space required.

The size of the recovery log depends on the number of concurrent client sessions and the number of background processes executing on the server. The maximum number of concurrent client sessions is set in the server options.

Attention: Be aware that the results are estimates. The actual size of the database may differ from the estimate because of a variety of factors such as the number of directories and the length of the path and file names. You should periodically monitor your database and recovery log and adjust their sizes as necessary.

Begin with at least a 12MB recovery log. If you use the database backup and recovery functions in roll-forward mode, you should begin with at least 25MB. See “Database and Recovery Log Protection” on page 460 and “Estimating the Size of the Recovery Log” on page 469 for more information.

Monitoring the Database and Recovery Log

After TSM is operational, you should monitor the database and recovery log to see if you should add or delete space. To monitor daily utilization, you might want to reset the maximum utilization counters each day. Utilization statistics are reset in two ways:

- Automatically when the server is restarted
- By issuing the `RESET DBMAXUTILIZATION` or `RESET LOGMAXUTILIZATION` commands

For example, to reset the database utilization statistic, enter:

```
reset dbmaxutilization
```

If the `SELFTUNEBUFPOOLSIZE` server option is in effect, the buffer pool cache hit ratio statistics are reset at the start of expiration. After expiration, the buffer pool size is increased if the cache hit ratio is less than 98%. The increase in the buffer pool size is in small increments and may change after each expiration. The change in the buffer pool size is not reflected in the server options file. You can check the current size at any time using the `QUERY STATUS` command. Use the `SETOPT BUFPOOLSIZE` command to change the buffer pool size.

To display information about the database or recovery log, issue the `QUERY DB` or `QUERY LOG`. For example:

```
query db
```

The server displays a report, like this:

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
96	96	0	92	4,096	24,576	86	0.3	0.3

See the indicated sections for details about the following entries:

- Available space, “Available Space” on page 389
- Assigned capacity, “Assigned Capacity” on page 389
- Utilization and maximum utilization, “Utilization” on page 389

If utilization is high, you may want to add space (see “Increasing the Size of the Database or Recovery Log” on page 393). If utilization is low, you may want to delete space (see “Decreasing the Size of the Database or Recovery Log” on page 397).

Note: You can also use a `DEFINE SPACETRIGGER` command to automatically check whether the database or recovery log exceeds a utilization percentage that you specify. See “Automating the Increase of the Database or Recovery Log” for details.

Increasing the Size of the Database or Recovery Log

As your requirements change, you can increase or decrease the sizes of the database and recovery log. You can automate the process of increasing the sizes, or you can perform all the steps manually. See “Automating the Increase of the Database or Recovery Log” or “Manually Increasing the Database or Recovery Log” on page 395.

Attention: Do not change the size of an allocated database or recovery log volume after it has been defined to TSM. If you change the size of a volume, TSM may not initialize correctly, and data may be lost.

Note: Significantly increasing the size of your recovery log could also significantly increase the time required to restart the server, to back up the database, and to restore the database.

Automating the Increase of the Database or Recovery Log

TSM lets you fully automate the process of increasing the database and recovery log sizes. With a `DEFINE SPACETRIGGER` command, you can specify the following:

- Utilization percentages at which the database or recovery log size is to be increased
- The size of the increase as a percentage of the current size of the database or recovery log
- The prefix to be used for a new volume
- The maximum size allowed for the database or recovery log

For example, assume that you have a 100GB database and a 3GB recovery log. You want to increase the database size by 25 percent when 85 percent is in use, but not to more than 200GB. You also want to increase the recovery log size by 30 percent when 75 percent is in use, but not to more than 5GB.

Note: There is one time when the database or recovery log might exceed the maximum size specified: If the database or recovery log is less than the maximum size when expansion begins, it continues to the full expansion value. However, no further expansion will occur unless the space trigger is updated.

To add the new volumes to the `/usr/lpp/admserv/bin/` directory, issue the following commands:

```
define spacetrigger db fullpct=85 spaceexpansion=25
expansionprefix=/usr/lpp/admserv/bin/ maximumsize=200000
```

```
define spacetrigger log fullpct=75 spaceexpansion=30
expansionprefix=/usr/lpp/admserv/bin/ maximumsize=50000
```

TSM then monitors the database or recovery log. If the utilization level is reached, TSM does the following:

- Displays a message (ANR4413I or ANR4414I) that states the amount of space required to meet the utilization parameter specified in the command.
- Allocates space for the new volume.

-
- Defines the new volume.
 - Extends the database or recovery log.
 - If a volume is mirrored and there is enough disk space, the preceding steps are also performed for the mirrored copies.

Notes:

1. The maximum size of the recovery log is 13GB. TSM will not automatically extend the recovery log beyond 12GB.
2. An automatic expansion may exceed the specified database or recovery log maximum size but not the 13GB recovery log limit. However, after the maximum has been reached, no further automatic expansions will occur.
3. A space trigger percentage may be exceeded during the period between the monitoring of the database or recovery log and the time that a new volume is brought online.
4. If TSM creates a database or recovery log volume and the attempt to add it to the server fails, the created volume is not deleted. After the problem is corrected, you can define it with the `DEFINE DBVOLUME` or `DEFINE LOGVOLUME` command.
5. Automatic expansion will not occur during a database backup.
6. The database and recovery log utilization percentage may not always be below the space trigger value. TSM checks utilization after a database or recovery log commit. Also, deleting database volumes and reducing the database does not activate the trigger. Therefore, the utilization percentage can exceed the set value before new volumes are online.
7. Setting a maximum size does not mean that the database and recovery log will always be less than that value. The value is a threshold for expansion. TSM does not automatically expand the database or recovery log if its size is greater than the maximum size. TSM checks the size and allows expansion if the database or recovery log is less than the maximum size. TSM only checks the size that results after expansion to ensure that maximum recovery log size is not exceeded.

Recovering When the Recovery Log Runs Out of Space

If the log mode is set to `ROLLFORWARD` and either the recovery log is too small or the database backup trigger is set too high, the recovery log could run out of space before database operations complete. If this happens, you may need to stop the server without enough recovery log space to restart the server. In some cases, the server halts itself.

To restart the server, first format a new volume (see “Using the `DSMFMT` Command to Format Volumes” on page 396). Then use the `DSMSERV EXTEND LOG` command to extend the size of the recovery log. For example, after formatting a 21MB volume named *new.reclog*, extend the recovery log by issuing the following command:

```
dsmserv extend log new.reclog 20
```

After the server is running, you can do the following:

- Back up the database, which frees the recovery log space
- Adjust the size of the recovery log, the database backup trigger, or both

Manually Increasing the Database or Recovery Log

To add space to the database or recovery log, do the following:

“Step 1: Creating Database and Recovery Log Volumes”

“Step 2: Extending the Capacity of the Database or Recovery Log” on page 396

Step 1: Creating Database and Recovery Log Volumes

You can allocate space and define a database or recovery log volume in a single operation. For example, to allocate a 100MB database volume named VOL5 in the /usr/lpp/admserv/bin directory and define the volume to TSM, enter:

```
define dbvolume /usr/lpp/admserv/bin/vol5 formatsize=100
```

The available space of the database increases to 196MB, but the assigned capacity remains at 96MB. For TSM to use the space, you must extend the capacity (see “Step 2: Extending the Capacity of the Database or Recovery Log” on page 396). To verify the change, query the database or recovery log. For example, to query the database, enter:

```
query db
```

The server displays a report, like this:

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
196	96	100	92	4,096	24,576	86	0.3	0.3

The value in the *Maximum Extension* field should equal the available space of the new volume. In this example, a 101MB volume was allocated. This report shows that the available space has increased by 100MB; the assigned capacity is unchanged at 96MB; and the maximum extension is 100MB. Figure 65 illustrates these changes.




Figure 65. Adding Volumes Increases Available Space

You can also query the database and recovery log volumes to display information about the physical volumes that make up the database and recovery log.

Notes:

1. The maximum size of the recovery log is 13GB, and the maximum size of the database is 530GB. If you allocate a volume that would cause the recovery log or database to exceed these limits, the subsequent DEFINE DBVOLUME or DEFINE LOGVOLUME command for the volume will fail.
2. For performance reasons, define more than one volume for the database and recovery log, and put these volumes on separate disks. This allows simultaneous access to different parts of the database or recovery log.
3. To use disk space efficiently, allocate a few large disk volumes rather than many small disk volumes. In this way, you avoid losing space to TSM overhead processing.
If you already have a number of small volumes and want to consolidate the space into one large volume, see “Decreasing the Size of the Database or Recovery Log” on page 397.
4. To protect database and recovery log volumes from media failure, use mirroring. See “Mirroring the Database and Recovery Log” on page 462 for details.

Using the DSMFMT Command to Format Volumes

You can still use the DSMFMT utility to allocate a database or recovery log volume. You would then issue the DEFINE DBVOLUME or DEFINE LOGVOLUME command without the FORMATSIZE parameter, and extend the database or recovery log (see “Step 2: Extending the Capacity of the Database or Recovery Log”).

To allocate an additional 101MB to the database as volume VOL5, enter:

```
> dsmfmt -db vol5 101
```

Step 2: Extending the Capacity of the Database or Recovery Log

The database and recovery log are extended in 4MB increments. If you do not specify the extension in 4MB increments, TSM rounds up to the next 4MB partition. For example, if you specify 1MB, TSM extends the capacity by 4MB.

To increase the capacity of the database by 100MB, enter:

```
extend db 100
```

After the database has been extended, the available space and assigned capacity are both equal to 196MB, as shown in Figure 66 on page 397.

Allocated Space on Physical Volumes		Available Space for the Database	Assigned Capacity
101 MB		100 MB	100 MB
25 MB		24 MB	24 MB
25 MB		24 MB	24 MB
25 MB		24 MB	24 MB
25 MB		24 MB	24 MB
Totals 201 MB		196 MB	196 MB

Figure 66. Extending the Capacity of the Database

You can query the database or recovery log (QUERY DB and QUERY LOG commands) to verify their assigned capacities. The server would display a report, like this:

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
196	196	0	192	4,096	50,176	111	0.2	0.2

Decreasing the Size of the Database or Recovery Log

You may want to delete database or recovery log volumes for a number of reasons. For example:

- You have a significant amount of space that is unused.
- You want to consolidate a number of small volumes, each of which may have unusable space, into one large volume. To create a volume, see “Increasing the Size of the Database or Recovery Log” on page 393.

When you delete a database or recovery log volume, TSM tries to move data from the volume being deleted to other physical volumes in the database or recovery log.

To delete space, perform the following steps:

1. Determine if you can delete one or more volumes (“Step 1: Determining If Volumes Can Be Deleted”).
2. Reduce the capacity of the database or recovery log to free existing space (“Step 2: Reducing the Capacity of the Database or Recovery Log” on page 398).
3. Delete the volume (“Step 3: Deleting a Volume from the Database or Recovery Log” on page 399).

Step 1: Determining If Volumes Can Be Deleted

To determine if volumes can be deleted from the database or recovery log, check the volume sizes and the amount of unused space. To check the sizes of the volumes in the database, enter:

```
query dbvolume format=detailed
```

The server displays the following type of information:

```
Volume Name (Copy 1): VOL1
    Copy Status: Sync'd
Volume Name (Copy 2):
    Copy Status: Undefined
Volume Name (Copy 3):
    Copy Status: Undefined
Available Space (MB): 24
Allocated Space (MB): 24
Free Space (MB): 0
```

In this example, VOL1, VOL2, VOL3, and VOL4 each have 24MB of available space, and VOL5 has 100MB. To determine if there is enough unused space to delete one or more volumes, enter:

```
query db
```

The server displays the following type of report.

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
196	196	0	176	4,096	50,176	4,755	9.5	9.5

The *Maximum Reduction* field shows the assigned capacity not in use. In this example, you could reduce the database by up to 176MB. This is enough space to allow the deletion of VOL1, VOL2, VOL3, and VOL4.

If there is not enough space on the remaining volumes, allocate more space and define an additional volume, as described in “Increasing the Size of the Database or Recovery Log” on page 393 and continue with “Step 2: Reducing the Capacity of the Database or Recovery Log”.

Step 2: Reducing the Capacity of the Database or Recovery Log

The database or recovery log capacity is reduced in 4MB increments. For example, assume that based on the utilization of the database, VOL5 alone could contain all the data. To reduce the database by the amount of available space in VOL1 through VOL4, 96MB, enter:

```
reduce db 96
```

Reducing capacity is run as a background process and can take a long time. Issue a QUERY PROCESS command to check on the status of the process.

After reducing the database by 96MB, the assigned capacity is 100MB and the maximum extension is 96MB, as shown in the following example:

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
196	100	96	92	4,096	24,576	86	0.3	0.3

Step 3: Deleting a Volume from the Database or Recovery Log

After you reduce the database or recovery log, use the smaller size for a few days. If the maximum utilization does not go over 70%, you can delete extra volumes.

Note: You cannot delete volumes if there is not enough free space for the server to move existing data from the volume being deleted to other physical volumes in the database or recovery log.

In our example, you determined that you can delete the four 24MB volumes from the database. You have reduced the database by 96MB. To delete VOL1 through VOL4 from the database, enter:

```
delete dbvolume vol1
delete dbvolume vol2
delete dbvolume vol3
delete dbvolume vol4
```

TSM moves data from the volumes being deleted to available space on other volumes, as shown in Figure 67.




Figure 67. Deleting Database Volumes

After the data has been moved, these volumes are deleted from the server.

Optimizing the Performance of the Database and Recovery Log

Periodically the database size and internal organization can progress to where it is no longer internally efficient. To improve database performance, the database can be unloaded and reloaded in an optimal manner that will:

- Improve the performance of the server database dump and load functions
- Improve the performance of the database audit functions
- Organize the database in an internally optimal manner so that an efficient amount of space is used, fragmented page allocations are reorganized, and the performance of long-running scans of the database is improved.

The database and recovery log buffer pool sizes can also affect TSM performance. A larger database buffer pool can improve performance, and a larger recovery log buffer pool reduces how often the server forces records to the recovery log.

See “Reorganizing the Database” on page 402 for more information about restoring database efficiency.

Dynamically Adjusting the Database Buffer Pool Size

TSM can dynamically adjust the size of the database buffer pool, or you can do this procedure yourself.

The SELFTUNEBUFPOOLSIZE option has two values: YES or NO. NO is the default. If YES is specified, TSM will dynamically adjust the database buffer pool.

If the SELFTUNEBUFPOOLSIZE option is specified as YES in the server options file, buffer pool cache hit ratio statistics will be reset at the beginning of expiration. After expiration processing completes, the BUFPOOLSIZE will be adjusted dynamically.

Server expiration processing resets the database buffer pool before the next processing starts and examines if the database buffer pool cache hit ratio is above 98%. If the cache hit ratio is lower than 98%, the database buffer pool will be increased; if it is higher, the buffer pool size will not change. Increasing the database buffer pool will not be more than 10% of available real storage.

Manually Adjusting the Database Buffer Pool Size

Perform the following steps to track the database buffer pool statistics and adjust the buffer pool size:

Step 1: Reset Database Buffer Pool Utilization Statistics

Reset the buffer pool statistics. Initially, you might want to reset the statistics twice a day. Later, you can reset them less often. To reset, enter:

```
reset bufpool
```

Step 2: Monitor the Database Buffer Pool

To see if the database buffer pool is adequate for database performance, enter:

```
query db format=detailed
```

The server displays a report, like this:

```
Available Space (MB): 196
Assigned Capacity (MB): 196
Maximum Extension (MB): 0
Maximum Reduction (MB): 176
  Page Size (bytes): 4,096
    Total Pages: 50,176
    Used Pages: 4,755
    %Util: 9.5
    Max. %Util: 9.5
  Physical Volumes: 5
  Buffer Pool Pages: 128
Total Buffer Requests: 1,193,212
  Cache Hit Pct.: 99.73
  Cache Wait Pct.: 0.00
```

Use the following fields to evaluate your current use of the database buffer pool:

Buffer Pool Pages

The number of pages in the database buffer pool. This value is determined by the

server option for the size of the database buffer pool. At installation, the database buffer pool is set to 2048KB, which equals 128 database pages.

Total Buffer Requests

The number of requests for database pages since the server was last started or the buffer pool was last reset. If you regularly reset the buffer pool, you can see trends over time.

Cache Hit Pct

The percentage of requests for cached database pages in the database buffer pool that were not read from disk. A high value indicates that the size of your database buffer pool is adequate. If the value falls below 98%, consider increasing the size of the database buffer pool. For larger installations, performance could improve significantly if your cache hit percentage is greater than 99%.

Cache Wait Pct

The percentage of requests for database pages that had to wait for a buffer to become available in the database buffer pool. When this value is greater than 0, increase the size of the database buffer pool.

Step 3: Adjust the Database Buffer Pool

Use the BUFPOOLSIZE server option to set the size of the database buffer pool.

Adjusting the Recovery Log Buffer Pool Size

Do the following to adjust the size of the recovery log buffer pool:

Step 1: Monitor the Recovery Log Buffer Pool

To see how the recovery log buffer pool size affects recovery log performance, enter:
query log format=detailed

The server displays a report, like this:

```

Available Space (MB): 12
Assigned Capacity (MB): 12
Maximum Extension (MB): 0
Maximum Reduction (MB): 8
  Page Size (bytes): 4,096
    Total Pages: 3,072
    Used Pages: 227
    %Util: 7.4
    Max. %Util: 69.6
  Physical Volumes: 1
    Log Pool Pages: 32
  Log Pool Pct. Util: 6.25
  Log Pool Pct. Wait: 0.00

```

Use the following fields to evaluate the log buffer pool size:

Log Pool Pages

The number of pages in the recovery log buffer pool. This value is set by the server option for the size of the recovery log buffer pool. At installation, the default setting is 128KB, which equals 32 recovery log pages.

Log Pool Pct. Util

The percentage of pages used to write changes to the recovery log after a transaction

is committed. A value below 10% means that the recovery log buffer pool size is adequate. If the percentage increases, consider increasing the recovery log buffer pool size.

Log Pool Pct. Wait

The percentage of requests for pages that are not available because all pages are waiting to write to the recovery log.

If this value is greater than 0, increase the recovery log buffer pool size.

Step 2: Adjust the Recovery Log Buffer Pool

Use the LOGPOOLSIZE server option to set the size of the database buffer pool.

Reorganizing the Database

Over time, database volumes become fragmented. You can restore the efficiency of the database and improve database performance by reorganizing the database using TSM database unload and reload processing. By reloading the database, you compress and reorganize it.

Procedure: Reorganizing the Database

Attention: Before you begin this procedure, perform a backup of your database. If an outage occurs while you are loading and reloading your database, you can use your backup copy for recovering the database.

To reorganize the TSM database, follow these steps:

1. Ensure that a current device configuration file exists. This file contains a copy of the device class, library, and drive definitions. These definitions are needed for the DSMSERV LOADDB utility.

Note: You must specify the name of the device configuration file by using the DEVCONFIG option in the server options file. See “Saving the Device Configuration File” on page 474. Also see *Administrator’s Reference* for details on the option and the command.

2. Before unloading the database, estimate how many tapes you will need:
 - If the TSM server is *not* running, use the size of your existing physical database volumes as an estimate of how many tapes to use.
 - If the TSM server is running, you can use the following steps to estimate the number of tapes required:
 - a. Request information about the database by using the following command:

```
query db
```
 - b. Using the output of the QUERY DB command, multiply the *Used Pages* by the *Page Size* to determine space occupied by the database.
 - c. Use the result to estimate the number of tapes of a specific device class that you will need to unload the database. The space required will likely be less than your estimate.
3. Halt the server if it is still running.
4. With the server not running, issue the DSMSERV UNLOADDB utility to unload the database to tape. For example:

```
dsmserv unloaddb devclass=tapeclass scratch=yes
```

Note: Keep track of the order in which the tape volumes are written when the database is unloaded. You must specify the volume names in the same order when you reload the database using the DSMSERV LOADDB utility. For this task, you can either:

- Review the output generated by the DSMSERV UNLOADDB utility and record the order of the volumes.
- Manually view the volume history file to identify the tape volumes containing the unloaded database. The volumes have a volume type of DBDUMP. See “Saving the Volume History File” on page 472 for details. (Do *not* restart the server and issue QUERY VOLHISTORY at this step.)

5. Format the database and recovery log. For example:

```
dsmserv loadformat 2 logvol1 logvol2 1 dbvol1
```

This utility prepares the existing server database for the DSMSERV LOADDB utility.

6. Reload the database using the volumes that contain the data from the unload operation.

For example:

```
dsmserv loaddb devclass=tapeclass volumenames=db001,db002,db003
```

For the volume names, ensure that you do the following:

- Enter the volume names in the same order in which they were used for the DSMSERV UNLOADDB utility.
- Separate the volume names with a comma and no intervening spaces.

20

Monitoring the Tivoli Storage Manager Server

Administrators can monitor the Tivoli Storage Manager server:

- To find the status of operations
- To display information about objects
- To monitor the record of activity
- To select the types of events to save
- To select a location to save events

See the following sections:

Tasks:
“Using Tivoli Storage Manager Queries to Display Information”
“Using SQL to Query the Tivoli Storage Manager Database” on page 410
“Using the Tivoli Storage Manager Activity Log” on page 416
“Logging Tivoli Storage Manager Events to Receivers” on page 418
“Monitoring Tivoli Storage Manager Accounting Records” on page 431

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Using Tivoli Storage Manager Queries to Display Information

Tivoli Storage Manager provides a variety of QUERY commands that display formatted information about definitions, settings, processes, and status. In some cases, you can display the information in either of two formats: standard or detailed. The standard format presents partial information and is useful in displaying an overview of many objects.

Note: For information about creating customized queries of the database, see “Using SQL to Query the Tivoli Storage Manager Database” on page 410.

Requesting Information about Tivoli Storage Manager Definitions

During TSM system setup, an administrator can define many objects. These objects include storage management policies, database and recovery log volumes, storage pools, and device classes. Tivoli Storage Manager provides queries that display information about these objects.

Most of these definition queries let you request standard format or detailed format. Standard format limits the information and usually displays it as one line per object. Use the standard format when you want to query many objects, for example, all registered client nodes. Detailed format displays the default and specific definition parameters. Use the detailed format when you want to see all the information about a limited number of objects.

Here is an example of the standard output for the QUERY NODES command:

Node Name	Platform	Policy Domain Name	Days Since Last Access	Days Since Password Set	Locked?
CLIENT1	(?)	STANDARD	6	6	No
GEORGE	OS/2	STANDARD	1	1	No
JANET	(?)	STANDARD	1	1	No
JOEOS2	OS/2	STANDARD	<1	<1	No
TOMC	(?)	STANDARD	1	1	No

Here is an example of the detailed output for the QUERY NODES command:

Node Name: JOEOS2
Platform: OS/2
Policy Domain Name: STANDARD
Last Access Date/Time: 05/19/2000 09:59:52
Days Since Last Access: 2
Password Set Date/Time: 05/18/2000 11:04:45
Days Since Password Set: 3
Invalid Password Limit:
Minimum Password Length:
Locked?: No
Contact:
Compression: No
Archive Delete Allowed?: Yes
Backup Delete Allowed?: No
Registration Date/Time: 05/18/2000 11:04:45
Registering Administrator: OPEN_REGISTRATION
Last Communication Method Used: Tcp/Ip
Bytes Received Last Session: 226
Bytes Sent Last Session: 556
Duration of Last Session (sec): 3.32
Pct. Idle Wait Last Session: 88.48
Pct. Comm. Wait Last Session: 6.63
Pct. Media Wait Last Session: 0.00

Requesting Information about Client Sessions

When administrators or users access Tivoli Storage Manager, an administrative or client node session is established with the server. The server assigns each client session a unique session number.

To request information about client sessions, enter:

query session

Figure 68 shows a sample client session report.

Sess Number	Comm. Method	Sess State	Wait Time	Bytes Sent	Bytes Recvd	Sess Type	Platform	Client Name
3	Tcp/Ip	IdleW	9 S	7.8 K	706	Admin	OS/2	TOMC
5	Tcp/Ip	IdleW	0 S	1.2 K	222	Admin	OS/2	GUEST
6	Tcp/Ip	Run	0 S	117	130	Admin	OS/2	MARIE

Figure 68. Information about Client Sessions

Check the *wait time* and *session state*. The *wait time* determines the length of time (seconds, minutes, hours) the server has been in the current state. The *session state* can be one of the following:

Start Connecting with a client session.

Run Running a client request.

End Ending a client session.

RecvW

Waiting to receive an expected message from the client while a database transaction is in progress. A session in this state is subject to the COMMTIMEOUT limit.

SendW

Waiting for acknowledgment that the client has received a message sent by the server.

MediaW

Waiting for removable media to become available.

IdleW Waiting for communication from the client, and a database transaction is NOT in progress. A session in this state is subject to the IDLETIMEOUT limit.

For example, Tivoli Storage Manager cancels the client session if the IDLETIMEOUT option is set to 30 minutes, and a user does not initiate any operations within those 30 minutes. The client session is automatically reconnected to the server when it starts to send data again.

Requesting Information about Server Processes

Most commands run in the foreground, but others generate background processes. In some cases, you can specify that a process run in the foreground. TSM issues messages that provide information about the start and end of processes. In addition, you can request information about active background processes. If you know the process ID number, you can use the number to limit the search. However, if you do not know the process ID, you can display information about all background processes by entering:

```
query process
```

Figure 69 on page 408 shows a server background process report after a DELETE FILESPACE command was issued. The report displays a process ID number, a description, and a completion status for each background process.

Process Number	Process Description	Status
2	DELETE FILESPACE	Deleting filespace DRIVE_D for node CLIENT1: 172 files deleted.

Figure 69. Information about Background Processes

Requesting Information about Server Settings

Any administrator can request general server information, most of which is defined by SET commands. To request this information, enter:

```
query status
```

The displayed information includes:

- The server name
- When the server was installed and last started
- Whether the server is enabled or disabled
- Whether client registration is open or closed
- Whether passwords are required for client/server authentication
- How long passwords are valid
- Whether accounting records are being generated
- How long messages remain in the activity log before being deleted
- How many client sessions can concurrently communicate with the server
- How many client node sessions are available for scheduled work
- What percentage of the scheduling start-up window is randomized
- What scheduling mode is being used
- How frequently client nodes can poll for scheduled work
- How many times and how often a client node can retry a failed attempt to perform a scheduled operation
- How long event records remain in the database
- The interval before re-authentication is required for the Web administrative client interface

Querying Server Options

Task	Required Privilege Class
Query server options	Any administrator

Use the QUERY OPTION command to display information about one or more server options.

You can issue the `QUERY OPTION` command with no operands to display general information about all defined server options. You also can issue the `QUERY OPTION` command with a specific option name or pattern-matching expression to display information on one or more server options.

To display general information about all defined server options, enter:

```
query option
```

You can set options by editing the server options file. See *Administrator's Reference* for more information.

Querying the System

The `QUERY SYSTEM` command lets you combine multiple queries of your Tivoli Storage Manager system into a single command. This command can be used to collect statistics and to provide information for problem analysis by IBM service. When you issue the `QUERY SYSTEM` command, the server issues the following queries:

QUERY ASSOCIATION

Displays all client nodes that are associated with one or more client schedules

QUERY COPYGROUP

Displays all backup and archive copy groups (standard format)

QUERY DB

Displays information about the database (detailed format)

QUERY DBVOLUME

Displays information about all database volumes (detailed format)

QUERY DEVCLASS

Displays all device classes (detailed format)

QUERY DOMAIN

Displays all policy domains (standard format)

QUERY LOG

Displays information about the recovery log (detailed format)

QUERY LOGVOLUME

Displays information about all recovery log volumes (detailed format)

QUERY MGMTCLASS

Displays all management classes (standard format)

QUERY OPTION

Displays all server options

QUERY PROCESS

Displays information about all active background processes

QUERY SCHEDULE

Displays client schedules (standard format)

QUERY SESSION

Displays information about all administrative and client node sessions in standard format

QUERY STATUS

Displays general server parameters, such as those defined by `SET` commands

QUERY STGPOOL

Displays information about all storage pools (detailed format)

QUERY VOLUME

Displays information about all storage pool volumes (standard format)

SELECT

Displays the results of two SQL queries:

```
select platform_name,count(*) from nodes group by platform_name
select stgpool_name,devclass_name,count(*) from volumes
group by stgpool_name,devclass_name
```

The first command displays the number of client nodes by platform.

The second command displays the name and associated device class of all storage pools having one or more volumes assigned to them.

Using SQL to Query the Tivoli Storage Manager Database

You can use a standard SQL SELECT statement to get information from the database. The SELECT command is a subset of the SQL92 and SQL93 standards.

Tivoli Storage Manager also provides an open database connectivity (ODBC) driver. The driver allows you to use a relational database product such as Lotus Approach[®] to query the database and display the results.

Using the ODBC Driver

Tivoli Storage Manager provides an ODBC driver for Windows. The driver supports the ODBC Version 2.5 application programming interface (API). Because TSM supports only the SQL SELECT statement (query), the driver does not conform to any ODBC API or SQL grammar conformance level. After you install this driver, you can use a spreadsheet or database application that complies with ODBC to access the database for information.

The ODBC driver set-up is included in the client installation package. The client installation program can install the ODBC driver and set the corresponding registry values for the driver and data sources. For more information on setting up the ODBC driver, see *Installing the Clients*.

To open the database through an ODBC application, you must log on to the server (the defined data source). Use the name and password of a registered administrator. After you log on to the server, you can perform query functions provided by the ODBC application to access database information.

Issuing SELECT Commands

You can issue the SELECT command from the command line of an administrative client. You cannot issue this command from the server console.

The SELECT command supports a subset of the syntax of the SELECT statement as documented in the SQL92 and SQL93 standards. For complete information about how to use the SELECT statement, refer to these standards or to other publications about SQL.

Issuing the SELECT command to the server can use a significant amount of server resources to run the query. Complicated queries or queries that run for a long time can interfere with

normal server operations. If your query requires excessive server resource to generate the results, you will receive a message asking you to confirm that you wish to continue.

Note: To allow any use of the SELECT command, the database must have at least 4MB of free space. For complex queries that require significant processing, additional free space is required in the database. See “Exhausting Temporary Table Storage” on page 413 for details.

Learning What Information Is Available: System Catalog Tables

To help you find what information is available in the database, Tivoli Storage Manager provides three system catalog tables:

SYSCAT.TABLES

Contains information about all tables that can be queried with the SELECT command.

SYSCAT.COLUMNS

Describes the columns in each table.

SYSCAT.ENUMTYPES

Defines the valid values for each enumerated type and the order of the values for each type.

You can issue the SELECT command to query these tables to determine the location of the information that you want. For example, to get a list of all tables available for querying in the database, enter the following command:

```
select * from syscat.tables
```

The following shows part of the results of this command:

```

    TABSCHEMA: TSM
      TABNAME: ACTLOG
    CREATE_TIME:
      COLCOUNT: 11
INDEX_COLCOUNT: 1
  UNIQUE_INDEX: FALSE
    REMARKS: Server activity log

    TABSCHEMA: TSM
      TABNAME: ADMINS
    CREATE_TIME:
      COLCOUNT: 17
INDEX_COLCOUNT: 1
  UNIQUE_INDEX: TRUE
    REMARKS: Server administrators

    TABSCHEMA: TSM
      TABNAME: ADMIN_SCHEDULES
    CREATE_TIME:
      COLCOUNT: 15
INDEX_COLCOUNT: 1
  UNIQUE_INDEX: TRUE
    REMARKS: Administrative command schedules

    TABSCHEMA: TSM
      TABNAME: ARCHIVES
    CREATE_TIME:
      COLCOUNT: 10
INDEX_COLCOUNT: 5
  UNIQUE_INDEX: FALSE
    REMARKS: Client archive files

```

Examples

The SELECT command lets you customize a wide variety of queries. This section shows two examples. For many more examples of the command, see the *Administrator's Reference*.

Example 1: Find the number of nodes by type of operating system by issuing the following command:

```
select platform_name,count(*) as "Number of Nodes" from nodes
group by platform_name
```

This command gives results like the following:

PLATFORM_NAME	Number of Nodes
OS/2	45
AIX	90
Windows	35

Example 2: For all active client sessions, determine how long they have been connected and their effective throughput in bytes per second:

```
select session_id as "Session", client_name as "Client", state as "State",
  current_timestamp-start_time as "Elapsed Time",
  (cast(bytes_sent as decimal(18,0)) /
  cast((current_timestamp-start_time)seconds as decimal(18,0)))
  as "Bytes sent/second",
```

```
(cast(bytes_received as decimal(18,0)) /
cast((current_timestamp-start_time)seconds as decimal(18,0)))
as "Bytes received/second"
from sessions
```

This command gives results like the following:

```
Session: 24
Client: ALBERT
State: Run
Elapsed Time: 0 01:14:05.000000
Bytes sent/second: 564321.9302768451
Bytes received/second: 0.0026748857944

Session: 26
Client: MILTON
State: Run
Elapsed Time: 0 00:06:13.000000
Bytes sent/second: 1638.5284210992221
Bytes received/second: 675821.6888561849
```

Exhausting Temporary Table Storage

SQL SELECT queries run from temporary table storage in the database. At least a 4MB partition must be available in the database for this purpose. Without this partition, temporary table storage space will become exhausted, and the SELECT query will no longer run.

To determine how much temporary table storage space is available in your database, issue the QUERY DB command. The server displays a report, like the following:

Available Space (MB)	Assigned Capacity (MB)	Maximum Extension (MB)	Maximum Reduction (MB)	Page Size (bytes)	Total Pages	Used Pages	%Util	Max. %Util
8	4	4	0	4,096	1,024	94	9.3	9.2

Check the value in the **Maximum Reduction** field. If this field shows a value of at least 4MB, you can perform SELECT queries.

If the **Maximum Reduction** value is below 4MB, you will not be able to perform SELECT queries. The database is either full or fragmented.

- If the database is full, increase the size of the database. See “Increasing the Size of the Database or Recovery Log” on page 393 for details.
- If the database is fragmented, either add a volume or unload and load your database. See “Reorganizing the Database” on page 402 for details.

Note: Complex SELECT queries (for example, those including the ORDER BY clause, the GROUP BY clause, or the DISTINCT operator) may require more than 4MB temporary table storage space.

Using SELECT Commands in Tivoli Storage Manager Scripts

A Tivoli Storage Manager script is one or more commands that are stored as an object in the database. You can run a script from an administrative client, the web interface, or the server console. You can also include it in an administrative command schedule to run automatically. See “Tivoli Storage Manager Server Scripts” on page 376 for details. You can define a script that contains one or more SELECT commands. Tivoli Storage Manager is shipped with a file that contains a number of sample scripts. The file, *scripts.smp*, is in the server directory. To create and store the scripts as objects in your server’s database, issue the DSMSERV RUNFILE command during installation:

```
> dsmserv runfile scripts.smp
```

You can also run the file as a macro from an administrative command line client:

```
macro scripts.smp
```

The sample scripts file contains TSM commands. These commands first delete any scripts with the same names as those to be defined, then define the scripts. The majority of the samples create SELECT commands, but others do such things as define and extend database volumes and back up storage pools. You can also copy and change the sample scripts file to create your own scripts.

Here are a few examples from the sample scripts file:

```
def script q_inactive_days '/* -----*/'
upd script q_inactive_days '/* Script Name:  Q_INACTIVE          */'
upd script q_inactive_days '/* Description: Display nodes that have not */'
upd script q_inactive_days '/*           accessed TSM for a          */'
upd script q_inactive_days '/*           specified number of days     */'
upd script q_inactive_days '/* Parameter 1: days                */'
upd script q_inactive_days '/* Example:   run q_inactive_days 5      */'
upd script q_inactive_days '/* -----*/'
upd script q_inactive_days "select node_name,lastacc time from nodes where -"
upd script q_inactive_days " cast((current_timestamp-lastacc_time)days as -"
upd script q_inactive_days " decimal) >= $1 "

/* Define a DB volume and extend the database          */

def script def_db_extend '/* -----*/'
upd script def_db_extend '/* Script Name:  DEF_DB_EXTEND          */'
upd script def_db_extend '/* Description: Define a database volume, */'
upd script def_db_extend '/*           and extend the database     */'
upd script def_db_extend '/* Parameter 1: db volume name          */'
upd script def_db_extend '/* Parameter 2: extension megabytes     */'
upd script def_db_extend '/* Example:   run def_db_extend VOLNAME 12 */'
upd script def_db_extend '/* -----*/'
upd script def_db_extend ' def dbv $1 '
upd script def_db_extend ' if (rc_ok) extend db $2'
upd script def_db_extend ' if (warning, error) q db f=d'
```

Canceling a SELECT Command

If a SELECT command will require a significant amount of resources, the server asks if you want to continue. You can cancel the command at that time. Cancel the command from the console session or an administrative client session.

Controlling the Format of SELECT Results

Tivoli Storage Manager provides commands to control the format of results of SELECT commands. You can control:

- How SQL data types such as VARCHAR are displayed, in wide or narrow format (SET SQLDISPLAYMODE)
- The format of date and time values in the results (SET SQLDATETIMEFORMAT)
- Whether SQL arithmetic results are truncated or rounded (SET SQLMATHMODE)

Note: Using the SET commands to change these settings keeps the settings in effect only for the current administrative client session. You can query these settings by using the QUERY SQLSESSION command.

Querying the SQL Activity Summary Table

You can query the SQL activity summary table to view statistics about each client session and server process. For a listing of the column names and their descriptions from the activity summary table, enter the following command:

```
select colname,remarks from columns where tablename='summary'
```

Here are a few example queries of the activity summary table.

- To display all events starting at 00:00 a.m. of the current day until the present time, enter:

```
select * from summary
```

The result might look like this:

```
START_TIME: 2000-07-22 19:32:00.000000
END_TIME: 2000-07-22 19:32:56.000000
ACTIVITY: BACKUP
NUMBER: 43
ENTITY: DWE
COMMETH: Named Pi
ADDRESS:
EXAMINED: 7
AFFECTED: 7
FAILED: 0
BYTES: 2882311
IDLE: 51
MEDIWA: 0
PROCESSES: 1
SUCCESSFUL: YES
```

ANS8002I Highest return code was 0.

- To display all events starting at or after 00:00 a.m. on September 24, 2000 until the present time, enter:

```
select * from summary where start_time>= '2000-09-24 00:00'
```

You can determine how long to keep information in the summary table. For example, to keep the information for 5 days, enter the following command:

```
set summaryretention 5
```

To keep no information in the table, specify a value of 0.

Creating Output for Use by Another Application

You can redirect the output of SELECT commands to a file in the same way as you would redirect the output of any command. When redirecting this output for use in another program (for example, a spreadsheet or database program), write the output in a format easily processed by the program to be used.

Two standard formats for tabular data files are *comma-separated values* (CSV) and *tab-separated values* (TSV). Most modern applications that can import tabular data can read one or both of these formats.

Use the administrative client command line options `-COMMADELIMITED` or `-TABDELIMITED` to select one of these formats for tabular query output. All tabular output during the administrative session will be formatted into either comma-separated or tab-separated values. For details about using command line options, see the *Administrator's Reference*.

The use of command output redirection and one of the delimited output format options lets you create queries whose output can be further processed in other applications. For example, based on the output of a `SELECT` command, a spreadsheet program could produce graphs of average file sizes and file counts summarized by type of client platform.

For details about redirecting command output, see the *Administrator's Reference*.

Using the Tivoli Storage Manager Activity Log

Task	Required Privilege Class
Request information from the activity log	Any administrator
Set the activity log retention period	System
Change the size of the activity log	System or unrestricted storage

The activity log contains all messages normally sent to the server console during server operation. The only exceptions are responses to commands entered at the console, such as responses to `QUERY` commands.

Examples of messages sent to the activity log include:

- When client sessions start or end
- When migration starts and ends
- When backup versions expire
- What data is exported to tape
- When expiration processing is performed
- What export or import processing is performed

Any error messages sent to the server console are also stored in the activity log.

Use the following sections to adjust the size of the activity log, set an activity log retention period, and request information about the activity log.

Requesting Information from the Activity Log

You can request information stored in the activity log. To minimize processing time when querying the activity log, you can:

- Specify a time period in which messages have been generated. The default for the `QUERY ACTLOG` command shows all activities that have occurred in the previous hour.

- Specify the message number of a specific message or set of messages.
- Specify a string expression to search for specific text in messages.
- Specify the QUERY ACTLOG command from the command line for large queries instead of using the graphical user interface.
- Specify whether the originator is the server or client. If it is the client, you can specify the node, owner, schedule, domain, or session number. If you are doing client event logging to the activity log and are only interested in server events, then specifying the server as the originator will greatly reduce the size of the results.

For example, to review messages generated on May 30 between 8 a.m. and 5 p.m., enter:

```
query actlog begindate=05/30/2000 enddate=05/30/2000
begintime=08:00 endtime=17:00
```

To request information about messages related to the expiration of files from the server storage inventory, enter:

```
query actlog msgno=0813
```

Refer to *Messages* for message numbers.

You can also request information only about messages logged by one or all clients. For example, to search the activity log for messages from the client for node JEE:

```
query actlog originator=client node=jee
```

Setting the Activity Log Retention Period

Use the SET ACTLOGRETENTION command to specify how long activity log information is kept in the database. The server automatically deletes messages from the activity log once the day that was specified with the SET ACTLOGRETENTION command has passed. At installation, the activity log retention period is set to one day. To change the retention period to 10 days, for example, enter:

```
set actlogretention 10
```

To disable activity log retention, set the SET ACTLOGRETENTION command to zero. To display the current retention period for the activity log, query the server status.

Changing the Size of the Activity Log

Because the activity log is stored in the database, the size of the activity log should be factored into the amount of space allocated for the database. Allow at least 1MB of additional space for the activity log.

The size of your activity log depends on how many messages are generated by daily processing operations and how long you want to retain those messages in the activity log. When retention time is increased, the amount of accumulated data also increases, requiring additional database storage.

When there is not enough space in the database or recovery log for activity log records, the server stops recording and sends messages to the server console. If you increase the size of the database or recovery log, the server starts activity log recording again.

If you do not have enough space in the database for the activity log, you can do one of the following:

- Allocate more space to the database

- Reduce the length of time that messages are kept in the activity log

For information about increasing the size of the database or recovery log, see “Increasing the Size of the Database or Recovery Log” on page 393.

Logging Tivoli Storage Manager Events to Receivers

The server and client messages provide a record of TSM activity that you, as an administrator, may use to monitor the server. You can log server messages and most client messages as *events* to one or more repositories called *receivers*. You can log the events to any combination of the following receivers:

TSM server console and activity log

See “Logging Events to the Tivoli Storage Manager Server Console and Activity Log” on page 420.

File and user exits

See “Logging Events to a File Exit and a User Exit” on page 420.

Tivoli event console

See “Logging Events to the Tivoli/Enterprise Console” on page 421.

Simple Network Management Protocol (SNMP)

See “Logging Events to an SNMP Manager” on page 423.

Event server receiver (Enterprise Event Logging)

Routes the events to an event server. See “Enterprise Event Logging: Logging Events to Another Server” on page 428.

In addition, you can filter the types of events to be enabled for logging. For example, you might enable only severe messages to the event server receiver and one or more specific messages, by number, to another receiver. Figure 70 shows a possible configuration in which both server and client messages are filtered by the event rules and logged to a set of specified receivers.




Figure 70. Event Logging Overview

Task	Required Privilege Class
Enable or disable events	Any administrator
Begin or end event logging	System

Enabling and Disabling Events

To enable or disable specific events or groups of events by receiver issue the ENABLE EVENTS and DISABLE EVENTS commands. When you enable or disable events, you can specify the following:

- A message number or an event severity (All, Info, Warning, Error, Severe).
- Events for one or more client nodes. If client events are to be enabled for matching nodes, use the NODENAME parameter.
- Events for one or more servers. If server events are to be enabled for matching servers, use the SERVERNAME parameter. See the ENABLE EVENTS command in *Administrator's Reference* for more information.

For example, to enable event logging to a user exit for server messages with a severity of WARNING and SEVERE, enter:

```
enable events userexit warning,severe
```

See the ENABLE EVENTS command in *Administrator's Reference* for more information.

Notes:

1. If you specify any invalid events, receivers, or names, the server issues an error message, but still enables any valid events, receivers, or names that you specified.
2. Certain events, such as messages that are issued during server start-up and shutdown, automatically go to the console. They do not go to other receivers, even if they are enabled.
3. Server messages in the SEVERE category and message ANR9999 can provide valuable diagnostic information if there is a serious problem. For this reason, you should not disable these messages.
4. Use the SET CONTEXTMESSAGING ON command to get additional information that could help determine the cause of ANR9999D messages. TSM polls the server components for information that includes process name, thread name, session ID, transaction data, locks that are held, and database tables that are in use.

Beginning and Ending Event Logging

Issue the BEGIN EVENTLOGGING and END EVENTLOGGING commands to begin and end logging for one or more receivers. A receiver for which event logging has begun is an *active receiver*.

At server start-up event logging begins automatically to the server console and activity log and for any receivers that are started based on entries in the server options file. See the appropriate receiver sections for details. However, you can begin logging events to receivers for which event logging is not automatically started at server startup using the BEGIN EVENTLOGGING command. You can also use this command after you have disabled event logging to one or more receivers.

You can specify multiple receivers by separating them with commas and no intervening spaces. If you specify ALL or no receiver, logging begins for all receivers that are configured.

To begin logging events to the event server for example, enter:

```
begin eventlogging eventserver
```

Logging Events to the Tivoli Storage Manager Server Console and Activity Log

Logging events to the server console and activity log begins automatically at server startup. To enable all error and severe client events to the console and activity log, issue the following command:

```
enable events console,actlog error,severe
```

Note: Enabling client events to the activity log will increase the database utilization. You can set a retention period for the log records by using the SET ACTLOGRETENTION command (see “Setting the Activity Log Retention Period” on page 417). At server installation, this value is set to one day. If you increase the retention period, utilization is further increased. For more information about the activity log, see “Using the Tivoli Storage Manager Activity Log” on page 416.

You can disable server and client events to the server console and client events to the activity log. However, you cannot disable server events to the activity log. Also, certain messages, such as those issued during server startup and shutdown and responses to administrative commands, will still be displayed at the console even if disabled.

Logging Events to a File Exit and a User Exit

You can log events to a file exit and a user exit:

- A file exit is a single file that receives all the information related to its enabled events. Be aware that this file can rapidly grow in size depending on the events enabled for it. There are two versions of the exit: binary and text.
- A user exit is an external interface in the form of an executable, user-written program. TSM supports user exits.

Note: Both types of event receivers must be specified in the server options (*dsmserv.opt*) file. See the server options section in *Administrator's Reference* for more information.

Both file and user exits receive event data in the same data block structure. Setting up logging for these receivers is also similar. Here are the steps involved:

To log events to a file exit:

1. Specify whether you want to log your events as a binary or text file exit. The binary file exit (FILEEXIT) stores each logged event as a record, while the text file exit (FILETEXTEXIT) stores each logged event as a fixed-sized, readable line. For more information about the text file exit, see “Readable Text File Exit (FILETEXTEXIT) Format” on page 570.
2. Specify whether event logging to the file exit receiver begins automatically at server startup. The parameters are YES and NO. If you do not specify YES, you must begin event logging manually by issuing the BEGIN EVENTLOGGING command.
3. Specify the file where each logged event is to be stored.

4. Specify how files will be stored if the file being stored already exists. REPLACE will overwrite the existing file, APPEND will append data to the existing file, and PRESERVE will not overwrite the existing file.

An example of how the file exit path will look in the *dsmserv.opt* file once all the desired parameters have been entered is:

```
filetextexit yes events.ftexit append
```

To log events to a user exit:

- a. Enter the USEREXIT parameter, then specify whether event logging to the user exit receiver begins automatically at server startup. The parameters for this option are YES and NO. If you do not specify YES, you must begin event logging manually by issuing the BEGIN EVENTLOGGING command.
 - b. Specify a DLL name that contains the user-exit function.
 - c. Specify the name of the user-exit function in the DLL.
 - d. Specify a module name of the user exit. This is the name of a shared library containing the exit. See the server options section in *Administrator's Reference* for more information.
- .
5. If YES was not specified in the server option, you must begin event logging from the administrative client. To begin event logging for a user-defined exit, for example, issue the following command:

```
begin eventlogging userexit
```

See “Beginning and Ending Event Logging” on page 419 for more information.

6. Enable events for the receiver. You must specify the name of the user exit in the USEREXIT server option and the name of the file in the FILEEXIT server option. Here are two examples:

```
enable events file error
enable events userexit error,severe
```

You can also enable events to one or more client nodes or servers by specify the NODENAME OR SERVERNAME parameter. See “Enabling and Disabling Events” on page 419 for more information.

Logging Events to the Tivoli/Enterprise Console

TSM includes the Tivoli receiver, a Tivoli/Enterprise Console (T/EC) adapter for sending events to the T/EC. You can specify the events to be logged based on their source. The valid event names are:

Event Name	Source
TSM_SERVER_EVENT	TSM server
TSM_CLIENT_EVENT	TSM clients
TSM_APPL_EVENT	TSM application program interface
TSM_TDP_DOMINO_EVENT	TDP for Domino
TSM_TDP_EXCHANGE_EVENT	TDP for MS Exchange
TSM_TDP_INFORMIX_EVENT	TDP for Informix
TSM_TDP_ORACLE_EVENT	TDP for Oracle

Event Name	Source
TSM_TDP_SQL_EVENT	TDP for MS SQL

Notes:

1. The application client must have enhanced T/EC support enabled in order to route the events to the T/EC.
2. Because of the number of messages, you should not enable all messages from a node to be logged to the T/EC.

To set up Tivoli as a receiver for event logging:

1. Define the TSM event classes to the T/EC with the *ibmtsm.baroc* file, which is distributed with the server.

Note: If you have migrated from ADISM Version 3 and have an existing *ibmadsm.baroc* file, do one of the following:

- Remove the file.
- Create a new rule base.
- Copy the file.

Before the events are displayed on a T/EC, you must import *ibmtsm.baroc* into an existing rule base or create a new rule base and activate it. To do this:

- From the TME desktop, click on the **Rule Base** icon to display the pop-up menu.
- Select **Import**, then specify the location of the *ibmtsm.baroc* file.
- Select the **Compile** pop-up menu.
- Select the **Load** pop-up menu and **Load, but activate only when server restarts** from the resulting dialog.
- Shut down the event server and restart it.

To create a new rule base, do the following:

- a. Click on the **Event Server** icon from the TME desktop. The **Event Server Rules Bases** window will open.
 - b. Select **Rule Base** from the **Create** menu.
 - c. Optionally, copy the contents of an existing rule base into the new rule base by selecting the **Copy** pop-up menu from the rule base to be copied.
 - d. Click on the **RuleBase** icon to display the pop-up menu.
 - e. Select **Import** and specify the location of the *ibmtsm.baroc* file.
 - f. Select the **Compile** pop-up menu.
 - g. Select the **Load** pop-up menu and **Load, but activate only when server restarts** from the resulting dialog.
 - h. Shut down the event server and restart it.
2. To define an event source and an event group:

- a. From the TME desktop, select **Source** from the **EventServer** pop-up menu. Define a new source whose name is TSM from the resulting dialog.
 - b. From the TME desktop, select **Event Groups** from the **EventServer** pop-up menu. From the resulting dialog, define a new event group for TSM and a filter that includes event classes `IBMTSMSEVER_EVENT` and `IBMTSMCLIENT_EVENT`.
 - c. Select the **Assign Event Group** pop-up menu item from the **Event Console** icon and assign the new event group to the event console.
 - d. Double-click on the **Event Console** icon to start the configured event console.
3. Enable events for logging to the Tivoli receiver. See “Enabling and Disabling Events” on page 419 for more information.
 4. In the server options file (*dsm serv.opt*), specify the location of the host on which the Tivoli server is running. For example, to specify a Tivoli server at the IP address 9.114.22.345:1555, enter the following:


```
techostname 9.114.22.345
tecport 1555
```
 5. Begin event logging for the Tivoli receiver. You do this in one of two ways:
 - To begin event logging automatically at server start up, specify the following server option:


```
tecbegineventlogging yes
```
 - Or
 - Enter the following command:


```
begin eventlogging tivoli
```

See “Beginning and Ending Event Logging” on page 419 for more information.

Logging Events to an SNMP Manager

You can use the simple network management protocol (SNMP) together with event logging to do the following:

- Set up an SNMP heartbeat monitor to regularly check that the TSM server is running.
- Send traps to an SNMP manager, such as NetView or Tivoli.
- Run TSM scripts and retrieve output and return codes. See “Tivoli Storage Manager Server Scripts” on page 376 for details.

The management information base (MIB), which is shipped with TSM, defines the variables that will run server scripts and return the server scripts’ results. You must register `SNMPADMIN`, the administrative client the server runs these scripts under. Although a password is not required for the subagent to communicate with the server and run scripts, a password should be defined for `SNMPADMIN` to prevent access to the server from unauthorized users. An SNMP password (community name) is required, however, to access the SNMP agent, which forwards the request to the subagent.

Note: Because the SNMP environment has weak security, you should consider not granting `SNMPADMIN` any administrative authority. This restricts `SNMPADMIN` to issuing only TSM queries.

SNMP SET requests are accepted for the name and input variables associated with the script names stored in the MIB by the SNMP subagent. This allows a script to be run by running a GET request for the *ibmAdsm1ReturnValue* and *ibmAdsm2ReturnValue* variables. A GETNEXT request will not cause the script to run. Instead, the results of the previous script processed will be retrieved. When an entire table row is retrieved, the GETNEXT request is used. When an individual variable is retrieved, the GET request is used.

Here is a sample TSM configuration with SNMP:

1. A TSM server on System A communicates with a subagent on system B.
2. The subagent on System B communicates with an agent on system C, which forward traps to a Netview system.
3. System D runs a TSM server that also uses the subagent on system B.
4. System B also has a TSM server that uses the subagent on system B.

To run an arbitrary command from an SNMP management application, for example, NetView, follow these steps:

1. Choose the name and parameters for a TSM script.
2. Use the application to communicate with the SNMP agent. This agent changes the TSM MIB variable for one of the two script names that the TSM subagent maintains. The SNMP agent also sets the parameter variables for one of the two scripts.
3. Use the application to retrieve the variable *ibmAdsmReturnValue1.x* or *ibmAdsmReturnValue2.x*, where *x* is the index of the server that is registered with the subagent.

To set the variables associated with the script (for example, *ibmAdsmServerScript1/2* or *ibmAdsmM1Parm1/2/3*), the nodes on which the subagent and the agent are run must have read-write authority to the MIB variables. This is done through the SNMP configuration process on the system that the SNMP agent runs on. In AIX, the file name is */etc/snmpd.conf*.

Here is an AIX example:

```
community public 9.115.20.174 255.255.255.254 readWrite
community public 9.115.46.25 255.255.255.254 readWrite
community public 127.0.0.1 255.255.255.254 readWrite
community public 9.115.20.176 255.255.255.254 readWrite
smux 1.3.6.1.4.1.2.3.1.2.2.1.1.2 public
```

The statements grant read-write authority to the MIB for the local node through the loopback mechanism (127.0.0.1), and to nodes with the three 9.115.xx.xx addresses. On AIX, TSM installation automatically updates the */etc/mib.defs* file with the names of the TSM MIB variables. This makes the MIB variables available to applications like the AIX System Monitor product. The smux statement allows the dpid2 daemon to communicate with snmpd.

The *snmpinfo* command is shipped with the System Monitor product. Here is an example of this command used to set and retrieve MIB variables:

```
snmpinfo -v -ms -c public -h tpcnov73 ibmAdsmServerScript1.1=QuerySessions
```

This command issues the set operation (-ms), passing in community name **public**, sending the command to host **tpcnov73**, and setting up variable *ibmAdsmServerScript1* to have the value *QuerySessions*. *QuerySessions* is the name of a server script that has been defined on a

server that will register with the TSM subagent. In this case, the first server that registers with the subagent is the *.1* suffix in *ibmAdsmServerScript1.1*. The following commands set the parameters for use with this script:

```
snmpinfo -v -ms -c public -h tpcnov73 ibmAdsmM1Parm1.1=xyz
snmpinfo -v -ms -c public -h tpcnov73 ibmAdsmM1Parm2.1=uvw
snmpinfo -v -ms -c public -h tpcnov73 ibmAdsmM1Parm3.1=xxx
```

You can set zero to three parameters. Only the script name is needed. To make the *QuerySessions* script run, retrieve the *ibmAdsmM1ReturnValue* variable (in this case, *ibmAdsmM1ReturnValue.1*). For example:

```
snmpinfo -v -mg -c public -h tpcnov73 ibmAdsmM1ReturnValue.1
```

The results of the command are returned as a single string with embedded carriage return/newline characters.

Note: Not all MIB browsers properly handle embedded carriage return/newline characters. In this case, *ibmAdsmM1ReturnCode.1* will contain the return code associated with the running of the script. If *ibmAdsmM2ReturnValue* is retrieved, the results of running the script named in *ibmAdsmServerScript2* are returned as a single numeric return code. Notice the *-mg* instead of *-ms* to signify the GET operation in the command to retrieve *ibmAdsmM1ReturnValue.1*. If the entire row is retrieved, the command is not run. Instead, the results from the last time the script was run are retrieved. This would be the case if the following command were issued:

```
snmpinfo -v -md -c public -h tpcnov73 ibmAdsm
```

in which all TSM MIB variables are displayed.

An SNMP agent is needed for communication between an SNMP manager and its managed systems. The SNMP agent is accomplished through the **snmpd daemon**. The Distributed Protocol Interface (DPI) Version 2 is an extension of this SNMP agent.

TSM management through SNMP requires additional information in the MIB of the local agent. Therefore, an SNMP agent supporting DPI Version 2 must be used to communicate with the TSM subagent. This SNMP agent is not included with TSM. AIX 4.2.1 and later include such an SNMP agent. IBM makes the SystemView[®] agent available for Windows and AIX. The TSM subagent is included with TSM and, before server startup, must be started as a separate process communicating with the SNMP agent.

The SNMP manager system can reside on the same system as the TSM server, but typically would be on another system connected through SNMP. The SNMP management tool can be any application, such as NetView or Tivoli, that can manage information through SNMP MIB monitoring and traps. The TSM server system runs the processes needed to send TSM event information to an SNMP management system. The processes are:

- SNMP agent (snmpd)
- TSM SNMP subagent (dsmsnmp)
- TSM server (dsmserv)

Cross-system support for communication between the server and subagent is not supported, and these products must be installed and run on the TSM server system. Figure 71 on page 426 illustrates a typical TSM implementation:




Figure 71. TSM SNMP Implementation

Figure 72 on page 427 shows how the communication for SNMP works in a TSM system:

- The SNMP manager and agent communicate with each other through the SNMP protocol. The SNMP manager passes all requests for variables to the agent.
- The agent then passes the request to the subagent and sends the answer back to the manager. The agent responds to the manager's requests and informs the manager about events by sending traps.
- The agent communicates with both the manager and subagent. It sends queries to the subagent and receives traps that inform the SNMP manager about events taking place on the application monitored through the subagent. The SNMP agent and subagent communicate through the Distributed Protocol Interface (DPI). Communication takes place over a stream connection, which typically is a TCP connection but could be another stream-connected transport mechanism.
- The subagent answers MIB queries of the agent and informs the agent about events by sending traps. The subagent can also create and delete objects or subtrees in the agent's MIB. This allows the subagent to define to the agent all the information needed to monitor the managed application.




Figure 72. Manager-Agent-Subagent Communication

Notes:

1. You can start *dsmsnmp* and the server in any order. However, starting *dsmsnmp* first is more efficient in that it avoids retries.
2. The MIB file name is *admserv.mib*.
3. The AIX install updates */etc/mib.defs*
4. *mib2adsm.tbl* is for concatenating to *mib2.tbl* for Windows SystemView agents.

Configuring Tivoli Storage Manager SNMP

The Tivoli Storage Manager SNMP set up procedure is illustrated by Figure 73:




Figure 73. Tivoli Storage Manager SNMP Set Up

To set up TSM monitoring through SNMP, do the following:

1. Modify the server options file (*dsmserv.opt*) to specify the SNMP communication method. Figure 74 on page 428 displays an example of a SNMP communication method setting in the server options file. For details about server options, see the server options section in *Administrator's Reference*.

```

commethod          snmp
snmpheartbeatinterval 5
snmpmessagecategory severity

```

Figure 74. Example of SNMP Communication Method Options

2. Install, configure, and start the SNMP agent as described in the documentation for that agent. The SNMP agent must support the DPI Version 2.0 standard. For example, the AIX SystemView agent is configured by customizing the file */etc/snmpd.conf*. A default configuration might look like this:

```

logging    file=/var/snmp/snmpd.log  enabled
logging    size=0  level=0
community public
community private 127.0.0.1 255.255.255.255 readWrite
community system 127.0.0.1 255.255.255.255 readWrite 1.17.2
view       1.17.2 system enterprises view
trap       public <snmp_manager_ip_adr> 1.2.3 fe
snmpd      maxpacket=16000 smuxtimeout=60
smux       1.3.6.1.4.1.2.3.1.2.2.1.1.2 public

```

where *<snmp_manager_ip_adr>* is the IP address of the system running the SNMP management application.

Before starting the agent, ensure that the DPI agent has been started and not the default SNMP agent that ships with the operating system or with TCP/IP.

Note: For AIX 4.2.1 and above, the correct agent is shipped with the system. If you are using the SystemView agent (rather than the version that ships with AIX 4.2.1 and later), you must set the *SVA_SNMPD* environment variable to ensure that the correct agent is started. You can set the variable to any value. For example, on AIX (korn shell) use the following export command:

```
# export SVA_SNMPD="active"
```

Then run *svstart*.

3. Start TSM SNMP subagent through the *dsmsnmp* executable.
4. Start the TSM server to begin communication through the configured TCP/IP port with the subagent.
5. Begin event logging for the SNMP receiver, and enable events to be reported to SNMP. For example, issue the following commands:

```
begin eventlogging snmp
enable event snmp all
```

6. Define the TSM SNMP MIB values for the SNMP manager to help format and display the TSM SNMP MIB variables and messages. The *admserv.mib* file ships with the TSM server and must be loaded by the SNMP manager. For example, when you run NetView for OS/2[®] as an SNMP manager, the *admserv.mib* file is copied to the *\netview_path\SNMP_MIB* directory and then loaded through the following command:

```
[C:\] loadmib -load admserv.mib
```

Enterprise Event Logging: Logging Events to Another Server

One or more servers can send server events and events from their own clients to another server for logging. The sending server receives the enabled events and routes them to a designated event server. This is done by a receiver that Tivoli Storage Manager provides. At the event server, an administrator can enable one or more receivers for the events being

routed from other servers. Figure 75 shows the relationship of a sending TSM server and a TSM event server.




Figure 75. Server to Server Event Logging

The following scenario is a simple example of how enterprise event logging can work.

The administrator at each sending server does the following:

1. Defines the server that will be the event server. For details about communication set up, see “Setting Up Communications for Enterprise Configuration and Enterprise Event Logging” on page 314.

```
define server server_b password=cholla
  haddress=9.115.3.45 lladdress=1505
```

2. Identifies the server just defined as the event server:

```
define eventserver server_b
```

3. Enables the logging of severe, error, and warning server messages from the sending server and severe and error messages from all clients to the event server receiver by issuing the following commands:

```
enable events eventserver severe,error,warning
enable events eventserver severe,error nodename=*
```

4. Begins event logging by issuing the following command:

```
begin eventlogging eventserver
```

The administrator at the event server does the following:

5. Enables the logging of severe and error messages to a file named *events* that are sent to it from the sending servers. The administrator defines the file with the following option in the server options file:

```
fileexit yes events append
```

Then the administrator enables the events by issuing the `ENABLE EVENTS` command for each sending server. For example, for `SERVER_A` the administrator would enter:

```
enable events file severe,error servername=server_a
```

Note: By default, logging of events from another server is enabled to the event server activity log. However, unlike events originating from a local server, events originating from another server can be disabled for the activity log at an event server.

One or more servers can send events to an event server. An administrator at the event server enables the logging of specific events from specific servers. In the previous example, SERVER_A routes severe, error, and warning messages to SERVER_B. SERVER_B, however, logs only the severe and error messages. If a third server sends events to SERVER_B, logging is enabled only if an ENABLE EVENTS command includes the third server. Furthermore, the SERVER_B determines the receiver to which the events are logged.

Attention: It is important that you do not set up server-to-server event logging in a loop. In such a situation, an event would continue logging indefinitely, tying up network and memory resources. TSM will detect such a situation and issue a message. Here are a few configurations to avoid:

- SERVER_A logs to SERVER_B, and SERVER_B logs to SERVER_A.
- SERVER_A logs to SERVER_B; SERVER_B logs to SERVER_C; SERVER_C logs to SERVER_A.

Querying Event Logging

The QUERY ENABLED command displays a list of server or client events that are enabled or disabled by a specified receiver. Because the lists of enabled and disabled events could be very long, TSM displays the shorter of the two lists. For example, assume that 1000 events for client node HSTANFORD were enabled for logging to the user exit and that later two events were disabled. To query the enabled events for HSTANFORD, enter:

```
query enabled userexit nodename=hstanford
```

The output would specify the *number* of enabled events and the *message names* of disabled events:

```
998 events are enabled for node HSTANFORD for the USEREXIT receiver.  
The following events are DISABLED for the node HSTANFORD for the USEREXIT  
receiver:  
ANE4000, ANE49999
```

The QUERY EVENTRULES command displays the history of events that are enabled or disabled by a specific receiver for the server or for a client node.

```
query enabled userexit nodename=hstanford
```

Using Tivoli Decision Support

Tivoli Decision Support (TDS) for Storage Management Analysis is a separate program product that works with Tivoli Storage Manager to let you strategically manage your enterprise network. Storage Management Analysis helps you make decisions concerning storage management by providing an overview of your system performance and resource usage. Using data collected from TSM servers, Storage Management Analysis displays multidimensional views and detailed reports.

Storage Management Analysis requires the Tivoli Storage Management Decision Support Loader, which runs daily to collect and aggregate the data into the database table. See “Scheduling the Decision Support Loader with Tivoli Storage Manager” on page 431 for information about automating the scheduling of Decision Support Loader runs. The Tivoli

Discovery Administrator interface is used to define queries that extract data from the TDS database into a file. Cognos Transformer builds a cube from the file, and Cognos PowerPlay generates reports from the cube. You can use the Tivoli Discovery Interface to view these reports. You can also use Crystal Reports to generate text-based views.

To use Storage Management Analysis on your TSM server or servers, you must first enable event logging of client events to the activity log. See “Logging Events to the Tivoli Storage Manager Server Console and Activity Log” on page 420 for details.

For documentation about TDS for Storage Management Analysis visit the Web site at http://www.tivoli.com/support/storage_mgr/tivolimain.html

Scheduling the Decision Support Loader with Tivoli Storage Manager

You can schedule the Decision Support Loader (DSL) to run automatically using the TSM Scheduler. Before defining a schedule, ensure that the backup-archive client is installed on a dedicated Windows workstation where the DSL is installed.

Use the following procedure to schedule the DSL:

1. On the TSM server:

- a. Register the client node. Assume that the client node you registered is called ASTROdsl.
- b. Define a client schedule on the server from which the DSL will extract data. For example, if the schedule is called TSMDSL and client node ASTROdsl is registered in the STANDARD domain, enter:

```
define schedule standard tsm_dsl action=c
object="c:\program files\tivoli\tsm\decision\tsmdsl"
```

Notes:

- 1) The installation directory path for the DSL is:
"c:\program files\tivoli\tsm\decision\tsmdsl.exe"
- 2) Enclose the full directory path in quotation marks as shown in the previous example.

- c. Associate the client node to the *tsm_dsl* schedule. For example:

```
define association standard tsm_dsl ASTROdsl
```

2. On the client's workstation:

- a. Ensure that the scheduler is installed.
- b. Start the scheduler for the client. Leave the scheduler running until scheduled rollups are no longer needed. To start the scheduler, you can open a command prompt window and navigate to where the backup-archive client is installed and enter:

```
> dsmc schedule
```

Note: If the DSL is not processed according to the schedule you have defined, check the directory path where the DSL is installed.

Monitoring Tivoli Storage Manager Accounting Records

Task	Required Privilege Class
Set accounting records on or off	System

TSM accounting records show the server resources that are used during a session. This information lets you track resources that are used by a client node session. At installation, accounting defaults to OFF. You can set accounting to ON by entering:

```
set accounting on
```

When accounting is on, the server creates a session resource usage accounting record whenever a client node session ends.

Accounting records are stored in the *dsmacct.log* file. The DSMSERV_ACCOUNTING_DIR environment variable specifies the directory where the accounting file is opened. If this variable is not set when the server is started, the *dsmacct.log* file is placed in the current directory when the server starts. For example, to set the environment variable to place the accounting records in the */home/engineering* directory, enter this command:

```
export DSMSERV_ACCOUNTING_DIR=/home/engineering
```

The accounting file contains text records that can be viewed directly or can be read into a spreadsheet program. The file remains opened while the server is running and accounting is set to ON. The file continues to grow until you delete it or prune old records from it. To close the file for pruning, either temporarily set accounting off or stop the server.

There are 31 fields, which are delimited by commas (.). Each record ends with a new-line character. Each record contains the following information:

Field	Contents
1	Product version
2	Product sublevel
3	Product name, 'ADSM',
4	Date of accounting (mm/dd/yyyy)
5	Time of accounting (hh:mm:ss)
6	Node name of TSM client
7	Client owner name (UNIX)
8	Client Platform
9	Authentication method used
10	Communication method used for the session
11	Normal server termination indicator (Normal=X'01', Abnormal=X'00')
12	Number of archive store transactions requested during the session
13	Amount of archived files, in kilobytes, sent by the client to the server
14	Number of archive retrieve transactions requested during the session
15	Amount of space, in kilobytes, retrieved by archived objects
16	Number of backup store transactions requested during the session
17	Amount of backup files, in kilobytes, sent by the client to the server
18	Number of backup retrieve transactions requested during the session
19	Amount of space, in kilobytes, retrieved by backed up objects
20	Amount of data, in kilobytes, communicated between the client node and the server during the session
21	Duration of the session, in seconds
22	Amount of idle wait time during the session, in seconds
23	Amount of communications wait time during the session, in seconds
24	Amount of media wait time during the session, in seconds

Field	Contents
25	Client session type. A value of 1 or 4 indicates a general client session. A value of 5 indicates a client session that is running a schedule.
26	Number of space-managed store transactions requested during the session
27	Amount of space-managed data, in kilobytes, sent by the client to the server
28	Number of space-managed retrieve transactions requested during the session
29	Amount of space, in kilobytes, retrieved by space-managed objects
30	Product release
31	Product level

The following shows a sample record:

```
3,8,ADSM,08/03/2000,16:26:37,node1,,AIX,1,Tcp/Ip,0,254,1713,0,0,47,1476,0,0,3316,960,27,5,1,4,0,0,0,0,7,2
```

Daily Monitoring Scenario

This section contains an example of the daily monitoring of a Tivoli Storage Manager system. Depending on the configuration of your system, you may want to perform additional monitoring tasks. If a function does not complete properly, you can review the activity log for errors that occurred at about the time of failure (see “Requesting Information from the Activity Log” on page 416 for details).

You can include the commands shown in a command script that you can run daily. Review the output of the script for any errors or problems.

1. Verify that drives are online. If there is a drive in the unavailable state, there may be errors with schedules.

```
query drive
```

2. Verify that database and recovery log volumes are online and synchronized.

```
query dbvolume
query logvolume
```

3. Check the status of disk volumes. If any are offline, check for hardware problems.

```
query volume devclass=disk
```

4. Check that scratch volumes are available.

```
query libvolume
```

5. Check the access state of the tape volumes. For example, a volume that is not in the read-write state may indicate a problem. You may need to move data and check the volumes out of the library.

```
query volume
```

6. Check database and recovery log statistics.

```
query db
query log
```

7. Verify that scheduled database backups completed successfully.

```
query volhistory type=dbbackup
```

8. Check the activity log for error messages.

```
query actlog search=ANR????E
```


21

Exporting and Importing Data

TSM provides an export-import facility that allows you to copy all or part of a server to removable media (export) so that data can be transferred to another server (import).

Task	Required Privilege Class
Perform export and import operations	System
Display information about export and import operations	Any administrator

This chapter takes you through the export and import tasks. See the following sections:

Concepts:
“Data That Can Be Exported and Imported”
Tasks:
“Preparing to Export or Import Data” on page 436
“Monitoring Export and Import Processes” on page 438
“Exporting Data to Sequential Media Volumes” on page 441
“Importing Data from Sequential Media Volumes” on page 445

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Data That Can Be Exported and Imported

Administrators can export or import the following types of TSM data:

- Server control information, which includes:
 - Administrator definitions
 - Client node definitions
 - Policy and scheduling definitions
- File data from server storage, which includes file space definitions and authorization rules. You can request that file data be exported in any of the following groupings of files:
 - Active and inactive versions of backed up files, archive copies of files, and space-managed files

-
- Active versions of backed up files, archive copies of files, and space-managed files
 - Active and inactive versions of backed up files
 - Active versions of backed up files
 - Archive copies of files
 - Space-managed files

Notes:

1. You can export information from an earlier version of TSM to a later one, but not from a later version to an earlier.
2. Data exported from a server with Unicode support cannot be imported to a server at an earlier version.

Your decision on what information to export depends on why you are exporting that information:

- To copy information to a second server (the target server), use the EXPORT NODE, EXPORT POLICY, and EXPORT ADMIN commands. This will balance the work load across servers. For example, when many client nodes access the same server, users contend for communication paths, server resources, and tape mounts during a restore or retrieve operation.

To relieve a server of some work load and improve its performance, you may want to take one or all of the following actions:

- Move a group of client nodes to a target server
- Move policy definitions associated with these client nodes
- Move administrator definitions for administrators who manage these client nodes

When you complete the import, you can delete file spaces, client nodes, policy objects, scheduling objects and administrators from the source server. This will reduce contention for server resources.

- To copy data for the purpose of installing a new server, use the EXPORT SERVER command to copy all data to sequential media volumes.

Note: Because results could be unpredictable, ensure that expiration, migration, backup, or archive are not running when the EXPORT NODE command is issued.

Preparing to Export or Import Data

Before you export or import data, do the following:

- Use the EXPORT or IMPORT command with the PREVIEW parameter to verify what data will be moved
- Prepare sequential media for exporting and importing data

Using Preview before Exporting or Importing Data

TSM provides the PREVIEW option on the EXPORT and IMPORT commands. When PREVIEW=YES, the report shows how much data will be transferred without actually moving any data. When PREVIEW=NO, the export or import operation is performed.

Issue each EXPORT or IMPORT command with PREVIEW=YES to determine which objects and how much data will be moved. The server sends the following types of messages to the server console and to the activity log for each operation:

Export

Reports the types of objects, number of objects, and number of bytes that would be copied to sequential media volumes. Use this information to determine how many sequential media volumes you will need.

Import

Reports the number and types of objects found on the sequential media volumes that meet your import specifications. Also reports information about any detected problems, such as corrupted data. Use this information to determine which data to move to the server and to determine if you have enough storage pool space allocated on the server.

To determine how much space is required to export all server data, enter:

```
export server filedata=all preview=yes
```

After you issue this command, the server starts a background process and issues a message similar to the following:

```
EXPORT SERVER started as Process 4
```

You can view the preview results on the server console or by querying the activity log.

You can request information about the background process, as described in “Requesting Information about an Export or Import Process” on page 438. If necessary, you can cancel an export or import process, as described in “Canceling Server Processes” on page 367.

Planning for Sequential Media Used to Export Data

To export data, you must specify a device class that supports sequential media and identify the volumes that will be used to store the exported data. Use this section to help you select the device classes and prepare sequential media volumes.

Selecting a Device Class

You can query the source and target servers to select a device class on each server that supports the same device type. If you cannot find a device class on each server that supports a matching device type, define a new device class for a device type that is available to both servers. See “Defining Device Classes” on page 105.

Notes:

1. If the mount limit for the device class selected is reached when you request an export (that is, if all the drives are busy), the server automatically cancels lower priority operations, such as reclamation, to make a mount point available for the export.
2. You can export data to a storage pool on another server by specifying a device class whose device type is SERVER. For details, see “Using Virtual Volumes to Store Data on Another Server” on page 348.

Estimating the Number of Removable Media Volumes to Label

To estimate the number of tapes or optical disks needed to store export data, divide the number of bytes to be moved by the estimated capacity of a volume.

For example, cartridge system tape volumes used with 3490 tape devices have an estimated capacity of 360MB. If the preview shows that you need to transfer 720MB of data, label at least two tape volumes before you export the data.

Using Scratch Media

TSM allows you to use scratch media to ensure that you have sufficient space to store all export data. If you use scratch media, record the label names and the order in which they were mounted. Or, use the `USEDVOLUMELIST` parameter on the export command to create a file containing the list of volumes used.

Labeling Removable Media Volumes

During an import process, you must specify the order in which volumes will be mounted. This order must match the order in which tapes or optical disks were mounted during the export process. To ensure that tapes or optical disks are mounted in the correct order, label tapes or optical disks with information that identifies the order in which they are mounted during the import process. For example, label tapes as `DSM001`, `DSM002`, `DSM003`, and so on.

When you export data, record the date and time for each labeled volume. Store this information in a safe location, because you will need the information when you import the data. Or, if you used the `USEDVOLUMELIST` parameter on the export command, save the resulting file. This file can be used on the import command `volumes` parameter.

Monitoring Export and Import Processes

The server lets you monitor export or import processes in two ways:

- You can view information about a process that is running on the server console or from an administrative client running in console mode.
- After a process has completed, you can query the activity log for status information from the server console or from an administrative client running in batch or interactive mode.

Requesting Information about an Export or Import Process

After you issue an `EXPORT` or `IMPORT` command, the server starts a background process, assigns a process ID to the operation, and displays the process ID when the operation starts.

You can query an export or import process by specifying the process ID number. For example, to request information about the `EXPORT SERVER` operation, which started as process 4, enter:

```
query process 4
```

If you issue a preview version of an `EXPORT` or `IMPORT` command and then query the process, the server reports the types of objects to be copied, the number of objects to be copied, and the number of bytes to be copied.

When you export or import data and then query the process, the server displays the number and types of objects copied so far, and the total number of bytes that have been transferred, along with information on any media mount requests that may be outstanding for the process.

For guidance information on querying background processes, see “Requesting Information about Server Processes” on page 407.

Viewing Information from the Server Console

When you issue an `IMPORT` or `EXPORT` command, either from the server console or from an administrative client, information is displayed on the server console. Figure 76 on page

439 shows an example of the information that is displayed after issuing an EXPORT SERVER command.

```

ANR0610I EXPORT SERVER started by SERVER_CONSOLE as process 1.
ANR0639I EXPORT SERVER: Processing domain ENGPOLDOM.
ANR0640I EXPORT SERVER: Processing policy set ACTIVE in policy domain
ENGPOLDOM.
ANR0640I EXPORT SERVER: Processing policy set STANDARD in policy domain
ENGPOLDOM.
ANR0641I EXPORT SERVER: Processing management class STANDARD in domain
ENGPOLDOM, set ACTIVE.
ANR0641I EXPORT SERVER: Processing management class STANDARD in domain
ENGPOLDOM, set STANDARD.
ANR0643I EXPORT SERVER: Processing archive copy group in domain
ENGPOLDOM, set STANDARD, management class ACTIVE.
ANR0643I EXPORT SERVER: Processing archive copy group in domain
ENGPOLDOM, set STANDARD, management class STANDARD.
ANR0643I EXPORT SERVER: Processing backup copy group in domain
ENGPOLDOM, set STANDARD, management class ACTIVE.
ANR0643I EXPORT SERVER: Processing backup copy group in domain
ENGPOLDOM, set STANDARD, management class STANDARD.
ANR0604I EXPORT SERVER: No schedules were found in policy domain * for
exporting.
ANR0635I EXPORT SERVER: Processing node TOMC.
ANR0605I EXPORT SERVER: No schedule associations were found in
policy domain * for exporting.
ANR0637I EXPORT SERVER: Processing file space DRIVED for node TOMC.
ANR0637I EXPORT SERVER: Processing file space OS2 for node TOMC.
ANR0637I EXPORT SERVER: Processing file space OS2VDISK for node TOMC.
ANR0617I EXPORT SERVER: Processing completed successfully.
ANR0620I EXPORT SERVER: Copied 1 domain(s).
ANR0621I EXPORT SERVER: Copied 2 policy set(s).
ANR0622I EXPORT SERVER: Copied 2 management class(es).
ANR0623I EXPORT SERVER: Copied 4 copy group(s).
ANR0626I EXPORT SERVER: Copied 1 node definition(s).
ANR0627I EXPORT SERVER: Copied 3 file space(s), 16 archive file(s)
and 0 backup file(s).
ANR0629I EXPORT SERVER: Copied 3045632 bytes of data.
ANR0611I EXPORT SERVER started by SERVER_CONSOLE as process 1 has ended.

```

Figure 76. Sample Export Server Output

Viewing Information from an Administrative Client

Use the console mode from an administrative client to monitor export or import operations or to capture processing messages to an output file. For example, to start an administrative session in console mode, enter:

```
> dsmadmc -consolemode
```

While the system is running in console mode, you cannot enter any administrative commands from the client session. You can, however, start another administrative client session for entering commands (for example, QUERY PROCESS) if you are using a multitasking workstation, such as OS/2 or AIX.

If you want TSM to write all terminal output to a file, specify the OUTFILE option with a destination. For example, to write output to the SAVE.OUT file, enter:

```
> dsmadmc -consolemode -outfile=save.out
```

For information about using the `CONSOLE` mode option and ending an administrative session in console mode, see *Administrator's Reference*.

Querying the Activity Log for Export or Import Information

After an export or import process has completed, you can query the activity log for status information and possible error messages.

To minimize processing time when querying the activity log for export or import information, restrict the search by specifying `EXPORT` or `IMPORT` in the `SEARCH` parameter of the `QUERY ACTLOG` command.

For example, to determine how much data will be moved after issuing the preview version of the `EXPORT SERVER` command, query the activity log by entering:

```
query actlog search=export
```

Figure 77 on page 441 displays a sample activity log report.

```

Date/Time          Message
-----
05/03/1998 10:50:28 ANR0610I EXPORT SERVER started by ADMIN as
process 1.
05/03/1998 10:50:28 ANR0639I EXPORT SERVER: Processing domain ENGPOLDOM.
05/03/1998 10:50:28 ANR0640I EXPORT SERVER: Processing policy set
ACTIVE in policy domain ENGPOLDOM.
05/03/1998 10:50:28 ANR0640I EXPORT SERVER: Processing policy set
STANDARD in policy domain ENGPOLDOM.
05/03/1998 10:50:29 ANR0641I EXPORT SERVER: Processing management class
STANDARD in domain ENGPOLDOM, set ACTIVE.
05/03/1998 10:50:29 ANR0641I EXPORT SERVER: Processing management class
STANDARD in domain ENGPOLDOM, set STANDARD.
05/03/1998 10:50:29 ANR0643I EXPORT SERVER: Processing archive copy
group in domain ENGPOLDOM, set STANDARD, management class ACTIVE.
05/03/1998 10:50:29 ANR0643I EXPORT SERVER: Processing archive copy
group in domain ENGPOLDOM, set STANDARD, management class STANDARD.
05/03/1998 10:50:29 ANR0642I EXPORT SERVER: Processing backup copy
group in domain ENGPOLDOM, set STANDARD, management class ACTIVE.
05/03/1998 10:50:29 ANR0642I EXPORT SERVER: Processing backup copy
group in domain ENGPOLDOM, set STANDARD, management class STANDARD.
05/03/1998 10:50:29 ANR0604I EXPORT SERVER: No schedules were found in policy
domain * for exporting.
05/03/1998 10:50:29 ANR0635I EXPORT SERVER: Processing node TOMC.
05/03/1998 10:50:29 ANR0605I EXPORT SERVER: No schedule associations were
found in policy domain * for exporting.
05/03/1998 10:50:29 ANR0637I EXPORT SERVER: Processing file space DRIVED for
node TOMC.
05/03/1998 10:50:29 ANR0637I EXPORT SERVER: Processing file space OS2 for node
TOMC.
05/03/1998 10:50:29 ANR0637I EXPORT SERVER: Processing file space OS2VDISK for
node TOMC.
05/03/1998 10:50:32 ANR0617I EXPORT SERVER: Processing completed successfully.
05/03/1998 10:50:32 ANR0620I EXPORT SERVER: Copied 1 domain(s).
05/03/1998 10:50:32 ANR0621I EXPORT SERVER: Copied 2 policy set(s).
05/03/1998 10:50:32 ANR0622I EXPORT SERVER: Copied 2 management class(es).
05/03/1998 10:50:32 ANR0623I EXPORT SERVER: Copied 4 copy group(s).
05/03/1998 10:50:32 ANR0626I EXPORT SERVER: Copied 1 node definition(s).
05/03/1998 10:50:32 ANR0627I EXPORT SERVER: Copied 3 file space(s),
16 export file(s) and 0 backup file(s).
05/03/1998 10:50:32 ANR0629I EXPORT SERVER: Copied 3045632 bytes of data.
05/03/1998 10:50:32 ANR0611I EXPORT SERVER started by ADMIN as
process 1 has ended.

```

Figure 77. Sample Activity Log Report on Exported Data

Exporting Data to Sequential Media Volumes

You can export all server control information or a subset of server control information by specifying one or more of the following export commands:

- EXPORT SERVER
- EXPORT ADMIN
- EXPORT NODE
- EXPORT POLICY

When you export data, you must specify the device class to which export data will be written. You must also list the volumes in the order in which they are to be mounted when the data is imported. See “Labeling Removable Media Volumes” on page 438 for information on labeling tape volumes.

You can specify the `USEDVOLUMELIST` parameter to indicate the name of a file where a list of volumes used in a successful export operation will be stored. If the specified file is created without errors, it can be used as input to the `IMPORT` command on the `VOLUMENAMES=FILE:filename` parameter. This file will contain comment lines with the date and time the export was done, and the command issued to create the export.

Note: If you specify this parameter with an existing filename, the existing file is overwritten with the new information.

Deciding When to Export Data

When you issue an `EXPORT` command, the operation runs as a background process. This process allows you to continue performing administrative tasks. In addition, users can continue to back up, archive, migrate, restore, retrieve, or recall files from TSM.

If you choose to perform an export operation during normal working hours, be aware that administrators can change server definitions and users may modify files that are in server storage. If administrators or users modify data shortly after it has been exported, then the information copied to tape may not be consistent with data stored on the source server.

If you want to export an exact point-in-time copy of server control information, you can prevent administrative and other client nodes from accessing the server. See “Preventing Administrative Clients from Accessing the Server” and “Preventing Client Nodes from Accessing the Server”.

Preventing Administrative Clients from Accessing the Server

Administrators can change administrator, policy, or client node definitions during an export process. To prevent administrators from modifying these definitions, you can lock out administrator access to the server and cancel any administrative sessions before issuing an `EXPORT` command. After the export process is complete, unlock administrator access.

For more information on canceling sessions, see “Canceling a Tivoli Storage Manager Session” on page 218. For more information on locking or unlocking administrators from the server, see “Locking and Unlocking Administrators from the Server” on page 226.

Preventing Client Nodes from Accessing the Server

If client node information is exported while that client is backing up, archiving, or migrating files, the latest file copies for the client may not be exported to tape. To prevent users from accessing the server during export operations, cancel existing client sessions as described in “Canceling a Tivoli Storage Manager Session” on page 218. Then you can do one of the following:

- Disable server access to prevent client nodes from accessing the server, as described in “Disabling or Enabling Access to the Server” on page 220.
This option is useful when you export all client node information from the source server and want to prevent all client nodes from accessing the server.
- Lock out particular client nodes from server access, as described in “Locking and Unlocking Client Nodes” on page 199.

This option is useful when you export a subset of client node information from the source server and want to prevent particular client nodes from accessing the server until the export operation is complete.

After the export operation is complete, allow client nodes to access the server again by:

- Enabling the server, as described in “Disabling or Enabling Access to the Server” on page 220
- Unlocking client nodes, as described in “Locking and Unlocking Client Nodes” on page 199

Exporting Server Data

When you issue the EXPORT SERVER command, the server exports all server control information. You can also export file data information with the EXPORT SERVER command.

For example, you want to export server data to four defined tape cartridges, which are supported by the TAPECLASS device class. You want the server to use scratch volumes if the four volumes are not enough, and so you use the default of SCRATCH=YES. To issue this command, enter:

```
export server devclass=tapeclass  
volumenames=dsm001,dsm002,dsm003,dsm004 filedata=all
```

During the export process, the server exports definition information before it exports file data information. This ensures that definition information is stored on the first tape volumes. This process allows you to mount a minimum number of tapes during the import process, if your goal is to copy only control information to the target server.

In the example above, the server exports:

- Administrator definitions
- Client node definitions
- Policy domain, policy set, management class, and copy group definitions
- Schedule definitions and client node associations
- File space definitions
- File space authorization rules
- Backed up, archived, and space-managed files

Exporting Administrator Information

When you issue the EXPORT ADMIN command, the server exports administrator definitions. Each administrator definition includes:

- Administrator name, password, and contact information
- Any administrative privilege classes the administrator has been granted
- Whether the administrator ID is locked from server access

You can specify a list of administrator names, or you can export all administrator names.

In the following example, definitions for the DAVEHIL and PENNER administrator IDs will be exported to the DSM001 tape volume, which is supported by the TAPECLASS device class. Do not allow any scratch media to be used during this export process. To issue this command, enter:

```
export admin davehil,penner devclass=tapeclass
volumenames=dsm001 scratch=no
```

Exporting Client Node Information

When you issue the EXPORT NODE command, the server exports client node definitions. Each client node definition includes:

- User ID, password, and contact information
- Name of the policy domain to which the client is assigned
- File compression status
- Whether the user has the authority to delete backed up or archived files from server storage
- Whether the client node ID is locked from server access

You can also specify whether to export file data. File data includes file space definitions and authorization rules. You can request that file data be exported in any of the following groupings of files:

- Active and inactive versions of backed up files, archive copies of files, and space-managed files
- Active versions of backed up files, archive copies of files, and space-managed files
- Active and inactive versions of backed up files
- Active versions of backed up files
- Archive copies of files
- Space-managed files

When client file data is exported, the server copies files to export volumes in the order of their physical location in server storage. This process minimizes the number of mounts required during the export process.

If you do not specify that you want to export file data, then the server only exports client node definitions.

For example, suppose you want to do the following:

- Export definitions for client nodes and file spaces in the ENGPOLDOM policy domain
- Export any active backup versions of files belonging to these client nodes
- Export this information to scratch volumes in the TAPECLASS device class

To issue this command, enter:

```
export node filespace=* domains=engpoldom
filedata=backupactive devclass=tapeclass
```

In this example, the server exports:

- Definitions of client nodes assigned to ENGPOLDOM

- File space definitions and backup authorizations for each client node in ENGPOLDOM
- Active versions of backed up files belonging to the client nodes assigned to ENGPOLDOM

Exporting Policy Information

When you issue the EXPORT POLICY command, the server exports the following information belonging to each specified policy domain:

- Policy domain definitions
- Policy set definitions, including the active policy set
- Management class definitions, including the default management class
- Backup copy group and archive copy group definitions
- Schedule definitions
- Associations between client nodes and schedules

For example, suppose you want to export policy and scheduling definitions from the policy domain named ENGPOLDOM. You want to use tape volumes DSM001 and DSM002, which belong to the TAPECLASS device class, but allow the server to use scratch tape volumes if necessary. To issue this command, enter:

```
export policy engpoldom
devclass=tapeclass volumenames=dsm001,dsm002
```

Importing Data from Sequential Media Volumes

Before you import data to a new target server, you must:

1. Install TSM on the target server. This step includes defining disk space for the database and recovery log.

For information on installing TSM, see *Quick Start*.

2. Define server storage for the target server.

Because each server operating system handles devices differently, TSM does not export server storage definitions. Therefore, you must define initial server storage for the target server. TSM must at least be able to use a drive that is compatible with the export media. This task can include defining libraries, drives, device classes, storage pools, and volumes. See the *Administrator's Guide* that applies to the target server.

After TSM is installed and set up on the target server, a system administrator can import all server control information or a subset of server control information by specifying one or more of the following import commands:

- IMPORT SERVER
- IMPORT ADMIN
- IMPORT NODE
- IMPORT POLICY

This section guides you through the entire process of importing all server control information and file data from tape volumes to a new target server. This process includes:

- Previewing information before you import data

-
- Importing definitions
 - Tailoring server storage definitions on the target server
 - Importing file data

After you understand how to import server control information and file data information, you can import any subset of data to the target server.

Step 1: Previewing Information before You Import Data

Before you import any data to the target server, preview each IMPORT command to determine what data you want to import to the target server. You can import all or a subset of export data from tapes.

When you set PREVIEW=YES, tape operators must mount export tape volumes so that the target server can calculate the statistics reported by the use of this parameter.

For example, to preview information for the IMPORT SERVER command, enter:

```
import server devclass=tapeclass preview=yes  
volumenames=dsm001,dsm002,dsm003,dsm004
```

Figure 78 on page 447 shows an example of the messages sent to the server console and the activity log.

```

ANR0402I Session 3 started for administrator SERVER_CONSOLE (Server).
ANR1363I Import volume DSM001 opened (sequence number 1).
ANR0610I IMPORT SERVER started by SERVER_CONSOLE as process 2.
ANR0612I IMPORT SERVER: Reading EXPORT SERVER data from server TSM exported
05/07/1996 12:39:48.
ANR0639I IMPORT SERVER: Processing domain ENGPOLDOM.
ANR0640I IMPORT SERVER: Processing policy set ACTIVE in policy domain
ENGPOLDOM.
ANR0640I IMPORT SERVER: Processing policy set STANDARD in policy domain
ENGPOLDOM.
ANR0641I IMPORT SERVER: Processing management class STANDARD in domain
ENGPOLDOM, set ACTIVE.
ANR0641I IMPORT SERVER: Processing management class MCENG in domain
ENGPOLDOM, set STANDARD.
ANR0641I IMPORT SERVER: Processing management class STANDARD in domain
ENGPOLDOM, set STANDARD.
ANR0643I IMPORT SERVER: Processing archive copy group in domain
ENGPOLDOM, set ACTIVE, management class STANDARD.
ANR0643I IMPORT SERVER: Processing archive copy group in domain ENGPOLDOM,
set STANDARD, management class MCENG.
ANR0643I IMPORT SERVER: Processing archive copy group in domain ENGPOLDOM,
set STANDARD, management class STANDARD.
ANR0642I IMPORT SERVER: Processing backup copy group in domain ENGPOLDOM,
set ACTIVE, management class STANDARD.
ANR0642I IMPORT SERVER: Processing backup copy group in domain ENGPOLDOM,
set STANDARD, management class MCENG.
ANR0642I IMPORT SERVER: Processing backup copy group in domain ENGPOLDOM,
set STANDARD, management class STANDARD.
ANR0638I IMPORT SERVER: Processing administrator DAVEHIL.
ANR0638I IMPORT SERVER: Processing administrator PENNER.
ANR0635I IMPORT SERVER: Processing node TOMC.
ANR0636I IMPORT SERVER: Processing file space OS2 for node TOMC as file
space OS1.
ANR0636I IMPORT SERVER: Processing file space DRIVED for node TOMC as file
space DRIVE1.
ANR0636I IMPORT SERVER: Processing file space OS2VDISK for node TOMC as file
space OS2VDIS1.
ANR1365I Import volume DSM001 closed (end reached).
ANR1363I Import volume DSM002 opened (sequence number 2).
ANR1365I Import volume DSM002 closed (end reached).
ANR1363I Import volume DSM003 opened (sequence number 3).
ANR1365I Import volume DSM003 closed (end reached).
ANR1363I Import volume DSM004 opened (sequence number 4).
ANR1365I Import volume DSM004 closed (end reached).
ANR0617I IMPORT SERVER: Processing completed successfully.
ANR0620I IMPORT SERVER: Copied 1 domain(s).
ANR0621I IMPORT SERVER: Copied 2 policy set(s).
ANR0622I IMPORT SERVER: Copied 2 management class(es).
ANR0623I IMPORT SERVER: Copied 6 copy group(s).
ANR0625I IMPORT SERVER: Copied 2 administrator(s).
ANR0626I IMPORT SERVER: Copied 1 node definition(s).
ANR0627I IMPORT SERVER: Copied 3 file space(s), 0 archive file(s) and 462
backup file(s).
ANR0629I IMPORT SERVER: Copied 8856358 bytes of data.
ANR0611I IMPORT SERVER started by SERVER_CONSOLE as process 2 has ended.

```

Figure 78. Sample Report Created by Issuing Preview for an Import Server Command

Use the value reported for the total number of bytes copied to estimate storage pool space needed to store imported file data.

For example, Figure 78 shows that 8 856 358 bytes of data will be imported. Ensure that you have at least 8 856 358 bytes of available space in the backup storage pools defined to the

server. You can use the `QUERY STGPOOL` and `QUERY VOLUME` commands to determine how much space is available in the server storage hierarchy.

In addition, the preview report shows that 0 archive files and 462 backup files will be imported. Because backup data is being imported, ensure that you have sufficient space in the backup storage pools used to store this backup data. See “Step 3: Tailoring Server Storage Definitions on the Target Server” on page 450 for information on identifying storage pools on the target server.

For information on specifying the `PREVIEW` parameter, see “Using Preview before Exporting or Importing Data” on page 436. For information on reviewing the results of a preview operation, see “Monitoring Export and Import Processes” on page 438.

Step 2: Importing Definitions

Next, you want to import server control information, which includes:

- Administrator definitions
- Client node definitions
- Policy domain, policy set, management class, and copy group definitions
- Schedule definitions and client node associations

However, do not import file data at this time, because some storage pools named in the copy group definitions may not exist yet on the target server.

Before you import server control information, do the following:

- Read and understand the following information:
 - “Determining Whether to Replace Existing Definitions”
 - “Understanding How the Server Imports Active Policy Sets”
- Start an administrative client session in console mode to capture import messages to an output file. See “Directing Import Messages to an Output File” on page 449.

Then import the server control information from specified tape volumes. See “Importing Server Control Information” on page 450.

Determining Whether to Replace Existing Definitions

By using the `REPLACEDFS` parameter with the `IMPORT` command, you can specify whether to replace existing definitions on the target server when TSM encounters an object with the same name during the import process.

For example, if a definition exists for the `ENGPOLDOM` policy domain on the target server before you import policy definitions, then you must specify `REPLACEDFS=YES` to have TSM replace the existing definition with the data from the export tape.

Definitions that can be replaced include administrator, client node, policy, or schedule definitions. The default is to not replace existing definitions on the target server.

Understanding How the Server Imports Active Policy Sets

When the server imports policy definitions, the following objects are imported to the target server:

- Policy domain definitions

- Policy set definitions, including the ACTIVE policy set
- Management class definitions
- Backup copy group definitions
- Archive copy group definitions
- Schedule definitions defined for each policy domain
- Client node associations, if the client node definition exists on the target server

If the server encounters a policy set named ACTIVE on the tape volume during the import process, it uses a temporary policy set named \$\$ACTIVE\$\$ to import the active policy set.

After \$\$ACTIVE\$\$ is imported to the target server, the server activates this policy set. During the activation process, the server validates the policy set by examining the management class and copy group definitions. If any of the following conditions occur, the server issues warning messages during validation:

- The storage destinations specified in the backup and archive copy groups do not refer to defined storage pools.
- The default management class does not contain a backup or archive copy group.
- The current ACTIVE policy set contains management class names that are not defined in the policy set to be activated.
- The current ACTIVE policy set contains copy group names that are not defined in the policy set to be activated.

After each \$\$ACTIVE\$\$ policy set has been activated, the server deletes that \$\$ACTIVE\$\$ policy set from the target server. To view information about active policy on the target server, you can use the following commands:

- QUERY COPYGROUP
- QUERY DOMAIN
- QUERY MGMTCLASS
- QUERY POLICYSET

Results from issuing the QUERY DOMAIN command show the activated policy set as \$\$ACTIVE\$\$. TSM uses the \$\$ACTIVE\$\$ name to show you that the policy set which is currently activated for this domain is the policy set that was active at the time the export was performed.

Directing Import Messages to an Output File

The information generated by the validation process can help you define a storage hierarchy that supports the storage destinations currently defined in the import data.

You can direct import messages to an output file to capture any error messages that are detected during the import process. Do this by starting an administrative client session in console mode before you invoke the import command.

For example, to direct messages to an output file named IMPSERV.OUT, enter:

```
> dsmadm -consolemode -outfile=impserv.out
```

Importing Server Control Information

Now you are ready to import the server control information. Based on the information generated during the preview operation, you know that all definition information has been stored on the first tape volume named DSM001. Specify that this tape volume can be read by a device belonging to the TAPECLASS device class.

From an administrative client session or from the server console, enter:

```
import server filedata=none devclass=tapeclass
volumenames=dsm001
```

Step 3: Tailoring Server Storage Definitions on the Target Server

After you import definition information, use the reports generated by the import process to help you tailor storage for the target server.

To tailor server storage definitions on the target server, complete the following steps:

1. Identify any storage destinations specified in copy groups and management classes that do not match defined storage pools:
 - If the policy definitions you imported included an ACTIVE policy set, that policy set is validated and activated on the target server. Error messages generated during validation include whether any management classes or copy groups refer to storage pools that do not exist on the target server. You have a copy of these messages in a file if you directed console messages to an output file as described in “Directing Import Messages to an Output File” on page 449.
 - Query management class and copy group definitions to compare the storage destinations specified with the names of existing storage pools on the target server. To request detailed reports for all management classes, backup copy groups, and archive copy groups in the ACTIVE policy set, enter these commands:

```
query mgmtclass * active * format=detailed
query copygroup * active * standard type=backup format=detailed
query copygroup * active * standard type=archive format=detailed
```
2. If storage destinations for management classes and copy groups in the ACTIVE policy set refer to storage pools that are not defined, do one of the following:
 - Define storage pools that match the storage destination names for the management classes and copy groups, as described in “Defining or Updating Primary Storage Pools” on page 123.
 - Change the storage destinations for the management classes and copy groups. Do the following:
 - a. Copy the ACTIVE policy set to another policy set
 - b. Modify the storage destinations of management classes and copy groups in that policy set, as required
 - c. Activate the new policy set

For information on copying policy sets, see “Defining and Updating a Policy Set” on page 254.

Depending on the amount of client file data that you expect to import, you may want to examine the storage hierarchy to ensure that sufficient storage space is available. Storage

pools specified as storage destinations by management classes and copy groups may fill up with data. For example, you may need to define additional storage pools to which data can migrate from the initial storage destinations.

Step 4: Importing File Data Information

After you have defined the appropriate storage hierarchy on the target server, you can import file data from the tape volumes. File data includes file space definitions and authorization rules. You can request that file data be imported in any of the following groupings:

- Active and inactive versions of backed up files, archive copies of files, and space-managed files
- Active versions of backed up files, archive copies of files, and space-managed files
- Active and inactive versions of backed up files
- Active versions of backed up files
- Archive copies of files
- Space-managed files

Before you import file data information:

- Understand how the server handles duplicate file space names
- Decide whether to keep the original creation date for backup versions and archive copies or to import file data using an adjusted date

Understanding How Duplicate File Spaces Are Handled

When the server imports file data information, it imports any file spaces belonging to each specified client node. If a file space definition already exists on the target server for the node, the server does *not* replace the existing file space name.

If the server encounters duplicate file space names when it imports file data information, it creates a new file space name for the imported definition by replacing the final character or characters with a number. A message showing the old and new file space names is written to the server console and to the activity log.

For example, if the C_DRIVE and D_DRIVE file space names reside on the target server for node FRED and on the tape volume for FRED, then the server imports the C_DRIVE file space as C_DRIV1 file space and the D_DRIVE file space as D_DRIV1 file space, both assigned to node FRED.

Deciding Whether to Use a Relative Date When Importing File Data

When you import file data, you can keep the original creation date for backup versions and archive copies, or you can specify that the server use an adjusted date.

Because tape volumes containing exported data might not be used for some time, the original dates defined for backup versions and archive copies may be old enough that files are expired immediately when the data is imported to the target server.

To prevent backup versions and archive copies from being expired immediately, specify `DATES=RELATIVE` on the `IMPORT NODE` or `IMPORT SERVER` commands to adjust for the elapsed time since the files were exported to tape.

For example, assume that data exported to tape includes an archive copy archived five days prior to the export operation. If the tape volume resides on the shelf for six months before the data is imported to the target server, the server resets the archival date to five days prior to the import operation.

If you want to keep the original dates set for backup versions and archive copies, use `DATES=ABSOLUTE`, which is the default. If you use the absolute value, any files whose retention period has passed will be expired shortly after they are imported to the target server.

Issuing an Import Server or Import Node Command

You can import file data, either by issuing the `IMPORT SERVER` or `IMPORT NODE` command. When you issue either of these commands, you can specify which type of files should be imported for all client nodes specified and found on the export tapes. You can specify any of the following values to import file data:

All Specifies that all active and inactive versions of backed up files, archive copies of files, and space-managed files for specified client nodes are imported to the target server

None Specifies that no files are imported to the target server; only client node definitions are imported

Archive

Specifies that only archive copies of files are imported to the target server

Backup

Specifies that only backup copies of files, whether active or inactive, are imported to the target server

Backupactive

Specifies that only active versions of backed up files are imported to the target server

Allactive

Specifies that only active versions of backed up files, archive copies of files, and space-managed files are imported to the target server

Spacemanaged

Specifies that only files that have been migrated from a user's local file system (space-managed files) are imported

For example, suppose you want to import all backup versions of files, archive copies of files, and space-managed files to the target server. You do not want to replace any existing server control information during this import operation. Specify the four tape volumes that were identified during the preview operation. These tape volumes can be read by any device in the `TAPECLASS` device class. To issue this command, enter:

```
import server filedata=all replacedefs=no
devclass=tapeclass volumenames=dsm001,dsm002,dsm003,dsm004
```

Considerations When Importing Data

You can use an import command to copy a subset of the information from export tapes to the target server. For example, if a tape was created with `EXPORT SERVER`, you can import only node information from the tape by using `IMPORT NODE`.

While the server allows you to issue any import command, data cannot be imported to the server if it has not been exported to tape. For example, if a tape is created with the EXPORT POLICY command, an IMPORT NODE command will not find any data on the tape because node information is not a subset of policy information.

Table 27 shows the commands you can use to import a subset of exported information to a target server.

Table 27. Importing a Subset of Information from Tapes

If tapes were created with this export command:	You can issue this import command:	You cannot issue this import command:
EXPORT SERVER	IMPORT SERVER IMPORT ADMIN IMPORT NODE IMPORT POLICY	—
EXPORT NODE	IMPORT NODE IMPORT SERVER	IMPORT ADMIN IMPORT POLICY
EXPORT ADMIN	IMPORT ADMIN IMPORT SERVER	IMPORT NODE IMPORT POLICY
EXPORT POLICY	IMPORT POLICY IMPORT SERVER	IMPORT ADMIN IMPORT NODE

Recovering from Errors during the Import Process

During import processing, the server may encounter invalid data due to corruption during storage on tape or in the database prior to the export operation. If invalid data is encountered during an import operation, the server does the following:

- The default value is used for the new object's definition
- If the object already exists, the existing parameter is not changed

The server reports on the affected objects to the server console and the activity log during import and export operations. You should query these objects when the import process is complete to see if they reflect information that is acceptable.

Each time you run the IMPORT NODE or IMPORT SERVER command with the FILEDATA parameter equal to a value other than NONE, TSM creates a new file space and imports data to it. This process ensures that the current import does not overwrite data from a previous import. For information on how TSM handles duplicate file spaces, see “Understanding How Duplicate File Spaces Are Handled” on page 451.

A file space definition may already exist on the target server for the node. If so, an administrator with system privilege can issue the DELETE FILESPACE command to remove file spaces that are corrupted or no longer needed. For more information on the DELETE FILESPACE command, refer to the *Administrator's Reference*.

Renaming a File Space

An imported file space can have the same name as a file space that already exists on a client node. In this case, the server does not overlay the existing file space, and the imported file space is given a new system generated file space name. This new name may match file

space names that have not been backed up and are unknown to the server. In this case, you can use the `RENAME FILESPACE` command to rename the imported file space to the naming convention used for the client node.

Exporting and Importing Data from Virtual Volumes

All `EXPORT` and `IMPORT` operations described in the previous sections can also be done to virtual volumes. Data stored as virtual volumes appear to be sequential storage pool volumes on the source server, but are actually stored as archive files on another server. Those archive files can be in random or sequential access storage pools. The `EXPORT` and `IMPORT` commands are identical to those previously shown, except that the device class specified in the commands must have a device type of `SERVER`. For details about how to configure your server to export to or import from virtual volumes, see “Using Virtual Volumes to Store Data on Another Server” on page 348.

V — Protecting the Server

Protecting and Recovering Your Server

Failure or loss of the TSM database, the recovery log, or storage pool(s) can cause loss of client data. This chapter describes how you can use TSM to protect your server and if necessary, how you can use TSM to recover your server.

Note: The term *tape* refers to any kind of sequential access, removable media unless otherwise indicated.

See the following sections:

Concepts:
“Levels of Protection” on page 458
“Storage Pool Protection: An Overview” on page 458
“Database and Recovery Log Protection: An Overview” on page 460
“Snapshot Database Protection” on page 462
Protecting Data:
“Mirroring the Database and Recovery Log” on page 462
“Backing Up Storage Pools” on page 465
“Using Copy Storage Pools to Improve Data Availability” on page 468
“Backing Up the Database” on page 468
Recovering Data:
“Recovering Your Server Using Database and Storage Pool Backups” on page 477
“Restoring Your Server Using Mirrored Volumes” on page 485
“Restoring Storage Pool Volumes” on page 485
“Auditing a Storage Pool Volume” on page 487
“Correcting Damaged Files” on page 490
Scenarios:
“Backup and Recovery Scenarios” on page 492

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.



Tivoli Disaster Recovery Manager (“Using Tivoli Disaster Recovery Manager” on page 497) automates some tasks associated with preparing for or recovering from a disaster. This icon identifies those tasks.

Levels of Protection

To get the best protection for your TSM data, you should use all of the following:

- Backups of your storage pools
- Mirrored copies of your database and recovery log, with the recovery log mode set to roll-forward
- Full and incremental backups of your database

As an adjunct to full and incremental database backups, you can also use snapshot database backups.

Attention: ADSM Version 1 provided database salvage commands in case of a catastrophic error. Although these commands are still available, you should use the current database backup and recovery functions for the best server protection. Do not use the database salvage commands without help from an IBM service representative.

Storage Pool Protection: An Overview

If one or more storage pool volumes is lost or damaged, the client data may be permanently lost. However, you can back up storage pools to sequential access copy storage pools and move the volumes offsite. If data is lost or damaged, you can restore individual volumes or entire storage pools from the copy storage pools. TSM tries to access the file from a copy storage pool if the primary copy of the file cannot be obtained for one of the following reasons:

- The primary file copy has been previously marked damaged (for information about damaged files, see “Correcting Damaged Files” on page 490).
- The primary file is stored on a volume that UNAVAILABLE or DESTROYED.
- The primary file is stored on an offline volume.
- The primary file is located in a storage pool that is UNAVAILABLE, and the operation is for restore, retrieve, or recall of files to a user, or export of file data.

For details, see “Restoring Storage Pools” on page 483, “Using Copy Storage Pools to Improve Data Availability” on page 468, “Recovering a Lost or Damaged Storage Pool Volume” on page 495, and “Maintaining the Integrity of Files” on page 491.

How Restore Processing Works

Two TSM commands let you restore files from copy storage pools:

RESTORE STGPOOL

Restores all storage pool files that have been identified as having read errors. These files are known as *damaged* files. This command also restores all files on any volumes that have been designated as *destroyed* by using the UPDATE VOLUME command. See “Restoring Storage Pools” on page 483 for details.

RESTORE VOLUME

Recreates files that reside on a volume or volumes in the same primary storage pool. You can use this command to recreate files for one or more volumes that have been lost or damaged. See “Restoring Storage Pool Volumes” on page 485 for details.

Because TSM uses database information to determine which files should be restored for a volume or storage pool; restore processing does not require that the original volumes be accessed. For example, if a primary storage pool volume is damaged, you could use the RESTORE VOLUME command to recreate files that were stored on that volume, even if the volume itself is not readable. However, if you delete the damaged files (DISCARDATA=YES on the DELETE VOLUME command), TSM removes from the database references to the files on the primary storage pool volume and to copies of the files on copy storage pool volumes. You could not restore those files.

Restore processing copies files from a copy storage pool onto new primary storage pool volumes. TSM then deletes database references to files on the original primary storage pool volumes. If a primary storage pool volume becomes empty because all files that were stored on that volume have been restored to other volumes, TSM automatically deletes the empty volume from the database.

How the Destroyed Volume Access Mode Works

To help restore processing of entire volumes, TSM has a *destroyed* volume access mode. This mode designates primary volumes for which files are to be restored. If a volume is designated as destroyed, TSM does not mount that volume for either read or write access. You can designate a volume as destroyed with either of two commands:

- **RESTORE VOLUME** — This command automatically changes the access mode of specified volumes to the destroyed volume access mode using a volume list provided as part of the command.
- **UPDATE VOLUME** — Before using this command to restore volumes in a storage pool, you must update the access mode of the volumes to destroyed.

The destroyed designation for volumes is important during restore processing, particularly when the RESTORE STGPOOL command is used to restore a large number of primary storage pool volumes after a major disaster:

- You can designate as destroyed only those volumes that need to be restored. If some volumes are known to be usable after a disaster, the access state of the usable volumes should not be set to destroyed, and therefore they will not be restored as they are usable as they are.
- After you have identified the primary volumes to be restored and changed their access mode to destroyed, you can add new volumes to the storage pool. The new volumes are used to contain the files as they are restored from the copy storage pool volumes. The new volumes can also be used for new files that end users back up, archive, or migrate.
- The designation of destroyed volumes lets TSM track the files that must still be restored from copy storage pools. If restore processing is ended before completion for any reason, you can restart the restore. Only the files that still reside on destroyed volumes would need to be restored.

Database and Recovery Log Protection: An Overview

The database contains information about the client data in your storage pools. The recovery log contains records of changes to the database. If you lose the recovery log, you lose the changes that have been made since the last database backup. If you lose the database, you lose all your client data.

You have several ways to protect this information:

- Mirror the database, or the recovery log, or both
- Back up the database to tape or remote virtual volumes (see “Using Virtual Volumes to Store Data on Another Server” on page 348)
- Back up the database to tape or remote virtual volumes (see “Using Virtual Volumes to Store Data on Another Server” on page 348), and in the recovery log save all the changes made to the database since that backup (this is called *roll-forward* mode)

Mirroring

You can prevent the loss of the database or recovery log due to a hardware failure on a single drive, by mirroring drives. Mirroring simultaneously writes the same data to multiple disks. However, mirroring does not protect against a disaster or a hardware failure that affects multiple drives or causes the loss of the entire system. While TSM is running, you can dynamically start or stop mirroring and change the capacity of the database.

Mirroring provides the following benefits:

- Protection against database and recovery log media failures
- Uninterrupted TSM operations if a database or recovery log volume fails
- Avoidance of costly database recoveries

However, there are also costs:

- Mirroring doubles the required DASD for those volumes that are mirrored
- Mirroring results in decreased performance

Database and Recovery Log Protection

TSM can perform full and incremental backups of the database to tape while the server is running and available to clients. With TSM in *normal* mode, the backup media can then be stored onsite or offsite and can be used to recover the database up to the point of the backup. You can run full or incremental backups as often as needed to ensure that the database can be restored to an acceptable point-in-time.

You can provide even more complete protection if you specify that TSM run in *roll-forward* mode. With TSM in *roll-forward* mode and with an intact recovery log, you can recover the database up to its most current state (the point at which the database was lost).

For the fastest recovery time and greatest availability of the database, mirror both the database and recovery log, and periodically back up the database. When operating in *roll-forward* mode, mirroring better ensures that you have an intact recovery log, which is necessary to restore the database to its most current state.

Normal Mode versus Roll-Forward Mode

Roll-forward mode offers the greatest protection for your data. However, there are costs to roll-forward mode. The following tables describe the protection afforded by each mode and the requirements for each mode.

Quality of Protection	
Normal Mode	Roll-forward Mode
Recover to a point-in-time of the latest full or incremental backup only.	Recover to a point-in-time of the latest full or incremental backup or, with an intact recovery log, to the most current state.
Recover the loss of client data up to the time when that data has been: <ul style="list-style-type: none"> ■ Backed up since the last database backup. ■ Moved due to storage pool migration, reclamation, or move data operations since the last database backup and then overwritten. 	With an intact recovery log, recover to the most current state with no loss of client data.
You must restore the entire database even if only one volume is damaged.	You can restore a single volume.
	Preferable if the server supports HSM clients (space-managed files should be protected as fully as possible from hardware failure).

Storage Requirements	
Normal Mode	Roll-forward Mode
Does not require a recovery log to restore to a point-in-time. The recovery log keeps only uncommitted transactions, and its size is not affected by normal mode.	Requires an intact recovery log to restore to the most current state. The recovery log keeps all transactions since the last database backup. In this mode you should significantly increase the recovery log size. However: <ul style="list-style-type: none"> ■ Frequent database backups reduce recovery log storage requirements (after a backup is completed, recovery log records preceding the backup are deleted). ■ Mirroring the recovery log requires much less space than mirroring the database.
For the greatest availability, you should mirror the database and recovery log or place them on devices that guarantee availability.	You should mirror the recovery log to recover to the most current state. Note: Unlike mirroring the database, roll-forward recovery does not provide continuous operations after a media failure. This is because the database must be brought down to perform the recovery.

The following table compares four typical TSM data recovery configurations, two for roll-forward mode and two for normal mode. In all four cases, the storage pools and the database are backed up. The benefits and costs are:

Mirroring

Whether the database and recovery log are mirrored. Mirroring costs additional disk space.

Coverage

How completely you can recover your data. Roll-forward recovery cannot be done if the recovery log is not intact. However, roll-forward mode does support point-in-time recovery.

Speed to Recover

How quickly data can be recovered.

Mode	Mirroring	Quality of Protection	Speed to Recover
Roll-Forward	Log and database	Greatest	Fastest
	Log Only	Medium	Moderate
Normal	Log and database	Medium	Moderate
	None	Least	Slowest

Attention: If the log mode is set to roll-forward after a point-in-time database restoration, a database backup starts when the server is brought up for the first time. This can cause loss of data: a tape can have current data on it, but because of the point-in-time restoration, it can be marked as scratch. When the server starts for the first time, TSM may use this tape to write the database backup, thus destroying the original data on this tape.

This situation could occur if roll-forward mode is enabled, but the administrator restored the database as if the server was operating in normal mode, not roll-forward mode. For example: the database is to be backed up at midnight everyday Monday through Friday. On Friday, the database was restored to a point-in-time of midnight Wednesday. Thursday's database backup was not used; this tape exists and does contain valid data. But because the database was restored to Wednesday at midnight, the Thursday's tape was marked as scratch. This tape was then inadvertently chosen and written with the database backup information. Therefore, the data for Thursday was lost.

Snapshot Database Protection

A snapshot database backup is a full database backup that does not interrupt the current full and incremental backup series. Snapshot database tapes can then be taken off-site for recovery purposes and therefore kept separate from the normal full and incremental backup tapes. For information about doing a snapshot of the database, see "Doing Snapshot Database Backups" on page 477.

Mirroring the Database and Recovery Log

Mirroring can be crucial in the recovery process. Consider the following scenario: Because of a sudden power outage, a partial page write occurs. The recovery log is corrupted and not completely readable. Without mirroring, recovery operations cannot complete when the server is restarted. However, if the recovery log is mirrored and a partial write is detected, a mirror volume can be used to construct valid images of the missing data.

This section explains how to:

- Allocate disk volumes to mirror the database and recovery log
- Define database or recovery log mirrored volume copies
- Specify mirroring and database page shadowing server options

- Request information about mirrored volumes

Task	Required Privilege Class
Define database and recovery log volumes	System or unrestricted storage
Query mirrored volumes	Any administrator

Separating Disk Volume Copies On Separate Physical Disks When Mirroring the Database and Recovery Log

By separating volume copies on different physical devices, you protect the server from media failure and increase the availability of the database and recovery log. If you cannot assign each volume copy to its own physical disk, allocate them as shown in Table 28.

Table 28. Separating Volume Copies

Physical Disk	Database Volume	Recovery Log Volume
Physical Disk 1	Database volume copy 1	Recovery log volume copy 3
Physical Disk 2	Recovery log volume copy 1	Database volume copy 2
Physical Disk 3	Database volume copy 3	Recovery log volume copy 2

TSM mirrored volumes must have at least the same capacity as the original volumes.

Defining Database or Recovery Log Mirrored Volume Copies

To mirror the database or recovery log, define a volume copy for each volume in the database or recovery log.

For example, the database consists of five volumes named VOL1, VOL2, VOL3, VOL4, and VOL5. To mirror the database, you must have five volumes that match the original volumes in size. Figure 79 shows a mirrored database in which VOL1–VOL5 are mirrored by VOLA–VOLE.




Figure 79. Mirrored Volumes

Use the DSMFMT command to format the space. For example, to format VOLA, a 25MB database volume, enter:

```
./dsmfmt -m -db vola 25
```

Then define the group of mirrored volumes. For example, you might enter the following commands:

```
define dbcopy vol1 vola
define dbcopy vol2 volb
```

```
define dbcopy vol3 volc
define dbcopy vol4 vold
define dbcopy vol5 vole
```

After a volume copy is defined, TSM synchronizes the volume copy with the original volume. This process can range from minutes to hours, depending on the size of the volumes and performance of your system. After synchronization is complete, the volume copies are mirror images of each other.

Specifying Mirroring and Database Page Shadowing Server Options

TSM provides four server options for database and recovery log mirroring so you can specify your preferred level of protection, recoverability and performance.

1. **MIRRORREAD** specifies how mirrored volumes are accessed when the server reads the recovery log or a database page during normal processing. You may specify **MIRRORREAD LOG** for reading recovery log pages, or **MIRRORREAD DB** for reading database pages. **MIRRORREAD LOG (or DB) NORMAL** specifies that only one mirrored volume is read to obtain the desired page. **MIRRORREAD LOG (or DB) VERIFY** specifies that all mirrored volumes for a page be read, compared, and re-synchronized if necessary. **MIRRORREAD LOG (or DB) VERIFY** can decrease server performance as each mirrored volume for the page is accessed on every read.
2. **MIRRORWRITE** specifies how mirrored volumes are written to. You may issue **MIRRORWRITE LOG** or **DB**, and then specify that write operations for the database and the recovery log be specified as **SEQUENTIAL** or **PARALLEL**:
 - A **PARALLEL** specification offers better performance but at the potential cost of recoverability. Pages are written to all copies at about the same time. If a system outage results in a partial page write and the outage affects both mirrored copies, then both copies could be corrupted.
 - A **SEQUENTIAL** specification offers improved recoverability but at the cost of performance. Pages are written to one copy at a time. If a system outage results in a partial page write, only one copy is affected. However, because a successful I/O must be completed after the write to the first copy but before the write to the second copy, performance can be affected.
3. **DBPAGESHADOW=YES** mirrors the latest batch of pages written to a database so that the server can recover those pages that have been partially written to should an outage occur that affects both mirrored volumes.
4. **DBPAGESHADOWFILE** specifies the name of the database page shadowing file. **DBPAGESHADOW** and **DBPAGESHADOWFILE** coordinate with the **MIRRORWRITE** server option and its specifications of **DB** and **SEQUENTIAL** or **PARALLEL** like this:
 - If database and recovery log mirroring is on with **MIRRORWRITE DB PARALLEL** and **DBPAGESHADOW=YES**, then page shadowing will be done.
 - If database and recovery log mirroring is on with **MIRRORWRITE DB SEQUENTIAL**, and **DBPAGESHADOW=YES**, then page shadowing will not be done.
 - If database and recovery log mirroring is on with **MIRRORWRITE DB SEQUENTIAL** and **DBPAGESHADOW=NO**, then page shadowing will not be done.

- If no name is specified in the DBPAGESHADOWFILE option, a dbpgshdw.bdt file will be created and used. If the DBPAGESHADOWFILE option specifies a file name, that file name will be used.

Requesting Information about Mirrored Volumes

You can request information about mirrored database or recovery log volumes by using the QUERY DBVOLUME and QUERY LOGVOLUME commands. For example:

```
query dbvolume
```

The following type of information is displayed:

Volume Name (Copy 1)	Copy Status	Volume Name (Copy 2)	Copy Status	Volume Name (Copy 3)	Copy Status
-----	-----	-----	-----	-----	-----
VOL1	Sync'd	VOLA	Sync'd		Undef-
VOL2	Sync'd	VOLB	Sync'd		ined
VOL3	Sync'd	VOLC	Sync'd		
VOL4	Sync'd	VOLD	Sync'd		
VOL5	Sync'd	VOLE	Sync'd		

- Each pair of vertical columns displays an image of the database or recovery log. For example, VOLA, VOLB, VOLC, VOLD, and VOLE (Copy 2) represent one image of the database.
- Each horizontal row displays a *group of mirrored volumes*. For example, VOL1, and VOLA represent the two volume copies.

Backing Up Storage Pools

Task	Required Privilege Class
Define, back up, or restore storage pools	System, unrestricted storage, or restricted storage (only for those pools to which you are authorized)
Restore volumes	
Update volumes	System or operator
Query volumes or storage pools	Any administrator

You can create backup copies of client files that are stored in primary storage pools. The backup copies are stored in copy storage pools, which you can use to restore the original files if they are damaged, lost, or unusable. Primary storage pools should be backed up incrementally each day to the same copy storage pool. Backing up to the same copy storage pool ensures that files do not need to be recopied if they have migrated to the next pool.

Attention: You can back up multiple primary storage pools to one copy storage pool. If multiple copies are necessary, you can also back up a primary storage pool to multiple copy storage pools. However, you should back up the entire primary storage pool hierarchy to the same copy storage pool for easier management of storage volumes.

Note: When a file exists in the Copy Storage Pool that used to exist in the primary storage pool - and this file during an incremental backup no longer exists in the primary storage pool; the file is deleted from the copy storage pool.




Figure 80. Copy Storage Pools

If you schedule storage pool backups and migrations and have enough disk storage, you can copy most files from the disk storage pool before they are migrated to tape and thus avoid unnecessary mounts. Here is the sequence:

1. Clients back up or archive data to disk
2. You issue the `BACKUP STGPOOL` command to back up the primary storage pools to copy storage pools
3. Data migrates from disk storage pools to primary tape storage pools

Backing up storage pools requires an additional 200 bytes of space in the database for each file copy. As more files are added to the copy storage pools, reevaluate your database size requirements.

Because the copies are made incrementally, you can cancel the backup process. Reissuing the `BACKUP STGPOOL` command lets the backup continue from the spot the backup was canceled. For example, to back up the `ARCHIVEPOOL` primary pool to the `DISASTER-RECOVERY` copy pool, enter:

```
backup stgpool archivepool disaster-recovery
```

You can define schedules to begin incremental backups of files in the primary storage pools. For example, to back up the `BACKUPPOOL`, `ARCHIVEPOOL`, and the `TAPEPOOL` every night, schedule the following commands:

```
backup stgpool backuppool disaster-recovery maxprocess=4
```

```
backup stgpool archivepool disaster-recovery maxprocess=4
```

```
backup stgpool tapepool disaster-recovery maxprocess=4
```

These commands use four parallel processes to perform an incremental backup of each primary storage pool to the copy pool. The only files backed up to the DISASTER-RECOVERY pool are files for which a copy does not already exist in the copy storage pool. See “Automating Server Operations” on page 371 for information about scheduling commands.

Notes:

1. Set the MAXPROCESS parameter in the BACKUP STGPOOL command to the number of mount points or drives that can be dedicated to this operation.
2. Backing up storage pools requires additional space on the TSM database.
3. If a copy is to be made in a copy storage pool and a copy already exists with the same insertion date, no action is taken.
4. Files in a copy storage pool do not migrate to another storage pool.
5. When a disk storage pool is backed up, copies of files that remain on disk after being migrated to the next storage pool (these are cached files) are not backed up.

For recovery scenarios that involve backed up copies of storage pools, see “Recovering to a Point-in-Time from a Disaster” on page 493 and “Recovering a Lost or Damaged Storage Pool Volume” on page 495.

Delaying Reuse of Sequential Access Volumes

When you define or update a sequential access storage pool (using the DEFINE STGPOOL or UPDATE STGPOOL commands), you can use the REUSEDELAY parameter. This parameter specifies the number of days that must elapse before a volume can be reused or returned to scratch status, after all files have been expired, deleted, or moved from the volume. When you delay reuse of such volumes and they no longer contain any files, they enter the *pending* state. Volumes remain in the pending state for as long as specified with the REUSEDELAY parameter for the storage pool to which the volume belongs.

Delaying reuse of volumes can be helpful under certain conditions for disaster recovery. When TSM expires, deletes, or moves files from a volume, the files are not actually erased from the volumes: the database references to these files are removed. Thus the file data may still exist on sequential volumes if the volumes are not immediately reused.

If a disaster forces you to restore the TSM database using a database backup that is old or is not the most recent backup, some files may not be recoverable because TSM cannot find them on current volumes. However, the files may exist on volumes that are in pending state. You may be able to use the volumes in pending state to recover data by doing the following:

1. Restore the database to a point-in-time prior to file expiration.
2. Use a primary or copy storage pool volume that has not been rewritten and contains the expired file at the time of database backup.

If you back up your primary storage pools, set the REUSEDELAY parameter for the primary storage pools to 0 to efficiently reuse primary scratch volumes. For your copy storage pools, you should delay reuse of volumes for as long as you keep your oldest database backup.

For an example of using database backup and delaying volume reuse, see “Protecting Your Database and Storage Pool” on page 492. For information about expiration, see “Running Expiration Processing to Delete Expired Files” on page 264.

Using Copy Storage Pools to Improve Data Availability

By using copy storage pools, you maintain multiple copies of files and reduce the potential for data loss due to media failure. If the primary file is not available or becomes corrupted, TSM accesses and uses the duplicate file from a copy storage pool.

Example: Simple Hierarchy with One Copy Storage Pool

Assume that you have two primary storage pools: one random access storage pool (DISKPOOL) and one tape storage pool (TAPEPOOL, with device class TAPECLASS). Files stored in DISKPOOL are migrated to TAPEPOOL. You want to back up the files in both primary storage pools to a copy storage pool.

To schedule daily incremental backups of the primary storage pools, do the following:

1. Define a copy storage pool called COPYPOOL, with the same device class as TAPEPOOL, by issuing the following command:

```
define stgpool copypool tapeclass pooltype=copy maxscratch=50
```

Notes:

- a. Because scratch volumes are allowed in this copy storage pool, you do not need to define volumes for the pool.
 - b. All storage volumes in COPYPOOL are located onsite.
2. Perform the initial backup of the primary storage pools by issuing the following commands:
 3. Define schedules to automatically run the commands for backing up the primary storage pools. The commands to schedule are those that you issued in step 2.

```
backup stgpool diskpool copypool  
backup stgpool tapepool copypool
```

To minimize tape mounts, back up the disk storage pool first, then the tape storage pool. For more information about scheduling, see “Automating Server Operations” on page 371.

Backing Up the Database

Backing up the database is a simple operation. You can backup the database with full and incremental backups or by taking a snapshot of a specific point-in-time of the database; these are called snapshot database backups. (See “Doing Full and Incremental Backups” on page 476 and “Doing Snapshot Database Backups” on page 477 for more information.)

Before your first backup, you must do some or all of the following steps:

- Define device classes for backups
- Set the recovery log mode
- Schedule database backups
- Estimate the recovery log size
- Automate database backups to occur according to a defined schedule or when the recovery log utilizations reaches a specified percentage.

To restore your database, you should have copies of (or be able to completely restore) the following information:

- Volume history file

- Device configuration file
- Server options file
- Database and recovery log set up (the output from detailed queries of your database and recovery log volumes).



DRM helps you save the previously listed information.

Defining Device Classes for Backups

You can use existing device classes for backups or define new ones. You can also specify different device classes for incremental backups and for full backups. For example, you might want to write full backups to tape and incremental backups to disk. Specifying a device class with a device type of `FILE` is useful if an incremental backup is run based on a database backup trigger. You should do this only if you are also backing up the files to tape and taking them off site. Otherwise, in a disaster you can only restore the full backup.

You can also reserve a device class and, therefore, a device for automatic backups only. In this way, TSM does not try to back up the database with no device available. If a database backup shares a device class with a low priority operation, such as reclamation, and all the devices are in use, TSM automatically cancels the lower priority operation. This frees a device for the database backup.

Note: Device class definitions are saved in the device configuration files (see “Saving the Device Configuration File” on page 474).

Setting the Recovery Log Mode

You can set the recovery log mode to either *normal* or *roll-forward*. See “Database and Recovery Log Protection” on page 460 for a description of the two modes and for a comparison their benefits and costs.

If you do not set the recovery log mode, TSM runs in normal mode. To set the log mode to roll-forward, enter:

```
set logmode rollforward
```

Note: The log mode is not in roll-forward mode until you perform the first full database backup after entering this command.

To set the log mode back to normal, enter:

```
set logmode normal
```

Estimating the Size of the Recovery Log

The number of TSM transactions affect how large you should make your recovery log. As you add more clients and increase concurrent transactions, you can extend the size of the log. In roll-forward mode you should also consider how often you perform database backups. In this mode, the recovery log keeps all transactions since the last database backup and typically requires much more space than normal mode does.

To determine the size that the recovery log should be in roll-forward mode, you must know how much recovery log space is used between database backups. For example, if you

perform daily incremental backups, check your daily usage over a period of time. You can use the following procedure to make your estimate:

1. Set the log mode to normal. In this way you are less likely to exceed your log space if your initial setting is too low for roll-forward mode.
2. After a scheduled database backup, reset the statistic on the amount of recovery log space used since the last reset by using the following command:
`reset logconsumption`
3. Just before the next scheduled database backup, display the current recovery log statistics by using the following command:
`query log format=detailed`

Record the *cumulative consumption* value, which shows the space, in megabytes, used since the statistic was last reset.

4. Repeat steps 2 and 3 for at least one week.
5. Increase the highest cumulative consumption value by 30 percent. Set your recovery log size to this increased value to account for periods of unusually high activity.

For example, over a period of a week the highest cumulative consumption value was 500MB. If you set your recovery log to 650MB, you should have enough space between daily backups.

For information on how to adjust the recovery log size, see “Increasing the Size of the Database or Recovery Log” on page 393 or “Decreasing the Size of the Database or Recovery Log” on page 397.

Note: If the recovery log runs out of space, you may not be able to start the server for normal operation. You can create an additional recovery log volume if needed to start the server and perform a database backup. For example, to create a 5MB volume A00, issue the following command:

```
> dsmserv extend log a00 5mb
```

Specify volume sizes in multiples of 4MB plus 1MB for overhead.

Scheduling Database Backups

Database backups require devices, media, and time. Consider scheduling backups to occur at certain times of the day and after activities such as the following:

- Major client backup or archive activities
- Storage pool migration and reclamation
- Storage pool backups
- MOVE DATA or DELETE VOLUME commands

Depending on the frequency of these activities and the amount of client data, you might back up your storage pools daily and then immediately back up the database.

Consider the following when you decide what kind of backups to do and when to do them:

- Full backups take longer than incremental backups
- Full backups have shorter recovery times than incremental backups (you must load only one set of volumes to restore the entire database)

- Full backups are required:
 - For the first backup
 - If there have been 32 incremental backups since the last full backup
 - After changing the log mode to roll-forward
 - After changing the database size (an extend or reduce operation)

Automating Database Backups

In roll-forward mode, you can set a database backup to occur automatically when the recovery log utilization reaches a defined percentage. TSM also automatically deletes any unnecessary recovery log records. You might want to automate database backups if you have scheduled database backups. However, while the newly automated database backups are occurring, the recovery log could grow faster than expected. You should try to coordinate the recovery log size and scheduled backups. A database backup has a higher priority than most operations, and backup based on a trigger could occur during high server activity and affect your other operations. Adjust the recovery log size to avoid triggering backups at non-scheduled times.

By setting a database backup trigger you ensure that the recovery log does not run out of space before the next backup.

If the log mode is changed from normal to roll-forward, the next database backup must be a full backup. If a database backup trigger is defined when you set the log mode to roll-forward, the full backup is done automatically. The server does not start saving log records for roll-forward recovery until this full backup completes successfully.

By doing the steps in “Estimating the Size of the Recovery Log” on page 469, you determined the size of your recovery log. Your database backup trigger should be based on that procedure. For example, assume that your recovery log size is 650MB. Assume also that its utilization percentage is usually less than 500MB between database backups. You want to trigger a backup only in unusual circumstances. Therefore, set the trigger to at least 75 percent (approximately 500MB). To set the trigger to 75 percent and run 20 incremental backups to every full backup, enter:

```
define dbbackuptrigger logfullpct=75 devclass=tapeclass
  numincremental=20
```

Each incremental backup, whether automatic or by command, is added to the count of incremental backups. Each full backup, whether automatic or by command, resets the count for incremental backups to 0. If you specify a NUMINCREMENTAL value of 0, TSM automatically runs only full backups.

Note: If you issue a BACKUP DB command with the TYPE=INCREMENTAL parameter, TSM performs an incremental backup of the database regardless of the NUMINCREMENTAL setting. For example, you set NUMINCREMENTAL to 5, and there have been five incremental backups since the last full backup. If you then issue BACKUP DB TYPE=INCREMENTAL, an incremental backup is still done, and the incremental backup counter is set to 6. This occurs if the BACKUP DB command is issued either by an administrator or through an administrative schedule.

After you set the database backup trigger, you might find that automatic backups occur too often. Check the backup trigger percentage by entering:

```
query dbbackuptrigger
```

TSM displays the following information:

```
Full Device Class: TAPECLASS
Incremental Device Class: TAPECLASS
Log Full Percentage: 75
Incrementals Between Fulls: 6
Last Update by (administrator): SERVER_CONSOLE
Last Update Date/Time: 03/06/1996 10:49:23
```

This information shows that the trigger is set to 75 percent. If automatic backups are occurring too often, you could increase the value to 80 percent by entering:

```
update dbbackuptrigger logfullpct=80
```

If the database backup trigger automatically runs backups more often than you want and the setting is high (for example, 90 percent or higher), you should probably increase the recovery log size. If you no longer want to use the database backup trigger, enter:

```
delete dbbackuptrigger
```

After you delete the database backup trigger, TSM no longer runs automatic database backups.

Note: If you delete the trigger and stay in roll-forward mode, transactions fail when the log fills. Therefore, you should change the log mode to normal. Remember, however, that normal mode does not let you perform roll-forward recovery. Increase the recovery log size if you want roll-forward recovery.

Saving the Volume History File

TSM stores the following volume information in the database:

- Sequential access storage pool volumes that have been added, reused (through reclamation or move data operations), or deleted (during delete volume or reclamation operations)
- Full and incremental database backup volume information
- Export volumes for administrator, node, policy, and server data
- Snapshot database volume information
- Backup set volume information.

TSM updates the volume history file as volumes are added. However, you must periodically run a delete operation to discard outdated information about volumes (see “Deleting Volume History Information” on page 473 for details).

This information is stored in the database, but during a database restore, it is not available from there. To perform a restore, therefore, TSM must get the information from the volume history file.

To ensure the availability of volume history information, do any of the following:

- Store at least one copy of the volume history file offsite or on a disk separate from the database
- Store a printout of the file offsite

- Store a copy of the file offsite with your database backups and device configuration file
- Store a remote copy of the file, for example, on an NFS-mounted file system.



DRM saves a copy of the volume history file in its disaster recovery plan file.

Note: You can recover the database without a volume history file. However, because you must examine every volume that may contain database backup information, this is a time-consuming and error-prone task.

The `VOLUMEHISTORY` server option lets you specify backup volume history files. Then, whenever TSM updates volume information in the database, it also updates the same information in the backup files.

You can also back up the volume history information at any time, by entering:

```
backup volhistory
```

If you do not specify file names, TSM backs up the volume history information to all files specified with the `VOLUMEHISTORY` server option.

Deleting Volume History Information

You should periodically delete outdated information from the volume history file. For example, if you keep backups for seven days, information older than that is not needed. When information about database backup volumes or export volumes is deleted, the volumes return to scratch status. For scratch volumes of device type `FILE`, the files are deleted. When information about storage pools volumes is deleted, the volumes themselves are not affected.

To display volume history information up to yesterday, enter:

```
query volhistory enddate=today-1
```

To delete information that is seven days old or older, enter:

```
delete volhistory type=all todate=today-8
```

Notes:

1. Existing volume history files are *not* automatically updated with the `DELETE VOLHISTORY` command.
2. Do not delete sequential volume history information until you no longer need that information. For example, do not delete dump volume information or storage volume reuse information, unless you have backed up or dumped the database at a later time than that specified for the delete operation.
3. Do not delete the volume history information for database dump, database backup, or export volumes that reside in automated libraries, unless you want to return the volumes to scratch status. When the `DELETE VOLHISTORY` command removes volume information for database dump, database backup, or export volumes, the volumes are automatically returned to scratch status if they reside in automated libraries. These volumes are then available for reuse by the server and the information stored on them

may be overwritten when the server reuses the volume for some other purpose, such as storage pool volumes or other database backups.



DRM expires database backup series and deletes the volume history entries.

Saving the Device Configuration File

The device configuration file contains information needed to read backup data. This information includes the following:

- Devices class definitions
- Library definitions
- Drive definitions
- Server definitions

Whenever TSM updates device configuration information in the database, it updates the device configuration file.

This information is stored in the database, but during a database restore, it is not available from there. To perform a restore, therefore, TSM must get the information from the device configuration file.

To ensure the availability of the device configuration information, you can do any of the following:

- Store at least one backup copy of the device configuration file on a disk separate from the database
- Store your device configuration file offsite with your volume history file and database backups
- Store a printout of the information stored offsite
- Store a remote copy, for example, on an NFS-mounted file system



DRM saves a copy of the device configuration file in its disaster recovery plan file.

The DEVCONFIG server option lets you specify backup device configuration files (for details, see the *Administrator's Reference*). After the server is restarted, whenever TSM updates device configuration information in the database, it also updates the same information in the backup files.

During a database restore operation, TSM tries to open the first device configuration file. If it cannot open or read that file, TSM tries to use any remaining device configuration files (in the order in which they occur in the server options) until it finds one that is usable. If none

can be found, you must recreate the file. See “Recreating a Device Configuration File” for details. After the database has been restored, you may have to update the device configuration.

You can also back up the device configuration information at any time, by entering:

```
backup devconfig
```

If you do not specify file names, TSM backs up the device configuration file to *all* files specified with the DEVCONFIG server option.

If you lose your device configuration file and need it to restore the database, you must recreate it manually. See “Recreating a Device Configuration File” for details.

If you are using automated tape libraries, TSM also saves volume location information in the device configuration file. The file is updated whenever CHECKIN LIBVOLUME, CHECKOUT LIBVOLUME, and AUDIT LIBRARY commands are issued, and the information is saved as comments (*/* */*). This information is used during restore or load operations to locate a volume in an automated library. If you must recreate the device configuration file, you will be unable to recreate the volume location information. Therefore, you must define your library as a manual library and manually mount the volumes during server processing. If an automated tape library is used at the recovery site, volume location information in comments (*/*...*/*) in the device configuration file must be modified. First, manually place the physical database backup volumes in the automated library and note the element numbers where you place them. Then manually edit the device configuration file to identify the locations of the database backup volumes so that TSM can find them to restore the database.

For virtual volumes, the device configuration file stores the password (in encrypted form) for connecting to the remote server. If you regressed the server to an earlier point-in-time, this password may not match what the remote server expects. In this case, manually set the password in the device configuration file. Then ensure that the password on the remote server matches the password in the device configuration file.

Note: Set the password in clear text. After the server is operational again, you can issue a BACKUP DEVCONFIG command to store the password in encrypted form.

Updating the Device Configuration File

Whenever you define, update, or delete device configuration information in the database, TSM automatically updates the device configuration file. This information includes definitions for device classes, libraries, drives, and servers.

If a disaster occurs, you may have to restore TSM by using devices other than those that are included in the device configuration file. In such a case, you will have to update the device configuration files manually with information about the new devices.

Recreating a Device Configuration File

The following commands read and execute the device configuration file:

- DSMSERV RESTORE DB
- DSMSERV LOADDB
- DSMSERV DISPLAY DBBACKUPVOLUME

Note: The DSMSERV LOADDB utility may increase the size of the database. The server packs data in pages in the order in which they are inserted. The DSMSERV DUMPDB utility does not preserve that order. Therefore, page packing is not optimized, and the database may require additional space.

If no device configuration file is found, you must recreate it before you can start the restore operation. The device configuration file must follow these conventions:

- The commands must be in this order:
 - DEFINE SERVER (if you are using virtual volumes)
 - DEFINE DEVCLASS
 - DEFINE LIBRARY
 - DEFINE DRIVE

You must provide those definitions needed to mount the volumes read by the TSM command that you issued. If you are restoring or loading from a FILE device class, you will need only the DEFINE DEVCLASS command.

- For virtual volumes, the device configuration file stores the password (in encrypted form) for connecting to the remote server. If you regressed the server to an earlier point-in-time, this password may not match what the remote server expects. In this case, manually set the password in the device configuration file. Then ensure that the password on the remote server matches the password in the device configuration file.
- You can use command defaults.
- The file can include blank lines.
- A single line can be up to 240 characters.
- The file can include continuation characters and comments as described in the *Administrator's Reference*.

The following figure shows an example of a device configuration file:

```
/* Tivoli Storage Manager Device Configuration */
define devclass tapeclass devtype=8mm library=manuallib
define library manuallib libtype=manual
define drive manuallib drive02 device=/dev/mt2
```

Saving the Server Options

Your server options are particular to your installation. You should make a copy of your server options and save them.

Saving the Database and Recovery Log Setup Information

The database and recovery log setup information is actually the output from detailed queries of your database and recovery log volumes. You should make copies of this output and save them.

Doing Full and Incremental Backups

The first backup of your database must be a full backup. You can run up to 32 incremental backups between full backups.

To perform a full backup of your database to the TAPECLASS device class, enter:

```
backup db type=full devclass=tapeclass
```

In this example, TSM writes the backup data to scratch volumes. You can also specify volumes by name. After a full backup, you can perform incremental backups, which copy only the changes to the database since the previous backup.

To do an incremental backup of the database to the TAPECLASS device class, enter:

```
backup db type=incremental devclass=tapeclass
```

Doing Snapshot Database Backups

A snapshot database backup is a full database backup that does not interrupt the current full and incremental backup series. Snapshot database tapes can then be taken off-site for recovery purposes and therefore kept separate from the normal full and incremental backup tapes. Snapshot database backups enhance the protection of your server and its data while maintaining the full and incremental database backup series. Although snapshot database backups cannot restore a database or a database volume to its most current state, you can use them to restore a database to a specific point-in-time.

Snapshot database backups:

- Copy the complete contents of a database, just like a full database backup.
- Create a new database backup series without interrupting the existing full and incremental backup series for the database.
- Do not truncate the server recovery log when the server is running in roll-forward mode.

Use the BACKUP DB command to perform a snapshot database backup. New volume history entries are created for the snapshot database volumes.

To perform a snapshot database backup to the TAPECLASS device class, enter:

```
backup db type=dbsnapshot devclass=tapeclass
```

Note: Snapshot database backups should be used as an adjunct to full and incremental backups. When the server is in roll-forward mode, and a snapshot database backup is performed, the recovery log keeps growing. When full and incremental backups are performed with roll-forward mode enabled, the recovery log is restarted each time a full backup is performed.

Recovering Your Server Using Database and Storage Pool Backups

This section explains how to recover by using backups of the database and storage pools. Figure 81 on page 478 shows the situation presented in the two scenarios in this section: an installation has lost its server, including the database and recovery log, and its onsite storage pools.




Figure 81. Recovery from a Disaster

The following topics are included:

- Restoring to a point-in-time
- Restoring to the most current state

To perform a restore, you should have the following information, preferably stored offsite (see Figure 81):

- A full database backup
- Any incremental database backups between the last full backup and the point-in-time to which you are recovering
- Copy storage pool volumes
- On tape or diskette, or as printouts:
 - Server options file
 - Volume history file
 - Device configuration file
 - Database and recovery log setup (the output from detailed queries of your database and recovery log volumes)



DRM can query the TSM server and generate a current, detailed disaster recovery plan for your installation.

Restoring a Database to a Point-in-Time

Point-in-time recovery is normally used for situations such as disaster recovery or to remove the effects of errors that can cause inconsistencies in the database.

You can use either full and incremental backups or snapshot database backups to restore a database to a point-in-time.

For a scenario of recovering to a point-in-time, see “Backup and Recovery Scenarios” on page 492.

Here is the procedure for restoring the database:

1. Rename and save a copy of the volume history file if it exists. After the database is restored, any volume history information pointed to by the server options is lost. You will need this information to identify the volumes to be audited. If you do not have a volume history file, see “Point-in-Time Restore Without a Volume History File” on page 481.
2. If the device configuration file is unavailable, recreate it manually (see “Recreating a Device Configuration File” on page 475). Put the existing or recreated device configuration file in the server work library. Do the same with the server options file. Have available your outputs from your detailed queries about your database and recovery log setup information.

You may need to modify the device configuration file based on the hardware available at the recovery site. For example, the recovery site might require a different device class, library, and drive definitions. For more information, see “Updating the Device Configuration File” on page 475.

3. If the original database or recovery log volumes were lost, issue the DSMSEV FORMAT utility to initialize the database and recovery log. For example:

```
dsmserv format 1 log1 9 1 dbvol1 5
```

Attention: Do not start the server until *after* you restore the database (the next step). Starting the server before the restore would destroy any existing volume history files.

4. Issue the DSMSEV RESTORE DB utility. For example, to restore the database to a backup series that was created on April 19, 1999, enter:

```
dsmserv restore db todate=04/19/1999
```

TSM does the following:

- a. Reads the volume history file to locate the last full backup that occurred on or before the specified date and time.

Note: If the volume history file is not available, you must mount tape volumes in the correct order or specify their order on the DSMSEV RESTORE DB utility.

- b. Using the device configuration file, requests a mount of the first volume, which should contain the beginning of the full backup.
- c. Restores the backup data from the first volume.
- d. Continues to request mounts and to restore data from the backup volumes that contain the full backup and any incremental backups that occurred on or before the date specified.

From the old volume history information (generated by the QUERY VOLHISTORY command) you need a list of all the volumes that were reused (STGREUSE), added (STGNEW), and deleted (STGDELETE) since the original backup. Use this list to perform the rest of this procedure.

It may also be necessary to update the device configurations in the restored database.

5. Audit all disk volumes, all reused volumes, and any deleted volumes located by the AUDIT VOLUME command using the FIX=YES parameter.

This process identifies files recorded in the database that can no longer be found on the volume. If a copy of the file is in a copy storage pool, the file on the audited volume is marked as damaged. Otherwise, the file is deleted from the database and is lost.

6. If the audit detects any damaged files, issue the RESTORE STGPOOL command to restore those files after you have audited the volumes in the storage pool. Include the FIX=YES parameter on the AUDIT VOLUME command to delete database entries for files not found in the copy storage pool.
7. Mark as destroyed any volumes that cannot be located, and recover those volumes from copy storage pool backups. If no backups are available, delete the volumes from the database by using the DELETE VOLUME command with the DISCARDDATA=YES parameter.
8. Redefine any storage pool volumes that were added since the database backup.

Notes:

1. Some files may be lost if they were moved since the backup (due to migration, reclamation, or move data requests) and the space occupied by those files has been reused. You can minimize this loss by using the REUSEDELAY parameter when defining or updating sequential access storage pools. This parameter delays volumes from being returned to scratch or being reused. See “Delaying Reuse of Sequential Access Volumes” on page 467 for more information on the REUSEDELAY parameter.
2. By backing up your storage pool and your database, you reduce the risk of losing data. To further minimize loss of data, you can:

- Mark the backup volumes in the copy storage pool as OFFSITE and move them to an offsite location.

In this way the backup volumes are preserved and are not reused or mounted until they are brought onsite. Ensure that you mark the volumes as OFFSITE before you back up the database.

To avoid having to mark volumes as offsite or physically move volumes:

- Specify a device class of DEVTYPE=SERVER in your database backup.
 - Back up a primary storage pool to a copy storage pool associated with a device class of DEVTYPE=SERVER.
- Back up the database immediately after you back up the storage pools.
 - Turn off migration and reclamation while you back up the database.
 - Do not perform any MOVE DATA operations while you back up the database.
 - Use the REUSEDELAY parameter’s interval to prevent your copy storage pool volumes from being reused or deleted before they might be needed.

3. If your old volume history file shows that any of the copy storage pool volumes needed to restore your storage pools have been reused (STGREUSE) or deleted (STGDELETE), you may not be able to restore all your files. You can avoid this problem by including the REUSEDELAY parameter when you define your copy storage pools.
4. After a restore, the volume inventories for TSM and for your tape management system may be inconsistent. For example, after a database backup, a new volume is added to TSM. The tape management system inventory records the volume as belonging to TSM. If the database is restored from the backup, TSM has no record of the added volume, but the tape management system does. You must synchronize these inventories. Similarly, the volume inventories for TSM and for any automated libraries may also be inconsistent. If they are, issue the AUDIT LIBRARY command to synchronize these inventories.

Point-in-Time Restore Without a Volume History File

You can use either full and incremental backups or snapshot database backups to restore a database to a point-in-time.

If you are doing a point-in-time restore and a volume history file is not available, you must enter the volume names in the DSMSEV RESTORE DB utility in the sequence in which they were written to. First, however, issue the DSMSEV DISPLAY DBBACKUPVOLUME utility to read your backup volumes and display the information needed to arrange them in order (backup series, backup operation, and volume sequence). For example:

```
dsmserv display dbbackupvolume devclass=tapeclass
volumenames=dsm012,dsm023,dsm037,dsm038,dsm058,dsm087
```

For example, the most recent backup series consists of three operations:

- 0** A full backup on three volumes in the sequence dsm023, dsm037, and dsm087
- 1** An incremental backup on one volume, dsm012
- 2** An incremental backup on two volumes in the sequence dsm038 and dsm058

You would issue three commands in the following order:

```
dsmserv restore db volumenames=dsm023,dsm037,dsm087
devclass=tapeclass commit=no
dsmserv restore db volumenames=dsm012
devclass=tapeclass commit=no
dsmserv restore db volumenames=dsm038,dsm058
devclass=tapeclass commit=no
```

Attention: If the original database or recovery log volumes are available, you issue only the DSMSEV RESTORE DB utility. However, if those volumes have been lost, you must first issue the DSMSEV FORMAT command to initialize the database and recovery log, then issue the DSMSEV RESTORE DB utility.

An Example of the Importance of Storage Pool Backups in a Point-of-Time Restore

The following example shows the importance of storage pool backups with a point-in-time restore. In this example, the storage pool was not backed up with the BACKUP STGPOOL command.

9:30 a.m.

Client A backs up its data to Volume 1.

Noon The system administrator backs up the database.

1:30 p.m.

Client A's files on Volume 1 (disk), is migrated to tape (Volume 2).

3:00 p.m.

Client B backs up its data to Volume 1.

The server places Client B's files in the location that contained Client A's files prior to the migration.

3:30 p.m.

The server goes down.

3:40 p.m.

The system administrator reloads the noon version of the database by using the DSMSEV RESTORE DB utility.

4:40 p.m.

Volume 1 is audited. The following then occurs:

1. The server compares the information on Volume 1 and with the restored database (which matches the database at noon).
2. The audit does not find Client A's files on Volume 1 where the reloaded database indicates they should be. Therefore, the server deletes these Client A file references.
3. The database has no record that Client A's files are on Volume 2, and the files are, in effect, lost.
4. The database has no record that Client B's files are on Volume 1, and the files are, in effect, lost.

If roll-forward recovery had been used, the database would have been rolled forward to 3:30 p.m. when the server went down, and neither Client A's files nor Client B's files would have been lost. If a point-in-time restore of the database had been performed and the storage pool had been backed up, Client A's files would not have been deleted by the volume audit and could have been restored with a RESTORE VOLUME or RESTORE STGPOOL command. Client B's files would still have been lost, however.

Restoring a Database to its Most Current State

You can use roll-forward recovery to restore a database to its most current state if:

- TSM has been in roll-forward mode continuously from the time of the last full backup to the time the database was damaged or lost.
- The last backup series created for the database is available. A backup series consists of a full backup, all applicable incremental backups, and all recovery log records for database changes since the last backup in the series was run.

You can only use full and incremental backups with roll-forward mode enabled to restore a database to its most current state. Snapshot database backups are complete database copies of a point-in-time.

To restore the database to its most current state, enter:

```
dsmserv restore db
```

Attention: If the original database or recovery log volumes are available, you issue only the DSMSEV RESTORE DB utility. However, if those volumes have been lost, you must first issue the DSMSEV FORMAT utility to initialize the database and recovery log, then issue the DSMSEV RESTORE DB utility.

Note: Roll-forward recovery does not apply if all recovery log volumes are lost. However, with the server running in roll-forward mode, you can still perform point-in-time recovery in such a case.

Restoring Storage Pools

You can recreate files in a primary storage pool by using duplicate copies in copy storage pools. The files must have been copied to the copy storage pools by using the BACKUP STGPOOL command.

Task	Required Privilege Class
Restoring storage pools	System, unrestricted storage, or restricted storage

The RESTORE STGPOOL command restores specified primary storage pools that have files with the following problems:

- The primary copy of the file has been identified as having read errors during a previous operation. Files with read errors are marked as damaged.
- The primary copy of the file resides on a volume that has an access mode of DESTROYED. For how the access mode of a volume changes to the DESTROYED access mode, see “How Restore Processing Works” on page 458.

When you restore a storage pool, be prepared to provide the following information:

Primary storage pool

Specifies the name of the primary storage pool that is being restored.

Copy storage pool

Specifies the name of the copy storage pool from which the files are to be restored. This information is optional. If you do not specify a particular copy storage pool, TSM restores the files from any copy storage pool where it can find them.

New storage pool

Specifies the name of the new primary storage pool to which to restore the files. This information is optional. If you do not specify a new storage pool, TSM restores the files to the original primary storage pool.

Maximum number of processes

Specifies the maximum number of parallel processes that are used for restoring files.

Preview

Specifies whether you want to preview the restore operation without actually restoring data.

See “Correcting Damaged Files” on page 490 and “Backup and Recovery Scenarios” on page 492 for examples of using the RESTORE STGPOOL command.

What Happens When a Storage Pool Is Restored

When you restore a storage pool, TSM determines which files are in the storage pool being restored, according to the TSM database. Using file copies from a copy storage pool, TSM restores the files that were in the storage pool to the same or a different storage pool.

Cached Files: Cached copies of files in a disk storage pool are never restored. References to any cached files that have been identified as having read errors or cached files that reside on a *destroyed* volume will be removed from the database during restore processing.

The RESTORE STGPOOL command with the PREVIEW=YES parameter can be used to identify volumes that contain damaged primary files. During restore processing, a message is issued for every volume in the restored storage pool that contains damaged, noncached files. To identify the specific files that are damaged on these volumes, use the QUERY CONTENT command.

After the files are restored, the old references to these files in the primary storage pool are deleted from the database. This means that TSM now locates these files on the volumes to which they were restored, rather than on the volumes on which they were previously stored. If a destroyed volume becomes empty because all files have been restored to other locations, the destroyed volume is automatically deleted from the database.

The RESTORE STGPOOL command generates a background process that can be canceled with the CANCEL PROCESS command. If a RESTORE STGPOOL background process is canceled, some files may have already been restored prior to the cancellation. To display information about background processes, use the QUERY PROCESS command.

The RESTORE STGPOOL command may be run in the foreground on an administrative client by issuing the command with the WAIT=YES parameter.

Restoring Files to a Storage Pool with Collocation Enabled

When restoring to a primary storage pool that has collocation enabled, the server restores files by client node and client file space. This process preserves the collocation of client files. However, if the copy storage pool being used to restore files does not have collocation enabled, restore processing can be slow.

If you need to use a copy storage pool that is not collocated to restore files to a primary storage pool that is collocated, you can improve performance by:

1. Restoring the files first to a random access storage pool (on disk).
2. Allowing or forcing the files to migrate to the target primary storage pool.

For the random access pool, set the target storage pool as the next storage pool. Adjust the migration threshold to control when migration occurs to the target storage pool.

When a Storage Pool Restoration Is Incomplete

The restoration of a storage pool volume may be incomplete. Use the QUERY CONTENT command to get more information on the remaining files on volumes for which restoration was incomplete. The restoration may be incomplete for one or more of the following reasons:

- Files were either never backed up or the backup copies are marked as damaged.
- A copy storage pool was specified on the RESTORE command, but files were backed up to a different copy storage pool. If you suspect this is a problem, use the RESTORE command again without specifying a copy storage pool from which to restore files. The PREVIEW option can be used on the second RESTORE command, if you do not actually want to restore files.

- Volumes in the copy storage pool needed to perform the restore operation are offsite or unavailable. Check the activity log for messages that occurred during restore processing.
- Backup file copies in copy storage pools were moved or deleted by other TSM processes during restore processing. To prevent this problem, do not issue the following commands for copy storage pool volumes while restore processing is in progress:
 - MOVE DATA
 - DELETE VOLUME (DISCARDATA=YES)
 - AUDIT VOLUME (FIX=YES)
- You can prevent reclamation processing for your copy storage pools by setting the RECLAIM parameter to 100 with the UPDATE STGPOOL command.

Restoring Your Server Using Mirrored Volumes

If a mirrored volume fails due to media failure, you can restore the volume by taking the following steps:

1. View the status of the database and recovery log volumes by using QUERY DBVOLUME or QUERY LOGVOLUME commands.
2. If necessary, place the failing volume offline from TSM by using DELETE DBVOLUME or DELETE LOGVOLUME commands. The server usually does this automatically.
3. Fix the failing physical device.
4. Allocate space to be used for a new volume by using the DSMFMT utility.
5. Bring the volume online by using DEFINE DBCOPY or DEFINE LOGCOPY commands.

After a database or recovery log volume copy is defined, the server synchronizes the volume copy with its associated database or recovery log volume.

Restoring Storage Pool Volumes

You can recreate files in primary storage pool volumes by using copies in a copy storage pool.

Task	Required Privilege Class
Restore volumes in any storage pool for which they have authority	System, unrestricted storage, or restricted storage

Use the RESTORE VOLUME command to restore all files that are currently stored on one or more volumes in the same primary storage pool, and that were previously backed up to copy storage pools by using the BACKUP STGPOOL command.

When using the RESTORE VOLUME command, be prepared to supply some or all of the following information:

Volume name

Specifies the name of the volume in the primary storage pool for which to restore files.

Tip: To restore more than one volume in the same primary storage pool, issue this command once and specify a list of volumes to be restored. When you specify more than one volume, TSM attempts to minimize volume mounts for the copy storage pool.

Copy storage pool name

Specifies the name of the copy pool from which the files are to be restored. This information is optional. If you do not specify a particular copy storage pool, TSM restores the files from any copy storage pool where it can find them.

New storage pool

Specifies the name of the new primary storage pool to which to restore the files. This information is optional. If you do not specify a new storage pool, TSM restores the files to the original primary storage pool.

Maximum number of processes

Specifies the maximum number of parallel processes that are used for restoring files.

Preview

Specifies whether you want to preview the restore operation without actually restoring data.

See “Recovering a Lost or Damaged Storage Pool Volume” on page 495 for an example of using the RESTORE VOLUME command.

What Happens When a Volume Is Restored

When you restore a volume, TSM obtains a copy of each file that was on the volume from a copy storage pool, and then stores the files on a different volume.

Cached Files: Cached copies of files in a disk storage pool are never restored. References to any cached files that reside on a volume that is being restored are removed from the database during restore processing.

After files are restored, the old references to these files in the primary storage pool are deleted from the database. TSM will now locate these files on the volumes to which they were restored, rather than on the volume on which they were previously stored.

The RESTORE VOLUME command changes the access mode of the volumes being restored to *destroyed*. When the restoration is complete (when all files on the volume are restored to other locations), the destroyed volume is empty and is then automatically deleted from the database.

The RESTORE VOLUME command generates a background process that can be canceled with the CANCEL PROCESS command. If a RESTORE VOLUME background process is canceled, some files may have already been restored prior to the cancellation. To display information on background processes, use the QUERY PROCESS command.

The RESTORE VOLUME command may be run in the foreground on an administrative client by issuing the command with the WAIT=YES parameter.

When a Volume Restoration Is Incomplete

The restoration of a volume may be incomplete. Use the QUERY CONTENT command to get more information on the remaining files on volumes for which restoration was incomplete. The restoration may be incomplete for one or more of the following reasons:

- Files were either never backed up or the backup copies are marked as damaged.
- A copy storage pool was specified on the RESTORE command, but files were backed up to a different copy storage pool. If you suspect this is a problem, use the RESTORE command again without specifying a copy storage pool from which to restore files. The PREVIEW option can be used on the second RESTORE command, if you do not actually want to restore files.
- Volumes in the copy storage pool needed to perform the restore operation are offsite or unavailable. Check the activity log for messages that occurred during restore processing.
- Backup file copies in copy storage pools were moved or deleted by other TSM processes during restore processing. To prevent this problem, do not issue the following commands for copy storage pool volumes while restore processing is in progress:
 - MOVE DATA
 - DELETE VOLUME (DISCARDDATA=YES)
 - AUDIT VOLUME (FIX=YES)

You can prevent reclamation processing for your copy storage pools by setting the RECLAIM parameter to 100 with the UPDATE STGPOOL command.

Auditing a Storage Pool Volume

Use this section to help you audit storage pool volumes for data integrity.

Task	Required Privilege Class
Audit volumes in storage pools over which they have authority	Restricted storage privilege
Audit a volume in any storage pool	System privilege, unrestricted storage privilege

The server database contains information about files on storage pool volumes. If there are inconsistencies between the information in the database about files and the files actually stored in a storage pool volume, users may be unable to access their files.

To ensure that all files are accessible on volumes in a storage pool, audit any volumes you suspect may have problems by using the AUDIT VOLUME command. You should audit a volume when:

- The volume is damaged
- The volume has not been accessed for a long period of time, for example, after six months
- A read or write error occurs while accessing the volume
- The database has been restored to an earlier point-in-time, and the volume is either a disk volume or a volume that was identified as being reused or deleted since the database backup took place

What Happens When You Audit Storage Pool Volumes

When you audit a volume, a background process is started. During the auditing process, the server:

- Records results of the audit in the activity log
- Sends informational messages about processing to the server console

-
- Prevents new files from being written to the volume

You can specify whether you want the server to correct the database if inconsistencies are detected. TSM corrects the database by deleting database records that refer to files on the volume that cannot be accessed. The TSM default is to report inconsistencies that are found (files that cannot be accessed), but to not correct the errors.

If TSM detects files with read errors, how TSM handles these files depends on the following:

- The type of storage pool to which the volume is assigned
- The FIX option of the AUDIT VOLUME command
- The location of file copies (whether a copy of the file exists in a copy storage pool)

To display the results of a volume audit after it has completed, use the QUERY ACTLOG command. See “Requesting Information from the Activity Log” on page 416.

Volumes in a Primary Storage Pool

For a volume in a primary storage pool, the values for the FIX parameter on an AUDIT VOLUME command have the following effects:

FIX=NO

TSM reports, but does not delete, any database records that refer to files found with logical inconsistencies. If the AUDIT VOLUME command detects a read error in a file, TSM marks the file as *damaged* in the database. You can do one of the following:

- If a backup copy of the file is stored in a copy storage pool, you can restore the file by using the RESTORE VOLUME or RESTORE STGPOOL command.
- If the file is a cached copy, you can delete references to the file on this volume by using the AUDIT VOLUME command again. Specify FIX=YES.

If the AUDIT VOLUME command does not detect a read error in a file that had previously been marked as damaged, the state of the file is reset so that the file can be used. For example, if a dirty tape head caused some files to be marked damaged, you can clean the head and then audit the volume to make the files accessible again.

FIX=YES

TSM fixes any inconsistencies as they are detected.

If the AUDIT VOLUME command detects a read error in a file:

- If the file is not a cached copy and a backup copy is stored in a copy storage pool, TSM marks the file as damaged in the database. The file can then be restored using the RESTORE VOLUME or RESTORE STGPOOL command.
- If the file is not a cached copy and a backup copy is not stored in a copy storage pool, TSM deletes all database records that refer to the file.
- If the file is a cached copy, TSM deletes the database records that refer to the cached file. The primary file is stored on another volume.

If the AUDIT VOLUME command does not detect a read error in a file that had previously been marked as damaged, TSM resets the state of the file so that it can

be used. For example, if a dirty tape head caused some files to be marked damaged, you can clean the head and then audit the volume to make the files accessible again.

Volumes in a Copy Storage Pool

For volumes in a copy storage pool, the values for the FIX parameter on an AUDIT VOLUME command have the following effects:

FIX=NO

TSM reports the error and marks the file copy as *damaged* in the database.

FIX=YES

TSM deletes references to the file on the audited volume from the database.

Auditing a Volume in a Disk Storage Pool

For example, to audit the /dev/vol1 disk volume and have only summary messages sent to the activity log and server console, enter:

```
audit volume /dev/vol1 quiet=yes
```

The audit volume process is run in the background and the server returns the following message:

```
ANR2313I Audit Volume NOFIX process started for volume /dev/vol1
(process id 4).
```

To view the status of the audit volume process, enter:

```
query process
```

The following figure displays an example of the audit volume process report.

Process Number	Process Description	Status
4	Audit Volume (Inspect Only)	Storage Pool BACKUPPOOL, Volume /dev/vol1, Files Processed: 680, Irretrievable Files Found: 0, Partial Files Skipped: 0

To display the results of a volume audit after it has completed, you can issue the QUERY ACTLOG command.

Auditing Multiple Volumes in a Sequential Access Storage Pool

When you audit a sequential storage volume containing files that span multiple volumes, the server selects all associated volumes. The server begins the audit process with the first volume on which the first file resides. For example, Figure 82 on page 490 shows five volumes defined to ENGBACK2. In this example, File A spans VOL1 and VOL2, and File D spans VOL2, VOL3, VOL4, and VOL5.




Figure 82. Tape Volumes with Files A, B, C, D, and E

If you request that the server audit volume VOL3, the server first accesses volume VOL2, because File D begins at VOL2. When volume VOL2 is accessed, the server *only* audits File D. It does not audit the other files on this volume.

Because File D spans multiple volumes, the server accesses volumes VOL2, VOL3, VOL4, and VOL5 to ensure that there are no inconsistencies between the database and the storage pool volumes.

For volumes that require manual mount and dismount operations, the audit process can require significant manual intervention.

Auditing a Single Volume in a Sequential Access Storage Pool

To audit a single volume in a sequential storage pool, you can request that the server skip any files that span from the single volume to other volumes in the storage pool. This option is useful when the volume you want to audit contains part of a file, the rest of which resides on a different, damaged volume.

For example, to audit only volume VOL5 in the example in Figure 82 and have the server fix any inconsistencies found between the database and the storage volume, enter:

```
audit volume vol5 fix=yes skippartial=yes
```

Correcting Damaged Files

A data error can be caused by such things as a tape deteriorating or being overwritten or by a drive needing cleaning. If a data error is detected when a client tries to restore, retrieve, or recall a file or during a volume audit, TSM marks the file as damaged. If the same file is stored in other copy storage pools, the status of those file copies is not changed.

If a client tries to access a file that is marked as damaged and an undamaged copy is available on an onsite copy storage pool volume, TSM sends the user the undamaged copy.

Files that are marked as damaged cannot be:

- Restored, retrieved, or recalled
- Moved by migration, reclamation, or the MOVE DATA command
- Backed up during a BACKUP STGPOOL operation if the primary file is damaged
- Restored during a RESTORE STGPOOL or RESTORE VOLUME operation if the backup copy in a copy storage pool is damaged

Maintaining the Integrity of Files

To maintain the data integrity of user files, you can:

1. Detect damaged files before the users do.

The `AUDIT VOLUME` command marks a file as damaged if a read error is detected for the file. If an undamaged copy is in an onsite copy storage pool, it is used to provide client access to the file.

2. Reset the damaged status of files if the error that caused the change to damaged status was temporary.

You can use the `AUDIT VOLUME` command to correct situations when files are marked damaged due to a temporary hardware problem, such as a dirty tape head. TSM resets the damaged status of files if the volume in which the files are stored is audited and no read errors are detected.

3. Correct files that are marked as damaged.

If a primary file copy is marked as damaged and a usable copy exists in a copy storage pool, the primary file can be corrected using the `RESTORE VOLUME` or `RESTORE STGPOOL` command. For an example, see “Restoring Damaged Files”.

4. Regularly run commands to identify files that are marked as damaged:

- The `RESTORE STGPOOL` command displays the name of each volume in the restored storage pool that contains one or more damaged primary files. Use this command with the preview option to identify primary volumes with damaged files without actually performing the restore operation.
- The `QUERY CONTENT` command with the `DAMAGED` option lets you display damaged files on a specific volume.

For an example of how to use these commands, see “Restoring Damaged Files”.

Restoring Damaged Files

If you use copy storage pools, you can restore damaged client files. You can also check storage pools for damaged files and restore the files. This section explains how to restore damaged files based on the scenario in “Example: Simple Hierarchy with One Copy Storage Pool” on page 468.

If a client tries to access a file stored in `TAPEPOOL` and a read error occurs, the file in `TAPEPOOL` is automatically marked as damaged. Future accesses to the file automatically use the copy in `COPYPOOL` as long as the copy in `TAPEPOOL` is marked as damaged.

To restore any *damaged* files in `TAPEPOOL`, you can define a schedule that issues the following command periodically:

```
restore stgpool tapepool
```

You can check for and replace any files that develop data-integrity problems in `TAPEPOOL` or in `COPYPOOL`. For example, every three months, query the volumes in `TAPEPOOL` and `COPYPOOL` by entering the following commands:

```
query volume stgpool=tapepool
query volume stgpool=copypool
```

Then issue the following command for each volume in `TAPEPOOL` and `COPYPOOL`:

```
audit volume <volname> fix=yes
```

If a read error occurs on a file in TAPEPOOL, that file is marked *damaged* and an error message is produced. If a read error occurs on file in COPYPOOL, that file is deleted and a message is produced.

Restore *damaged* primary files by entering:

```
restore stgpool tapepool
```

Finally, create new copies in COPYPOOL by entering:

```
backup stgpool tapepool copypool
```

Backup and Recovery Scenarios

This section presents scenarios for protecting and recovering a TSM server. You can modify the procedures to meet your needs.



DRM can help you track your onsite and offsite volumes and query the TSM server and generate a current, detailed disaster recovery plan for your installation.

These scenarios assume a storage hierarchy consisting of:

- The default random access storage pools (BACKUPPOOL, ARCHIVEPOOL, and SPACEMGPOOL)
- TAPEPOOL, a tape storage pool

Protecting Your Database and Storage Pool

A company's standard procedures include the following:

- Perform reclamation of its copy storage pool, once a week. Reclamation for the copy storage pools is turned off at other times.

Note: In a copy storage pool definition, the REUSEDELAY parameter delays volumes from being returned to scratch or being reused. The value should be set high enough to ensure that the database can be restored to an earlier point-in-time and that the database references to files in the storage pool is still valid. For example, a user may want to retain database backups for seven days and, therefore, sets REUSEDELAY to 7.

- Back up its storage pools every night.
- Perform a full backup of the database once a week and incremental backups on the other days.
- Ship the database and copy storage pool volumes to an offsite location every day.

To protect client data, the administrator does the following:

1. Creates a copy storage pool named DISASTER-RECOVERY. Only scratch tapes are used, and the maximum number of scratch volumes is set to 100. The copy storage pool is defined by entering:

```
define stgpool disaster-recovery tapeclass pooltype=copy  
maxscratch=100
```

2. Performs the first backup of the primary storage pools.

Note: The first backup of a primary storage pool is a full backup and, depending on the size of the storage pool, could take a long time.

3. Defines schedules for the following daily operations:

- a. Incremental backups of the primary storage pools each night by issuing:

```
backup stgpool backuppool disaster-recovery maxprocess=2
backup stgpool archivepool disaster-recovery maxprocess=2
backup stgpool spacemgpool disaster-recovery maxprocess=2
backup stgpool tapepool disaster-recovery maxprocess=2
```

These commands use multiple, parallel processes to perform an incremental backup of each primary storage pool to the copy pool. Only those files for which a copy does not already exist in the copy pool are backed up.

Note: Migration should be turned off during the rest of the day. You could add a schedule to migrate from disk to tape at this point. In this way, the backups are done while the files are still on disk.

- b. Change the access mode to OFFSITE for volumes that have read-write or read-only access, are onsite, and are at least partially filled. This is done by entering:

```
update volume * access=offsite location='vault site info'
wherestgpool=disaster-recovery whereaccess=readwrite,readonly
wherestatus=filling,full
```

- c. Back up the database by entering:

```
backup db type=incremental devclass=tapeclass scratch=yes
```

4. Does the following operations nightly after the scheduled operations have completed:

- a. Backs up the volume history and device configuration files. If they have changed, back up the server options files and the database and recovery log setup information.
- b. Moves the volumes marked offsite, the database backup volumes, volume history files, device configuration files, server options files and the database and recovery log setup information to the offsite location.
- c. Identifies offsite volumes that should be returned onsite by using the QUERY VOLUME command:

```
query volume stgpool=disaster-recovery access=offsite status=empty
```

These volumes, which have become empty through expiration, reclamation, and file space deletion, have waited the delay time specified by the REUSEDELAY parameter. The administrator periodically returns outdated backup database volumes. These volumes are displayed with the QUERY VOLHISTORY command and can be released for reuse with the DELETE VOLHISTORY command.

5. Brings the volumes identified in step 4c onsite and updates their access to read-write.

Recovering to a Point-in-Time from a Disaster

In this scenario, the processor on which TSM resides, the database, and all onsite storage pool volumes are destroyed by fire. An administrator restores the server to the point-in-time of the last backup. You can use either full and incremental backups or snapshot database backups to restore a database to a point-in-time.



DRM can help you do these steps.

Do the following:

1. Install the TSM server on the replacement processor with the same server options and the same size database and recovery log as on the destroyed system. For example, to initialize the database and recovery log, enter:

```
dsmserv format 1 log1 1 dbvol1
```

2. Move the latest backup and all of the DISASTER-RECOVERY volumes onsite from the offsite location.

Note: Do not change the access mode of these volumes until after you have completed step 7.

3. If a current, undamaged volume history file exists, save it.
4. Restore the volume history and device configuration files, the server options and the database and recovery log setup. For example, the recovery site might require different device class, library, and drive definitions. For more information, see “Updating the Device Configuration File” on page 475.
5. Restore the database from the latest backup level by issuing the DSMSERV RESTORE DB utility (see “Recovering Your Server Using Database and Storage Pool Backups” on page 477).

6. Change the access mode of all the existing primary storage pool volumes in the damaged storage pools to DESTROYED by entering:

```
update volume * access=destroyed wherestgpool=backuppools
update volume * access=destroyed wherestgpool=archivepool
update volume * access=destroyed wherestgpool=spacemgpool
update volume * access=destroyed wherestgpool=tapepool
```

7. Issue the QUERY VOLUME command to identify any volumes in the DISASTER-RECOVERY storage pool that were onsite at the time of the disaster. Any volumes that were onsite would have been destroyed in the disaster and could not be used for restore processing. Delete each of these volumes from the database by using the DELETE VOLUME command with the DISCARDATA option. Any files backed up to these volumes cannot be restored.

8. Change the access mode of the remaining volumes in the DISASTER-RECOVERY pool to READWRITE by entering:

```
update volume * access=readwrite wherestgpool=disaster-recovery
```

Note: Clients can get files from TSM at this point. If a client tries to get a file that was stored on a destroyed volume, the retrieval request goes to the copy storage pool. In this way, clients can access their files without waiting for the primary storage pool to be restored. When you update volumes brought from offsite to change their access, you greatly speed recovery time.

9. Define new volumes in the primary storage pool so the files on the damaged volumes can be restored to the new volumes. The new volumes also let clients backup, archive, or migrate files to the server. You do not need to perform this step if you use only scratch volumes in the storage pool.
10. Restore files in the primary storage pool from the copies located in the DISASTER-RECOVERY pool by entering:


```
restore stgpool backuppool maxprocess=2
restore stgpool archivepool maxprocess=2
restore stgpool spacemgpool maxprocess=2
restore stgpool tapepool maxprocess=2
```

These commands use multiple parallel processes to restore files to primary storage pools. After all the files have been restored for a destroyed volume, that volume is automatically deleted from the database. See “When a Storage Pool Restoration Is Incomplete” on page 484 for what to do if one or more volumes cannot be fully restored.

11. To ensure against another loss of data, immediately back up all storage volumes and the database. Then resume normal activity, including weekly disaster backups and movement of data to the offsite location.

Recovering a Lost or Damaged Storage Pool Volume

If a company makes the preparations described in “Protecting Your Database and Storage Pool” on page 492 it can recover from a media loss by using TSM features.

In this scenario, an operator inadvertently destroys a tape volume (DSM087) belonging to the TAPEPOOL storage pool. An administrator performs the following actions to recover the data stored on the destroyed volume by using the offsite copy storage pool:

1. Determine the copy pool volumes that contain the backup copies of the files that were stored on the volume that was destroyed by entering:


```
restore volume dsm087 preview=volumesonly
```

This command produces a list of offsite volumes that contain the backed up copies of the files that were on tape volume DSM087.

2. Set the access mode of the copy volumes identified as UNAVAILABLE to prevent reclamation.

Note: This precaution prevents the movement of files stored on these volumes until volume DSM087 is restored.

3. Bring the identified volumes to the onsite location and set their access mode to READONLY to prevent accidental writes. If these offsite volumes are being used in an automated library, the volumes must be checked into the library when they are brought back onsite.
4. Restore the destroyed files by entering:


```
restore volume dsm087
```

This command sets the access mode of DSM087 to DESTROYED and attempts to restore all the files that were stored on volume DSM087. The files are not actually

restored to volume DSM087, but to another volume in the TAPEPOOL storage pool. All references to the files on DSM087 are deleted from the database and the volume itself is deleted from the database.

5. Set the access mode of the volumes used to restore DSM087 to OFFSITE using the UPDATE VOLUME command.
6. Set the access mode of the restored volumes, that are now onsite, to READWRITE.
7. Return the volumes to the offsite location. If the offsite volumes used for the restoration were checked into an automated library, these volumes must be checked out of the automated library when the restoration process is complete.

23

Using Tivoli Disaster Recovery Manager

You can use Tivoli Disaster Recovery Manager (DRM) product to do any one or all the following:

- Prepare a disaster recovery plan that can help you to recover your applications in the case of a disaster. You can recover at an alternate site, on replacement computer hardware, and with people who are not familiar with the applications.
- Manage your offsite recovery media.
- Store your client recovery information.

You can also use the disaster recovery plan for audits to certify the recoverability of the server.

Note: DRM is a separate program product that must be licensed before using. For more information, see “Registering Licensed Features” on page 356.

Before using this chapter, you should be familiar with “Protecting and Recovering Your Server” on page 457.

This chapter contains the following sections:

Tasks:
“Specifying Defaults for Tivoli Disaster Recovery Manager” on page 498
“Specifying Recovery Instructions for Your Site” on page 502
“Specifying Information About Your Server and Client Node Machines” on page 504
“Specifying Recovery Media for Client Machines” on page 506
“Creating and Storing the Disaster Recovery Plan” on page 506
“Managing Disaster Recovery Plan Files Stored on Target Servers” on page 508
“Moving Backup Media” on page 510
“Summary of Tivoli Disaster Recovery Manager Daily Tasks” on page 515
“Staying Prepared for a Disaster” on page 516
“Recovering From a Disaster” on page 517
Disaster Recovery Reference:
“Tivoli Disaster Recovery Manager Checklist” on page 525
“The Disaster Recovery Plan File” on page 528

In this chapter, most examples illustrate how to perform tasks by using the TSM command line interface. For information about the TSM commands, see *Administrator’s Reference*, or issue the HELP command from the command line of a TSM administrative client.

All of the TSM commands can be performed from the administrative Web interface. For more information about using the administrative interface, see *Quick Start*.

Task	Required Privilege Class
All DRM tasks unless otherwise noted.	System

Note: The default installation directories changed for Tivoli Storage Manager. If you created a recovery plan file with ADSM Version 3 Release 1, some names in that file may no longer be valid. After installing Tivoli Storage Manager, immediately back up your storage pools and database and create a new recovery plan file.

You can use a recovery plan file and database backup that were created on an ADSM Version 3 Release 1 server to restore a Tivoli Storage Manager server. After the restore is complete, start the server with the following command:

```
dsmserv upgradedb
```

Use the UPGRADEDDB parameter only for the initial startup.

To recover from a disaster, you must know the location of offsite recovery media. DRM helps you to determine which volumes to move offsite and back onsite and, tracks the location of the volumes.

Specifying Defaults for Tivoli Disaster Recovery Manager

DRM provides default settings for the preparation of the recovery plan file and for the management of offsite recovery media. However, you can override these default settings. To query the settings, issue the following command:

```
query drmstatus
```

The output will be similar to the following:

```
Recovery Plan Prefix: /u/recovery/plans/rpp
Plan Instructions Prefix: /u/recovery/plans/source/
Replacement Volume Postfix: @
Primary Storage Pools: PRIM1 PRIM2
Copy Storage Pools: COPY*
Not Mountable Location Name: Local
Courier Name: Joe's Courier Service
Vault Site Name: Ironvault, D. Lastname, 1-000-000-0000
DB Backup Series Expiration Days: 30 Day(s)
Check Label?: Yes
Process FILE Device Type?: No
Command File Name: /drm/orm/exec.cmds
```

Specifying Defaults for the Disaster Recovery Plan File

The following table describes how to set defaults for the disaster recovery plan file.

Table 29. Defaults for the Disaster Recovery Plan File

Primary storage pools to be processed	<p>When the recovery plan file is generated, you can limit processing to specified pools.</p> <p>The default at installation: All primary storage pools.</p> <p>To change the default: SET DRMPRIMSTGPOOL</p> <p>For example, to specify that only the primary storage pools named PRIM1 and PRIM2 are to be processed, enter: <pre>set drmprimstgpool prim1,prim2</pre></p> <p>Note: To remove all previously specified primary storage pool names and thus select all primary storage pools for processing, specify a null string ("") in SET DRMPRIMSTGPOOL.</p> <p>To override the default: Specify primary storage pool names in the PREPARE command</p>
Copy storage pools to be processed	<p>When the recovery plan file is generated, you can limit processing to specified pools.</p> <p>The default at installation: All copy storage pools.</p> <p>To change the default: SET DRMCOPYSTGPOOL</p> <p>For example, to specify that only the copy storage pools named COPY1 and COPY2 are to be processed, enter: <pre>set drmcopystgpool copy1,copy2</pre></p> <p>Notes:</p> <ol style="list-style-type: none"> 1. To remove any specified primary storage pool names, and thus select all primary storage pools, specify a null string ("") in SET DRMCOPYSTGPOOL. 2. If you specify both primary and copy storage pools, the specified copy storage pools should be those used to back up the specified primary storage pools. <p>To override the default: Specify copy storage pool names in the PREPARE command</p>
Identifier for replacement volume names	<p>To restore a primary storage pool volume, mark the original volume <i>destroyed</i> and create a replacement volume having a unique name. You can specify a character to be appended to the name of the original volume in order to create a name for the replacement volume. This character can help you find the replacement volume names in the disaster recovery plan. For details about the restore process, see “How Restore Processing Works” on page 458.</p> <p>The default identifier at installation: @</p> <p>To change the default: SET DRMPLANVPOSTFIX</p> <p>For example, to use the character r, enter: <pre>set drmplanvpostfix r</pre></p>

Table 29. Defaults for the Disaster Recovery Plan File (continued)

<p>Recovery instructions prefix</p>	<p>You can specify a prefix for the names of the recovery instructions source files in the recovery plan file.</p> <p>The default at installation: For a description of how DRM determines the default prefix, see the INSTRPREFIX parameter of the PREPARE command section in the <i>Administrator's Reference</i> or enter HELP PREPARE from administrative client command line.</p> <p>To set a default: SET DRMINSTRPREFIX</p> <p>For example, to specify the prefix as <code>/u/recovery/plans/rpp</code>, enter:</p> <pre>set drminstrprefix /u/recovery/plans/rpp</pre> <p>The disaster recovery plan file will include, for example, the following file:</p> <pre>/u/recovery/plans/rpp.RECOVERY.INSTRUCTIONS.GENERAL</pre> <p>To override the default: The INSTRPREFIX parameter with the PREPARE command</p>
<p>Prefix for the recovery plan file</p>	<p>You can specify a prefix to the path name of the recovery plan file. DRM uses this prefix to identify the location of the recovery plan file and to generate the macros and script file names included in the RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE and RECOVERY.SCRIPT.NORMAL.MODERECOVERY.DRMODE and RECOVERY.NMODE stanzas.</p> <p>The default at installation: For a description of how DRM determines the default prefix, see the PLANPREFIX parameter of the PREPARE command section in the <i>Administrator's Reference</i> or enter HELP PREPARE from administrative client command line.</p> <p>To change the default: SET DRMPPLANPREFIX</p> <p>For example, to specify the prefix as <code>/u/server/recoveryplans/</code>, enter:</p> <pre>set drmplprefix /u/server/recoveryplans/</pre> <p>The disaster recovery plan file name created by PREPARE processing will be in the following format:</p> <pre>/u/server/recoveryplans/20000603.013030</pre> <p>To override the default: The PLANPREFIX parameter with the PREPARE command</p>
<p>The disaster recovery plan expiration period</p>	<p>You can set the numbers of days after creation that a disaster recovery plan file stored on a target server expires. After the number of days has elapsed, all recovery plan files that meet both of the following conditions are eligible for expiration:</p> <ul style="list-style-type: none"> ■ The last recovery plan associated with the database series is older than the set number of days. ■ The recovery plan file is not associated with the most recent backup series. <p>The default at installation: 60 days</p> <p>To change the default: SET DRMRPFEXPIREDAYS</p> <p>For example, to change the time to 90 days, enter:</p> <pre>set drmrpfexpiredays 90</pre>

Specifying Defaults for Offsite Recovery Media Management

The following table describes how to set defaults for offsite recovery media management.

<p>Copy storage pool volumes to be processed</p>	<p>MOVE DRMEDIA and QUERY DRMEDIA can process copy storage pool volumes in the MOUNTABLE state. You can limit processing to specified copy storage pools.</p> <p>The default at installation: All copy storage pool volumes in the MOUNTABLE state</p> <p>To change the default: SET DRMCOPYSTGPOOL</p> <p>To override the default: COPYSTGPOOL parameter on MOVE DRMEDIA or QUERY DRMEDIA</p>
<p>Executable commands file name</p>	<p>You can use MOVE DRMEDIA or QUERY DRMEDIA to generate executable commands and store them in a file.</p> <p>The default file name at installation: None</p> <p>To set a default: SET DRMCMDFILENAME. For example, to set the file name as <i>/drm/orm/exec.cmds</i> enter:</p> <pre>set drmcmdfilename /drm/orm/exec.cmds</pre> <p>To override the default: CMDFILENAME parameter on MOVE DRMEDIA or QUERY DRMEDIA</p>
<p>Location name for volumes that move to the NOTMOUNTABLE state</p>	<p>MOVE DRMEDIA generates a location name for volumes that move to the NOTMOUNTABLE state.</p> <p>The default at installation: NOTMOUNTABLE</p> <p>To change the default: SET DRMNOTMOUNTABLENAME</p> <p>For example, to specify a location named LOCAL, enter:</p> <pre>set drmnotmountablename local</pre>
<p>Location name for volumes that move to the COURIER or COURIERRETRIEVE state</p>	<p>MOVE DRMEDIA generates a location name for volumes that are changing from NOTMOUNTABLE to COURIER or from VAULTRETRIEVE to COURIERRETRIEVE.</p> <p>The default at installation: COURIER</p> <p>To change the default: SET DRMCOURIERNAME</p> <p>For example, to specify a courier named Joe's Courier Service, enter:</p> <pre>set drmcouriername "Joe's Courier Service"</pre>
<p>Reading labels of checked out volumes</p>	<p>To determine whether DRM reads the sequential media labels of volumes that are checked out with MOVE DRMEDIA.</p> <p>Note: This command does not apply to 349X library types.</p> <p>The default at installation: DRM reads the volume labels.</p> <p>To change the default: SET DRMCHECKLABEL</p> <p>For example, to specify that DRM should not read the volume labels, enter:</p> <pre>set drmchecklabel no</pre>

Expiration period of a database backup series	<p>A database backup series (full plus incremental and snapshot) is eligible for expiration if all of these conditions are true:</p> <ul style="list-style-type: none"> ■ The volume state is VAULT or the volume is associated with a device type of SERVER (for virtual volumes). ■ It is not the most recent database backup series. ■ The last volume of the series exceeds the expiration value, number of days since the last backup in the series. <p>The default at installation: 60 days</p> <p>To change the default: SET DRMDBBACKUPEXPIREDAYS</p> <p>For example, to set the expiration value to 30 days, enter:</p> <pre>set drmdbbackupexpiredays 30</pre>
Whether to process backup volumes of the FILE device type	<p>At installation, MOVE DRMEDIA and QUERY DRMEDIA will not process backup volumes that are associated with a device type of FILE.</p> <p>The default at installation: Backup volumes of the FILE device type are not processed</p> <p>To change the default: SET DRMFILEPROCESS</p> <p>To allow processing, enter:</p> <pre>set drmfileprocess yes</pre>
Vault Name	<p>MOVE DRMEDIA uses the vault name to set the location of volumes that are moving from the COURIER state to the VAULT state</p> <p>The default at installation: The vault name is set to VAULT.</p> <p>To change the default: SET DRMVaultNAME</p> <p>For example, to specify the vault name as IRONVAULT, the contact name as J. SMITH, and the telephone number as 1-555-000-0000, enter:</p> <pre>set drmvaultname "Ironvault, J. Smith, 1-555-000-0000"</pre>

Specifying Recovery Instructions for Your Site

The disaster recovery plan includes instructions that you create. Enter your instructions in flat files that have the following names:

- *prefix*.RECOVERY.INSTRUCTIONS.GENERAL
- *prefix*.RECOVERY.INSTRUCTIONS.OFFSITE
- *prefix*.RECOVERY.INSTRUCTIONS.INSTALL
- *prefix*.RECOVERY.INSTRUCTIONS.DATABASE
- *prefix*.RECOVERY.INSTRUCTIONS.STGPOOL

Note: The files created for the recovery instructions must be physical sequential files.

RECOVERY.INSTRUCTIONS.GENERAL

Include information such as administrator names, telephone numbers, and location of passwords. For example:

Recovery Instructions for TSM Server ACMESRV on system ZEUS
Joe Smith (wk 002-000-1111 hm 002-003-0000): primary system programmer
Sally Doe (wk 002-000-1112 hm 002-005-0000): primary recovery administrator
Jane Smith (wk 002-000-1113 hm 002-004-0000): responsible manager

Security Considerations:

Joe Smith has the password for the Admin ID ACMEADM. If Joe is unavailable, you need to either issue SET AUTHENTICATION OFF or define a new administrative user ID at the replacement TSM server console.

RECOVERY.INSTRUCTIONS.OFFSITE

Include information such as the offsite vault location, courier's name, and telephone numbers. For example:

Our offsite vault location is Ironvault, Safetown, Az.
The phone number is 1-800-000-0008. You need to contact them directly to authorize release of the tapes to the courier.
Our courier's name is Fred Harvey. You can contact him at 1-800-444-0000.
Since our vault is so far away, be sure to give the courier a list of both the database backup and copy storage pool volumes required. Fred is committed to returning these volumes to us in less than 12 hours.

RECOVERY.INSTRUCTIONS.INSTALL

Include information about restoring the base server system from boot media or, if boot media is unavailable, about server installation and the location of installation volumes. For example:

Most likely you will not need to reinstall the TSM server and administrative clients because we use mksysb to backup the rootvg volume group, and the TSM server code and configuration files exist in this group.
However, if you cannot do a mksysb restore of the base server system, and instead have to start with a fresh AIX build, you may need to add TSM server code to that AIX system.
The install volume for the TSM server is INS001. If that is lost, you will need to contact Copy4You Software, at 1-800-000-0000, and obtain a new copy. Another possibility is the local IBM Branch office at 555-7777.

RECOVERY.INSTRUCTIONS.DATABASE

Include information about how to recover the database and about how much hardware space requirements. For example:

You will need to find replacement disk space for the server database. We have an agreement with Joe Replace that in the event of a disaster, he will provide us with disk space.

RECOVERY.INSTRUCTIONS.STGPOOL

Include information on primary storage pool recovery instructions. For example:

Do not worry about the archive storage pools during this disaster recovery. Focus on migration and backup storage pools.
The most important storage pool is XYZZZZ.

Specifying Information About Your Server and Client Node Machines

You need information about your server machine to rebuild its replacement. You also need information about client node machines to rebuild or restore them. Follow this procedure to specify that information and store it in the server database:

Server Machine

1. Specify server machine information:

Issue the `DEFINE MACHINE` command. with `ADSMSEVER=YES`. For example, to define machine `MACH22` in building 021, 2nd floor, in room 2929, with a priority of 1, enter:

```
define machine tsm1 adsmserver=yes priority=1
```

Client Machines

2. Specify the client node location and business priority:

Issue the `DEFINE MACHINE` command. For example, to define machine `MACH22` in building 021, 2nd floor, in room 2929, with a priority of 1, enter:

```
define machine mach22 building=021 floor=2 room=2929 priority=1
```

3. Associate one or more client nodes with a machine:

Issue the `DEFINE MACHNODEASSOCIATION` command. Use this association information to identify client nodes on machines that were destroyed. You should restore the file spaces associated with these nodes. For example, to associate node `CAMPBELL` with machine `MACH22`, enter:

```
define machnodeassociation mach22 campbell
```

To query machine definitions, issue the `QUERY MACHINE` command. See the example, in “Client Recovery Scenario” on page 520.

4. To add machine characteristics and recovery instructions to the database, issue the `INSERT MACHINE` command. You must first query the operating system to identify the characteristics for your client machine. You can add the information manually or use an `awk` script to do it. A sample program is shipped with `DRM`.

■ Add information manually:

The following partial output is from a query on an AIX client machine.

```
--1 Host Name: mach22 with 256 MB Memory Card
---   256 MB Memory Card
---
--4 Operating System: AIX Version 4 Release 3
---
--- Hardware Address: 10:00:5x:a8:6a:46
```

Specify characteristics and recovery instructions one line at a time with separate `INSERT MACHINE` commands:

- To save the first line (Host Name: mach22 with 256 MB Memory Card) as line 1 and to save the fourth line (Operating System: AIX Version 4 Release 3) as line 2 for machine `MACH22`, issue the following commands:

```
insert machine mach22 1 characteristics="Host Name: mach22 with
256 MB Memory Card"
```

```
insert machine mach22 2 characteristics="Operating System:
AIX Version 4 Release 3"
```

- To specify recovery instructions for your client machine, issue the following command:

```
insert machine mach22 1 -
recoveryinstructions="Recover this machine for accounts
receivable dept."
```

■ Add Information Using an Awk Script

To help automate the adding of client machine information, a sample awk script named *machchar.awk.smp* is shipped with DRM. The following example shows how to use a local program to add machine characteristics or recovery instructions:

- The output from the AIX commands *lsdev*, *lsvg*, and *df* is written to the file *clientinfo.txt* on the AIX client machine that backed up data to the server. These commands list the devices, logical volumes by volume group, and file systems.
- The file, *clientinfo.txt*, is processed by the awk script, which builds a macro of INSERT MACHINE commands (one command for each line in the file).
- Run the macro to load the data into the database. From an AIX prompt, issue the following commands:

```
echo "devices" > clientinfo.txt
lsdev -C | sort -d -f >> clientinfo.txt
echo "logical volumes by volume group" >> clientinfo.txt
lsvg -o | lsvg -i -l >> clientinfo.txt
echo "file systems" >> clientinfo.txt
df >> clientinfo.txt
```

Figure 83 is an example procedure named *machchar* to add machine characteristics. The *machchar.awk.smp* script is shipped with DRM and is located in the */usr/tivoli/tsm/server/bin* directory.

```
# Read machine characteristics from a file and build TSM macro commands
# to insert the information into the machine characteristics table.
# Invoke with:
# awk -f machchar.awk -v machine=acctrcv filewithinfo

BEGIN {
    print "delete machine "machine" type=characteri"
    }
    {
    print "insert machine "machine" "NR" characteri=\""$0"\"
    }
END
{
}
```

Figure 83. Example of Awk Script File to Insert Machine Characteristics

- The *machchar.awk* script is then run from an AIX prompt as follows:

```
awk -f machchar.awk -v machine=acctrcv clientinfo.txt >
clientinfo.mac
```


-
- e. To add the machine characteristics, start an administrative client and run the macro. For example:

```
> dsmadm -id=xxx -pw=xxx macro clientinfo.mac
```

You can view your machine characteristics by issuing the `QUERY MACHINE` command with `FORMAT=CHARACTERISTICS` parameter.

- f. To specify recovery instructions for your client machine, use this same awk script process but with the `RECOVERYINSTRUCTIONS` parameter.

Specifying Recovery Media for Client Machines

Follow these steps to specify the bootable media needed to reinitialize or reinstall an operating system on a client machine and to associate machines with media. You can also associate non-executable media such as application user guides with client machines.

1. Define the bootable media. For example, define the media named `TELLERWRKSTNIMAGE` which is for AIX Version 4.3, contains the required volumes named `AIX001`, `AIX002`, and `AIX003`, and is located in Building 21.

```
define recoverymedia tellerwrkstnimage type=boot
  volumenames=aix001,aix002,aix003 product="AIX 4.3"
  location="Building 21"
```

You should define the recovery media after a client machine configuration changes. For example, after you have installed a new level of AIX on a client machine and created a bootable image using `mksysb`, issue the `DEFINE RECOVERYMEDIA` command to define the new `mksysb` volumes.

To query your recovery media definitions, issue the `QUERY RECOVERYMEDIA` command with the `FORMAT=DETAILED` parameter.

2. Associate one or more machines with recovery media. Use the association information to identify the boot media to use in the replacement machines. For example, to associate machine `MACH255` with recovery media `TELLERWRKSTNIMAGE`, issue the following command:

```
define recmedmachassociation tellerwrkstnimage mach255
```

3. When the boot media is moved offsite, update its location. For example, to update the location of boot media `TELLERWRKSTNIMAGE` to the offsite location `IRONVAULT`, issue the following command:

```
update recoverymedia tellerwrkstnimage location=ironvault
```

You can define media that contain softcopy manuals that you would need during recovery. For example, to define a CD-ROM containing the AIX 4.3 manuals that are on volume `CD0001`, enter:

```
define recoverymedia aix43manuals type=other volumes=cd0001
  description="AIX 4.3 Bookshelf"
```

Creating and Storing the Disaster Recovery Plan

You can create a disaster recovery plan file and store the file locally or on another server.

The recovery plan contains the following information:

- The recovery procedure

- A list of required database and storage pool backup volumes, devices to read those volumes, and database and recovery log space requirements
- Copies of the server options file, device configuration file, and volume history information file
- Commands for performing database recovery and primary storage pool recovery
- Commands for registering licenses
- Instructions that you define
- Machine and recovery media information that you define

For details about the recovery plan file, see “The Disaster Recovery Plan File” on page 528.

DRM creates one copy of the disaster recovery plan file each time you issue the PREPARE command. You should create multiple copies of the plan for safekeeping. For example, keep copies in print, on diskettes, on NFS-mounted disk space that is located offsite, or on a remote server.

Before creating a disaster recovery plan, back up your storage pools then backup the database. See “Backing Up Storage Pools” on page 465 and “Backing Up the Database” on page 468 for details about these procedures.

If you manually send backup media offsite, see “Moving Backup Volumes Offsite” on page 512. If you use virtual volumes, see “Using Virtual Volumes to Store Data on Another Server” on page 348.

When your backups are both offsite and marked offsite, you can create a disaster recovery plan.

You can use the Tivoli Storage Manager scheduler to periodically run the PREPARE command (see “Automating Server Operations” on page 371).

Note: DRM creates a plan that assumes that the latest database full plus incremental series would be used to restore the database. However, you may want to use DBSNAPSHOT backups for disaster recovery and retain your full plus incremental backup series on site to recover from possible availability problems. In this case, you must specify the use of DBSNAPSHOT backups in the PREPARE command. For example:

```
prepare source=dbsnapshot
```

Storing the Disaster Recovery Plan Locally

When you create a recovery plan file but do not specify a device class, the file is stored locally in a file system. If you store the file locally, you can specify a storage location. For example, to store the recovery plan file locally in the `/u/server/recoveryplans/` directory, enter:

```
prepare planprefix=/u/server/recoveryplans/
```

Recovery plan files that are stored locally are not automatically expired. You should periodically delete down-level recovery plan files manually.

DRM appends to the file name the date and time (yyyymmdd.hhmmss). For example:
`/u/server/recoveryplans/20000925.120532`

Storing the Disaster Recovery Plan on a Target Server

When you create a recovery plan file and specify a device class, the file is stored on a target server. Storing recovery plan files on a target server provides the following:

- A central repository on a target server for recovery plan files
- Automatic expiration of plan files
- Query capabilities that display information about recovery plan files and the ability to display the contents of a recovery plan file located on a target server
- Recovery plan file retrieval from a target server

First, set up the source and target servers and define a device class a device type of SERVER (see “Setting Up Source and Target Servers for Virtual Volumes” on page 349 for details). For example, assume a device class named TARGETCLASS is defined on the source server where you create the recovery plan file. Then to create the plan file, enter:

```
prepare devclass=targetclass
```

The recovery plan file is written as an object on the target server, and a volume history record is created on the source server. For more about recovery plan files that are stored on target servers, see “Displaying Information about Recovery Plan Files”.

Managing Disaster Recovery Plan Files Stored on Target Servers

The following sections describe how you can view information about disaster recovery plan files stored on a target server and view their contents. It also describes how to direct the contents of a disaster recovery plan file to another file and how to delete volume history records of the recovery plan files.

Displaying Information about Recovery Plan Files

You can display information about recovery plan files from the server that created the files (the source server) or from the server on which the files are stored (the target server):

- **From the source server:** Issue QUERY RPFIL command with the DEVCLASS parameter that was used on the PREPARE command. Specify the type of database backups that were assumed when the plan was created (either full plus incremental or snapshot). For example, to display a list of all recovery plan files that have been saved for the source server on any target servers and created assuming snapshot database backups, enter:

```
query rpfil devclass=* source=dbsnapshot
```

You can also issue the QUERY VOLHISTORY command to display a list of recovery plan files for the source server. Specify recovery plan files that were created assuming either full plus incremental database backups (TYPE=RPFIL) or database snapshot backups (TYPE=RPFSNAPSHOT). For example:

```
query volhistory type=rpfil
```

- **From the target server:** Issue a QUERY RPFIL command that specifies the node name associated with the server or servers that prepared the plan. For example, to display a list of all recovery plan files that have been saved in the target server, enter:

```
query rpfil nodename=*
```

Displaying the Contents of a Recovery Plan File

From the server that created the recovery plan file (the source server) or from the server on which the file is stored (the target server), you can display the contents of that file that was saved as an object on the target server. For example,

- **From the source server:** Issue the following command for a recovery plan file created on September 1, 2000 at 4:39 a.m. with the device class TARGETCLASS:

```
query rpfcontent marketing.20000901.043900 devclass=targetclass
```
- **From the target server:** Issue the following command for a recovery plan file created on August 31,2000 at 4:50 a.m. on a source server named MARKETING whose node name is BRANCH8:

```
query rpfcontent marketing.20000831.045000 nodename=branch8
```

Notes:

1. You cannot issue these commands from a server console.
2. An output delay can occur when the plan file is located on tape.

See “The Disaster Recovery Plan File” on page 528 for an example of the contents of a recovery plan file.

Restoring a Recovery Plan File

To restore a recovery plan file, use the QUERY RPFCONTENT command and direct the output to a file. You can issue the command from the server that created the files (the source server) or from the server on which the files are stored (the target server). To see a list of recovery plan file names, issue the QUERY RPFFILE command.

For example, a recovery plan file named *marketing.20000831.045000* was created using the device class of TARGETCLASS and on a source server whose node name at the target server is BRANCH8. You want to restore the file and direct the output to *rpf.out*:

- **From the source server:** Enter,

```
query rpfcontent marketing.20000831.045000  
devclass=targetclass > rpf.out
```
- **From the target server:** Enter,

```
query rpfcontent marketing.20000831.045000  
nodename=branch8 > rpf.out
```

To display a list of recovery plan files, use the QUERY RPFFILE command. See “Displaying Information about Recovery Plan Files” on page 508 for more information.

Expiring Recovery Plan Files Automatically

You can set DRM to expire recovery plan files a certain number of days after they are created. To set up expiration, issue the SET DRMRPFEXPIREDDAYS command. The default value is 60 days. For example, to change the time to 90 days, enter:

```
set drmprfexpiredays 90
```

All recovery plan files that meet the criteria are eligible for expiration if both of the following conditions exist:

- The last recovery plan file of the series is over 90 days old.

-
- The recovery plan file is not associated with the most recent backup series. A backup series consists of a full database backup and all incremental backups that apply to that full backup. Another series begins with the next full backup of the database.

Expiration applies to plan files based on both full plus incremental and snapshot database backups.

Deleting Recovery Plan Files Manually

You can delete volume history records containing information about recovery plan file objects. When the records are deleted from the source server and the grace period is reached, the objects are deleted from the target server.

Note: The record for the latest recovery plan file is not deleted.

For example, to delete records for recovery plan files that were created on or before 08/30/2000 and assuming full plus incremental database backup series, enter:

```
delete volhistory type=rpfile todate=08/30/2000
```

To limit the operation to recovery plan files that were created assuming database snapshot backups, specify `TYPE=RPFSNAPSHOT`.

Moving Backup Media

To recover from a disaster you will need database backup volumes and copy storage pool volumes. To prepare for a disaster, you will need perform the following daily tasks:

1. Move new backup media offsite and update the database with their locations. See “Moving Backup Volumes Offsite” on page 512 for details.
2. Return expired or reclaimed backup media onsite and update the database with their locations. See “Moving Backup Volumes Onsite” on page 513 for details.

Task	Required Privilege Class
Send backup volumes offsite and back onsite	Unrestricted storage or operator

Offsite recovery media management does not process virtual volumes. To display all virtual copy storage pool and database backup volumes that have their backup objects on the remote target server, issue the following command:

```
query drmedia * wherestate=remote
```

The disaster recovery plan includes backup volume location information and can provide a list of offsite volumes required to restore a server.

The following diagram shows the typical life cycle of the recovery media:




Figure 84. Recovery Media Life Cycle

DRM assigns the following states to volumes. The location of a volume is known at each state.

MOUNTABLE

The volume contains valid data, and TSM can access it.

NOTMOUNTABLE

The volume contains valid data and is onsite, but TSM cannot access it.

COURIER

The volume contains valid data and is in transit to the vault.

VAULT

The volume contains valid data and is at the vault.

VAULTRETRIEVE

The volume no longer contain valid data and are to be returned to the site. For more information on reclamation of offsite copy storage pool volumes, see “Reclamation of Offsite Volumes” on page 156. For information on expiration of database backup volumes, see step 1 on page 514 below.

COURIERRETRIEVE

The volume no longer contain valid data and are in the process of being returned by the courier.

ONSITERETRIEVE

The volume no longer contain valid data and have been moved back to the onsite location. The volume records of database backup and scratch copy storage pool volumes are deleted from the database. For private copy storage pool volumes, the access mode is updated to READWRITE.

Moving Backup Volumes Offsite

After you have created the backup copies of your primary storage pools and database, you can send your backup media offsite. To send media offsite, mark the volumes as unavailable to TSM and give them to the courier. Do the following to identify the database backup and copy storage pool volumes and move them offsite:

1. Identify the copy storage pool and database backup volumes to be moved offsite:

```
query drmedia * wherestate=mountable
```

DRM displays information similar to the following:

Volume Name	State	Last Update Date/Time	Automated LibName
TPBK05	Mountable	01/01/2000 12:00:31	LIBRARY
TPBK99	Mountable	01/01/2000 12:00:32	LIBRARY
TPBK06	Mountable	01/01/2000 12:01:03	LIBRARY

2. Indicate the movement of volumes whose current state is MOUNTABLE by issuing the following command:

```
move drmedia * wherestate=mountable
```

For all volumes in the MOUNTABLE state, DRM does the following:

- Updates the volume state to NOTMOUNTABLE and the volume location according to the SET DRMNOTMOUNTABLENAME. If this command has not been issued, the default location is NOTMOUNTABLE.
- For a copy storage pool volume, updates the access mode to unavailable.
- For a volume in an automated library, checks the volume out of the library.

Notes:

- a. During checkout processing, SCSI libraries request operator intervention. To bypass these requests and eject the cartridges from the library, first issue the following command:

```
move drmedia * wherestate=mountable remove=no
```

Next, access a list of the volumes by issuing the following command:

```
query drmedia wherestate=notmountable
```

From this list identify and remove the cartridges (volumes) from the library.

- b. For the 349X library type, if the number of cartridges to be checked out of the library is greater than the number of slots in the I/O station, you can define a high

capacity area in your library. Then use the following command to eject the cartridges to the high capacity area, rather than to the I/O station:

```
move drmedia * wherestate=mountable remove=bulk
```

- Send the volumes to the offsite vault. Issue the following command to have DRM select volumes in the NOTMOUNTABLE state:

```
move drmedia * wherestate=notmountable
```

For all volumes in the NOTMOUNTABLE state, DRM updates the volume state to COURIER and the volume location according to the SET DRMCOURIERNAME. If the SET command has not yet been issued, the default location is COURIER. For more information, see “Specifying Defaults for Offsite Recovery Media Management” on page 500

- When the vault location confirms receipt of the volumes, issue the MOVE DRMEDIA command in the COURIER state. For example:

```
move drmedia * wherestate=courier
```

For all volumes in the COURIER state, DRM updates the volume state to VAULT and the volume location according to the SET DRMVAULTNAME command. If the SET command has not yet been issued, the default location is VAULT. For more information, see “Specifying Defaults for Offsite Recovery Media Management” on page 500.

- To display a list of volumes that contain valid data at the vault, issue the following command:

```
query drmedia wherestate=vault
```

DRM displays information similar to the following:

Volume Name	State	Last Update Date/Time	Automated LibName
TAPE0P	Vault	01/05/2000 10:53:20	
TAPE1P	Vault	01/05/2000 10:53:20	
DBT02	Vault	01/05/2000 10:53:20	
TAPE3S	Vault	01/05/2000 10:53:20	

- If you do not want to step through all the states, you can use the TOSTATE parameter on the MOVE DRMEDIA command to specify the destination state. For example, to transition the volumes from NOTMOUNTABLE state to VAULT state, issue the following command:

```
move drmedia * wherestate=notmountable tostate=vault
```

For all volumes in the NOTMOUNTABLE state, DRM updates the volume state to VAULT and the volume location according to the SET DRMVAULTNAME command. If the SET command has not yet been issued, the default location is VAULT.

See “Staying Prepared for a Disaster” on page 516 for an example that demonstrates sending server backup volumes offsite using MOVE DRMEDIA and QUERY DRMEDIA commands.

Moving Backup Volumes Onsite

Use the following procedure to expire the non-virtual database backup volumes and return the volumes back onsite for reuse or disposal.

-
1. To specify the number of days before a database backup series is expired, issue the SET DRMDBBACKUPEXPIREDDAYS command. To ensure that the database can be returned to an earlier level and database references to files in the copy storage pool are still valid, specify the same value for the REUSEDELAY parameter in your copy storage pool definition.

The following example sets the number of days to 30.

```
set drmdbbackupexpiredays 30
```

A database backup volume is considered eligible for expiration if all of the following conditions are true:

- The age of the last volume of the series has exceeded the expiration value. This value is the number of days since the last backup in the series. At installation, the expiration value is 60 days. To override this value, issue the SET DRMDBBACKUPEXPIREDDAYS command.
- For volumes that are not virtual volumes, all volumes in the series are in the VAULT state.
- The volume is not part of the most recent database backup series.

Note: Database backup volumes that are virtual volumes are removed during expiration processing. This processing is started manually by issuing the EXPIRE INVENTORY command or automatically through the EXPINTERVAL option setting specified in the server options file.

2. Move a backup volume onsite for reuse or disposal when the volume is reclaimed and:
 - The status for a copy storage pool volume is EMPTY.
 - The database backup series is EXPIRED.

To determine which volumes to retrieve, issue the following command:

```
query drmedia * wherestate=vaultretrieve
```

3. After the vault location acknowledges that the volumes have been given to the courier, issue the following command:

```
move drmedia * wherestate=vaultretrieve
```

The server does the following for all volumes in the VAULTRETRIEVE state:

- Change the volume state to COURIERRETRIEVE.
- Update the location of the volume according to what is specified in the SET DRMCOURIERNAME command. For more information, see “Specifying Defaults for Offsite Recovery Media Management” on page 500.

4. When the courier delivers the volumes, acknowledge that the courier has returned the volumes onsite, by issuing:

```
move drmedia * wherestate=courierretrieve
```

The server does the following for all volumes in the COURIERRETRIEVE state:

- The volumes are now onsite and can be reused or disposed.
- The database backup volumes are deleted from the volume history table.
- For scratch copy storage pool volumes, the record in the database is deleted. For private copy storage pool volumes, the access is updated to read/write.

5. If you do not want to step through all the states, you can use the TOSTATE parameter on the MOVE DRMEDIA command to specify the destination state. For example, to transition the volumes from VAULTRETRIEVE state to ONSITERETRIEVE state, issue the following command:

```
move drmedia * wherestate=vaultretrieve tostateretrie
```

The server does the following for all volumes with in the VAULTRETRIEVE state:

- The volumes are now onsite and can be reused or disposed.
- The database backup volumes are deleted from the volume history table.
- For scratch copy storage pool volumes, the record in the database is deleted. For private copy storage pool volumes, the access is updated to read/write.

Summary of Tivoli Disaster Recovery Manager Daily Tasks

This section summarizes the use of DRM during routine operations and during disaster recovery.

Setup

1. License DRM
2. Ensure the device configuration and volume history files exist.
3. Back up the storage pools.
4. Do a full backup the database (for example, a database snapshot backup).
5. Define site-specific server recovery instructions.
6. Describe priority client machines.
7. Generate the disaster recovery plan.

Daily Preparation Operations

Day 1

1. Back up client files.
2. Back up the primary storage pools.
3. Back up the database (for example, a database snapshot backup).
4. Mark the backup volumes as unavailable to TSM.
5. Send the backup volumes and disaster recovery plan file to the vault.
6. Generate the disaster recovery plan.

Day 2

1. Back up client files
2. Back up the primary storage pools.
3. Back up the database (for example, a database snapshot backup).
4. Mark the backup volumes as unavailable to TSM.
5. Send the backup volumes and disaster recovery plan file to the vault.
6. Generate the disaster recovery plan.

Day 3

1. Automatic storage pool reclamation processing occurs.
2. Back up client files.
3. Back up the primary storage pools.
4. Back up the database (for example, a database snapshot backup).
5. Send the backup volumes and a list of expired volumes to be reclaimed to the vault.
6. The vault acknowledges receipt of the volumes sent on the previous day.
7. Generate the disaster recovery plan.

Disaster and Recovery

Day 4

The server and the client machines are destroyed.

1. Restore the server using the latest recovery plan.
2. Identify the top priority client nodes at the disaster site.
3. Restore client machine files from the copy storage pools.
4. Restore the primary storage pools.
5. Move database backup and copy storage pool volumes to the vault.

Daily Operations

Day 5

1. Back up client files.
2. Back up the primary storage pools.
3. Back up the database (for example, a database snapshot backup).
4. Send the backup volumes and a list of expired volumes to be reclaimed to the vault.
5. Generate the disaster recovery plan.

Staying Prepared for a Disaster

This section provides an overview and a scenario of the tasks required to stay prepared for a disaster. The steps are performed by the onsite TSM administrator unless otherwise indicated.

1. Record the following information in the RECOVERY.INSTRUCTIONS stanza source files:
 - Software license numbers
 - Sources of replacement hardware
 - Any recovery steps specific to your installation
2. Store the following information in the database:
 - Server and client node machine information (DEFINE MACHINE, DEFINE MACHINENODE ASSOCIATION, and INSERT MACHINE)
 - The location of the boot recovery media (DEFINE RECOVERYMEDIA)
3. Schedule automatic nightly backups to occur in the following order:
 - a. Primary Storage Pools
 - b. Database
4. Daily, create a list of the previous night's database and storage pool backup volumes to be sent offsite:

```
query drmedia * wherestate=mountable
```

 - a. Check the volumes out of the library:

```
move drmedia * wherestate=mountable
```
 - b. Send the volumes offsite and record that the volumes were given to the courier:

```
move drmedia * wherestate=notmountable
```
5. Create a new recovery plan:

```
prepare
```
6. Copy the recovery plan file to a diskette to be given to the courier.

7. Create a list of tapes that contain data that is no longer valid and that should be returned to the site:

```
query drmedia * wherestate=vaultretrieve
```
8. Give the courier the database and storage pool backup tapes, the recovery plan file diskette, and the list of volumes to be returned from the vault.
9. The courier gives you any tapes that were on the previous day's return from the vault list.

Update the state of these tapes and check them into the library:

```
move drmedia * wherestate=courierretrieve cmdf=/drm/checkin.libvol
cmd="checkin libvol libauto &vol status=scratch"
```

The volume records for the tapes that were in the COURIERRETRIEVE state are deleted from the database. The MOVE DRMEDIA command also generates the CHECKIN LIBVOL command for each tape processed in the file */drm/checkin.libvol*. For example:

```
checkin libvol libauto tape01 status=scratch
checkin libvol libauto tape02 status=scratch
...
```

Note: An administrator can run the MACRO command by specifying */drm/checkin.libvol*.

```
> dsmadm -id=xxxxx -pa=yyyyy MACRO /drm/checkin.libvol
```

10. The courier takes the database and storage pool backup tapes, the recovery plan diskette, and the list of volumes to return from the vault.
11. Call the vault and verify that the backup tapes arrived and are secure, and that the tapes to be returned to the site have been given to the courier.
12. Set the location of the volumes sent to the vault:

```
move drmedia * wherestate=courier
```
13. Set the location of the volumes given to the courier by the vault:

```
move drmedia * wherestate=vaultretrieve
```

Recovering From a Disaster

This section provides an overview of the tasks involved in recovering the server and clients. It also presents scenarios of both procedures.

Recovering the Server: Here are guidelines for recovering your server:

1. Obtain the latest disaster recovery plan file.
2. Break out the file to view, update, print, or run as macros or scripts (for example, batch programs or batch files).
3. Obtain the backup volumes from the vault.
4. Locate a suitable replacement machine.
5. Restore an AIX image to your replacement machine.
6. Review the RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE RECOVERY.SCRIPT.NORMAL.MODE scripts because they are important for restoring the server to a point where clients can be recovered (see "Disaster Recovery Mode Stanza" on page 535).

Recovering the Clients: To recover clients, do the following:

1. Get the following information by querying the recovered database:
 - Client machines that have been defined to TSM, along with their location and restore priority value
 - The location of the boot recovery media
 - Specific recovery instructions for the machine
 - Hardware requirements for the machine
2. With this information restore the client machines.

Server Recovery Scenario

Here is the procedure for a complete recovery of the server after a disaster has destroyed it. In this example virtual volumes are not used. The steps are performed by the onsite administrator unless otherwise indicated.

1. Review the recovery steps described in the RECOVERY.INSTRUCTIONS.GENERAL stanza of the plan.
2. Request the server backup tapes from the offsite vault.
3. Break out the recovery plan file stanzas into multiple files (see “Breaking Out a Disaster Recovery Plan File” on page 528.) These files can be viewed, updated, printed, or run as TSM macros or scripts.
4. Print the RECOVERY.VOLUMES.REQUIRED file. Give the printout to the courier to retrieve the backup volumes.
5. Find a replacement server. The RECOVERY.DEVICES.REQUIRED stanza specifies the device type that is needed to read the backups. The SERVER.REQUIREMENTS stanza specifies the disk space required.
6. Restore an AIX image to the replacement server using a **mksysb** tape. This tape, which includes the TSM server software, is created whenever software updates or configuration changes are made to the AIX system. The tape location should be specified in the RECOVERY.INSTRUCTIONS.INSTALL stanza.

Restoration from the **mksysb** tapes includes recreating the root volume group, and the file system where the database, recovery log, storage pool and disk volumes are located..
7. Review the TSM macros contained in the recovery plan.

If, at the time of the disaster, the courier had not picked up the previous night’s database and storage pool incremental backup volumes but they were not destroyed, remove the entry for the storage pool backup volumes from the COPYSTGPOOL.VOLUMES.DESTROYED file.
8. If some required storage pool backup volumes could not be retrieved from the vault, remove the volume entries from the COPYSTGPOOL.VOLUMES.AVAILABLE file.
9. If all primary volumes were destroyed, no changes are required to the PRIMARY.VOLUMES script and TSM macro files.
10. Review the device configuration file to ensure that the hardware configuration at the recovery site is the same as the original site. Any differences must be updated in the device configuration file. Examples of configuration changes that require updates to the configuration information are:

- Different device names
- Use of a manual library instead of an automated library
- For automated libraries, the requirement of manually placing the database backup volumes in the automated library and updating the configuration information to identify the element within the library. This allows the server to locate the required database backup volumes.

For information about updating the device configuration file, see “Updating the Device Configuration File” on page 475.

11. To restore the database to a point where clients can be recovered, invoke the RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script file. Enter the script file name at the command prompt. As an alternative, you can use the recovery script as a guide and manually issue the steps.

The following are some sample steps from a recovery script:

- a. Copy the TSM server options file from the DSMSERV.OPT file to its original location.
- b. Copy the volume history file required by database restore processing from the VOLUME.HISTORY.FILE file to its original location.

Note: Use this copy of the volume history file unless you have a more recent copy (after the disaster occurred).

- c. Copy the device configuration file required by database restore processing from the DEVICE.CONFIGURATION.FILE file to its original location.
- d. Create the TSM server recovery log and database volumes using DSMFMT.
- e. Issue DSMSERV FORMAT command to format the recovery log and database files.
- f. Issue the DSMSERV RESTORE DB command.
- g. Start the server.
- h. Register TSM server licenses.
- i. Mark copy storage pool volumes retrieved from vault as available.
- j. Mark copy storage pool volumes that cannot be obtained as unavailable.
- k. Mark primary storage pool volumes as *destroyed*.

Notes:

- a. Due to changes in hardware configuration during recovery, you might have to update the device configuration file located in the restored TSM database (see “Updating the Device Configuration File” on page 475).
 - b. You can mount copy storage pool volumes upon request, check in the volumes in advance, or manually place the volumes in the library and ensure consistency by issuing the AUDIT LIBRARY command.
 - c. Use the AUDIT LIBRARY command to ensure that the restored TSM database is consistent with the automated library volumes.
12. If client machines are not damaged, invoke the RECOVERY.SCRIPT.NORMAL.MODE script file to restore the server primary storage pools. If client machines are damaged, you may want to delay this action until after all clients are recovered.

Note: This action is optional because TSM can access the copy storage pool volumes directly to restore client data. Using this feature, you can minimize client recovery time because server primary storage pools do not have to be restored first. However, in this scenario, the client machines were not damaged, so the focus of the administrator is to restore full TSM server operation.

As an alternative, you can use the recovery script as a guide and manually run each step. The steps run in this script are:

- a. Create replacement primary volumes.
 - b. Define the replacement primary volumes to TSM.
 - c. Restore the primary storage pools.
13. Collect the database backup and copy storage pool volumes used in the recovery for return to the vault. For these backup volumes to be returned to the vault using the routine MOVE DRMEDIA process, issue the following commands:

```
update volhist TPBK50 devcl=lib8mm ormstate=mountable
update volhist TPBK51 devcl=lib8mm ormstate=mountable
```

The copy storage pool volumes used in the recovery already have the correct ORMSTATE.

14. Issue the BACKUP DB command to back up the newly restored database.
15. Issue the following command to check the volumes out of the library:

```
move drmedia * wherestate=mountable
```
16. Create a list of the volumes to be given to the courier:

```
query drmedia * wherestate=notmountable
```
17. Give the volumes to the courier and issue the following command:

```
move drmedia * wherestate=notmountable
```
18. Issue the PREPARE command.

Client Recovery Scenario

The following scenario demonstrates the recovery of clients.

1. To view a list of client machines that were lost in building 21 and their restore priority, issue the following command:

```
query machine building=021 format=detailed
```

DRM displays information similar to the following:

```
Machine Name: POLARIS
Machine Priority: 1
  Building: 21
  Floor: 2
  Room: 1
  Server?: No
  Description: Payroll
  Node Name: POLARIS
Recovery Media Name: MKSYSB1
  Characteristics?: Yes
Recovery Instructions?: Yes
```

2. For *each* machine, issue the following commands:

- a. Determine the location of the boot media. For example:
`query recoverymedia mksysb1`

The server displays the following information:

Recovery Media Name	Volume Names	Location	Machine Name
MKSYSB1	vol1 vol2 vol3	IRONVAULT	POLARIS

- b. Determine the machine-specific recovery instructions. For example:
`query machine polaris format=recoveryinstructions`

The server displays the following:

```
Recovery Instructions for Polaris.
Primary Contact:
  Jane Smith (wk 520-000-0000 hm 520-001-0001)
Secondary Contact:
  John Adams (wk 520-000-0001 hm 520-002-0002)
```

- c. Determine the machine hardware requirements. For example:
`query machine polaris format=characteristics`

The server displays information similar to the following:

```

devices
aio0      Defined      Asynchronous I/O
bus0      Available 00-00      Microchannel Bus
fd0       Available 00-00-0D-00    Diskette Drive
fda0      Available 00-00-0D      Standard I/O Diskette Adapter
fpa0      Available 00-00      Floating Point Processor
gda0      Available 00-04      Color Graphics Display Adapter
hd1       Defined      Logical volume
hd2       Defined      Logical volume
hd3       Defined      Logical volume
hdisk0    Available 00-01-00-00 400 MB SCSI Disk Drive
hdisk1    Available 00-01-00-40 Other SCSI Disk Drive
hft0      Available      High Function Terminal Subsystem
inet0     Available      Internet Network Extension
ioplanar0 Available 00-00      I/O Planar
kbd0      Defined 00-00-0K-00    United States keyboard
lb0       Available 00-02-00-20 TIVSM Library
lo0       Available      Loopback Network Interface
loglv00   Defined      Logical volume
lp0       Available 00-00-0P-00 IBM 4201 Model 3 Proprinter III
lv03      Defined      Logical volume
lv04      Defined      Logical volume
lvdd      Available      N/A
mem0      Available 00-0B      8 MB Memory Card
mem1      Available 00-0C      16 MB Memory Card
mous0     Defined 00-00-0M-00 3 button mouse
mt0       Available 00-02-00-40 TIVSM Tape Drive
ppa0      Available 00-00-0P Standard I/O Parallel Port Adapter
pty0      Available      Asynchronous Pseudo-Terminal
rootvg    Defined      Volume group
sa0       Available 00-00-S1 Standard I/O Serial Port 1
sa1       Available 00-00-S2 Standard I/O Serial Port 2
scsi0     Available 00-01      SCSI I/O Controller
scsi1     Available 00-02      SCSI I/O Controller
sio0      Available 00-00      Standard I/O Planar
siokb0    Available 00-00-0K Keyboard Adapter
sioms0    Available 00-00-0M Mouse Adapter
siotb0    Available 00-00-0T Tablet Adapter
sys0      Available 00-00      System Object
sysplanar0 Available 00-00      CPU Planar
sysunit0  Available 00-00      System Unit
tok0      Available 00-03      Token-Ring High-Performance Adapter
tr0       Available      Token Ring Network Interface
tty0      Available 00-00-S1-00 Asynchronous Terminal
tty1      Available 00-00-S2-00 Asynchronous Terminal
usrvice   Defined      Logical volume
veggie2   Defined      Volume group
logical volumes by volume group
veggie2:
LV NAME      TYPE      LPs  PPs  PVs  LV STATE      MOUNT POINT
hd2          jfs       103  103  1   open/syncd    /usr
hd1          jfs       1    1    1   open/syncd    /home
hd3          jfs       3    3    1   open/syncd    /tmp
hd9var       jfs       1    1    1   open/syncd    /var
file systems
Filesystem   Total KB   free %used   iused %iused Mounted on
/dev/hd4     8192      420  94%      909  44% /
/dev/hd9var  4096      2972  27%      87   8% /var
/dev/hd2     421888    10964 97%      17435 16% /usr
/dev/hd3     12288     11588 5%        49   1% /tmp
/dev/hd1     4096      3896 4%        26   2% /home

```

3. With the information obtained, restore each client machine.

Recovering When Using Different Hardware at the Recovery Site

You may have to recover your system using hardware that is different from that used when you backed up your database and created disaster recovery plan file. Before restoring the database, update the device configuration file included in the recovery plan file. After restoring the database, update the device configuration on the database.

This section describes a number of such situations in detail. If the hardware environment is different at the recovery site, you must update the device configuration file. TSM uses the device configuration file to access the devices that are needed to read the database backup volumes. The RECOVERY.VOLUMES.REQUIRED stanza in the plan file identifies the volumes that are needed to restore the database.

Automated SCSI Library at the Original Site and a Manual SCSI Library at the Recovery Site

Ensure that the DEFINE DRIVE and DEFINE LIBRARY commands in the device configuration file are valid for the new hardware configuration. For example, if an automated tape library was used originally and cannot be used at the recovery site, update the device configuration file. Include the DEFINE LIBRARY and DEFINE DRIVE commands that are needed to define the manual drive to be used. In this case, you must manually mount the backup volumes.

Note: If you are using an automated library, you may also need to update the device configuration file to specify the location of the database backup volume.

Here is an example of an original device configuration file, which describes an automated tape library:

```
/* Device Configuration */

define devclass auto8mm_class devtype=8mm format=drive
  mountlimit=2 mountwait=60 mountretention=60
  prefix=tsm library=auto8mmlib

define library auto8mmlib libtype=scsi device=/dev/lb4

define drive auto8mmlib 8mm_tape0 device=/dev/mt1
  element=82 online=yes

define drive auto8mmlib 8mm_tape1 device=/dev/mt2
  element=83 online=yes

/* LIBRARYINVENTORY SCSI AUTO8MMLIB KEV004 1 101*/
/* LIBRARYINVENTORY SCSI AUTO8MMLIB KEV005 3 101*/
```

Here is an example of the updated device configuration file when a manual library is used at the recovery site:

```
/* Device Configuration */

define devclass auto8mm_class devtype=8mm format=drive
  mountlimit=1 mountwait=60 mountretention=60 prefix=tsm
  library>manual8mm

define library manual8mm libtype>manual

define drive manual8mm 8mm_tape0 device=/dev/mt1
```

The following changes were made:

- In the device class definition, the library name was changed from AUTO8MMLIB to MANUAL8MM. The device class name remains the same because it is associated with the database backup volumes in the volume history file.
- The manual library, MANUAL8MM, was defined.
- A new drive, 8MM_TAPE0, was defined for the manual library.
- The comments that named the location of volumes in the automated library were removed.

After you restore the database, modify the device configuration file in the database. After starting the server, define, update, and delete your library and drive definitions to match your new configuration.

Note: If you are using an automated library, you may need to use the `AUDIT LIBRARY` command to update the server inventory of the library volumes.

Automated SCSI Library at the Original and Recovery Sites

Manually place the database backup volumes in the automated library and note the element numbers where you place them. Then update the comments in the device configuration file to identify the locations of those volumes.

Note: You may also need to audit the library after the database is restored in order to update the server inventory of the library volumes.

Here is an example of an original device configuration file, which describes an automated tape library:

```
/* Device Configuration */

define devclass auto8mm_class devtype=8mm format=drive
  mountlimit=2 mountwait=60 mountretention=60 prefix=tsm
  library=auto8mmlib

define library auto8mmlib libtype=scsi device=/dev/lb4

define drive auto8mmlib 8mm_tape0 device=/dev/mt1
  element=82 online=yes

define drive auto8mmlib 8mm_tape1 device=/dev/mt2
  element=83 online=yes

/* LIBRARYINVENTORY SCSI AUTO8MMLIB KEV004 1 101*/
/* LIBRARYINVENTORY SCSI AUTO8MMLIB KEV005 3 101*/
```

Here is an example of the updated device configuration file when an automated library is used at the recovery site to read a database volume DBBK01:

```
/* Device Configuration */

define devclass auto8mm_class devtype=8mm format=drive
  mountlimit=2 mountwait=60 mountretention=60 prefix=tsm
  library=auto8mmlib

define library auto8mmlib libtype=scsi device=/dev/lb4

define drive auto8mmlib 8mm_tape0 device=/dev/mt1
  element=82 online=yes

define drive auto8mmlib 8mm_tape1 device=/dev/mt2
```

```
element=83 online=yes
```

```
/* LIBRARYINVENTORY SCSI AUTO8MMLIB DBBK01 1 101*/
```

In this example, database backup volume DBBK01 was placed in element 1 of the automated library. Then a comment is added to the device configuration file to identify the location of the volume. Tivoli Storage Manager needs this information to restore the database restore. Comments that no longer apply at the recovery site are removed.

Managing Copy Storage Pool Volumes at the Recovery Site

The RECOVERY.VOLUMES.REQUIRED stanza in the recovery plan file identifies the required copy storage pool volumes. The restored server uses copy storage pool volumes to satisfy requests (for example, from backup/archive clients) and to restore primary storage pool volumes that were destroyed. These volumes must be available to the restored server. After the database is restored, you can handle copy storage pool volumes at the recovery site in three ways:

- Mount each volume as requested by TSM. If an automated library is used at the recovery site, check the volumes into the library.
- Check the volumes into an automated library before TSM requests them.
- Manually place the volumes in an automated library and audit the library to update the server inventory.

Note: If you are using an automated library, you may also need to audit the library after the database is restored in order to update the TSM inventory of the volumes in the library.

Tivoli Disaster Recovery Manager Checklist

The following checklist can help you set up Tivoli Disaster Recovery Manager.

Table 30. Tivoli Disaster Recovery Manager Checklist

Activity	Start Date	End Date	Status	Person Resp.	Backup Person
Plan for DRM					
Evaluate your disaster recovery requirements <ul style="list-style-type: none">■ What are the business priorities for recovering your clients?■ Where is the recovery site?■ Is the recovery site hot, warm, or cold?■ Do the clients have connectivity to recovery server?■ Who are the system and TSM administrators?■ Will you need to return to the original site?■ Where are the offsite backups stored?■ How does the vault handle the backup media?■ How are the backups packaged or processed?■ Who provides the courier service?					

Table 30. Tivoli Disaster Recovery Manager Checklist (continued)

Activity	Start Date	End Date	Status	Person Resp.	Backup Person
Evaluate the current storage pool backup implementation <ul style="list-style-type: none"> ■ What primary storage pools are being backed up? ■ When are the backups performed? ■ Will the backups remain onsite or be sent offsite? ■ Naming conventions for replacement volumes for primary storage pools 					
Evaluate the current database backup implementation <ul style="list-style-type: none"> ■ When are the backups performed? ■ Backup purpose: offsite or onsite ■ Will you use snapshot database backups or full plus incremental database backups? ■ How long do you want to keep backup series? Verify that the values for copy storage pool REUSEDELAY and DRMDBBACKUPEXPIREDDAYS are the same. 					
Determine which primary storage pools are to be managed by DRM					
Determine which copy storage pools are to be managed by DRM <ul style="list-style-type: none"> ■ Offsite copy storage pools 					
Where to Save the Recovery Plan File <p>Locally:</p> <ul style="list-style-type: none"> ■ What is the recovery plan file pathname prefix? ■ How will recovery plan files be made available at the recovery site? <ul style="list-style-type: none"> • Print and store offsite • Tape/diskette copy stored offsite • Copy sent/NFS to recovery site <p>On Another Server:</p> <ul style="list-style-type: none"> ■ What server is to be used as the target server? ■ What is the name of the target server's device class? ■ How long do you want to keep recovery plan files? 					
Determine where you want to create the user-specified recovery instructions <p>What is the prefix of the instructions pathname?</p>					
Analyze the sequence of steps related to the PREPARE command backup movement <p>Document the flow of activities and timings</p> <ul style="list-style-type: none"> ■ Sending of volumes offsite ■ Return of empty volumes ■ PREPARE timing 					
Installation					

Table 30. Tivoli Disaster Recovery Manager Checklist (continued)

Activity	Start Date	End Date	Status	Person Resp.	Backup Person
Receive and Install the TSM code					
License DRM <ul style="list-style-type: none"> ■ REGISTER LICENSE or ■ Update the server options 					
Set DRM defaults <p>Issue:</p> <ul style="list-style-type: none"> ■ SET DRMDBBACKUPEXPIREDDAYS to define the database backup expiration ■ SET DRMPRIMSTGPOOL to specify the DRM-managed primary storage pools ■ SET DRMCOPYSTGPOOL to specify the DRM-managed copy storage pools ■ SET DRMPLANVPOSTFIX to specify a character to be appended to new storage pools ■ SET DRMPLANPREFIX to specify the RPF prefix ■ SET DRMINSTRPREFIX to specify the user instruction file prefix ■ SET DRMNOTMOUNTABLENAME to specify the default location for media to be sent offsite ■ SET DRMCOURIERNAME to specify the default courier ■ SET DRMVaultNAME to specify the default vault ■ SET DRMCMDFILENAME to specify the default file name to contain the commands specified with the CMD parameter on MOVE and QUERY DRMEDIA ■ SET DRMCHECKLABEL to specify whether volume labels are verified when checked out by the MOVE DRMEDIA command ■ SET DRMRPFEXPIREDDAYS to specify a value for the frequency of RPF expiration (when plan files are stored on another server) 					
Define the site-specific recovery instructions <p>Identify:</p> <ul style="list-style-type: none"> ■ Target disaster recovery server location ■ Target server software requirements ■ Target server hardware requirements (storage devices) ■ TSM administrator contact ■ Courier name and telephone number ■ Vault location and contact person <p>Create:</p> <ul style="list-style-type: none"> ■ Enter the site-specific recovery instructions data into files created in the same path/HLQ as specified by SET DRMINSTRPREFIX 					
Test Tivoli Disaster Recovery Manager					

Table 30. Tivoli Disaster Recovery Manager Checklist (continued)

Activity	Start Date	End Date	Status	Person Resp.	Backup Person
Test the installation and customization <ul style="list-style-type: none"> ■ QUERY DRMSTATUS to display the DRM setup ■ Back up the primary storage pools ■ Back up the TSM database ■ QUERY DRMEDIA to list the backup volumes ■ MOVE DRMEDIA to move offsite ■ PREPARE to create the recovery plan file 					
Examine the recovery plan file created					
Test the recovery plan file break out <ul style="list-style-type: none"> ■ awk script planexpl.awk ■ Locally written procedure 					
Set up the schedules for automated functions					

The Disaster Recovery Plan File

The disaster recovery plan file contains the information required to recover a TSM server to the point in time represented by the last database backup operation that is completed before the plan is created. The plan is organized into stanzas, which you can break out into multiple files.

Breaking Out a Disaster Recovery Plan File

You can use an awk script or an editor to break out the stanzas into individual files. A sample procedure, *planexpl.awk.smp*, is shipped with DRM and is located in */usr/tivoli/tsm/server/bin/* or wherever the server resides. You can modify this procedure for your installation. Store a copy of the procedure offsite for recovery.

Structure of the Disaster Recovery Plan File

The disaster recovery plan is divided into the following types of stanzas:

Command stanzas

Consist of scripts (for example, batch programs or batch files) and TSM macros. You can view, print, and update these stanzas, and run them during recovery.

Note: The RECOVERY.SCRIPT.NORMAL.MODE and RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE stanzas contain the commands that invoke the scripts and macros contained in the other stanzas.

Instruction stanzas

Consist of recovery instructions specific to your site. You can view, print, and update these stanzas, and use them during recovery.

Server requirements stanzas

Include the database and recovery log requirements, device and volume requirements, and license information. You can view and print these stanzas, and use them during recovery.

Configuration file stanzas

Consist of the volume history, device configuration, and server options files.

Machine and recovery media stanzas

Consist of machine recovery instructions and information about machine hardware, software, and recovery media. You can print and update these stanzas, and use them during server recovery.

Table 31 lists the recovery plan file stanzas, and indicates what type of administrative processing is required during set up, routine operations, and disaster recovery. The table also indicates whether the stanza contains a macro, a script, or a configuration file.

Note: For tasks identified as **During setup or periodic updates**, DRM automatically collects this information for the plan.

Table 31. Administrative Tasks Associated with the Disaster Recovery Plan File

Stanza Name	Tasks
PLANFILE.DESCRPTION	—
PLANFILE.TABLE.OF.CONTENTS	—
SERVER.REQUIREMENTS	—
RECOVERY.INSTRUCTIONS.GENERAL	During setup or periodic updates: Edit the source file associated with the stanza (optional)
RECOVERY.INSTRUCTIONS.OFFSITE	During setup or periodic updates: Edit the source file associated with the stanza (optional)
RECOVERY.INSTRUCTIONS.INSTALL	During setup or periodic updates: Edit the source file associated with the stanza (optional)
RECOVERY.INSTRUCTIONS.DATABASE	During setup or periodic updates: Edit the source file associated with the stanza (optional)
RECOVERY.INSTRUCTIONS.STGPOOL	During setup or periodic updates: Edit the source file associated with the stanza (optional)
RECOVERY.VOLUMES.REQUIRED	During routine processing: MOVE DRMEDIA
RECOVERY.DEVICES.REQUIRED	—
RECOVERY.SCRIPT. DISASTER.RECOVERY.MODE script	During disaster recovery: Edit and run (optional)
RECOVERY.SCRIPT. NORMAL.MODE script	During disaster recovery: Edit and run (optional)
LOGANDDB.VOLUMES.CREATE script	During disaster recovery: Edit and run (optional)
LOG.VOLUMES	During disaster recovery: Optionally edit/copy
DB.VOLUMES	During disaster recovery: Optionally edit/copy
LOGANDDB.VOLUMES.INSTALL script	During disaster recovery: Edit and run (optional)
LICENSE.REGISTRATION macro	During disaster recovery: Edit and run (optional)
COPYSTGPOOL.VOLUMES.AVAILABLE macro	During routine processing: MOVE DRMEDIA During disaster recovery: Edit and run (optional)

Table 31. Administrative Tasks Associated with the Disaster Recovery Plan File (continued)

Stanza Name	Tasks
COPYSTGPOOL.VOLUMES.DESTROYED macro	During routine processing: MOVE DRMEDIA During disaster recovery: Edit and run (optional)
PRIMARY.VOLUMES.DESTROYED macro	During disaster recovery: Edit and run (optional)
PRIMARY.VOLUMES.REPLACEMENT.CREATE script	During disaster recovery: Edit and run (optional)
PRIMARY.VOLUMES.REPLACEMENT macro	During disaster recovery: Edit and run (optional)
STGPOOLS.RESTORE macro	During disaster recovery: Edit and run (optional)
VOLUME.HISTORY.FILE configuration file	During disaster recovery: Copy (optional)
DEVICE.CONFIGURATION.FILE configuration file	During disaster recovery: Edit and copy (optional)
DSMSERV.OPT.FILE configuration file	During disaster recovery: Edit and copy (optional)
LICENSE.INFORMATION	—
MACHINE.GENERAL.INFORMATION	During setup or periodic updates: Issue DEFINE MACHINE ADSMSERVER=YES (optional)
MACHINE.RECOVERY.INSTRUCTIONS	During setup or periodic updates: Issue INSERT MACHINE RECOVERYINSTRUCTIONS (optional)
MACHINE.RECOVERY.CHARACTERISTICS	During setup or periodic updates: Issue INSERT MACHINE CHARACTERISTICS (optional)
MACHINE.RECOVERY.MEDIA	During setup or periodic updates: Issue DEFINE RECOVERYMEDIA and DEFINE RECMEDMACHASSOCIATION (optional)

Example Disaster Recovery Plan File

This section contains an example of a disaster recovery plan file and information about each stanza. The disaster recovery plan file has been divided into separate figures that correlate to the descriptions of specific stanzas within each figure.

Description and Table of Contents Stanzas PLANFILE.DESCRPTION

Identifies the server for this recovery plan, and the date and time the plan is created.


```

begin PLANFILE.DESCRPTION

Recovery Plan for Server DESIGN_DEPARTMENT
Created by DRM PREPARE on 02/11/2000 10:20:34
Server for AIX-RS/6000 - Version 4, Release 1, Level x.x/x.x

end PLANFILE.DESCRPTION

```

Figure 85. Description Stanza

PLANFILE.TABLE.OF.CONTENTS

Lists the stanzas documented in this plan.

```

begin PLANFILE.TABLE.OF.CONTENTS

PLANFILE.DESCRPTION
PLANFILE.TABLE.OF.CONTENTS

Server Recovery Stanzas:
  SERVER.REQUIREMENTS
  RECOVERY.INSTRUCTIONS.GENERAL
  RECOVERY.INSTRUCTIONS.OFFSITE
  RECOVERY.INSTRUCTIONS.INSTALL
  RECOVERY.VOLUMES.REQUIRED
  RECOVERY.DEVICES.REQUIRED
  RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script
  RECOVERY.SCRIPT.NORMAL.MODE script
  LOGANDB.VOLUMES.CREATE script
  LOG.VOLUMES
  DB.VOLUMES
  LOGANDB.VOLUMES.INSTALL script
  LICENSE.REGISTRATION macro
  COPYSTGPOOL.VOLUMES.AVAILABLE macro
  COPYSTGPOOL.VOLUMES.DESTROYED macro
  PRIMARY.VOLUMES.DESTROYED macro
  PRIMARY.VOLUMES.REPLACEMENT.CREATE script
  PRIMARY.VOLUMES.REPLACEMENT macro
  STGPOOLS.RESTORE macro
  VOLUME.HISTORY.FILE
  DEVICE.CONFIGURATION.FILE
  DSMSERV.OPT.FILE

Machine Description Stanzas:
  MACHINE.GENERAL.INFORMATION
  MACHINE.RECOVERY.INSTRUCTIONS
  MACHINE.CHARACTERISTICS
  MACHINE.RECOVERY.MEDIA.REQUIRED

end PLANFILE.TABLE.OF.CONTENTS

```

Figure 86. Table of Contents Stanza

Server Requirements Stanza SERVER.REQUIREMENTS

Identifies the database and recovery log storage requirements for the server. The replacement server must have enough disk space to install the database and recovery log volumes. This stanza also identifies the directory where the server executable resided when the server was started. If the server executable is in a different directory on the replacement server, edit the plan file to account for this change.

If you use links to the server executable file, you must create the links on the replacement machine or modify the following plan file stanzas:

- RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE
- LOGANDDB.VOLUMES.CREATE
- LOGANDDB.VOLUMES.INSTALL
- PRIMARY.VOLUMES.REPLACEMENT.CREATE

```
begin SERVER.REQUIREMENTS
Database Requirements Summary:
    Available Space (MB): 20
    Assigned Capacity (MB): 20
    Pct. Utilization: 2.2
Maximum Pct. Utilization: 2.2
    Physical Volumes: 2
Recovery Log Requirements Summary:
    Available Space (MB): 20
    Assigned Capacity (MB): 20
    Pct. Utilization: 4.4
Maximum Pct. Utilization: 4.8
    Physical Volumes: 2
Server Executable Location: /usr/tivoli/tsm/server/bin
end SERVER.REQUIREMENTS
```

Figure 87. Server Requirements Stanza

Recovery Instructions Stanzas

The administrator enters recovery instructions into source files that the PREPARE command includes in the plan files. See “Specifying Recovery Instructions for Your Site” on page 502 for details.

Note: In the following descriptions, *prefix* represents the prefix portion of the file name. See “Specifying Defaults for the Disaster Recovery Plan File” on page 498 for details.

RECOVERY.INSTRUCTIONS.GENERAL

Identifies site-specific instructions that the administrator has entered in the file identified by *prefix* RECOVERY.INSTRUCTIONS.GENERAL. The instructions should include the recovery strategy, key contact names, an overview of key applications backed up by this server, and other relevant recovery instructions.

```
begin RECOVERY.INSTRUCTIONS.GENERAL

This server contains the backup and archive data for FileRight Company
accounts receivable system. It also is used by various end users in the
finance and materials distribution organizations.
The storage administrator in charge of this server is Jane Doe 004-001-0006.
If a disaster is declared, here is the outline of steps that must be completed.
1. Determine the recovery site. Our alternate recovery site vendor is IBM
   BRS in Tampa, FL, USA 213-000-0007.
2. Get the list of required recovery volumes from this recovery plan file
   and contact our offsite vault so that they can start pulling the
   volumes for transfer to the recovery site.
3. etc...

end RECOVERY.INSTRUCTIONS.GENERAL
```

Figure 88. Recovery Instructions General Stanza

RECOVERY.INSTRUCTIONS.OFFSITE

Contains instructions that the administrator has entered in the file identified by *prefix* RECOVERY.INSTRUCTIONS.OFFSITE. The instructions should include the name and location of the offsite vault, and how to contact the vault (for example, a name and phone number).

```
begin RECOVERY.INSTRUCTIONS.OFFSITE

Our offsite vaulting vendor is OffsiteVault Inc.
Their telephone number is 514-555-2341. Our account rep is Joe Smith.
Our account number is 1239992. Their address is ...
Here is a map to their warehouse ...
Our courier is ...

end RECOVERY.INSTRUCTIONS.OFFSITE
```

Figure 89. Recovery Instructions Offsite Stanza

RECOVERY.INSTRUCTIONS.INSTALL

Contains instructions that the administrator has entered in the file identified by *prefix* RECOVERY.INSTRUCTIONS.INSTALL. The instructions should include how to rebuild the base server machine and the location of the system image backup copies.

```
begin RECOVERY.INSTRUCTIONS.INSTALL
```

```
The base server system is AIX 4.3 running on an RS6K model 320.  
Use mksysb volume serial number svrbas to restore this system image.  
A copy of this mksysb tape is stored at the vault. There is also a copy  
in bldg 24 room 4 cabinet a. The image includes the server code.  
The system programmer responsible for this image is Fred Myers.  
Following are the instructions to do a mksysb based OS install:
```

```
end RECOVERY.INSTRUCTIONS.INSTALL
```

Figure 90. Recovery Instructions Install Stanza

RECOVERY.INSTRUCTIONS.DATABASE

Contains instructions that the administrator has entered in the file identified by *prefix* RECOVERY.INSTRUCTIONS.DATABASE. The instructions should include how to prepare for the database recovery. For example, you may enter instructions on how to initialize or load the backup volumes for an automated library. No sample of this stanza is provided.

RECOVERY.INSTRUCTIONS.STGPOOL

Contains instructions that the administrator has entered in the file identified by *prefix* RECOVERY.INSTRUCTIONS.STGPOOL. The instructions should include the names of your software applications and the copy storage pool names containing the backup of these applications. No sample of this stanza is provided.

Volume and Device Requirements Stanzas

RECOVERY.VOLUMES.REQUIRED

Provides a list of the database backup and copy storage pool volumes required to recover the server. This list can include both virtual volumes and nonvirtual volumes. A database backup volume is included if it is part of the most recent database backup series. A copy storage pool volume is included if it is not empty and not marked *destroyed*.

If you are using a nonvirtual volume environment and issuing the MOVE DRMEDIA command, a blank location field means that the volumes are onsite and available to the server. This volume list can be used in periodic audits of the volume inventory of the courier and vault. You can use the list to collect the required volumes before recovering the server.

For virtual volumes, the location field contains the target server name.

```

begin RECOVERY.VOLUMES.REQUIRED

Volumes required for data base restore
  Location = OffsiteVault Inc.
  Device Class = LIB8MM
  Volume Name =
    TPBK08
  Location = OffsiteVault Inc.
  Device Class = LIB8MM
  Volume Name =
    TPBK06

Volumes required for storage pool restore
  Location = OffsiteVault Inc.
  Copy Storage Pool = CSTORAGEPF
  Device Class = LIB8MM
  Volume Name =
    TPBK05
    TPBK07

end RECOVERY.VOLUMES.REQUIRED

```

Figure 91. Volume Requirements Stanza

RECOVERY.DEVICES.REQUIRED

Provides details about the devices needed to read the backup volumes.

```

begin RECOVERY.DEVICES.REQUIRED

Purpose: Description of the devices required to read the
        volumes listed in the recovery volumes required stanza.

        Device Class Name: LIB8MM
        Device Access Strategy: Sequential
        Storage Pool Count: 2
            Device Type: 8MM
            Format: DRIVE
        Est/Max Capacity (MB): 4.0
            Mount Limit: 2
            Mount Wait (min): 60
        Mount Retention (min): 10
            Label Prefix: TIVSM
            Library: RLLIB
            Directory:
Last Update by (administrator): Bill
        Last Update Date/Time: 12/11/2000 10:18:34

end RECOVERY.DEVICES.REQUIRED

```

Figure 92. Volume and Device Requirements Stanzas

Disaster Recovery Mode Stanza

RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE

Contains a script with the commands needed to recover the server. You can use the script as a guide and run the commands from a command line. Or you can copy it to a file, modify it and the files it refers to, and run the script. You may need to modify the script because of differences between the original and the replacement systems. At the completion of these steps, client requests for file restores are satisfied directly from copy storage pool volumes.

The disaster recovery plan issues commands using the administrative client. The disaster recovery plan file issues commands using the administrative client. Ensure that the path to the administrative client is established before running the script. For example, set the shell variable `PATH` or update the scripts with the path specification for the administrative client.

The commands in the script do the following:

- Restore the server options, volume history, and device configuration information files.
- Invoke the scripts contained in the `LOGANDDDB.VOLUMES.CREATE` and `LOGANDDDB.VOLUMES.INSTALL` stanzas.

Attention: When this script runs, any log volumes or database volumes with the same names as those named in the plan are *removed* (see `LOGANDDDB.VOLUMES.CREATE` under “Create and Install Database and Recovery Log Volumes Stanzas” on page 540). In most disaster recoveries, the TSM server is installed on a new machine. When this script is run, it is assumed that there is no TSM data in the log or database volumes. TSM installation includes the creation of database and recovery log volumes. If you have created a log volume or a database volume (for example, for testing), and you want to preserve the contents, you must take some action such as renaming the volume or copying the contents before executing this script.

- Invoke the macros contained in the following stanzas:
 - `LICENSE.REGISTRATION`
 - `COPYSTGPOOL.VOLUMES.AVAILABLE`
 - `COPYSTGPOOL.VOLUMES.DESTROYED`
 - `PRIMARY.VOLUMES.DESTROYED`.

To help understand the operations being performed in this script, see “Backup and Recovery Scenarios” on page 492.

To invoke this script, specify the following positional parameters:

- \$1 (the administrator ID)
- \$2 (the administrator password)
- \$3 (the server ID as specified in the `dsm.sys` file)

Note: The default location for `dsm.sys` is `/usr/tivoli/tsm/client/admin/bin`.

For example, to invoke this script using an administrator ID of `don`, password of `mox`, server name of `prodtsm`, enter the following command:

```
planprefix/RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE don mox prodtsm
```

For more information, see the entry for the recovery plan prefix in Table 29 on page 499.

```
begin RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script

#!/bin/ksh
set -x

# Purpose: This script contains the steps required to recover the server
# to the point where client restore requests can be satisfied
# directly from available copy storage pool volumes.
# Note: This script assumes that all volumes necessary for the restore have
# been retrieved from the vault and are available. This script assumes
# the recovery environment is compatible (essentially the same) as the
# original. Any deviations require modification to this script and the
# macros and shell scripts it runs. Alternatively, you can use this
# script as a guide, and manually execute each step.

if [ -z "$1" -o -z "$2" -o -z "$3" ]
then
  print "Specify the following positional parameters:"
  print "administrative client ID, password, and server ID."
  print "Script stopped."
  exit
fi
# Set the server working directory
cd /usr/tivoli/tsm/server/bin/

# Restore server options, volume history, device configuration files.
cp /prepare/DSMSERV.OPT.FILE \
  /usr/tivoli/tsm/server/bin/dsmserv.optx
cp /prepare/VOLUME.HISTORY.FILE \
  /usr/tivoli/tsm/server/bin/volhistory.txtx
cp /prepare/DEVICE.CONFIGURATION.FILE \
  /usr/tivoli/tsm/server/bin/devconfig.txtx

export DSMSERV_CONFIG=/usr/tivoli/tsm/server/bin/dsmserv.optx
export DSMSERV_DIR=/opt/admserv/bin
```

Figure 93. Disaster Recovery Mode Script (Part 1 of 2)

```

# Create and format log and database files.
/prepare/LOGANDB.VOLUMES.CREATE 2>&1 \
| tee /prepare/LOGANDB.VOLUMES.CREATE.log

# Initialize the log and database files.
/prepare/LOGANDB.VOLUMES.INSTALL 2>&1 \
| tee /prepare/LOGANDB.VOLUMES.INSTALL.log

# Restore the server database to latest version backed up per the
# volume history file.
/usr/tivoli/tsm/server/bin/dsmserv restore db todate=08/11/2000 totime=10:20:22

# Start the server.
nohup /usr/tivoli/tsm/server/bin/dsmserv &
print Please start new server console with command dsmadm -CONSOLE.
print Press enter to continue recovery script execution.
read pause

# Register Server Licenses.
dsmadm -id=$1 -pass=$2 -serv=$3 -ITEMCOMMIT
  -OUTFILE=/prepare/LICENSE.REGISTRATION.log
  macro /prepare/LICENSE.REGISTRATION.mac

# Tell Server these copy storage pool volumes are available for use.
# Recovery Administrator: Remove from macro any volumes not obtained from vault.
dsmadm -id=$1 -pass=$2 -serv=$3 -ITEMCOMMIT \
  -OUTFILE=/prepare/COPYSTGPOOL.VOLUMES.AVAILABLE.log \
  macro /prepare/COPYSTGPOOL.VOLUMES.AVAILABLE

# Volumes in this macro were not marked as 'offsite' at the time
# PREPARE ran. They were likely destroyed in the disaster.
# Recovery Administrator: Remove from macro any volumes not destroyed.
dsmadm -id=$1 -pass=$2 -serv=$3 -ITEMCOMMIT \
  -OUTFILE=/prepare/COPYSTGPOOL.VOLUMES.DESTROYED.log \
  macro /prepare/COPYSTGPOOL.VOLUMES.DESTROYED
# Mark primary storage pool volumes as ACCESS=DESTROYED.
# Recovery administrator: Remove from macro any volumes not destroyed.
dsmadm -id=$1 -pass=$2 -serv=$3 -ITEMCOMMIT \
  -OUTFILE=/prepare/PRIMARY.VOLUMES.DESTROYED.log \
  macro /prepare/PRIMARY.VOLUMES.DESTROYED

end RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script

```

Figure 93. Disaster Recovery Mode Script (Part 2 of 2)

Normal Mode Stanza

RECOVERY.SCRIPT.NORMAL.MODE

Contains a script with the commands needed to restore the server primary storage pools. You can use the script as a guide and run the commands from a command line. Or you can copy it to a file, modify it and the files it refers to, and run the script. You may need to modify the script because of differences between the original and the replacement systems.

The disaster recovery plan issues commands using the administrative client. The disaster recovery plan file issues commands using the administrative client. Ensure that the path to the administrative client is established before running the script. For example, set the shell variable `PATH` or update the scripts with the path specification for the administrative client.

At the completion of these steps, client requests for file restores are satisfied from primary storage pool volumes. Clients should also be able to resume file backup, archive, and migration functions.

This script invokes the script contained in the PRIMARY.VOLUMES.REPLACEMENT.CREATE stanza: It also invokes the macros contained in the following stanzas:

```
PRIMARY.VOLUMES.REPLACEMENT
STGPOOLS.RESTORE
```

To help understand the operations being performed in this script, see “Backup and Recovery Scenarios” on page 492.

To invoke this script, the following positional parameters must be specified:

- \$1 (the administrator ID)
- \$2 (the administrator password)
- \$3 (the server ID as specified in the dsm.sys file)

For example, to invoke this script using an administrator ID of *don*, password of *mox*, server name of *prodtsm*, enter the following command:

```
planprefix/RECOVERY.SCRIPT.NORMAL.MODE don mox prodtsm
```

For more information, see the entry for the recovery plan prefix in Table 29 on page 499.

```

begin RECOVERY.SCRIPT.NORMAL.MODE script
#!/bin/ksh
set -x

# Purpose: This script contains the steps required to recover the server
#          primary storage pools. This mode allows you to return the
#          copy storage pool volumes to the vault and to run the
#          server as normal.
# Note: This script assumes that all volumes necessary for the restore
#       have been retrieved from the vault and are available. This script
#       assumes the recovery environment is compatible (essentially the
#       same) as the original. Any deviations require modification to this
#       script and the macros and shell scripts it runs. Alternatively,
#       you can use this script as a guide, and manually execute each step.

if [ -z "$1" -o -z "$2" -o -z "$3" ]
then
  print "Specify the following positional parameters:"
  print "administrative client ID, password, and server ID."
  print "Script stopped."
  exit
fi

# Create replacement volumes in the primary storage pools (If any
# are implemented as disk but not logical volume.)
# Recovery administrator: Edit script for your replacement volumes.
/prepare/PRIMARY.VOLUMES.REPLACEMENT.CREATE 2>&1 \
| tee /prepare/PRIMARY.VOLUMES.REPLACEMENT.CREATE.log

# Define replacement volumes in the primary storage pools. Must
# have different name than original.
# Recovery administrator: Edit macro for your replacement volumes.
dsmadm -id=$1 -pass=$2 -serv=$3 -ITEMCOMMIT \
  -OUTFILE=/prepare/PRIMARY.VOLUMES.REPLACEMENT.log \
  macro /prepare/PRIMARY.VOLUMES.REPLACEMENT

# Restore the primary storage pools from the copy storage pools.
dsmadm -id=$1 -pass=$2 -serv=$3 -ITEMCOMMIT \
  -OUTFILE=/prepare/STGPOOLS.RESTORE.log \
  macro /prepare/STGPOOLS.RESTORE

end RECOVERY.SCRIPT.NORMAL.MODE script

```

Figure 94. Normal Mode Script

Create and Install Database and Recovery Log Volumes Stanzas LOGANddb.VOLUMES.CREATE

Contains a script with the commands needed to recreate the database and log volumes. You can use the script as a guide and issue the commands as needed from a command line, or you can copy it to a file, modify it, and run it. This script is invoked by the RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script.

The plan assumes that the volume formatting command (DSMFMT) resides in the same directory as the server executable indicated in the stanza SERVER.REQUIREMENTS.

```

begin LOGANDB.VOLUMES.CREATE script
#!/bin/ksh
set -x
# Purpose: Create log and database volumes.
# Recovery Administrator: Run this to format server log and
# database volumes.
print Remove database volume /usr/tivoli/tsm/server/bin/db01x.
rm -f /usr/tivoli/tsm/server/bin/db01x

print Create database volume /usr/tivoli/tsm/server/bin/db01x 12M
/usr/tivoli/tsm/server/bin/dsmfmt -m -db /usr/tivoli/tsm/server/bin/db01x 12M

print Remove database volume /usr/tivoli/tsm/server/bin/db02x.
rm -f /usr/tivoli/tsm/server/bin/db02x

print Create database volume /usr/tivoli/tsm/server/bin/db02x 8M
/usr/tivoli/tsm/server/bin/dsmfmt -m -db /usr/tivoli/tsm/server/bin/db02x 8

print Remove log volume /usr/tivoli/tsm/server/bin/lg01x.
rm -f /usr/tivoli/tsm/server/bin/lg01x

print Create log volume /usr/tivoli/tsm/server/bin/lg01x 12M
/usr/tivoli/tsm/server/bin/dsmfmt -m -log /usr/tivoli/tsm/server/bin/lg01x 12M

print Remove log volume /usr/tivoli/tsm/server/bin/lg02x.
rm -f /usr/tivoli/tsm/server/bin/..lg02x

print Create log volume /usr/tivoli/tsm/server/bin/lg02x 8M
/usr/tivoli/tsm/server/bin/dsmfmt -m -log /usr/tivoli/tsm/server/bin/lg02x 8

end LOGANDB.VOLUMES.CREATE script

```

Figure 95. Create Database and Recovery Log Volumes Stanza

LOG.VOLUMES

Contains the names of the log volumes to be initialized. The contents of this stanza must be placed into a separate file to be used by the LOGANDB.VOLUMES.INSTALL script.

```

begin LOG.VOLUMES
/usr/tivoli/tsm/server/bin/lg01x
/usr/tivoli/tsm/server/bin/lg02x

end LOG.VOLUMES

```

Figure 96. Recovery Log Volumes Stanza

DB.VOLUMES

Contains the names of the database volumes to be initialized. The contents of this stanza must be placed into a separate file to be used by the LOGANDB.VOLUMES.INSTALL script.

```

begin DB.VOLUMES

/usr/tivoli/tsm/server/bin/db01x
/usr/tivoli/tsm/server/bin/db02x

end DB.VOLUMES

```

Figure 97. Database Volume Stanza

LOGANDB.VOLUMES.INSTALL

Contains a script with the commands required to initialize the database and log volumes. This script is invoked by the RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script.

```

begin LOGANDB.VOLUMES.INSTALL script

#!/bin/ksh
set -x

# Purpose: Initialize the log and database volumes.
# Recovery Administrator: Run this to initialize an server.

/usr/tivoli/tsm/server/bin/dsmserv install \
  2 FILE:/prepare/LOG.VOLUMES \
  2 FILE:/prepare/DB.VOLUMES

end LOGANDB.VOLUMES.INSTALL script

```

Figure 98. Install Database and Recovery Log Volumes Stanza

License Registration Stanza

LICENSE.REGISTRATION

Contains a macro to register your server licenses. This macro is invoked by the RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script.

```

begin LICENSE.REGISTRATION macro

/* Purpose: Register the Server licenses by specifying the names */
/* of the enrollment certificate files necessary to recreate the */
/* licenses that existed in the server. */
/* Recovery Administrator: Review licenses and add or delete licenses */
/* as necessary. */

register license file(50client.lic)
register license file(network.lic)
register license file(drm.lic)

end LICENSE.REGISTRATION macro

```

Figure 99. License Registration Macro Stanza

Copy Storage Pool Volumes Stanzas

COPYSTGPOOL.VOLUMES.AVAILABLE

Contains a macro to mark copy storage pool volumes that were moved offsite and then moved back onsite. This stanza does not include copy storage pool virtual volumes. You can use the information as a guide and issue the administrative commands, or you can copy it to a file, modify it, and run it. This macro is invoked by the RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script.

After a disaster, compare the copy storage pool volumes listed in this stanza with the volumes that were moved back onsite. You should remove entries from this stanza for any missing volumes.

```
begin COPYSTGPOOL.VOLUMES.AVAILABLE macro

/* Purpose: Mark copy storage pool volumes as available for use in recovery. */
/* Recovery Administrator: Remove any volumes that have not been obtained */
/* from the vault or are not available for any reason. */
/* Note: It is possible to use the mass update capability of the */
/* UPDATE command instead of issuing an update for each volume. However, */
/* the 'update by volume' technique used here allows you to select */
/* a subset of volumes to be processed. */

upd vol TPBK05 acc=READW wherestg=CSTORAGEEPF
upd vol TPBK07 acc=READW wherestg=CSTORAGEEPF

end COPYSTGPOOL.VOLUMES.AVAILABLE macro
```

Figure 100. Copy Storage Pool Volumes Available Stanza

COPYSTGPOOL.VOLUMES.DESTROYED

Contains a macro to mark copy storage pool volumes as unavailable if the volumes were onsite at the time of the disaster. This stanza does not include copy storage pool virtual volumes. These volumes are considered offsite and have not been destroyed in a disaster. You can use the information as a guide and issue the administrative commands from a command line, or you can copy it to a file, modify it, and run it. This macro is invoked by the RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script.

After a disaster, compare the copy storage pool volumes listed in this stanza with the volumes that were left onsite. If you have any of the volumes and they are usable, you should remove their entries from this stanza.

```

begin COPYSTGPOOL.VOLUMES.DESTROYED macro

/* Purpose: Mark destroyed copy storage pool volumes as unavailable.      */
/* Volumes in this macro were not marked as 'offsite' at the time the    */
/* PREPARE ran. They were likely destroyed in the disaster.              */
/* Recovery Administrator: Remove any volumes that were not destroyed.    */

end COPYSTGPOOL.VOLUMES.DESTROYED macro

```

Figure 101. Copy Storage Pool Volumes Destroyed Stanza

Primary Storage Volumes Stanzas

PRIMARY.VOLUMES.DESTROYED

Contains a macro to mark primary storage pool volumes as *destroyed* if the volumes were onsite at the time of disaster. You can use the information as a guide and run the administrative commands from a command line, or you can copy it to a file, modify it, and run it. This macro is invoked by the RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script.

During recovery, compare the primary storage pool volumes listed in this stanza with the volumes that were onsite. If you have any of the volumes and they are usable, remove their entries from the stanza.

This stanza does not include primary storage pool virtual volumes. These volumes are considered offsite and have not been destroyed in a disaster.

```

begin PRIMARY.VOLUMES.DESTROYED macro

/* Purpose: Mark primary storage pool volumes as ACCESS=DESTROYED.      */
/* Recovery administrator: Delete any volumes listed here                 */
/* that you do not want to recover.                                       */
/* Note: It is possible to use the mass update capability of the          */
/* UPDATE command instead of issuing an update for each volume. However*/
/* the 'update by volume' technique used here allows you to select       */
/* a subset of volumes to be marked as destroyed.                        */

upd vol /usr/tivoli/tsm/server/bin/bk02 acc=DESTROYED wherestg=BACKUPPOOL
upd vol /usr/tivoli/tsm/server/bin/bk01x acc=DESTROYED wherestg=BACKUPPOOL
upd vol /usr/tivoli/tsm/server/bin/bk03 acc=DESTROYED wherestg= BACKUPPOOLF
upd vol BACK4X acc=DESTROYED wherestg=BACKUPPOOLT

end PRIMARY.VOLUMES.DESTROYED macro

```

Figure 102. Primary Storage Volumes Destroyed Stanza

PRIMARY.VOLUMES.REPLACEMENT.CREATE

Contains a script with the commands needed to recreate the primary disk storage pool volumes. You can use the script as a guide and run the commands from a command line, or

you can copy the script to a file, modify it, and run it. This script is invoked by the `RECOVERY.SCRIPT.NORMAL.MODE` script.

The plan file assumes that the volume formatting program (`DSMFMT`) resides in the same directory as the server executable indicated in the stanza `SERVER.REQUIREMENTS`.

The `SET DRMPLANVPOSTFIX` command adds a character to the end of the names of the original volumes listed in this stanza. This character does the following:

- Improves retrievability of volume names that require renaming in the stanzas. Before using the volume names, change these names to new names that are valid for the device class and valid on the replacement system.
- Generates a new name that can be used by the replacement server. Your naming convention must take into account the appended character.

Notes:

1. Replacement primary volume names must be different from any other original volume name or replacement name.
2. The `RESTORE STGPOOL` command restores storage pools on a logical basis. There is no one-to-one relationship between an original volume and its replacement.
3. There will be entries for the same volumes in `PRIMARY.VOLUMES.REPLACEMENT`.

This stanza does not include primary storage pool virtual volumes, because these volumes are considered offsite and have not been destroyed in a disaster.

```
begin PRIMARY.VOLUMES.REPLACEMENT.CREATE script

#!/bin/ksh
set -x

# Purpose: Create replacement volumes for primary storage pools that
# use device class DISK.
# Recovery administrator: Edit this section for your replacement
# volume names. New name must be unique, i.e. different from any
# original or other new name.

print Replace /usr/tivoli/tsm/server/bin/bk02 DISK 16M in BACKUPPOOL
/usr/tivoli/tsm/server/bin/dsmfmt -m -data /usr/tivoli/tsm/server/bin/bk02@ 16

print Replace /usr/tivoli/tsm/server/bin/bk01x DISK 5M in BACKUPPOOL
/usr/tivoli/tsm/server/bin/dsmfmt -m -data /usr/tivoli/tsm/server/bin/bk01x@ 5

end PRIMARY.VOLUMES.REPLACEMENT.CREATE script
```

Figure 103. Primary Storage Volumes Replacement Stanza

PRIMARY.VOLUMES.REPLACEMENT

Contains a macro to define primary storage pool volumes to the server. You can use the macro as a guide and run the administrative commands from a command line, or you can copy it to a file, modify it, and execute it. This macro is invoked by the `RECOVERY.SCRIPT.NORMAL.MODE` script.

Primary storage pool volumes with entries in this stanza have at least one of the following three characteristics:

1. Original volume in a storage pool whose device class was DISK.
2. Original volume in a storage pool with MAXSCRATCH=0.
3. Original volume in a storage pool and volume scratch attribute=no.

The SET DRMPLANVPOSTFIX command adds a character to the end of the names of the original volumes listed in this stanza. This character does the following:

- Improves the retrievability of volume names that must be renamed in the stanzas. Before using the volume names, change these names to new names that are valid for the device class on the replacement system.
- Generates a new name that can be used by the replacement server. Your naming convention must take into account the appended character.

Notes:

1. Replacement primary volume names must be different from any other original volume name or replacement name.
2. The RESTORE STGPOOL command restores storage pools on a logical basis. There is no one-to-one relationship between an original volume and its replacement.
3. There could be entries for the same volume in PRIMARY.VOLUMES.REPLACEMENT.CREATE and PRIMARY.VOLUMES.REPLACEMENT if the volume has a device class of DISK.

This stanza does not include primary storage pool virtual volumes. These volumes are considered offsite and have not been destroyed in a disaster.

```
begin PRIMARY.VOLUMES.REPLACEMENT macro

/* Purpose: Define replacement primary storage pool volumes for either: */
/* 1. Original volume in a storage pool whose device class was DISK. */
/* 2. Original volume in a storage pool with MAXSCRATCH=0. */
/* 3. Original volume in a storage pool and volume scratch=no. */
/* Recovery administrator: Edit this section for your replacement */
/* volume names. New name must be unique, i.e. different from any */
/* original or other new name. */

/* Replace /usr/tivoli/tsm/server/bin/bk02 DISK 16M in BACKUPPOOL */
def vol BACKUPPOOL /usr/tivoli/tsm/server/bin/bk02@ acc=READW

/* Replace /usr/tivoli/tsm/server/bin/bk01x DISK 5M in BACKUPPOOL */
def vol BACKUPPOOL /usr/tivoli/tsm/server/bin/bk01x@ acc=READW

/* Replace /usr/tivoli/tsm/server/bin/bk03 FILES 4M in BACKUPPOOLF */
def vol BACKUPPOOLF /usr/tivoli/tsm/server/bin/bk03@ acc=READW

/* Replace BACK4X COOL8MM 0M in BACKUPPOOLT */
def vol BACKUPPOOLT BACK4X@ acc=READW

end PRIMARY.VOLUMES.REPLACEMENT macro
```

Figure 104. Primary Storage Volumes Replacement Stanza

Storage Pools Restore Stanza STGPOOLS.RESTORE

Contains a macro to restore the primary storage pools. You can use it as a guide and execute the administrative commands from a command line. You can also copy it to a file, modify it, and execute it. This macro is invoked by the RECOVERY.SCRIPT.NORMAL.MODE script.

This stanza does not include primary storage pool virtual volumes. These volumes are considered offsite and have not been destroyed in a disaster.

```
begin STGPOOLS.RESTORE macro

/* Purpose: Restore the primary storage pools from copy storage pool(s). */
/* Recovery Administrator: Delete entries for any primary storage pools */
/* that you do not want to restore. */

restore stgp ARCHIVEPOOL
restore stgp BACKUPPOOL
restore stgp BACKUPPOOLF
restore stgp BACKUPPOOLT
restore stgp SPACEMGPOL

end STGPOOLS.RESTORE macro
```

Figure 105. Storage Pools Restore Stanza

Configuration Stanzas VOLUME.HISTORY.FILE

Contains a copy of the volume history information when the recovery plan was created. The DSMSEV RESTORE DB command uses the volume history file to determine what volumes are needed to restore the database. It is used by the RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script.

The following rules determine where to place the volume history file at restore time:

- If the server option file contains VOLUMEHISTORY options, the server uses the fully qualified file name associated with the first entry. If the file name does not begin with a directory specification (for example, '.' or '/'), the server uses the prefix *volhprefix*.
- If the server option file does not contain VOLUMEHISTORY options, the server uses the default name *volhprefix* followed by *drmvolh.txt*. For example, if *volhprefix* is */usr/tivoli/tsm/server/bin/*, the file name is */usr/tivoli/tsm/server/bin/drmvolh.txt*.

Note: The *volhprefix* is set based on the following:

- If the environmental variable DSMSEV_DIR has been defined, it is used as the *volhprefix*.
- If the environmental variable DSMSEV_DIR has not been defined, the directory where the server is started from is used as the *volhprefix*.

If a fully qualified file name was not specified in the server options file for the VOLUMEHISTORY option, the server adds it to the DSMSERV.OPT.FILE stanza.

```
begin VOLUME.HISTORY.FILE
*****
*
*           Tivoli Storage Manager Sequential Volume Usage History
*           Updated 02/11/2000 10:20:34
*
*   Operation      Volume  Backup Backup Volume Device      Volume
*   Date/Time      Type    Series Oper.  Seq  Class Name  Name
*****
2000/08/11 10:18:43 STGNEW      0      0      0 COOL8MM  BACK4X
2000/08/11 10:18:43 STGNEW      0      0      0 FILES    BK03
2000/08/11 10:18:46 STGNEW      0      0      0 LIB8MM   TPBK05
* Location for volume TPBK06 is: 'Ironvault Inc.'
2000/08/11 10:19:23 BACKUPFULL  1      0      1 LIB8MM   TPBK06
2000/08/11 10:20:03 STGNEW      0      0      0 LIB8MM   TPBK07
2000/08/11 10:20:22 BACKUPINCR  1      1      1 LIB8MM   TPBK08
end VOLUME.HISTORY.FILE
```

Figure 106. Volume History File Stanza

DEVICE.CONFIGURATION.FILE

Contains a copy of the server device configuration information when the recovery plan was created. The DSMSERV RESTORE DB command uses the device configuration file to read the database backup volumes. It is used by the RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE script.

At recovery time, you may need to modify this stanza. You must update the device configuration information if the hardware configuration at the recovery site has changed. Examples of changes requiring updates to the configuration information are:

- Different device names
- Use of a manual library instead of an automated library
- For automated libraries, the requirement to manually place the database backup volumes in the automated library and update the configuration information to identify the element within the library. This allows the server to locate the required database backup volumes.

For details, see “Updating the Device Configuration File” on page 475.

The following rules determine where the device configuration file is placed at restore time:

- If the server options file contains DEVCONFIG entries, the server uses the fully qualified file name associated with the first entry. If the specified file name does not begin with a directory specification (for example, ‘.’ or ‘/’), the server adds the prefix *devcprefix*.
- If the server options file does not contain DEVCONFIG entries, the server uses the default name *devcprefix* followed by *drmdevc.txt*. For example, if *devcprefix* is */usr/tivoli/tsm/server/bin/*, the file name used by PREPARE is */usr/tivoli/tsm/server/bin/drmdevc.txt*.

Note: The *devcprefix* is set based on the following:

- If the environmental variable `DSMSERV_DIR` has been defined, it is used as the *devcprefix*.
- If the environmental variable `DSMSERV_DIR` has not been defined, the directory where the server is started from is used as the *devcprefix*.

If a fully qualified file name was not specified for the `DEVCONFIG` option in the server options file, the server adds it to the stanza `DSMSERV.OPT.FILE`.

```
begin DEVICE.CONFIGURATION.FILE

/* Tivoli Storage Manager Device Configuration */
DEFINE DEVCLASS COOL8MM DEVTYPE=8MM FORMAT=DRIVE MOUNTLIMIT=1 MOUNTWAIT=60
MOUNTRETENTION=60 PREFIX=TIVSM LIBRARY=ITSML
DEFINE DEVCLASS FILES DEVTYPE=FILE MAXCAPACITY=4096K MOUNTLIMIT=2 +
DIRECTORY=/usr/tivoli/tsm/server/bin/
DEFINE DEVCLASS FILESSM DEVTYPE=FILE MAXCAPACITY=100K MOUNTLIMIT=2 +
DIRECTORY=/usr/tivoli/tsm/server/bin/
DEFINE DEVCLASS LIB8MM DEVTYPE=8MM FORMAT=DRIVE MOUNTLIMIT=1 MOUNTWAIT=60+
MOUNTRETENTION=60 PREFIX=TIVSM LIBRARY=RLLIB
end DEVICE.CONFIGURATION.FILE
```

Figure 107. Device Configuration File Stanza

DSMSERV.OPT.FILE

Contains a copy of the server options file. This stanza is used by the `RECOVERY.SCRIPT.DISASTER.RECOVERY.MODE` script.

Note: The following figure contains text strings that are too long to display in hardcopy or softcopy publications. The long text strings have a plus symbol (+) at the end of the string to indicate that they continue on the next line.

The disaster recovery plan file adds the `DISABLESCHEDS` option to the server options file and sets it to `YES`. This option disables administrative and client schedules while the server is being recovered. After the server is recovered, you can enable scheduling by deleting the option or setting it to `NO` and then restarting the server.

```
begin DSMSERV.OPT.FILE

* Server options file located in /usr/tivoli/tsm/server/bin/dsmserv.optx
TCPPOrt 1509
VOLUMEHISTORY /usr/tivoli/tsm/server/bin/volhistory.txtx
DEVCONFIG /usr/tivoli/tsm/server/bin/devconfig.txtx
* The following option was added by PREPARE.
DISABLESCHEDS YES

end DSMSERV.OPT.FILE
```

Figure 108. Server Options File Stanza

License Information Stanza

LICENSE.INFORMATION

Contains a copy of the latest license audit results and the server license terms.

```
begin LICENSE.INFORMATION
                                Last License Audit: 12/30/2000 10:25:34
                                Registered Client Nodes: 1
                                Licensed Client Nodes: 51
                                Are network connections in use ?: Yes
                                Are network connections licensed ?: Yes
Are Open Systems Environment clients registered ?: No
  Are Open Systems Environment clients licensed ?: No
    Is space management in use ?: No
    Is space management licensed ?: No
    Is disaster recovery manager in use ?: Yes
    Is disaster recovery manager licensed ?: Yes
  Are Server-to-Server Virtual Volumes in use ?: No
  Are Server-to-Server Virtual Volumes licensed ?: Yes
    Is Advanced Device Support required ?: No
    Is Advanced Device Support licensed ?: No
    Server License Compliance: Valid
end LICENSE.INFORMATION
```

Figure 109. License Information Stanza

Machine Files Stanza

MACHINE.GENERAL.INFORMATION

Provides information for the server machine (for example, machine location). This stanza is included in the plan file if the machine information is saved in the database using the DEFINE MACHINE with ADSMSERVER=YES.

```
begin MACHINE.GENERAL.INFORMATION
Purpose: General information for machine DSMSRV1.
      This is the machine that contains DSM server DSM.
      Machine Name: DSMSRV1
      Machine Priority: 1
        Building: 21
        Floor: 2
        Room: 2749
      Description: DSM Server for Branch 51
      Recovery Media Name: DSMSRVIMAGE
end MACHINE.GENERAL.INFORMATION
```

Figure 110. Machine General Information Stanza

MACHINE.RECOVERY.INSTRUCTIONS

Provides the recovery instructions for the server machine. This stanza is included in the plan file if the machine recovery instructions are saved in the database.

```
begin MACHINE.RECOVERY.INSTRUCTIONS
  Purpose: Recovery instructions for machine DSMSRV1.

  Primary Contact:
    Jane Smith (wk 520-000-0000 hm 520-001-0001)
  Secondary Contact:
    John Adams (wk 520-000-0001 hm 520-002-0002)

end MACHINE.RECOVERY.INSTRUCTIONS
```

Figure 111. Machine Recovery Instructions Stanza

MACHINE.RECOVERY.CHARACTERISTICS

Provides the hardware and software characteristics for the server machine. This stanza is included in the plan file if the machine characteristics are saved in the database.

```
begin MACHINE.CHARACTERISTICS
  Purpose: Hardware and software characteristics of machine DSMSRV1.

  devices
    aio0          Defined          Asynchronous I/O
    bb10          Available 00-0J    GXT150 Graphics Adapter
    bus0          Available 00-00    Microchannel Bus
    DSM1509bk02   Available          N/A
    DSM1509db01x Available          N/A
    DSM1509lg01x Available          N/A
    en0           Defined          Standard Ethernet Network Interface

end MACHINE.CHARACTERISTICS
```

Figure 112. Machine Recovery Characteristics Stanza

MACHINE.RECOVERY.MEDIA

Provides information about the media (for example, boot media) needed for rebuilding the machine that contains the server. This stanza is included in the plan file if recovery media information is saved in the database and it has been associated with the machine that contains the server.

```
begin MACHINE.RECOVERY.MEDIA.REQUIRED
Purpose: Recovery media for machine DSMSRV1.
Recovery Media Name: DSMSRVIMAGE
      Type: Boot
Volume Names: mkssy1
      Location: IRONMNT
      Description: mksysb image of server machine base OS
      Product: mksysb
Product Information: this mksysb was generated by AIX 4.3
end MACHINE.RECOVERY.MEDIA.REQUIRED
```

Figure 113. Machine Recovery Media Stanza

VI — Appendixes



External Media Management Interface Description

This appendix contains Programming Interface information for the interface that Tivoli Storage Manager provides to external media management programs. To use the interface, you must first define an EXTERNAL-type TSM library that represents the media manager. You do not define drives, label volumes, or check in media to TSM. See “Configuring Libraries Controlled by Media Manager Programs” on page 69. Refer to your media manager’s documentation set for that product’s setup information.

The interface consists of request description strings that Tivoli Storage Manager sends and response strings that the external program sends.

The details of the request types and the required processing are described in the sections that follow. The request types are:

- Initialization of the external program
- Begin Batch
- End Batch
- Volume Query
- Volume Eject
- Volume Release
- Volume Mount
- Volume Dismount

The responses can be right-padded with any number of white-space characters.

The *libraryname* passed in a request must be returned in the response. The *volume* specified in an eject request or a query request must be returned in the response. The *volume* specified in a mount request (except for ‘SCRTCH’) must be returned in the response. When ‘SCRTCH’ is specified in a mount request, the actual volume mounted must be returned.

CreateProcess Call

The server creates two anonymous uni-directional pipes and maps them to **stdin** and **stdout** during the **CreateProcess** call. According to Microsoft Developer Network documentation, if a standard handle has been redirected to refer to a file or a pipe, the handle can only be used by the ReadFile and WriteFile functions. This precludes normal C functions such as **gets** or **printf**. Since the server will never terminate the external program process, it is imperative that the external program recognize a read or write failure on the pipes and exit the process. In addition, the external program should exit the process if it reads an unrecognized command.

The external program may obtain values for the read and write handles using the following calls:

```
readPipe=GetStdHandle(STD_INPUT_HANDLE) and writePipe=GetStdHandle(STD_OUTPUT_HANDLE)
```

Processing during Server Initialization

Ensure that the external media management program cooperates with the server during the server's initialization. For each external library defined to the server, the following must occur during server initialization:

1. The server loads the external program (**CreateProcess**) in a newly created process and creates pipes to the external program.
2. The server sends an initialization request description string, in text form, into the standard input (**stdin**) stream of the external program. The server waits for the response.
3. When the external process completes the request, the process must write an initialization response string, in text form, into its standard output (**stdout**) stream.
4. The server closes the pipes.
5. When the agent detects that the pipes are closed, it performs any necessary cleanup and calls the **stdlib** exit routine.

Processing for Mount Requests

To process the mount request:

1. The server loads the external program in a newly created process and creates pipes to the external program.
2. The server sends an initialization request description string (in text form) into the standard input (**stdin**) stream of the external program. The server waits for the response.
3. When the external process completes the request, the process must write an initialization response string (in text form) into its standard output (**stdout**) stream.
4. The server sends the MOUNT request (**stdin**).
5. The agent sends the MOUNT response (**stdout**).
6. The agent waits.
7. The server sends the DISMOUNT request (**stdin**).
8. The agent sends the DISMOUNT response (**stdout**), performs any necessary cleanup, and calls the **stdlib** exit routine.

Processing for Release Requests

To process the release request:

1. The server loads the external program in a newly created process and creates pipes to the external program.
2. The server sends an initialization request description string (in text form) into the standard input (**stdin**) stream of the external program. The server waits for the response.
3. When the external process completes the request, the process must write an initialization response string (in text form) into its standard output (**stdout**) stream.

-
4. The server sends the RELEASE request (**stdin**).
 5. The agent sends the RELEASE response (**stdout**), performs any necessary cleanup, and calls the **stdlib** exit routine.

Processing for Batch Requests

Batch processing is done during MOVE MEDIA, MOVE DRMEDIA, and QUERY MEDIA command execution when performed on volumes in external libraries. The move commands will cause a QUERY to be issued for a volume. If the QUERY indicates that the volume is in the library, a subsequent EJECT for that volume is issued. As the move commands can match any number of volumes, a QUERY and an EJECT request is issued for each matching volume.

The QUERY MEDIA command will result in QUERY requests being sent to the agent. During certain types of processing, TSM may need to know if a volume is present in a library. The external agent should verify that the volume is physically present in the library.

1. The server loads the external program in a newly created process and creates pipes to the external program.
2. The server sends an initialization request description string (in text form) into the standard input (**stdin**) stream of the external program. The server waits for the response.
3. When the external process completes the request, the process must write an initialization response string (in text form) into its standard output (**stdout**) stream.
4. The server sends the BEGIN BATCH request (**stdin**).
5. The agent sends the BEGIN BATCH response (**stdout**).
6. The server sends 1 to n volume requests ($n > 1$). These can be any number of QUERY or EJECT requests. For each request, the agent will send the applicable QUERY response or EJECT response.
7. The server sends the END BATCH request (**stdin**).
8. The agent sends the END BATCH response (**stdout**), performs any necessary cleanup, and calls the **stdlib** exit routine.

Error Handling

If the server encounters an error during processing, it will close the **stdin** and **stdout** streams to the agent exit. The agent will detect this when it tries to read from **stdin** or write to **stdout**. If this occurs, the agent performs any necessary cleanup and calls the **stdlib** exit routine.

If the code for any response (except for EJECT and QUERY) is not equal to SUCCESS, TSM does not proceed with the subsequent steps. After the agent sends a non-SUCCESS return code for any response, the agent will perform any necessary cleanup and call the **stdlib** exit routine.

However, even if the code for EJECT or QUERY requests is not equal to SUCCESS, the agent will continue to send these requests.

If the server gets an error while trying to write to the agent, it will close the pipes, perform any necessary cleanup, and terminate the current request.

Begin Batch Request

The format of the Begin Batch Request is:

```
BEGIN BATCH
```

Format of the external program response:

```
BEGIN BATCH COMPLETE, RESULT=resultCode
```

where:

resultCode

One of the following:

- SUCCESS
- INTERNAL_ERROR

End Batch Request

The End Batch Request is sent by TSM to indicate that no more requests are to be sent by the external library manager for the current process. The external agent must send the End Batch Response and end by using the **stdlib** exit routine.

The format of the End Batch Request is:

```
END BATCH
```

Format of the external program response:

```
END BATCH COMPLETE, RESULT=resultCode
```

where:

resultCode

One of the following:

- SUCCESS
- INTERNAL_ERROR

Volume Query Request

The format of the Volume Query Request is:

```
QUERY libraryname volume
```

where:

libraryname

Specifies the name of the EXTERNAL library as defined to TSM.

volume

Specifies the volume name to be queried.

Format of the external program response:

```
QUERY libraryname volume COMPLETE, STATUS=statusValue, RESULT=resultCode
```

where:

libraryname

Specifies the name of the EXTERNAL library as defined to TSM.

volume

Specifies the volume name queried.

resultCode

One of the following:

- SUCCESS
- LIBRARY_ERROR
- VOLUME_UNKNOWN
- VOLUME_UNAVAILABLE
- CANCELLED
- TIMED_OUT
- INTERNAL_ERROR

If *resultCode* is not SUCCESS, the exit must return *statusValue* set to UNDEFINED. If *resultCode* is SUCCESS, STATUS must be one of the following values:

- IN_LIBRARY
- NOT_IN_LIBRARY

IN_LIBRARY means that the volume is currently in the library and available to be mounted.

NOT_IN_LIBRARY means that the volume is not currently in the library.

Initialization Requests

When the server is started, the server sends an initialization request to the external media management program for each EXTERNAL library. The external program must process this request to ensure that the external program is present, functional, and ready to process requests. If the initialization request is successful, TSM informs its operators that the external program reported its readiness for operations. Otherwise, TSM reports a failure to its operators.

TSM does not attempt any other type of operation with that library until an initialization request has succeeded. The server sends an initialization request first. If the initialization is successful, the request is sent. If the initialization is not successful, the request fails. The external media management program can detect whether the initialization request is being sent by itself or with another request by detecting end-of-file on the **stdin** stream. When end-of-file is detected, the external program must end by using the **stdlib** exit routine (not the **return** call).

When a valid response is sent by the external program, the external program must end by using the **exit** routine.

Format of the request:

INITIALIZE *libraryname*

where *libraryname* is the name of the EXTERNAL library as defined to TSM.

Format of the external program response:

INITIALIZE *libraryname* COMPLETE, RESULT=*resultcode*

where:

libraryname

Specifies the name of the EXTERNAL library as defined to TSM.

resultcode

One of the following:

- SUCCESS
- NOT_READY
- INTERNAL_ERROR

Volume Eject Request

The format of the Volume Eject Request is:

```
EJECT libraryname volume 'location info'
```

where:

libraryname

Specifies the name of the EXTERNAL library as defined to TSM.

volume

Specifies the volume to be ejected.

'location info'

Specifies the location information associated with the volume from the TSM inventory. It is delimited with single quotation marks. This information is passed without any modification from the TSM inventory. The customer is responsible for setting its contents with the appropriate UPDATE MEDIA or UPDATE VOLUME command before the move command is invoked. Set this field to some target location value that will assist in placing the volume after it is ejected from the library. It is suggested that the external agent post the value of this field to the operator.

Format of the external program response:

```
EJECT libraryname volume COMPLETE, RESULT=resultCode
```

where:

libraryname

Specifies the name of the EXTERNAL library as defined to TSM.

volume

Specifies the ejected volume.

resultCode

One of the following:

- SUCCESS
- LIBRARY_ERROR
- VOLUME_UNKNOWN
- VOLUME_UNAVAILABLE
- CANCELLED
- TIMED_OUT
- INTERNAL_ERROR

Volume Release Request

When the server returns a volume to scratch status, the server starts the external media management program, issues a request to initialize, then issues a request to release a volume.

The external program must send a response to the release request. No matter what response is received from the external program, TSM returns the volume to scratch. For this reason, TSM and the external program can have conflicting information on which volumes are scratch. If an error occurs, the external program should log the failure so that the external library inventory can be synchronized later with TSM. The synchronization can be a manual operation.

Format of the request:

```
RELEASE libraryname volname
```

where:

libraryname

Specifies the name of the EXTERNAL library as defined to TSM.

volname

Specifies the name of the volume to be returned to scratch (released).

Format of the external program response:

```
RELEASE libraryname volname COMPLETE, RESULT=resultcode
```

where:

libraryname

Specifies the name of the EXTERNAL library as defined to TSM.

volname

Specifies the name of the volume returned to scratch (released).

resultcode

One of the following:

- SUCCESS
- VOLUME_UNKNOWN
- VOLUME_UNAVAILABLE
- INTERNAL_ERROR

Volume Mount Request

When the server requires a volume mount, the server starts the external media management program, issues a request to initialize, then issues a request to mount a volume. The external program is responsible for verifying that this request is coming from TSM and not from an unauthorized system.

The volume mounted by the external media management program must be a tape with a standard IBM label that matches the external volume label. When the external program completes the mount request, the program must send a response. If the mount was successful, the external program must remain active. If the mount failed, the external program must end immediately by using the **stdlib** exit routine.

Format of the request:

```
MOUNT libraryname volname accessmode devicetypes timelimit userid  
volumenumber 'location'
```

where:

libraryname

Specifies the name of the EXTERNAL library as defined to TSM.

volname

Specifies the actual volume name if the request is for an existing volume. If a scratch mount is requested, the *volname* is set to SCRTCH.

accessmode

Specifies the access mode required for the volume. Possible values are READONLY and READWRITE.

devicetypes

Specifies a list of device types that can be used to satisfy the request for the volume and the FORMAT specified in the device class. The most preferred device type is first in the list. Items are separated by commas, with no intervening spaces. Possible values are:

- 3480
- 3480XF
- 3490E
- 3570
- 3590
- 3590E
- 4MM_DDS1
- 4MM_DDS1C
- 4MM_DDS2
- 4MM_DDS2C
- 4MM_DDS3
- 4MM_DDS3C
- 4MM_DDS4
- 4MM_DDS4C
- 4MM_HP_DDS4
- 4MM_HP_DDS4C
- 8MM_8200
- 8MM_8205
- 8MM_8500
- 8MM_8500C
- 8MM_8900
- 8MM_AIT
- 8MM_AITC
- 8MM_ELIANT
- 8MM_M2
- DLT_2000
- DLT_4000
- DLT_7000
- DLT_8000
- DTF
- GENERICTAPE
- IBM_QIC4GBC
- LTO_ULTRIUM
- OPT_RW_650MB
- OPT_RW_1300MB
- OPT_RW_2600MB
- OPT_RW_5200MB
- OPT_WORM_650MB

- OPT_WORM_1300MB
- OPT_WORM12_5600MB
- OPT_WORM12_12000MB
- OPT_WORM14_14800MB
- QIC_12GBC
- QIC_20GBC
- QIC_25GBC
- QIC_30GBC
- QIC_50GBC
- QIC_IBM1000
- QIC_525
- QIC_5010C
- REMOVABLEFILE
- STK_9490
- STK_9840
- STK_9940
- STK_SD3

timelimit

Specifies the maximum number of minutes that the server waits for the volume to be mounted. If the mount request is not completed within this time, the external manager responds with the result code TIMED_OUT.

userid

Specifies the user ID of the process that needs access to the drive.

volumenumber

For non-optical media, the *volumenumber* is 1. For optical media, the *volumenumber* is 1 for side A, 2 for side B.

'location'

Specifies the value of the location field from the TSM inventory (for example, 'Room 617 Floor 2'). One blank character is inserted between the volume number and the left single quotation mark in the location information. If no location information is associated with a volume, nothing is passed to the exit. If no volume information exists, the single quotation marks are not passed. Also, if volume information is passed, then probably the volume has been ejected from the library and needs to be returned to the library before the mount operation can proceed. The location information should be posted by the agent so that the operator can obtain the volume and return it to the library.

Format of the external program response:

MOUNT *libraryname volname* COMPLETE ON *specialfile*, RESULT=*resultcode*

where:

libraryname

Specifies the name of the EXTERNAL library as defined to TSM.

volname

Specifies the name of the volume mounted for the request.

specialfile

The fully qualified path name of the device special file for the drive in which the volume was mounted. If the mount request fails, the value should be set to /dev/null.

The external program must ensure that the special file is closed before the response is returned to the server.

resultcode

One of the following:

- SUCCESS
- DRIVE_ERROR
- LIBRARY_ERROR
- VOLUME_UNKNOWN
- VOLUME_UNAVAILABLE
- CANCELLED
- TIMED_OUT
- INTERNAL_ERROR

Volume Dismount Request

When a successful mount operation completes, the external process must wait for a request to dismount the volume. When the dismount operation completes, the external program must send a response to the server.

After the dismount response is sent, the external process ends immediately by using the **stdlib** exit routine.

Format of the request:

DISMOUNT *libraryname volname*

where:

libraryname

Specifies the name of the EXTERNAL library as defined to TSM.

volname

Specifies the name of the volume to be dismounted.

Format of the external program response:

DISMOUNT *libraryname volname* COMPLETE, RESULT=*resultcode*

where:

libraryname

Specifies the name of the EXTERNAL library as defined to TSM.

volname

Specifies the name of the volume dismounted.

resultcode

One of the following:

- SUCCESS
- DRIVE_ERROR
- LIBRARY_ERROR
- INTERNAL_ERROR

B

User Exit and File Exit Receivers

This appendix contains samples of the user exit receiver for event logging. The data structure of the user exit receivers also applies to the file exit receivers. To use one of these exits with TSM, you must specify the corresponding server option (FILEEXIT, FILETEXTEXT, or USEREXIT) in the server options file. You can also use TSM commands to control event logging. See “Logging Tivoli Storage Manager Events to Receivers” on page 418 and *Administrator’s Reference* for details. The samples for the C, H, and make files are shipped with the server code in the `/usr/lpp/admserv/bin` directory.

Notes:

1. Use caution in modifying these exits. A user exit abend will bring down the server.
2. The file specified in the file exit option will continue to grow unless you prune it.

Sample User Exit Declarations

```
/******  
 * Name:          userExitSample.h  
 * Description:   Declarations for a user-exit  
 * Environment:   AIX 4.1.4+ on RS/6000  
*****/  
  
#ifndef _H_USEREXITSAMPLE  
#define _H_USEREXITSAMPLE  
  
#include <stdio.h>  
#include <sys/types.h>  
  
/***** Do not modify below this line. *****/  
  
#define BASE_YEAR      1900  
  
typedef short int16;  
typedef int int32;  
  
/* uchar is usually defined in <sys/types.h> */  
/* DateTime Structure Definitions - TSM representation of a timestamp*/  
  
typedef struct  
{  
    uchar  year; /* Years since BASE_YEAR (0-255) */  
    uchar  mon;  /* Month (1 - 12) */  
    uchar  day;  /* Day (1 - 31) */  
    uchar  hour; /* Hour (0 - 23) */  
    uchar  min;  /* Minutes (0 - 59) */  
    uchar  sec;  /* Seconds (0 - 59) */  
} DateTime;  
  
/*****  
 * Some field size definitions (in bytes) *  
*****/  
  
#define MAX_SERVERNAME_LENGTH  64  
#define MAX_NODE_LENGTH        64  
#define MAX_COMMNAME_LENGTH    16  
#define MAX_OWNER_LENGTH       64  
#define MAX_HL_ADDRESS         64  
#define MAX_LL_ADDRESS         32  
#define MAX_SCHED_LENGTH       30  
#define MAX_DOMAIN_LENGTH      30  
#define MAX_MSGTEXT_LENGTH     1600
```

Figure 114. Sample User Exit Declarations (Part 1 of 3)

```

/*****
 * Event Types (in e1EventRecvData.eventType) *
 *****/

#define TSM_SERVER_EVENT      0x03 /* Server Events */
#define TSM_CLIENT_EVENT     0x05 /* Client Events */

/*****
 * Application Types (in e1EventRecvData.applType) *
 *****/

#define TSM_APPL_BACKARCH    1 /* Backup or Archive client */
#define TSM_APPL_HSM        2 /* Space manage client */
#define TSM_APPL_API        3 /* API client */
#define TSM_APPL_SERVER     4 /* Server (ie. server to server)*/

/*****
 * Event Severity Codes (in e1EventRecvData.sevCode) *
 *****/

#define TSM_SEV_INFO        0x02 /* Informational message. */
#define TSM_SEV_WARNING    0x03 /* Warning message. */
/*
#define TSM_SEV_ERROR      0x04 /* Error message. */
#define TSM_SEV_SEVERE    0x05 /* Severe error message. */
#define TSM_SEV_DIAGNOSTIC 0x06 /* Diagnostic message. */
#define TSM_SEV_TEXT      0x07 /* Text message. */

/*****
 * Data Structure of Event that is passed to the User-Exit. *
 * This data structure is the same for a file generated via *
 * FILEEXIT option on the server. *
 *****/

typedef struct evRdata
{
    int32    eventNum;          /* the event number. */
    int16    sevCode;          /* event severity. */
    int16    applType;        /* application type (hsm, api, etc)*/
    int32    sessId;          /* session number */
    int32    version;         /* Version number of this structure (1)*/
    int32    eventType;       /* event type
                               * (TSM_CLIENT_EVENT, TSM_SERVER_EVENT)*/
}

```

Figure 114. Sample User Exit Declarations (Part 2 of 3)

```

    DateTime timeStamp;          /* timestamp for event data.          */
    uchar  serverName[MAX_SERVERNAME_LENGTH+1]; /* server name          */
    uchar  nodeName[MAX_NODE_LENGTH+1]; /* Node name for session */
    uchar  commMethod[MAX_COMMNAME_LENGTH+1]; /* communication method */
    uchar  ownerName[MAX_OWNER_LENGTH+1]; /* owner                */
    uchar  hlAddress[MAX_HL_ADDRESS+1]; /* high-level address    */
    uchar  llAddress[MAX_LL_ADDRESS+1]; /* low-level address     */
    uchar  schedName[MAX_SCHED_LENGTH+1]; /* schedule name if applicable*/
    uchar  domainName[MAX_DOMAIN_LENGTH+1]; /* domain name for node  */
    uchar  event[MAX_MSGTEXT_LENGTH]; /* event text            */
} elEventRecvData;

/*****
 * Size of the Event data structure *
 *****/

#define ELEVENTRECVDATA_SIZE      sizeof(elEventRecvData)

/*****
 * User Exit EventNumber for Exiting *
 *****/

#define USEREXIT_END_EVENTNUM      1822 /* Only user-exit receiver to exit*/
#define END_ALL_RECEIVER_EVENTNUM 1823 /* All receivers told to exit */

/*****
 *** Do not modify above this line. ***
 *****/

/***** Additional Declarations *****/

#endif

```

Figure 114. Sample User Exit Declarations (Part 3 of 3)

Sample User Exit Program

```

/*****
 * Name:          userExitSample.c
 * Description:   Example user-exit program invoked by the TSM V3 Server
 * Environment:   AIX 4.1.4+ on RS/6000
 *****/

#include <stdio.h>
#include "userExitSample.h"

/*****
 *** Do not modify below this line. ***
 *****/

extern void adsmV3UserExit( void *anEvent );

/*****
 *** Main ***
 *****/

int main(int argc, char *argv[])
{
/* Do nothing, main() is never invoked, but stub is needed */
exit(0); /* For picky compilers */
} /* End of main() */

/*****
 * Procedure: adsmV3UserExit
 * If the user-exit is specified on the server, a valid and
 * appropriate event causes an e1EventRecvData structure (see
 * userExitSample.h) to be passed to adsmV3UserExit that returns a void.
 * INPUT : A (void *) to the e1EventRecvData structure
 * RETURNS: Nothing
 *****/

void adsmV3UserExit( void *anEvent )
{
/* Typecast the event data passed */
e1EventRecvData *eventData = (e1EventRecvData *)anEvent;

```

Figure 115. Sample User Exit Program (Part 1 of 2)

```

/*****
*** Do not modify above this line. ***
*****/

if( ( eventData->eventNum == USEREXIT_END_EVENTNUM ) ||
    ( eventData->eventNum == END_ALL_RECEIVER_EVENTNUM ) )
{
    /* Server says to end this user-exit. Perform any cleanup, *
     * but do NOT exit() !!!                                     */
    return;
}

/* Field Access: eventData->.... */
/* Your code here ... */

return; /* For picky compilers */
} /* End of adsmV3UserExit() */

```


Figure 115. Sample User Exit Program (Part 2 of 2)

Readable Text File Exit (FILETEXTEXIT) Format

If you specify the readable text file exit (FILETEXTEXIT), each logged event is written to a fixed-size, readable line. The following table presents the format of the output. Fields are separated by blank spaces.

Table 32. Readable Text File Exit (FILETEXTEXIT) Format

Column	Description
0001-0006	Event number (with leading zeros)
0008-0010	Severity code number
0012-0013	Application type number
0015-0023	Session ID number
0025-0027	Event structure version number
0029-0031	Event type number
0033-0046	Date/Time (YYYYMMDDHHmmSS)
0048-0111	Server name (right padded with spaces)
0113-0176	Node name
0178-0193	Communications method name
0195-0258	Owner name
0260-0323	High-level internet address (n.n.n.n)
0325-0356	Port number from high-level internet address
0358-0387	Schedule name
0389-0418	Domain name
0420-2019	Event text
2020-2499	Unused spaces
2500	New line character



Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
Information Enabling Requests
Dept. M13
5600 Cottle Road
San Jose CA 95193-0001
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Programming Interface

This publication is intended to help the customer plan for and manage the Tivoli Storage Manager server.

This publication also documents intended Programming Interfaces that allow the customer to write programs to obtain the services of Tivoli Storage Manager. This information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

Programming interface information

End of Programming interface information

Trademarks

The following terms are trademarks of the International Business Machines Corporation in the United States or other countries or both:

ACF/VTAM	Extended Services
AD/Cycle	IBM
Advanced Peer-to-Peer Networking	IBMLink
AFS	MVS/ESA
AIX	MVS/SP
Application System/400	OpenEdition
APPN	Operating System/2
AS/400	Operating System/400
AT	OS/2
C/370	OS/390
Common User Access	OS/400
CUA	POWERparallel
DATABASE 2	RACF
DB2	RISC System/6000
DFDSM	RS/6000
DFS	SP
DFSMS/MVS	System/370
DFSMS/VM	System/390
DFSMSdss	SystemView
DFSMShsm	VM/ESA
DFSMSrmm	VTAM
ES/9000	XT
ESCON	

Lotus, Lotus 1–2–3, Lotus Approach, Lotus Domino and Lotus Notes are trademarks of Lotus Development Corporation in the United States and/or other countries.

Tivoli and Tivoli ADSM are trademarks of Tivoli Systems Inc. in the United States and/or other countries.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States and/or other countries.

UNIX is a registered trademark of the Open Group in the United States and/or other countries.

Java and all Java-based trademarks and logos are trademarks of Sun Microsystems, Inc. in the United States and/or other countries.

Intel is a registered trademark of the Intel Corporation in the United States and/or other countries.

Other company, product, and service names may be trademarks or service marks of others.

Glossary

The terms in this glossary are defined as they pertain to the Tivoli Storage Manager library. If you do not find the term you need, refer to the IBM Software Glossary on the Web at this URL: www.ibm.com/ibm/terminology/. You can also refer to *IBM Dictionary of Computing*, New York: McGraw-Hill, 1994.

This glossary may include terms and definitions from:

- The *American National Standard Dictionary for Information Systems*, ANSI X3.172-1990, copyright (ANSI). Copies may be purchased from the American National Standards Institute, 11 West 42nd Street, New York 10036.
- The *Information Technology Vocabulary*, developed by Subcommittee 1, Joint Technical Committee 1, of the International Organization for Standardization and the International Electrotechnical Commission (ISO/IEC JTC2/SC1).

A

absolute

A value for the backup copy group mode indicating that a file is considered for incremental backup even if the file has not changed since the last backup. See also *mode*. Contrast with *modified*.

access mode

An attribute of a storage pool or a storage volume attribute that specifies whether TSM can write to or read from the storage pool or storage volume. The access mode can be read/write, read-only, or unavailable. Volumes in primary storage pools can also have an access mode of destroyed. Volumes in copy storage pools can also have an access mode of offsite.

accounting facility

A facility that records statistics about client session activity.

accounting records

Files that record session resource usage at the end of each client session.

activate

The process of validating the contents of a policy set and copying the policy set to the ACTIVE policy set.

active policy set

The policy set that contains the policy rules currently in use by all client nodes assigned to the policy domain. The active policy set is the policy set that was most recently activated for the policy domain. See *policy set*.

active version

The most recent backup copy of a file stored by TSM. Such a file is not eligible for deletion until a backup process detects that the user has either replaced the file with a newer version, or has deleted the file from the workstation. Contrast with *inactive version*.

activity log

A log that records normal activity messages generated by the server. These messages include information about server and client operations, such as the start time of sessions or device I/O errors. Each message includes a message ID, date and time stamp, and a text description. The number of days to retain messages in the activity log can be specified.

administrative client

A program that runs on a file server, workstation, or mainframe that allows administrators to control and monitor the server through administrator commands. Contrast with *backup-archive client*.

administrative command schedule

A database record that describes the planned processing of an administrative command during a specific time period. See also *client schedule*.

administrative privilege class

A level of authority granted to an administrator of TSM. The privilege class determines which TSM administrative tasks the administrator can perform. For example, an administrator with system privilege class can perform any administrative task. See *system privilege class*, *policy privilege class*, *storage privilege class*, *operator privilege class*, and *analyst privilege class*.

administrative session

A period of time in which an administrator user ID communicates with a server to perform administrative tasks. Contrast with *client node session*.

administrator

A user who has been registered to the server. Administrators can be authorized to one or more of the following administrative privilege classes: system, policy, storage, operator, or analyst. Administrators can use the administrative commands and queries allowed by their privileges.

Advanced Interactive Executive (AIX)

An operating system used in the RISC System/6000® computers. The AIX operating system is the IBM implementation of the UNIX operating system.

Advanced Peer-to-Peer Networking® (APPN®)

An extension to the LU6.2 peer orientation for end-user services. See *SNA LU6.2* and *Systems Network Architecture*.

Advanced Program-to-Program Communication (APPC)

An implementation of the SNA/SDLC LU6.2 protocol that allows interconnected systems to communicate and share the processing of programs. See *SNA LU6.2*, *Systems Network Architecture*, and *Common Programming Interface Communications*.

AFS

Andrew file system.

aggregate file

A file, stored in one or more storage pools, consisting of a group of logical files packaged together. See *logical file* and *physical file*.

AIX

Advanced Interactive Executive.

analyst privilege class

An administrative privilege class that allows an administrator to reset statistics.

Andrew file system (AFS)

A distributed file system developed for UNIX operating systems.

API

Application program interface.

APPC

Advanced Program-to-Program Communication.

application client

One of the Tivoli Data Protection for application programs installed on a system. The Tivoli Storage Manager server provides backup services to these clients.

application program interface

A set of functions that applications running on a client platform can call to store, query, and retrieve objects from TSM storage.

APPN

Advanced Peer-to-Peer Networking.

archive

A function that allows users to copy one or more files to a storage pool for long-term storage. Archive copies may be accompanied by descriptive information and may be retrieved by archive date, by file name, or by description. Contrast with *retrieve*.

archive copy

A user file that has been archived to a TSM storage pool.

archive copy group

A policy object containing attributes that control the generation, destination, and expiration of archive files. An archive copy group belongs to a management class.

archive retention grace period

The number of days that TSM retains an archive copy when the server is unable to rebind the file to an appropriate management class.

AS/400®

Application System/400®.

assigned capacity

The portion of available space that can be used to store database or recovery log information. See also *available space*.

association

(1) The defined relationship between a client node and a client schedule. An association identifies the name of a schedule, the name of the policy domain to which the schedule belongs, and the name of a client node that performs scheduled operations. (2) On a configuration manager, the defined relationship between a profile and an object such as a policy domain. Profile associations define the configuration information that will be distributed to managed servers when they subscribe to the profile.

audit

The process of checking for logical inconsistencies between information that the server has and the actual condition of the system. TSM has processes for auditing volumes, the database, libraries, and licenses. For example, in auditing a volume TSM checks for inconsistencies between information about backed up or archived files stored in the database and actual data associated with each backup version or archive copy in server storage.

authentication

The process of checking a user's password before allowing that user access to the server. Authentication can be turned on or off by an administrator with system privilege.

authority

The right granted to a user to perform tasks with TSM servers and clients. See *administrative privilege class*.

autochanger

A small multislot tape device that has a mechanism that automatically puts tape cartridges into the tape drive or drives. Also called *medium* or *media changer*, or a *library*.

availability management

Managing recovery from relatively common computer system outages such as a disk drive head crash. Recovery is often accomplished by using disk mirroring and other forms of RAID technology, or by maintaining onsite backup copies of data.

available space

The amount of space, in megabytes, that is available to the database and recovery log. This space can be used to extend the capacity of the database or recovery log, or to provide sufficient free space before a volume is deleted from the database or recovery log.

awk

In AIX, a pattern-matching program for processing text files. With the DRM product, you can use an awk script to break up the disaster recovery plan file into usable parts.

B

background process

A server process that runs in the background, allowing the administrative session to be used for other work.

backup

The process of copying information for safekeeping. TSM has processes for backing up user files, the TSM database, and storage pools. For example, users can back up one or more files to a storage pool to ensure against loss of data. Contrast with *restore*. See also *database backup series* and *incremental backup*.

backup-archive client

A program that runs on a workstation or file server and provides a means for users to back up, archive, restore, and retrieve files. Contrast with *administrative client*.

backup copy

A user file that has been backed up to a TSM storage pool.

backup copy group

A policy object containing attributes that control the generation, destination, and expiration of backup files. A backup copy group belongs to a management class.

backup retention grace period

The number of days that TSM retains a backup version after the server is unable to rebind the file to an appropriate management class.

backup series

See *database backup series*.

backup set

A portable, consolidated group of active backup files for a single client. Generation of a backup set is possible for selected backup-archive clients that obtain services from a server at the latest software level.

backup version

A file, directory, or file space that a user has backed up, which resides in TSM server storage. There may be more than one backup version of a file in the storage pool, but at most only one is an active backup version. See *active version* and *inactive version*.

binding

The process of associating a file with a management class name. See *rebinding*.

boot media

Media that contains operating system and other files essential to running a workstation or server.

buffer

Storage used to compensate for differences in the data rate flow, when transferring data from one device to another.

buffer pool

Temporary space used by the server to hold database or recovery log pages. See *database buffer pool* and *recovery log buffer pool*.

C

cache

The process of leaving a duplicate copy on random access media when the server migrates a file to another storage pool in the hierarchy.

CARTRIDGE

On TSM servers that support it, a device class that is used to categorize tape devices that support tape cartridges, such as the 3490 Magnetic Tape Subsystem.

cartridge system tape (CST)

The base tape cartridge media used with 3480 or 3490 Magnetic Tape Subsystems. When specified as a media type in TSM, CST identifies standard length tape. Contrast with *enhanced capacity cartridge system tape*.

central scheduler

A function that allows an administrator to schedule client operations and administrative commands. The operations can be scheduled to occur periodically or on a specific date. See *client schedule* and *administrative command schedule*.

CID

Configuration Installation and Distribution.

client

A program running on a PC, workstation, file server, LAN server, or mainframe that requests services of another program, called the server. The following types of clients can obtain services from a TSM server: administrative client, application client, API client, backup-archive client, HSM client (also known as space manager client), and host server.

Client Access™/400®

A software product that supports advanced program-to-program communications (APPC) in the DOS, OS/2, and Microsoft Windows environments and provides a set of end user services.

client domain

The set of drives, file systems, or volumes selected by a backup-archive client user during a backup or archive operation.

client migration

The process of copying a file from a client node to TSM storage and replacing the file with a stub file on the client node. The process is controlled by the user and by space management attributes in the management class. See also *space management*.

client node

A file server or workstation on which the backup-archive client program has been installed, which has been registered to the server.

client node session

A period of time in which a user communicates with a server to perform backup, restore, archive, retrieve, migrate, or recall requests. Contrast with *administrative session*.

client options file

A file that a client can change, containing a set of processing options that identify the server, communication method, and options for backup, archive, hierarchical storage management, and scheduling. Also called the *dsm.opt* file.

client polling scheduling mode

A client/server communication technique where the client queries the server for work.

client schedule

A database record that describes the planned processing of a client operation during a specific time period. The client operation can be a backup, archive, restore, or retrieve operation, a client operating system command, or a macro. See also *administrative command schedule*.

client/server

A system architecture in which one or more programs (clients) request computing or data services from another program (server).

client system options file

A file, used on UNIX clients, containing a set of processing options that identify the TSM servers to be contacted for services. This file also specifies communication methods and options for backup, archive, hierarchical storage management, and scheduling. Also called the *dsm.sys* file. See also *client user options file*.

client user options file

A user-created file, used on UNIX clients, containing a set of processing options that identify the server, communication method, backup and archive options, space management options, and scheduling options. Also called the *dsm.opt* file. See also *client system options file*.

closed registration

A registration process in which an administrator must register workstations as client nodes with the server. Contrast with *open registration*.

cluster

In a Microsoft environment, a set of independent computer systems, called nodes, that are set up to work together as a single system. The cluster helps ensure that critical applications and resources remain available.

collocation

A process that attempts to keep all data belonging to a single client node or a single client file space on a minimal number of sequential access media volumes within a storage pool. Collocation can reduce the number of volumes that must be accessed when a large amount of data must be restored.

code page

An assignment of graphic characters and control function meanings to all code points; for example, assignment of characters and meanings to 256 code points for an 8-bit code, assignment of characters and meanings to 128 code points for a 7-bit code. Describes how binary values are mapped to human-readable characters.

commit

To make changes permanent in the database. Changes made to the database files are not permanent until they are committed.

Common Programming Interface Communications (CPI-C)

A programming interface that allows program-to-program communication using SNA LU6.2. See also *Systems Network Architecture*.

Common User Access® (CUA®)

Guidelines for the dialog between a human and a workstation or terminal. One of the three Systems Application Architecture areas.

communication manager

A component of OS/2 that allows a workstation to connect to a host computer and use the host resources as well as the resources of other personal computers to which the workstation is attached, either directly or through a host.

communication method

The method used by a client and server for exchanging information.

communication protocol

A set of defined interfaces that allow computers to communicate with each other.

compression

The process of saving storage space by eliminating empty fields or unnecessary data in a file. In TSM, compression can occur at a workstation before files are backed up or archived to server storage. On some types of tape drives, hardware compression can be used.

Configuration Installation and Distribution (CID)

The term used to describe the capability of IBM products for automated installation. CID-enabled products are capable of unattended, remote installation.

configuration manager

One TSM server that distributes configuration information to other TSM servers (called managed servers) via profiles. Configuration information can include policy and schedules. See *managed server* and *profile*.

copy group

A policy object that contains attributes that control the generation, destination, and expiration of backup and archive files. There are two kinds of copy groups: backup and archive. Copy groups belong to management classes. See also *frequency*, *destination*, *mode*, *serialization*, *retention*, and *version*.

copy status

The status of volume copies defined to the database or recovery log. The copy status can be synchronized, stale, off-line, or undefined.

copy storage pool

A named set of volumes that contains copies of files that reside in primary storage pools. Copy storage pools are used only to back up the data stored in primary storage pools. A copy storage pool cannot be a destination for a backup copy group, an archive copy group, or a management class (for space-managed files). See *primary storage pool* and *destination*.

CPI-C

Common Programming Interface Communications.

CST

Cartridge system tape.

CUA

Common User Access.

D**daemon**

In the AIX operating system, a program that runs unattended to perform a standard service. Some daemons are triggered automatically to perform their tasks; others operate periodically.

daemon process

In the AIX operating system, a process begun by the root user or by the root shell that can be stopped only by the root user. Daemon processes generally provide services that must be available at all times, such as sending data to a printer.

damaged file

A physical file for which TSM has detected read errors.

DASD

Direct access storage device.

database

A collection of information about all objects managed by the server, including policy management objects, users and administrators, and client nodes.

database audit

A utility that checks for and optionally corrects inconsistent database references.

database backup series

One full backup of the database, plus up to 32 incremental backups made since that full backup. Each full backup that is run starts a new database backup series. A backup series is identified with a number.

database backup trigger

A set of criteria that defines when and how database backups are run automatically. The criteria determine how often the backup is run, whether the backup is a full or incremental backup, and where the backup is stored.

database buffer pool

Storage that is used as a cache to allow database pages to remain in memory for long periods of time, so that the server can make continuous updates to pages without requiring input or output (I/O) operations from external storage.

database dump

The action performed by the DSMSERV DUMPDB utility (DMPADSM command on AS/400), which copies TSM database entries to media for later reload in case a catastrophic error occurs.

database load

The action performed by the DSMSERV LOADDB utility (LODADSM command on AS/400), which copies TSM database entries from media to a newly installed database.

database snapshot

A function of TSM that backs up the entire TSM database to media that can be taken off-site. The database snapshot does not interrupt any database backup series and cannot have incremental database backups associated with it. Contrast with *full backup*.

database volume

A volume that has been assigned to the TSM database.

dataserver

See *Tape Library Dataserver*.

data set

See *linear data set*.

DDM

Distributed Data Management.

default management class

A management class assigned to a policy set, which is used to govern backed up or archived files when a user does not specify a management class for a file.

deletion exit

For MVS or VM, an installation-wide exit that informs a tape management system or operator that the server has deleted a sequential access media volume from its database.

delimiter

(1) A character used to indicate the beginning and end of a character string. (2) A character that groups or separates words or values in a line of input.

desktop client

The group of backup-archive clients supported by TSM that includes clients on OS/2, DOS, Windows, Apple, and Novell NetWare operating systems.

destination

A copy group or management class attribute that specifies the primary storage pool to which a client file will be backed up, archived, or migrated.

device class

A named group of storage devices with common characteristics. Each device class has a unique name and represents a device type of disk, file, optical disk, or tape.

device configuration file

A file that contains information about defined device classes, and, on some TSM servers, defined libraries and drives. The file can be created by using a TSM command or by using an option in the server options file. The information is a copy of the device configuration information in the TSM database.

device driver

A collection of subroutines that control the interface between I/O device adapters and the processor.

device type

A category of storage device. Each device class is categorized with one of the supported device types, for example, DISK or CARTRIDGE.

direct access storage device (DASD)

A device in which access time is effectively independent of the location of the data.

disaster recovery

Recovery from catastrophic interruptions of computer systems, such as loss of the system location because of natural events. Backup data is kept offsite to protect against such catastrophes.

Disaster Recovery Manager

See *Tivoli Disaster Recovery Manager*.

disaster recovery plan

A document that contains information about how to recover computer systems if a disaster occurs. The Tivoli Disaster Recovery Manager (DRM) product allows you to create the plan for a TSM server. The plan is a file that contains information about the software and hardware used by the TSM server, and the location of recovery media.

DISK

A device class that is defined by TSM at installation. It is used to categorize disk drives, such as internal disk drives or 3390 DASD.

disk operating system (DOS)

An operating system used in IBM PC, PS/2, and compatible computers.

Distributed Data Management (DDM)

A feature of the System Support Program Product that allows an application program (client) to use server program functions to work on files that reside in a remote system.

DLL

Dynamic link library.

DLT

Digital linear tape.

domain

See *policy domain* or *client domain*.

DOS

Disk operating system.

drive

A device used to read and write data on a medium such as a magnetic disk, optical disk, or tape.

DRM

A short name for Tivoli Disaster Recovery Manager.

drive mapping

The correlation of drive names between a TSM server and a TSM storage agent.

dsm.opt file

See *client options file* and *client user options file*.

dsmserv.opt

See *server options file*.

dsm.sys file

See *client system options file*.

dynamic

A copy group serialization value that specifies that TSM accepts the first attempt to back up or archive a file regardless of whether the file is modified during the backup or archive process. See also *serialization*. Contrast with *shared dynamic*, *shared static*, and *static*.

dynamic link library

A file containing executable code and data bound to a program at load time or run time, rather than during linking. The code and data in a dynamic link library can be shared by several applications simultaneously.

E**ECCST**

Enhanced capacity cartridge system tape.

enhanced capacity cartridge system tape (ECCST)

Cartridge system tape with increased capacity that can only be used with 3490E tape subsystems. Contrast with *cartridge system tape*.

enterprise configuration

A capability that allows the administrator to distribute the configuration of one TSM server to other servers using server-to-server communication. See *configuration manager*, *managed server*, *profile*, and *subscription*.

enterprise logging

The sending of events from TSM servers to a designated event server. The event server routes the events to designated receivers, such as to a user exit. See also *event*.

error log

A character file written on random access media that contains information about errors detected by the server or client.

estimated capacity

The available space, in megabytes, of a storage pool.

Ethernet

A data link protocol and LAN that interconnects personal computers and workstations via coaxial cable.

event

(1) An administrative command or a client operation that is scheduled to be run using TSM scheduling. (2) A message that a TSM server or client issues. Messages can be logged using TSM event logging.

event record

A database record that describes actual status and results for events.

event server

A server to which other servers can send events for logging. The event server routes the events to any receivers that are enabled for the sending server's events.

exclude

The process of identifying files or directories in an include-exclude list to prevent these objects from being backed up whenever a user or schedule issues an incremental or selective backup operation, or to prevent these objects from being migrated off the client node via Tivoli Space Manager space management.

exclude-include list

See *include-exclude list*.

exit

To execute an instruction within a portion of a computer program in order to terminate the execution of that portion.

exit machine

On a VM server, a virtual machine that runs the mount and deletion installation-wide exits on VM systems.

expiration

The process by which files are identified for deletion because their expiration date or retention period has passed. Backed up or archived files are marked expired by TSM based on the criteria defined in the backup or archive copy group.

expiration date

On MVS, VM, and VSE servers, a device class attribute used to notify tape management systems of the date when TSM no longer needs a tape volume. The date is placed in the tape label so that the tape management system does not overwrite the information on the tape volume before the expiration date.

export

The process of copying administrator definitions, client node definitions, policy definitions, server control information or file data to external media.

export/import facility

See *import/export facility*.

extend

The process of increasing the portion of available space that can be used to store database or recovery log information. Contrast with *reduce*.

F

failover

For a Microsoft cluster configuration, the process that occurs when one resource, for example a server, fails and operations are automatically taken over by another resource in the cluster.

file record extent

The extent of the file enumerated in number of records.

file space

A logical space in a client's storage that can contain a group of files. For clients on Windows systems, a file space is a logical partition that is identified by a volume label. For clients on systems such as AIX and UNIX, a file space can consist of any subset of directories and subdirectories stemming from a virtual mount point. Clients can restore, retrieve, or delete their file spaces from TSM server storage. TSM does not necessarily store all the files from a single file space together, but can identify all the files in server storage that came from a single file space.

File Transfer Protocol (FTP)

In TCP/IP, the protocol that makes it possible to transfer data among hosts and to use foreign hosts indirectly.

format

A device class attribute that specifies the recording format used to read or write to sequential access media such as tape.

frequency

A copy group attribute that specifies the minimum interval, in days, between incremental backups.

FSID

File space ID. A unique numeric identifier that the server assigns to a file space when it is stored in server storage.

FTP

File Transfer Protocol.

full backup

A function of TSM that copies the entire database. A full backup begins a new database backup series. Contrast with *incremental backup* and *database snapshot*. See *database backup series*.

fuzzy copy

A backup version or archive copy of a file that might not accurately reflect what is currently in the file because TSM backed up or archived the file while the file was being modified.

G

GUI

Graphical user interface.

H

HDA

Head-disk assembly.

head-disk assembly (HDA)

A field replaceable unit in a direct access storage device containing the disks and actuators.

hierarchical storage management (HSM) client

The Tivoli Space Manager program that runs on workstations to allow users to maintain free space on their workstations by migrating and recalling files to and from Tivoli Storage Manager storage. Synonymous with *space manager client*.

high migration threshold

A percentage of the storage pool capacity that identifies when TSM can start migrating files to the next available storage pool in the hierarchy. Contrast with *low migration threshold*. See *server migration*.

host server

The name for the system on which the Tivoli Data Protection for Workgroups program runs. The host server obtains scheduling services from Tivoli Storage Manager.

HP-UX

Hewlett-Packard UNIX operating system.

HSM client

Hierarchical storage management client. Also known as the space manager client.

import

The process of copying exported administrator definitions, client node definitions, policy definitions, server control information or file data from external media to a target server.

import/export facility

The facility that allows system administrators to copy definitions and file data from a source server to external media to move or copy information between servers. A subset of information can be imported to a target server from the external media.

inactive version

A backup version of a file for which a more recently backed-up version exists. Inactive backup versions are eligible for expiration processing according to the management class assigned to the file. Contrast with *active version*.

include-exclude file

On UNIX and Windows clients, a file containing statements that TSM uses to determine whether to back up or migrate certain files, and to determine the associated management classes to use for backup, archive, and space management. See *include-exclude list*.

include-exclude list

A group of include and exclude option statements that TSM uses. The exclude options identify files that should not be backed up or migrated off the client node. The include options identify files that are exempt from the exclusion rules, or assign a management class to a file or group of files for backup, archive, or space management services. The include-exclude list for a client may include option statements from the include-exclude file (for UNIX clients) or the client options file (for other clients), and from a client option set on the server.

incremental backup

(1) A function that allows users to back up files or directories that are new or have changed since the last incremental backup. With this function, users can back up files or directories from a client domain that are not excluded in the include-exclude list and that meet the requirements for frequency, mode, and serialization as defined in the backup copy group of the management class assigned to the files. Contrast with *selective backup*.
(2) A function of TSM that copies only the pages in the database that are new or changed since the last full or incremental backup of the database. Contrast with *full backup*. See *database backup series*.

internal mounting facility

On a VM server, a VM facility that allows the server to request tape mounts by sending a message to a mount operator. The message is repeated until the tape is mounted or until the mount wait time is exceeded.

inter-user communication vehicle (IUCV) facility

On a VM server, a VM communication method used to pass data between virtual machines and VM components.

IPX/SPX

Internetwork Packet Exchange/Sequenced Packet Exchange. IPX/SPX is Novell NetWare's communication protocol.

IUCV
Inter-user communication vehicle.

K

KB
Kilobyte.

kernel
The part of an operating system that performs basic functions such as allocating hardware resources.

kernel extension
A program that modifies parts of the kernel that can be customized to provide additional services and calls. See *kernel*.

kilobyte (KB)
1024 bytes.

L

LAN
Local area network.

LAN-free data transfer
The movement of client data directly from a client to a storage device over a SAN, rather than over the LAN.

length
A device class attribute that specifies the length of cartridge tape by specifying one of the following media types: CST for standard length tape or ECCST for double length tape.

library
(1) A repository for demountable recorded media, such as magnetic tapes. (2) For TSM, a collection of one or more drives, and possibly robotic devices (depending on the library type), which can be used to access storage volumes. (3) In the AS/400 system, a system object that serves as a directory to other objects. A library groups related objects, and allows the user to find objects by name.

library client
A TSM server that uses server-to-server communications when multiple TSM servers share a storage device to contact a library manager and request device services.

library manager
A TSM server that controls device operations when multiple TSM servers share a storage device. These operations include mount, dismount, volume ownership, and library inventory.

linear data set
A type of MVS data set that TSM uses for the database, the recovery log, and storage pools. The data set must be preallocated using VSAM IDCAMS and formatted by TSM for its use.

load
See *mount*.

local area network (LAN)
A network in which a set of devices are connected to one another for communication and that can be connected to a larger network.

logical file
A client file stored in one or more server storage pools, either by itself or as part of an aggregate file. See also *aggregate file* and *physical file*.

logical occupancy
The space required for the storage of logical files in a storage pool. Because logical occupancy does not include the unused space created when logical files are deleted from aggregates, it may be less than *physical occupancy*. See also *physical file* and *logical file*.

logical volume

(1) A portion of a physical volume that contains a filesystem. (2) For the TSM server, the combined space from all volumes defined to either the database or the recovery log. The database is one logical volume and the recovery log is one logical volume.

log pool size

The size of an area in memory used to store recovery log pages.

low migration threshold

A percentage of the storage pool capacity that specifies when TSM can stop the migration of files to the next storage pool. Contrast with *high migration threshold*. See *server migration*.

M

machine information

Details about the machine on which a client node resides.

macro file

A file that contains one or more administrative commands and that is run from an administrative client. Contrast with *TSM command script*.

managed object

A definition in the TSM database of a managed server that was distributed to the managed server by a configuration manager. In general, the definition cannot be modified locally on the managed server. When a managed server subscribes to a profile, all objects associated with that profile become managed objects in the database of the managed server. Objects can include policy, schedules, client options sets, server scripts, administrator registrations, and server and server group definitions.

managed server

A TSM server that receives configuration information from a configuration manager via subscription to one or more profiles. Configuration information can include definitions of objects such as policy and schedules. See *configuration manager*, *subscription*, and *profile*.

managed system

A client or server that requests services from the Tivoli Storage Manager server.

management class

A policy object that users can bind to each file to specify how the server manages the file. The management class can contain a backup copy group, an archive copy group, and space management attributes. The copy groups determine how the TSM server manages backup versions or archive copies of files. The space management attributes determine whether files are eligible for migration from space manager client nodes to TSM storage, and under what conditions. See also *copy group*, *binding* and *rebinding*.

mask

A pattern of characters that controls the keeping, deleting, or testing of positions of another pattern of characters or bits.

maximum extension

Specifies the maximum amount of storage space, in megabytes, that you can extend the database or recovery log.

maximum reduction

Specifies the maximum amount of storage space, in megabytes, that you can reduce the database or recovery log.

maximum utilization

The highest percentage of assigned capacity used by the database or recovery log.

MB

Megabyte.

megabyte (MB)

(1) For processor storage and real and virtual memory, 2^{20} or 1 048 576 bytes. (2) For disk storage capacity and transmission rates, 1 000 000 bytes.

migrate

(1) To move data from one storage pool to the storage pool specified as the next pool in the hierarchy. The process is controlled by the high and low migration thresholds for the first storage pool. See *high migration threshold* and *low migration threshold*. (2) To copy a file from a Tivoli Space Manager client node to TSM storage. Tivoli Space Manager replaces the file with a stub file on the client node. The process is controlled by the include-exclude list and by space management attributes in management classes.

migration

The process of moving data from one storage location to another. See *client migration* and *server migration*.

minidisk

A logical subdivision of a VM physical disk that provides storage on contiguous cylinders of DASD. On a VM server, a minidisk can be defined as a disk volume that can be used by the database, recovery log, or a storage pool.

mirroring

A feature that protects against data loss within the database or recovery log by writing the same data to multiple disks at the same time. Mirroring supports up to three exact copies of each database or recovery log volume.

mm

Millimeter.

mode

A copy group attribute that specifies whether to back up a file that has not been modified since the last time the file was backed up. See *modified* and *absolute*.

modified

A backup copy group mode value indicating that a file is considered for incremental backup only if it has changed since the last backup. A file is considered changed if the date, size, owner, or permissions have changed. See *mode*. Contrast with *absolute*.

Motif

A graphical user interface that performs window management and contains a high level toolkit for application program development. It provides an icon view of the UNIX file system. Also known as X-Windows/Motif or Motif X—Toolkit.

mount

To place a data medium (such as a tape cartridge) on a drive in a position to operate.

mount exit

On a VM server, an installation-wide exit (DSMMOUNT EXEC) that requests tape mounts on behalf of the server on VM systems.

mount limit

A device class attribute specifying the maximum number of volumes that can be simultaneously accessed from the same device class, that is, the maximum number of mount points. See *mount point*.

mount operator

On a VM server, a VM user ID that can receive tape mount messages from the server.

mount point

A logical drive through which TSM accesses volumes in a sequential access device class. For a device class with a removable media device type (for example, CARTRIDGE), a mount point is a logical drive associated with a physical drive. For a device class with the device type of FILE, a mount point is a logical drive associated with an I/O stream. The number of mount points for a device class is determined by the mount limit for that class. See *mount limit*.

mount request

A server request to mount a sequential access media volume so that data can be read from or written to the sequential access media.

mount retention period

A device class attribute that specifies the maximum number of minutes that the server retains a mounted sequential access media volume that is not being used before it dismounts the sequential access media volume.

mount wait period

A device class attribute that specifies the maximum number of minutes that the server waits for a sequential access volume mount request to be satisfied before canceling the request.

MSCS

Microsoft Cluster Server.

Multiple Virtual Storage (MVS)

One of the family of IBM operating systems for the System/370™ or System/390® processor, such as MVS/ESA™.

MVS

Multiple Virtual Storage.

N

Named Pipes

A communication protocol that is built into the Windows NT or OS/2 operating system. It can be used to establish communications between the TSM server and any TSM clients on the same system.

NetBIOS

Network Basic Input/Output System.

network adapter

A physical device, and its associated software, that enables a processor or controller to be connected to a network.

Network Basic Input/Output System (NetBIOS)

An operating system interface for application programs used on IBM personal computers that are attached to the IBM Token-Ring Network.

Network File System (NFS)

A protocol defined by Sun Microsystems that extends TCP/IP network file services. NFS permits remote node files to appear as though they are stored on a local workstation.

Networking Services/DOS (NS/DOS)

A software product that supports advanced program-to-program communications (APPC) in the DOS and Microsoft Windows 3.1 environments. With NS/DOS, communications applications on your workstation “talk to” partner applications on other systems that support APPC.

NFS

Network File System.

node

(1) A unique name used to identify a workstation to the server. See also *client node*. (2) In a Microsoft cluster configuration, one of the computer systems that make up the cluster. See *cluster*.

node privilege class

An administrative privilege class that allows a user to remotely access a Web backup-archive client with an administrative user ID and password. A user with node privilege can have client owner or client access authority for a specific client node or for all clients in a policy domain.

notify operator

A VM user ID that specifies an operator who receives messages about severe errors and abnormal conditions.

O

object

A collection of data managed as a single entity.

offsite recovery media

Media that is kept at a different location to ensure its safety if a disaster occurs at the primary location of the computer system. The media contains data necessary to recover the TSM server and clients. The offsite recovery media manager, which is part of DRM, identifies recovery media to be moved offsite and back onsite, and tracks media status.

offsite volume

A removable media volume that is at a location where it cannot be mounted for use.

open registration

A registration process in which users can register their own workstations as client nodes with the server. Contrast with *closed registration*.

Operating System/2[®] (OS/2)

An operating system used in IBM PC AT[®], PS/2, and compatible computers.

operator privilege class

An administrative privilege class that allows an administrator to issue commands that control the operation of the server. This privilege class allows disabling or halting the server to perform maintenance, enabling the server, canceling server processes, and managing tape.

optical library

A storage device that houses optical disk drives and optical disks, and contains a mechanism for moving optical disks between a storage area and optical disk drives.

OS/2

Operating System/2.

OS/390[®]

Operating System/390.

OS/400[®]

Operating System/400[®].

owner

The owner of backup-archive files sent from a multiuser client node, such as AIX.

P

page

(1) A block of instructions, data, or both. (2) In TSM, a unit of space allocation within database volumes. (3) In a virtual storage system, a fixed block that has a virtual address and is transferred as a unit between real storage and auxiliary storage.

paging

(1) The action of transferring instructions, data, or both, between real storage and external page storage. (2) Moving data between memory and a mass storage device as the data is needed.

pattern-matching expression

A string expression that uses wildcard characters to specify one or more TSM objects. See also *wildcard character*.

physical file

A file, stored in one or more storage pools, consisting of either a single logical file, or a group of logical files packaged together (an aggregate file). See also *aggregate file* and *logical file*.

physical occupancy

The occupancy of physical files in a storage pool. This is the actual space required for the storage of physical files, including the unused space created when logical files are deleted from aggregates. See also *physical file*, *logical file*, and *logical occupancy*.

platform

The operating system environment in which a program runs.

policy domain

A policy object that contains policy sets, management classes, and copy groups that are used by a group of client nodes. See *policy set*, *management class*, and *copy group*.

policy privilege class

An administrative privilege class that allows an administrator to manage policy objects, register client nodes, and schedule client operations (such as backup services) for client nodes. Administrators can be authorized with unrestricted or restricted policy privilege.

policy set

A policy object that contains a group of management class definitions that exist for a policy domain. At any one time there can be many policy sets within a policy domain but only one policy set can be active. See *management class* and *active policy set*.

premigration

For an HSM client, the process of copying files that are eligible for migration to TSM storage, but leaving the original file intact on the local system.

primary storage pool

A named set of volumes that TSM uses to store backup versions of files, archive copies of files, and files migrated from HSM client nodes. A primary storage pool may be backed up to a copy storage pool. See *destination* and *copy storage pool*.

privilege class

A level of authority granted to an administrator of TSM . The privilege class determines which TSM administrative tasks the administrator can perform. For example, an administrator with system privilege class can perform any administrative task. See *system privilege class*, *policy privilege class*, *storage privilege class*, *operator privilege class*, and *analyst privilege class*.

profile

A named group of configuration information that can be distributed from a configuration manager when a managed server subscribes. Configuration information can include registered administrators, policy, client schedules, client option sets, administrative schedules, server command macros, server definitions, and server group definitions. See *configuration manager* and *managed server*.

protection status

A device class attribute that specifies whether to update the RACF® profile to identify which users have access to cartridge tapes associated with this device class on MVS servers.

Q**QIC**

Quarter-inch cartridge (a type of magnetic tape media).

R**random access media**

Any volume accessed in a nonsequential manner. In TSM, volumes are accessed in a nonsequential manner if they reside in the DISK device class.

randomization

The percentage of the startup window that the server can use to randomize start times for different client nodes associated with a schedule.

rebinding

The process of associating a file with a backed-up file with a new management class name. For example, rebinding occurs when the management class associated with a file is deleted. See *binding*.

recall

A function that allows users to access files that have been migrated from their workstations to TSM storage via the Tivoli Space Manager (HSM client). Contrast with *migrate*.

receiver

A server repository that contains a log of server messages and most client messages as events. For example, a receiver can be file and user exits, or the TSM server console and activity log. See also *event*.

reclamation

A process of consolidating the remaining data from many sequential access volumes onto fewer new sequential access volumes.

reclamation threshold

The percentage of reclaimable space that a sequential access media volume must have before the server can reclaim the volume. Space becomes reclaimable when files are expired or are deleted. The percentage is set for a storage pool.

recovery log

A log of updates that are about to be written to the database. The log can be used to recover from system and media failures.

recovery log buffer pool

Used to hold new transactions records until they can be written to the recovery log.

recovery media

Media that contains data necessary to recover the TSM server and clients.

reduce

The process of freeing up enough space to allow you to delete a volume from the database or recovery log. Contrast with *extend*.

REEL

On TSM servers that support it, a device class that is used to categorize tape devices that support tape reels, such as the 3420 9-track tape device.

register

(1) Define a client node or administrator who can access the server. See *registration*. (2) Specify licenses that have been purchased for the server.

registration

The process of identifying a client node or administrator to the server.

reply operator

On a VM server, a VM user ID that specifies an operator who will reply to tape mount requests by the server.

restore

The process of returning a backup copy to an active storage location for use. TSM has processes for restoring its database, storage pools, storage pool volumes, and users' backed-up files. For example, users can copy a backup version of a file from the storage pool to the workstation. The backup version in the storage pool is not affected. Contrast with *backup*.

retention

The amount of time, in days, that inactive backed up or archived files are kept in the storage pool before they are deleted. Copy group attributes and default retention grace periods for the domain define retention.

retention period

On an MVS server, a device class attribute that specifies how long files are retained on sequential access media. When used, TSM passes this information to the MVS operating system to ensure that other tape management systems do not overwrite tape volumes that contain retained data.

retrieve

A function that allows users to copy an archive copy from the storage pool to the workstation. The archive copy in the storage pool is not affected. Contrast with *archive*.

rollback

To remove changes that were made to database files since the last commit point.

root user

In the AIX and UNIX environments, a user who has superuser authority. The user can log in and execute restricted commands, shut down the system, and edit or delete protected files.

S**SAN**

Storage area network.

schedule

A database record that describes scheduled client operations or administrative commands. See *administrative command schedule* and *client schedule*.

scheduling mode

The type of scheduling operation set for the server and client. TSM supports two scheduling modes for client operations: client-polling and server-prompted.

scratch volume

A volume that is available for TSM use. The volume is labeled, is either blank or contains no valid data, and is not defined to TSM.

script

See *TSM command script*.

SCSI

Small computer system interface.

selective backup

A function that allows users to back up specific files or directories from a client domain. With this function, users can back up files or directories that are not excluded in the include-exclude list and that meet the requirement for serialization as defined in the backup copy group of the management class assigned to the files. Contrast with *incremental backup*.

sequential access media

Any volume that is accessed in a sequential manner, as opposed to a random manner. In TSM, volumes are accessed sequentially if they reside in a device class other than DISK.

serialization

A copy group attribute that specifies what TSM does if files are modified during back up or archive processing. The value of this attribute determines whether processing continues, is retried, or is stopped. See *static*, *dynamic*, *shared static*, and *shared dynamic*.

server

The program that provides backup, archive, space management, and administrative services to clients. The server program must be at the necessary level to provide all of these services.

server migration

The process of moving data from one storage pool to the next storage pool as controlled by the high and low migration thresholds. See *high migration threshold* and *low migration threshold*.

server options file

A file that contains settings that control various server operations. These settings, or options, affect such things as communications, devices, and performance.

server-prompted scheduling mode

A client/server communication technique where the server contacts the client when a scheduled operation needs to be done.

server storage

The primary and copy storage pools used by the server to store users' files: backup versions, archive copies, and files migrated from Tivoli Space Manager client nodes (space-managed files). See *primary storage pool*, *copy storage pool*, *storage pool volume*, and *volume*.

session resource usage

The amount of wait time, CPU time, and space used or retrieved during a client session.

shared dynamic

A copy group serialization value that specifies that a file must not be modified during a backup or archive operation. TSM attempts to retry the backup or archive operation a number of times; if the file is in use during each attempt, TSM will back up or archive the file on its last try even though the file is in use. See also *serialization*. Contrast with *dynamic*, *shared static*, and *static*.

shared library

A library device that is shared among multiple Tivoli Storage Manager servers.

shared static

A copy group serialization value that specifies that the file must not be modified during backup or archive. TSM will retry the backup or archive operation a number of times; if the file is in use during each attempt, TSM will not back up or archive the file. See also *serialization*. Contrast with *dynamic*, *shared dynamic*, and *static*.

shell

In the AIX and UNIX environments, a software interface between a user and the operating system of a computer. Shell programs interpret commands and user interactions on devices such as keyboards, pointing devices, and touch-sensitive screens and communicate them to the operating system.

SMIT

System Management Interface Tool.

SNA LU6.2

Systems Network Architecture Logical Unit 6.2.

snapshot

See *database snapshot*.

socket

(1) An endpoint for communication between processes or applications. (2) A pair consisting of TCP port and IP address, or UDP port and IP address.

source server

A server that can send data, in the form of *virtual volumes*, to another server. Contrast with *target server*.

space-managed file

A file that is migrated from and recalled to a client node via Tivoli Space Manager (HSM client).

space management

The process performed by Tivoli Space Manager to keep sufficient free storage space available on a client node by migrating files to Tivoli Storage Manager storage. The files are migrated based on criteria defined in management classes to which files are bound, and the include-exclude list. Synonymous with *hierarchical storage management*. See also *migration*.

space manager client

Synonym for *hierarchical storage management (HSM) client*.

stale copy status

Specifies that a volume copy is not available to the database or recovery log.

stanza

A group of lines in a file that together have a common function or define a part of the system. Stanzas are usually separated by blank lines or colons, and each stanza has a name.

startup window

A time period during which a schedule must be initiated.

static

A copy group serialization value that specifies that the file must not be modified during backup or archive. If the file is modified during the attempt, TSM will not back up or archive the file. See also *serialization*. Contrast with *dynamic*, *shared dynamic*, and *shared static*.

storage area network (SAN)

A high-speed communications network optimized for storage.

storage agent

A program that enables Tivoli Storage Manager to back up and restore client data directly to and from SAN-attached storage.

storage hierarchy

A logical ordering of primary storage pools, as defined by an administrator with system privilege. Generally, the ordering is based on the speed and capacity of the devices that the storage pools use. In TSM, the storage hierarchy is defined by identifying the *next* storage pool in a storage pool definition. See *storage pool*.

storage management services

A component that allows a central system to act as a file backup, archive, and space management server for local area network file servers and workstations.

storage pool

A named set of storage volumes that TSM uses to store client data. A storage pool is either a primary storage pool or a copy storage pool. See *primary storage pool* and *copy storage pool*.

storage pool volume

A volume that has been assigned to a TSM storage pool. See *volume*, *copy storage pool*, and *primary storage pool*.

storage privilege class

An administrative privilege class that allows an administrator to control the allocation and use of storage resources for the server, such as monitoring the database, recovery log, and server storage. Administrators can be authorized with unrestricted or restricted storage privilege.

stub file

A file that replaces the original file on a client node when the file is migrated from the client node to TSM storage.

subscription

The method by which a managed server requests that it receive configuration information associated with a particular profile on a configuration manager. See *managed server*, *configuration manager*, and *profile*.

superuser

See *root user*.

synchronized copy status

Specifies that the volume is the only volume copy or is synchronized with other volume copies in the database or recovery log. When synchronized, mirroring has started.

system privilege class

An administrative privilege class that allows an administrator to issue all server commands.

Systems Application Architecture (SAA)

Software interfaces, conventions, and protocols that provide a framework for designing and developing applications that are consistent across systems.

Systems Network Architecture (SNA)

A set of rules for data to be transmitted in a network. Application programs communicate with each other using a layer of SNA called advanced program-to-program communications (APPC).

T

tape library

(1) A term used to refer to a collection of tape cartridges. (2) An automated device that performs tape cartridge mounts and demounts without operator intervention.

Tape Library Dataserver

An automated tape library consisting of mechanical components, cartridge storage frames, IBM tape subsystems, and controlling hardware and software. The tape library dataserver performs tape cartridge mounts and demounts without operator intervention.

tape volume prefix

A device class attribute that is the high-level-qualifier of the file name or the data set name in the standard tape label.

target server

A server that can receive data sent from another server. Contrast with *source server*. See also *virtual volumes*.

TCP/IP

Transmission Control Protocol/Internet Protocol.

Telnet

In TCP/IP, the protocol that opens the connection to the system.

Tivoli Disaster Recovery Manager (DRM)

A product that works with TSM to assist in preparing and later using a disaster recovery plan for the TSM server.

Tivoli Storage Manager (TSM)

A client/server program that provides storage management to customers in a multivendor computer environment.

Transmission Control Protocol/Internet Protocol (TCP/IP)

A set of communication protocols that support peer-to-peer connectivity functions for both local and wide area networks.

trusted communication agent

A program that performs communication tasks on behalf of the client or server, and ensures the security of the communications.

TSM

Tivoli Storage Manager.

TSM application program interface (API)

A set of functions that applications running on a client platform can call to store, query, and retrieve objects from TSM storage.

TSM command script

A sequence of TSM administrative commands that are stored in the TSM database. The script can include substitution for command parameters and conditional logic. You can run the script from any interface to the server.

U

UCS-2

An ISO/IEC 10646 encoding form, Universal Character Set coded in 2 octets. The TSM client on Windows NT and Windows 2000 uses the UCS-2 code page when the client is enabled for Unicode.

Unicode Standard

A universal character encoding standard that supports the interchange, processing, and display of text that is written in any of the languages of the modern world. It can also support many classical and historical texts and is continually being expanded. The Unicode Standard is compatible with ISO/IEC 10646. For more information, see <http://www.unicode.org>.

unit name

On an MVS server, a device class attribute that specifies a group of tape devices used with the MVS server. A unit name can be a generic device type, an esoteric unit name, or a physical device.

UNIX System Services

MVS/ESA services that support an environment within which operating systems, servers, distributed systems, and workstations share common interfaces. UNIX System Services supports standard application development across

multivendor systems and is required to create and use applications that conform to the POSIX standard. UNIX System Services was formerly known as OpenEdition® MVS.

| **UTF-8**

| Unicode transformation format - 8. A byte-oriented encoding form specified by the Unicode Standard.

utilization

The percent of assigned capacity used by the database or recovery log at a specific point of time.

V

validate

The process of ensuring that the active policy set contains a default management class and reporting on copy group definition errors.

version

| A backup copy of a file stored in server storage. The most recent backup copy of a file is the active version.
| Earlier copies of the same file are inactive versions. The number of versions retained by the server is determined
| by the copy group attributes in the management class.

Virtual Machine (VM)

One of the family of IBM operating systems for the System/390 processor, including VM/ESA®.

| **virtual server**

| In a Microsoft cluster configuration, an MSCS cluster group that appears to be a single Windows server. The
| virtual server has a network name, an IP address, one or more physical disks, and a service.

Virtual Storage Extended (VSE)

One of the family of IBM operating systems for the System/390 processor, including VSE/ESA™.

virtual volume

A volume that appears to be a sequential media volume on a *source server* but that is actually stored as an archive file on a *target server*.

VM

Virtual Machine.

volume

The basic unit of storage for the TSM database, recovery log, and storage pools. A volume can be an LVM logical volume, a standard file system file, a tape cartridge, or an optical cartridge. Each volume is identified by a unique volume identifier. See *database volume*, *scratch volume*, and *storage pool volume*.

volume history file

A file that contains information about: volumes used for database backups and database dumps; volumes used for export of administrator, node, policy, or server data; and sequential access storage pool volumes that have been added, reused, or deleted. The information is a copy of the same types of volume information in the TSM database.

VSE

Virtual Storage Extended.

W

| **wildcard character**

| A special character such as an asterisk (*) or a question mark (?) that can be used to represent one or more
| characters. Any character or set of characters can replace a wildcard character. Also called *pattern-matching*
| *character*.

WORM

A type of optical media that can only be written to and cannot be erased.

X

X Windows

A network transparent windowing system developed by MIT. It is the basis for other products, such as Enhanced X Windows which runs on the AIX operating system.

Z

z/OS

An IBM operating system based on the 64-bit z/Architecture.

Index

Special Characters

\$\$CONFIG_MANAGER\$\$ 338

Numerics

- 3480 tape drive
 - cleaner cartridge 103
 - device class 106
- 3490 tape drive
 - cleaner cartridge 103
 - device class 106
- 3494 automated library device 27, 67
- 3570 tape drive
 - defining device class 40, 105
- 3590 tape drive
 - defining device class 40, 105, 107
 - device support 67, 68

A

- absolute mode, description of 257
- ACCEPT DATE command 360
- access authority, client 201
- access mode, volume
 - changing 130
 - description 131
 - determining for storage pool 123, 181
- accounting record
 - description of 431
 - monitoring 431
- accounting variable 432
- ACSL (Automated Cartridge System Library Software)
 - StorageTek library 28, 71
- ACTIVATE POLICYSET command 263
- ACTIVE policy set
 - creating 254, 263
 - replacing 237
- activity log
 - adjusting the size 417
 - description of 416
 - monitoring 416
 - querying 416
 - setting the retention period 417
- administrative client
 - description of 3
 - viewing information after IMPORT or EXPORT 439
- administrative commands
 - ACCEPT DATE 365
 - ASSIGN DEFMGMTCLASS 236, 262
 - AUDIT LIBVOLUME 95

administrative commands (continued)

- AUDIT LICENSE 359
- AUDIT VOLUME 489
- BACKUP DB 476
- BACKUP DEVCONFIG 475
- BACKUP STGPOOL 465
- BACKUP VOLHISTORY 473
- BEGIN EVENTLOGGING 419
- CANCEL PROCESS 367
- CANCEL RESTORE 221
- CANCEL SESSION 218
- CHECKIN LIBVOLUME 87
- CHECKOUT LIBVOLUME 93
- CLEAN DRIVE 101
- COMMIT 386
- COPY CLOPTSET 216
- COPY DOMAIN 254
- COPY POLICYSET 254
- COPY SCHEDULE 294
- COPY SCRIPT 381
- COPY SERVERGROUP 347
- DEFINE ASSOCIATION 287
- DEFINE BACKUPSET 280
- DEFINE CLIENTACTION 304
- DEFINE CLIENTOPT 304
- DEFINE CLOPTSET 214
- DEFINE COPYGROUP 255, 260, 261
- DEFINE DBBACKUPTRIGGER 469, 471
- DEFINE DBVOLUME 395
- DEFINE DEVCLASS 107, 109, 111
- DEFINE DOMAIN 253
- DEFINE DRIVE 82
- DEFINE GRPMEMBER 346
- DEFINE LIBRARY 27, 81
- DEFINE LOGCOPY 485
- DEFINE LOGVOLUME 395
- DEFINE MACHINE 504
- DEFINE MACHNODEASSOCIATION 504
- DEFINE POLICYSET 254
- DEFINE PROFASSOCIATION 327, 329
- DEFINE PROFILE 327
- DEFINE RECMEDMACHASSOCIATION 506
- DEFINE RECOVERYMEDIA 506
- DEFINE SCHEDULE 373
- DEFINE SCRIPT 377
- DEFINE SERVER 315, 316, 319, 343, 349
- DEFINE SERVERGROUP 346
- DEFINE SPACETRIGGER 393
- DEFINE STGPOOL 125, 126, 134
- DEFINE SUBSCRIPTION 337
- DEFINE VOLUME 35, 36, 130
- DELETE ASSOCIATION 296
- DELETE BACKUPSET 282
- DELETE COPYGROUP 274
- DELETE DBBACKUPTRIGGER 471

administrative commands *(continued)*

DELETE DBVOLUME 399
DELETE DEVCLASS 115
DELETE DOMAIN 275
DELETE DRIVE 104
DELETE EVENT 298
DELETE GRPMEMBER 347
DELETE LIBRARY 100
DELETE LOGVOLUME 399
DELETE MGMTCLASS 274
DELETE POLICYSET 274
DELETE PROFASSOCIATION 331
DELETE PROFILE 332
DELETE SCHEDULE 294
DELETE SCRIPT 382
DELETE SERVERGROUP 347
DELETE STGPOOL 183
DELETE SUBSCRIBER 342
DELETE SUBSCRIPTION 332, 338
DELETE VOLHISTORY 472, 473
DELETE VOLUME 184, 185
DISABLE EVENTS 419
DISABLE SESSIONS 220
DISMOUNT VOLUME 98
DSMFMT 127, 463
DSMSERV FORMAT 479
ENABLE EVENTS 419
ENABLE SESSIONS 220
END EVENTLOGGING 419
EXPIRE INVENTORY 264
EXPORT ADMIN 435
EXPORT NODE 441
EXPORT POLICY 441
EXPORT SERVER 441
EXTEND DB 396
EXTEND LOG 469
GENERATE BACKUPSET 278
GRANT AUTHORITY 222
HALT 364
HELP 369
IMPORT 438, 439
IMPORT ADMIN 445
IMPORT NODE 445, 452
IMPORT POLICY 445
IMPORT SERVER 445, 452
LABEL LIBVOLUME 61, 65, 68, 73, 84
LOCK ADMIN 226
LOCK NODE 199
LOCK PROFILE 330, 332
MOVE DATA 176
NOTIFY SUBSCRIBERS 330, 332
PING SERVER 347
PREPARE 506
QUERY ACTLOG 416
QUERY BACKUPSET 281
QUERY BACKUPSETCONTENTS 281
QUERY CONTENT 166
QUERY COPYGROUP 271, 450
QUERY DB 398
QUERY DBBACKUPTRIGGER 471
QUERY DBVOLUME 397, 465

administrative commands *(continued)*

QUERY DEVCLASS 114
QUERY DOMAIN 273
QUERY DRIVE 100
QUERY ENABLED 430
QUERY EVENT 288
QUERY FILESPACE 213
QUERY LIBRARY 99
QUERY LICENSE 359
QUERY LOG 401
QUERY LOGVOLUME 397, 465
QUERY MGMTCLASS 272
QUERY MOUNT 98
QUERY NODE 199
QUERY OCCUPANCY 173, 174, 175, 209
QUERY OPTION 408
QUERY POLICYSET 273
QUERY PROCESS 178
QUERY REQUEST 96
QUERY RESTORE 221
QUERY RPFCONTENT 508
QUERY RPFIL 508
QUERY SCHEDULE 288
QUERY SCRIPT 381
QUERY SERVERGROUP 346
QUERY STGPOOL 161, 169, 448
QUERY SUBSCRIPTION 337
QUERY SYSTEM 409
QUERY VOLHISTORY 472
QUERY VOLUME 162, 163, 179
RECONCILE VOLUMES 352
REDUCE DB 398
REDUCE LOG 398
REGISTER ADMIN 222
REGISTER LICENSE 358
REMOVE ADMIN 224
REMOVE NODE 199
RENAME ADMIN 224
RENAME FILESPACE 453
RENAME NODE 198
RENAME SCRIPT 382
RENAME SERVERGROUP 347
RENAME STGPOOL 180
RESET BUFPOOL 399
RESET DBMAXUTILIZATION 389, 392
RESET LOGCONSUMPTION 470
RESET LOGMAXUTILIZATION 389, 392
RESTORE STGPOOL 467, 493
RESTORE VOLUME 495
ROLLBACK 386
RUN 382
SELECT 410
SET ACCOUNTING 431
SET ACTLOGRETENTION 418
SET AUTHENTICATION 229
SET CLIENTACTDURATION 304
SET CONFIGMANAGER 323, 326
SET CONFIGREFRESH 337
SET CONTEXTMESSAGING 419
SET CROSSDEFINE 316, 319
SET DRMCHECKLABEL 501

administrative commands (*continued*)

SET DRMCOPYSTGPOOL 499
SET DRMCOURIERNAME 501
SET DRMDBBACKUPRXPIREDAYS 502
SET DRMFILEPROCESS 502
SET DRMINSTPREFIX 500
SET DRMNOTMOUNTABLE 501
SET DRMPLANPOSTFIX 499
SET DRMPLANPREFIX 500
SET DRMPRIMSTGPOOL 499
SET DRMRPFEXPIREDAYS 508
SET DRMVaultNAME 502
SET EVENTRETENTION 298, 376
SET INVALIDPWLIMIT 228
SET LICENSEAUDITPERIOD 359
SET LOGMODE 472
SET MAXCMDRETRIES 303
SET MAXSCHEDSESSIONS 301
SET MINPWLENGTH 229
SET PASSEXP 228
SET QUERYSCHEDPERIOD 303
SET RANDOMIZE 302
SET REGISTRATION 191
SET RETRYPERIOD 304
SET SCHEDMODES 299
SET SERVERHLADDRESS 316, 319
SET SERVERLLADDRESS 316, 319
SET SERVERNAME 315, 316, 319, 408
SET SERVERPASSWORD 315, 316, 319
SET SUBFILE 282
SET SUMMARYRETENTION 415
SET WEBAUTHTIMEOUT 228
SETOPT 368
UNLOCK PROFILE 330, 332
UPDATE ADMIN 222
UPDATE BACKUPSET 281
UPDATE CLIENTOPT 216
UPDATE CLOPTSET 216
UPDATE COPYGROUP 255, 261
UPDATE DBBACKUPTRIGGER 472
UPDATE DEVCLASS 110
UPDATE DOMAIN 253
UPDATE DRIVE 100
UPDATE LIBRARY 99
UPDATE LIBVOLUME 35, 93
UPDATE MGMTCLASS 254
UPDATE NODE 198
UPDATE POLICYSET 254
UPDATE RECOVERYMEDIA 506
UPDATE SCHEDULE 373
UPDATE SCRIPT 380
UPDATE SERVER 321
UPDATE SERVERGROUP 347
UPDATE VOLUME 130

administrative privilege class

analyst 232
description of 222
granting authority 222
operator 232
policy 231
reducing 226

administrative privilege class (*continued*)

revoking all 226
storage 231, 232
system 230

administrative user ID

creating automatically 202
description of 190
preventing automatic creation of 203

administrative web interface

description 14
setting authentication time-out value 228

administrator

authorizing to manage a policy domain 222
description of 4
locking 226
managing registration 355
querying 224
registering 222
removing 224
renaming 227
restrictions when registering 222
unlocking 226
updating 222, 224
viewing information about 224

aggregate file

controlling the size of 135
definition 134
reclaiming space in 152, 153
unused space in 173
viewing information about 167

analyst privilege class

description of 232
granting 232
revoking 226

ANR9999D message 419

application client

adding node for 190
description 3
policy for 267

application program interface (API)

client, registering 192
compression option 192
deletion option 193
description of 3
registering to server 192

archive

amount of space used 175
defining criteria 252
description of 16
file while changing 261
processing 249

archive copy group

defining 261, 262
deleting 274
description of 240

archive file management 239

archiving a file 238, 249

ASSIGN DEFMGMTCLASS command 236, 262

assigned capacity 389, 396

association, client with schedule

defining 287

association, client with schedule (*continued*)
 deleting 296

association, file with management class 244, 245

association, object with profile
 administrative command schedule 329
 administrator 327, 340
 client option set 329
 deleting 331
 policy domain 328
 script 329

Atape device driver 51

atldd device driver 51

AUDIT LIBVOLUME command 95

AUDIT LICENSE command 359

AUDIT VOLUME command 487, 489

auditing
 library's volume inventory 95
 license, automatic by server 358
 multiple volumes in sequential access storage pool 489
 single volume in sequential access storage pool 490
 volume, reasons for 487
 volume in disk storage pool 489

authentication, client/server 227

authority
 granting to administrators 222

AUTOFSRENAME parameter 206

Automated Cartridge System Library Software (ACSLs)
 StorageTek library 28, 71

automated library device
 auditing 95
 changing volume status 93
 checking in volumes 87
 defining 27
 informing server of new volumes 87
 labeling volumes 85
 overflow location 125
 removing volumes 93
 returning volumes 94
 scratch and private volumes 35
 updating 99
 volume inventory 35

automatically renaming file spaces 206

automating
 client operations 286
 server operations 371

B

background processes 365

backing up subfiles on the server 282

backup
 amount of space used by client 175
 database 471, 476
 default policy 235
 defining criteria for client files 252
 description of 16
 file 238, 247, 248
 file management 238
 file while open 256

backup (*continued*)
 frequency for file 256
 incremental 238, 247
 logical volume 249
 selective 238, 248
 storage pool 465
 when to perform for database 470

backup-archive client
 description of 3
 performing operations for 277, 293, 298
 policy for 242
 registering node 190
 scheduling operations for 286

backup copy group
 defining 255, 260
 deleting 274
 description of 240
 frequency 247
 mode 247
 serialization 247

BACKUP DB command 476

BACKUP DEVCONFIG command 475

backup period, specifying for incremental 300

backup set
 adding subfiles to 284
 deleting 282
 description of 278
 displaying contents of 281
 example of generating 279
 generating 278
 how the server manages and tracks 280
 media, selecting 278
 moving to other servers 280
 OST extension on 278
 selecting a name for 279
 selecting retention period for 280
 updating 281
 viewing information about 281

BACKUP STGPOOL command 465

BACKUP VOLHISTORY command 472

bar-code reader
 auditing volumes in a library 95
 checking in volumes for a library 90
 labeling volumes in a library 86

base file 283

batch file, scheduling on client 289

binding a file to a management class 244

buffer pool 399

BUFPOOLSIZE option 401

C

cache
 deleting files from 147, 176
 description of 15
 disabling for disk storage pools 146
 effect on performance 146
 effect on statistics 147
 enabling for disk storage pools 124, 146

cache (*continued*)
 monitoring utilization on disk 172
 CANCEL PROCESS command 171, 367
 CANCEL RESTORE command 221
 CANCEL SESSION command 218
 capacity, assigned 389, 396
 capturing server messages to a user log 360
 cartridge
 cleaner cartridge 103
 device class 106
 category, 349X library 67
 central scheduling
 client operations 277, 285, 293, 298
 controlling the workload 301
 coordinating 298
 description of 17, 285
 server operations 372
 changing date and time on server 365
 characteristics, machine 504
 check in
 cleaner cartridge 102
 library volume 87
 CHECKIN LIBVOLUME command 87
 checking the log file generated by processed schedules 294
 checklist for DRM project plan 525
 CHECKOUT LIBVOLUME command 93
 class, administrator privilege
 analyst 232
 description of 222
 granting authority 222
 operator 232
 policy 231
 reducing 226
 revoking all 226
 storage 231, 232
 system 230
 class, device
 3570 105, 107
 3590 105, 107
 4MM 105, 107
 8MM 105, 107
 amount of space used 174
 CARTRIDGE 107
 defining 109
 defining for database backup 469
 deleting 115
 description of 15
 DISK 105
 DLT 105, 107
 DTF 105
 ECARTRIDGE 105
 FILE 105
 GENERICTAPE 105
 OPTICAL 105, 110
 QIC 105, 107
 requesting information about 114
 selecting for import and export 437
 SERVER 105, 107, 349
 tape 107, 109, 110
 updating 109
 WORM 105
 class, device (*continued*)
 WORM12 105
 WORM14 105
 class, policy privilege
 description of restricted 231
 granting restricted 231
 revoking 226
 class, storage privilege
 description of restricted 232
 granting restricted 232
 revoking 226
 CLEAN DRIVE command 101
 cleaner cartridge
 checking in 102
 operations with 103
 client
 access user ID 202
 administrative 3
 API (application program interface) 3, 192
 application client (Tivoli Data Protection) 3, 267
 backup-archive 3
 configuring to use SAN devices 79
 options file 193
 Tivoli Space Manager (HSM client) 3, 242
 client, application
 adding node for 190
 description 3
 policy for 267
 client file
 allowing archive while changing 236
 allowing backup while changing 235, 256
 associating with management class 244, 245
 delaying migration of 142
 deleting 184
 deleting from a storage pool 183
 deleting from cache 147
 deleting when deleting a volume 184
 eligible for archive 236, 246
 eligible for backup 235, 246
 eligible for expiration 237
 eligible for space management 250
 how TSM stores 134
 on a volume, querying 166
 server migration of 138
 client migration 250
 client node
 adding 189
 amount of space used 173
 creating backup sets for 278
 file spaces, QUERY OCCUPANCY command 173
 finding tapes used by 168
 immediate processing 304
 locking 199
 managing registration 190, 198, 355
 options file 193
 performing operations for 277, 293, 298
 querying 199
 registering 192
 removing 199
 renaming 198
 scheduling operations for 286

client node (*continued*)

- setting password authentication 229
- setting scheduling mode 300
- setting up subfile backups 283
- unlocking 199
- updating 198
- viewing information about 199

client option

- TXNBYTELIMIT 135
- VIRTUALMOUNTPOINT 204

client option set

- adding client options to 215
- assigning clients to 215
- copying 216
- creating 215
- deleting 216
- deleting an option from 216
- requesting information about 216
- updating description for 216

client point-in-time restore, enabling 270

client-polling scheduling 299, 302

client queries to the server, setting the frequency 303

client restartable restore session

- canceling 221
- interrupting, active 221
- requesting information about 221

client/server, description of 3

client session

- canceling 218
- managing 217
- querying 217, 406
- recycling 219
- viewing information about 217, 406

client system options file 193

closed registration

- setting 191

collocation

- changing, effect of 151
- definition 124, 147, 181
- description of 15
- determining whether to use collocation 124, 147, 181
- effects on operations 148
- effects on volume reclamation 158
- enabling for sequential storage pool 124, 147, 181
- how the server selects volumes when disabled 150
- how the server selects volumes when enabled 149
- migration thresholds 144

command file, scheduling on client 289

command retry attempts

- setting the amount of time between 304
- setting the number of 303

command routing 343

command script 377

commands, administrative

- ACCEPT DATE 365
- ASSIGN DEFMGMTCLASS 236, 262
- AUDIT LIBVOLUME 95
- AUDIT LICENSE 359
- AUDIT VOLUME 489
- BACKUP DB 476
- BACKUP DEVCONFIG 475

commands, administrative (*continued*)

- BACKUP STGPOOL 465
- BACKUP VOLHISTORY 473
- BEGIN EVENTLOGGING 419
- CANCEL PROCESS 367
- CANCEL RESTORE 221
- CANCEL SESSION 218
- CHECKIN LIBVOLUME 87
- CHECKOUT LIBVOLUME 93
- CLEAN DRIVE 101
- COMMIT 386
- COPY CLOPTSET 216
- COPY DOMAIN 254
- COPY POLICYSET 254
- COPY SCHEDULE 294
- COPY SCRIPT 381
- COPY SERVERGROUP 347
- DEFINE ASSOCIATION 287
- DEFINE BACKUPSET 280
- DEFINE CLIENTACTION 304
- DEFINE CLIENTOPT 304
- DEFINE CLOPTSET 214
- DEFINE COPYGROUP 255, 260, 261
- DEFINE DBBACKUPTRIGGER 469, 471
- DEFINE DBVOLUME 395
- DEFINE DEVCLASS 107, 109, 111
- DEFINE DOMAIN 253
- DEFINE DRIVE 82
- DEFINE GRPMEMBER 346
- DEFINE LIBRARY 27, 81
- DEFINE LOGCOPY 485
- DEFINE LOGVOLUME 395
- DEFINE MACHINE 504
- DEFINE MACHNODEASSOCIATION 504
- DEFINE POLICYSET 254
- DEFINE PROFASSOCIATION 327, 329
- DEFINE PROFILE 327
- DEFINE RECMEDMACHASSOCIATION 506
- DEFINE RECOVERYMEDIA 506
- DEFINE SCHEDULE 373
- DEFINE SCRIPT 377
- DEFINE SERVER 315, 316, 319, 343, 349
- DEFINE SERVERGROUP 346
- DEFINE SPACETRIGGER 393
- DEFINE STGPOOL 125, 126, 134
- DEFINE SUBSCRIPTION 337
- DEFINE VOLUME 35, 36, 130
- DELETE ASSOCIATION 296
- DELETE BACKUPSET 282
- DELETE COPYGROUP 274
- DELETE DBBACKUPTRIGGER 471
- DELETE DBVOLUME 399
- DELETE DEVCLASS 115
- DELETE DOMAIN 275
- DELETE DRIVE 104
- DELETE EVENT 298
- DELETE GRPMEMBER 347
- DELETE LIBRARY 100
- DELETE LOGVOLUME 399
- DELETE MGMTCLASS 274
- DELETE POLICYSET 274

commands, administrative (*continued*)

DELETE PROFASSOCIATION 331
DELETE PROFILE 332
DELETE SCHEDULE 294
DELETE SCRIPT 382
DELETE SERVERGROUP 347
DELETE STGPOOL 183
DELETE SUBSCRIBER 342
DELETE SUBSCRIPTION 332, 338
DELETE VOLHISTORY 472, 473
DELETE VOLUME 184, 185
DISABLE EVENTS 419
DISABLE SESSIONS 220
DISMOUNT VOLUME 98
DSMFMT 127, 463
DSMSERV FORMAT 479
ENABLE EVENTS 419
ENABLE SESSIONS 220
END EVENTLOGGING 419
EXPIRE INVENTORY 264
EXPORT ADMIN 435
EXPORT NODE 441
EXPORT POLICY 441
EXPORT SERVER 441
EXTEND DB 396
EXTEND LOG 469
GENERATE BACKUPSET 278
GRANT AUTHORITY 222
HALT 364
HELP 369
IMPORT 438, 439
IMPORT ADMIN 445
IMPORT NODE 445, 452
IMPORT POLICY 445
IMPORT SERVER 445, 452
LABEL LIBVOLUME 61, 65, 68, 73, 84
LOCK ADMIN 226
LOCK NODE 199
LOCK PROFILE 330, 332
MOVE DATA 176
NOTIFY SUBSCRIBERS 330, 332
PING SERVER 347
PREPARE 506
QUERY ACTLOG 416
QUERY BACKUPSET 281
QUERY BACKUPSETCONTENTS 281
QUERY CONTENT 166
QUERY COPYGROUP 271, 450
QUERY DB 398
QUERY DBBACKUPTRIGGER 471
QUERY DBVOLUME 397, 465
QUERY DEVCLASS 114
QUERY DOMAIN 273
QUERY DRIVE 100
QUERY ENABLED 430
QUERY EVENT 288
QUERY FILESPACE 213
QUERY LIBRARY 99
QUERY LICENSE 359
QUERY LOG 401
QUERY LOGVOLUME 397, 465

commands, administrative (*continued*)

QUERY MGMTCLASS 272
QUERY MOUNT 98
QUERY NODE 199
QUERY OCCUPANCY 173, 174, 175, 209
QUERY OPTION 408
QUERY POLICYSET 273
QUERY PROCESS 178
QUERY REQUEST 96
QUERY RESTORE 221
QUERY RPFCONTENT 508
QUERY RPFFILE 508
QUERY SCHEDULE 288
QUERY SCRIPT 381
QUERY SERVERGROUP 346
QUERY STGPOOL 161, 169, 448
QUERY SUBSCRIPTION 337
QUERY SYSTEM 409
QUERY VOLHISTORY 472
QUERY VOLUME 162, 163, 179
RECONCILE VOLUMES 352
REDUCE DB 398
REDUCE LOG 398
REGISTER ADMIN 222
REGISTER LICENSE 358
REMOVE ADMIN 224
REMOVE NODE 199
RENAME ADMIN 224
RENAME FILESPACE 453
RENAME NODE 198
RENAME SCRIPT 382
RENAME SERVERGROUP 347
RENAME STGPOOL 180
RESET BUFPOOL 399
RESET DBMAXUTILIZATION 389, 392
RESET LOGCONSUMPTION 470
RESET LOGMAXUTILIZATION 389, 392
RESTORE STGPOOL 467, 493
RESTORE VOLUME 495
ROLLBACK 386
RUN 382
SELECT 410
SET ACCOUNTING 431
SET ACTLOGRETENTION 418
SET AUTHENTICATION 229
SET CLIENTACTDURATION 304
SET CONFIGMANAGER 323, 326
SET CONFIGREFRESH 337
SET CONTEXTMESSAGING 419
SET CROSSDEFINE 316, 319
SET DRMCHECKLABEL 501
SET DRMCOPYSTGPOOL 499
SET DRMCOURIERNAME 501
SET DRMDBBACKUPRXPIREDAYS 502
SET DRMFILEPROCESS 502
SET DRMINSTPREFIX 500
SET DRMNOTMOUNTABLE 501
SET DRMPLANPOSTFIX 499
SET DRMPLANPREFIX 500
SET DRMPRIMSTGPOOL 499
SET DRMRPFEXPIREDAYS 508

commands, administrative (*continued*)
 SET DRMVaultNAME 502
 SET EVENTREtENTION 298, 376
 SET INVALIDPWLIMIT 228
 SET LICENSEAUDITPERIOD 359
 SET LOGMODE 472
 SET MAXCMDRETRIES 303
 SET MAXSCHEDSESSIONS 301
 SET MINPWLLENGTH 229
 SET PASSEXP 228
 SET QUERYSCHEdPERIOD 303
 SET RANDOMIZE 302
 SET REGISTRAtION 191
 SET RETRYPERIOD 304
 SET SCHEDMODES 299
 SET SERVERHLADDRESS 316, 319
 SET SERVERLLADDRESS 316, 319
 SET SERVERNAME 315, 316, 319, 408
 SET SERVERPASSWOrd 315, 316, 319
 SET SUBFILE 282
 SET SUMMARYREtENTION 415
 SET WEBAuthTIMEOUT 228
 SETOPT 368
 UNLOCK PROFILE 330, 332
 UPDATE ADMIN 222
 UPDATE BACKUPSET 281
 UPDATE CLIENTOPT 216
 UPDATE CLOPTSET 216
 UPDATE COPYGROUP 255, 261
 UPDATE DBBACKUPTRIGGER 472
 UPDATE DEVCLASS 110
 UPDATE DOMAIN 253
 UPDATE DRIVE 100
 UPDATE LIBRARY 99
 UPDATE LIBVOLUME 35, 93
 UPDATE MGMTCLASS 254
 UPDATE NODE 198
 UPDATE POLICYSET 254
 UPDATE RECOVERYMEDIA 506
 UPDATE SCHEDULE 373
 UPDATE SCRIPT 380
 UPDATE SERVER 321
 UPDATE SERVERGROUP 347
 UPDATE VOLUME 130
 COMMIT command 386
 COMMTIMEOUT server option 217, 219
 communication set up
 among servers 314
 command routing, for 317
 cross definition 315, 316, 319
 enterprise configuration, for 314
 enterprise event logging, for 314, 428
 security 316
 server-to-server virtual volumes 349
 compressing the server database 402
 compression
 choosing client or drive 116
 option for API 192
 options for clients 191
 setting 191
 tape volume capacity, effect on 116
 configuration file, device
 backing up 474
 example 476
 information 474
 recreating 475
 using when compressing the database 402
 configuration information
 administrative command schedule 324, 325, 329
 administrator 327, 340
 changing 330
 client option set 324, 329
 client schedule 324, 325, 328
 copy group 324, 328
 deleting 331, 332
 distributing 321, 329, 330
 management class 328
 policy domain 324, 325, 328
 refreshing 330, 337, 339
 script 324, 329
 server 327
 server group 327
 configuration manager
 communication setup 314
 default profile 323, 327
 scenario 323
 setting up 323, 326
 configuring
 client data transfer over a SAN 79
 devices, automated library example 63, 65
 devices, manual library example 59
 planning your storage environment 39
 shared library on a SAN 73, 75
 console mode 439
 contents of a volume 166
 context messaging for ANR9999D 419
 continuation characters, using 378
 COPY CLOPTSET command 216
 COPY DOMAIN command 253
 copy group
 archive, description of 240
 backup, description of 240
 defining archive 261
 defining backup 255
 deleting 274
 COPY MGMTCLASS command 255
 COPY POLICYSET command 254
 COPY SCHEDULE command 294, 375
 COPY SCRIPT command 381
 COPY SERVERGROUP command 347
 copy storage pool
 compared with primary 182
 role in storage pool migration 146
 storage hierarchy, effect on 137
 creating backup sets
 benefits of 278
 example for 279
 creating server scripts 377
 cross definition 315, 316, 319

D

data

- considering user needs for recovering 41
- exporting 435
- importing 435

data movement, querying 178

data storage

- client files, process for storing 4
- concepts overview 4
- considering user needs for recovering 41
- deleting files from 184
- evaluating 39
- example 121
- managing 4
- monitoring 487
- planning 39
- protection, methods 458
- tailoring definitions 450
- using another TSM server 348
- using disk devices 43
- using the storage hierarchy 137

database, TSM

- adding space to 395
- automating increase of 393
- available space 389, 392
- backup 476
- backup trigger 471
- buffer pool 399, 401
- committing data to 401
- compressing 402
- defining a volume 395
- defining mirrored volumes 463
- deleting a volume 399
- deleting space 397
- description of 18, 387
- determining how much space is allocated 388, 392
- DEVCONFIG option 402
- ensuring integrity of 18
- estimating the amount of space needed 390
- formatting 402
- fragmented 402
- loading 402
- logical volume 388, 392
- managing 387
- mirroring 463
- monitoring space 389, 392
- monitoring the buffer 401
- optimizing performance 399
- querying the buffer pool 400
- querying using SQL 410
- recovering 477
- reducing capacity 398
- reloading 402
- reorganize 402
- resetting buffer pool statistics 400
- restoring 469
- shadowing 464
- space trigger 393
- storage pool size effect 387
- transactions 387, 388
- unloading 402

database, TSM (continued)

- viewing information about 400

database backup and recovery

- database backup trigger 471, 482
- defining device classes for 469
- example recovery procedures 492
- full backup 470, 476
- general strategy 348, 457, 458
- incremental backup 470
- methods 348, 457
- point-in-time 478
- providing 348, 457
- roll-forward 461, 482
- to most current state 482
- unloading 402
- using Disaster Recovery Manager 458
- when to back up 470

date and time, changing on the server 365

day of the week parameter 373

DBPAGESHADOW server option 464

DBPAGESHADOWFILE server option 464

deactivating policy 237

Decision Support Loader 430, 431

default management class

- assigning for a policy set 262
- binding files to 245
- description of 241
- purpose 242
- recommendation for using 244

default policy 235

default profile 323, 327, 336

DEFINE ASSOCIATION command 287

DEFINE BACKUPSET command 280

DEFINE CLIENTACTION command 304

DEFINE CLIENTOPT command 215

DEFINE CLOPTSET command 214

DEFINE COPYGROUP command 255, 260, 261, 262

DEFINE DBBACKUPTRIGGER command 469, 471

DEFINE DBVOLUME command 395

DEFINE DEVCLASS command 107, 109

DEFINE DOMAIN command 253

DEFINE DRIVE command 82

DEFINE GRPMEMBER command 346

DEFINE LIBRARY command 81

DEFINE LOGCOPY command 485

DEFINE LOGVOLUME command 395

DEFINE MACHINE command 504

DEFINE MACHNODEASSOCIATION command 504

DEFINE MGMTCLASS command 254

DEFINE POLICYSET command 254

DEFINE PROFASSOCIATION command 329

DEFINE RECMEDMACHASSOCIATION command 506

DEFINE RECOVERYMEDIA command 506

DEFINE SCHEDULE command 373

DEFINE SCRIPT command 377

DEFINE SERVER command 315, 316, 319, 343, 349

DEFINE SPACETRIGGER command 393

DEFINE STGPOOL command 125, 126, 134

DEFINE SUBSCRIPTION command 337

DEFINE VOLUME command 130

delaying migration for files 142

delaying reuse of volumes 158
 DELETE ASSOCIATION command 296
 DELETE BACKUPSET command 282
 DELETE CLIENTOPT command 216
 DELETE COPYGROUP command 274
 DELETE DBBACKUPTRIGGER 471
 DELETE DBVOLUME command 399
 DELETE DEVCLASS command 115
 DELETE DOMAIN command 275
 DELETE DRIVE command 104
 DELETE EVENT command 298, 376
 DELETE FILESPACE command 213
 DELETE GRPMEMBER command 347
 DELETE LIBRARY command 100
 DELETE LOGVOLUME command 399
 DELETE MGMTCLASS command 274
 DELETE POLICYSET command 274
 DELETE PROFASSOCIATION command 331
 DELETE PROFILE command 332
 DELETE SCHEDULE command 294, 375
 DELETE SCRIPT command 382
 DELETE SERVER command 321
 DELETE SERVERGROUP command 347
 DELETE STGPOOL command 183
 DELETE SUBSCRIBER command 342
 DELETE SUBSCRIPTION command 338
 DELETE VOLHISTORY command 472, 473
 DELETE VOLUME command 184, 185
 deleting
 cached files on disk 176
 empty volume 184, 473
 file spaces 213
 files 184, 264
 media-managed storage pools 71
 scratch volume 128, 473
 storage volume 185
 subfile 284
 volume history information 473
 volume with residual data 185
 DESTINATION parameter (storage pool) 235, 236, 255, 261
 destroyed volume access mode 132, 459
 determining
 cause of ANR9999D messages 419
 whether LAN-free data transfer was successful 81
 DEVCONFIG option 474
 device, storage
 automated library device 63, 65
 disk 43
 manual library device 59
 optical device 59, 61, 111
 overview for removable media 57
 removable media device 61, 111
 required Tivoli Storage Manager definitions 40
 device class
 3570 105, 107
 3590 105, 107
 4MM 105, 107
 8MM 105, 107
 amount of space used 174
 CARTRIDGE 107
 defining 109
 device class (*continued*)
 defining for database backup 469
 deleting 115
 description of 15
 DISK 105
 DLT 105, 107
 DTF 105
 ECARTRIDGE 105
 FILE 105
 GENERICTAPE 105
 OPTICAL 105, 110
 QIC 105, 107
 requesting information about 114
 selecting for import and export 437
 SERVER 105, 107, 349
 tape 107, 109, 110
 updating 109
 WORM 105
 WORM12 105
 WORM14 105
 device configuration file
 backing up 474
 example 476
 information 474
 recreating 475
 using when compressing the database 402
 device driver
 for automated tape devices 51
 for IBM 3490, 3570, and 3590 tape drives 52
 for manual tape devices 49, 50, 51, 60, 63, 65, 74, 75
 for optical devices 51
 installing 49, 51
 mapping TSM devices to 51
 requirements 49, 51
 Tivoli Storage Manager, installing 49, 50, 58, 60, 63, 65,
 74, 75
 device names 52
 device sharing 39
 device type
 3570 107
 3590 107
 4MM 107
 8MM 107
 CARTRIDGE 107
 DISK 105
 DLT 107
 DTF 107
 ECARTRIDGE 107
 GENERICTAPE 107
 LTO 106
 OPTICAL 110
 QIC 107
 SERVER 107, 348, 349
 WORM 107
 WORM12 107
 WORM14 107
 diagnosing ANR9999D messages 419
 direct-to-tape, policy for 266
 DISABLE EVENTS command 419
 DISABLE SESSIONS command 220

- disaster recovery
 - auditing storage pool volumes 491
 - example recovery procedures 492
 - general strategy 348, 457
 - methods 348, 457
 - providing 348, 457
 - when to backup 458, 470
 - disaster recovery manager
 - awk script 528
 - client recovery information 498
 - creating a disaster recovery plan 506
 - customizing 498
 - displaying a disaster recovery plan 508
 - enabling 497
 - expiring a disaster recovery plan 508
 - features 498
 - moving volumes back onsite 513
 - project plan, checklist 525
 - querying a disaster recovery plan 508
 - recovery media 506
 - saving machine characteristics 504
 - stanzas, recovery instructions 502
 - storing a disaster recovery plan 506
 - disk device class, defined 105
 - disk storage pool
 - cache, use of 146
 - deleting cached files from 176
 - estimating space 159
 - estimating space for archived files 160
 - estimating space for backed up files 159
 - migration threshold 139
 - setting up 43
 - DISMOUNT VOLUME command 98
 - domain, policy
 - assigning client node 264
 - changing 237
 - creating 253
 - deleting 275
 - description of 240
 - distributing via profile 270, 325
 - querying 273
 - updating 251, 253
 - drive
 - cleaning 101
 - defining 82
 - deleting 104
 - limiting the number using the MAXNUMMP parameter 81
 - querying 100
 - updating 100
 - drive mapping (SAN clients) 80
 - guidelines for 80
 - driver, device
 - for automated tape devices 51
 - for IBM 3490, 3570, and 3590 tape drives 52
 - for manual tape devices 49, 50, 51, 60, 63, 65, 74, 75
 - for optical devices 51
 - installing 49, 51
 - mapping TSM devices to 51
 - requirements 49, 51
 - Tivoli Storage Manager, installing 49, 50, 58, 60, 63, 65, 74, 75
 - dsm.opt file 193, 214, 286
 - dsmacct.log 432
 - DSMADMC command 439, 449
 - DSMFMT utility 127, 463
 - DSMLABEL utility 85, 86, 87, 129
 - dmsched.log file 294
 - DSMSERV_ACCOUNTING_DIR 432
 - DSMSERV_DISPLAY DBBACKUPVOLUME command 475
 - DSMSERV FORMAT utility 363
 - DSMSERV LOADDDB utility 402, 403
 - DSMSERV LOADFORMAT utility 402
 - DSMSERV RESTORE DB command 475
 - DSMULOG utility 360
 - dumping, database 476
 - dynamic serialization, description of 256, 261
- ## E
- element address 82
 - ENABLE EVENTS command 419
 - ENABLE SESSIONS command 220
 - ENABLE3590LIBRARY parameter 67
 - END EVENTLOGGING command 419
 - Enterprise Administration
 - description 309
 - enterprise configuration
 - communication setup 314
 - description 310, 321
 - procedure for setup 322
 - profile for 324
 - scenario 312, 322
 - subscription to 325
 - enterprise event logging 314, 428
 - enterprise logon 202, 311, 343
 - environment variable, accounting 432
 - environment variables 362, 363
 - error analysis 409
 - error reporting for ANR9999D messages 419
 - error reports for volumes 164
 - establishing server-to-server communications
 - enterprise configuration 314
 - enterprise event logging 314
 - virtual volumes 321
 - estimated capacity for storage pools 161
 - estimated capacity for tape volumes 164
 - event logging 418
 - event record (for a schedule)
 - deleting 298, 376
 - description of 288, 296
 - managing 375
 - querying 375
 - removing from the database 298, 376
 - setting retention period 298, 376
 - event server 428
 - EXPINTERVAL option 264
 - expiration date, setting 374
 - expiration processing
 - description 264, 467
 - files eligible 237, 264

expiration processing (*continued*)
 of subfiles 237, 258, 265, 284
 starting 264
 using Tivoli Disaster Recovery Manager 265

EXPIRE INVENTORY command
 deleting expired files 264
 duration of process 265

export
 labeling tapes 438
 monitoring 438
 planning for sequential media 437
 PREVIEW parameter 436
 querying about a process 438
 querying the activity log 440
 using scratch media 438
 viewing information about a process 438

EXPORT ADMIN command 443

EXPORT commands 438, 439

EXPORT NODE command 444

EXPORT POLICY command 445

EXPORT SERVER command 437, 443

exporting
 administrator data 443
 client node data 444
 data to tape 441
 description of 435
 policy data 445
 server data 443
 subfiles 284

EXPQUIET server option 265

EXTEND DB command 396

EXTEND LOG command 396

EXTERNAL library type 559

external media management
 initialization requests 559
 interface description 555
 overview 69
 processing during server initialization 556
 TSM setup 69
 using with TSM 70
 volume dismount requests 564
 volume mount requests 561
 volume release requests 560

F

Fibre Channel support 79

file, client

 allowing archive while changing 236
 allowing backup while changing 235, 256
 associating with management class 244, 245
 delaying migration of 142
 deleting 184
 deleting from a storage pool 183
 deleting from cache 147
 deleting when deleting a volume 184
 eligible for archive 236, 246
 eligible for backup 235, 246
 eligible for expiration 237

file, client (*continued*)

 eligible for space management 250
 how TSM stores 134
 on a volume, querying 166
 server migration of 138

file data, importing 435

FILE device type
 defining device class 105
 deleting scratch volumes 473
 setting up storage pool 45

file exit 418

file names for devices 52

file retrieval date 147

file size, determining maximum for storage pool 124

file space
 deleting 213
 description of 16, 204
 names that do not display correctly 213
 QUERY OCCUPANCY command 173
 querying 204
 renaming 453
 Unicode enabled 212
 viewing information about 204

file space identifier (FSID) 212

formatting
 database volume 396
 recovery log volume 396
 storage pool volume 44, 129

frequency of backup 256

FSID 212

full library 94

G

GENERATE BACKUPSET command 278

GENERICTAPE device type 109

GRANT AUTHORITY command 222

group, server

 copying 347
 defining 346
 deleting 347
 member, deleting 347
 moving a member 347
 querying 346
 renaming 347
 updating description 347

H

HALT command 364

halting the server 364

HELP command 369

hierarchy, storage

 defining in reverse order 125, 134
 establishing 133
 example 121
 how TSM stores files in 134

hierarchy, storage (*continued*)
 next storage pool 133, 138, 146, 169, 183
 staging data on disk for tape storage 137
home pages xxi
host server 189
how the backup sets are managed 280
how to cause the server to accept date and time 365

I

IBM error analysis 409
IBM service xxiii
IBMtape device driver 51
IDLETIMEOUT server option 218, 219
import
 monitoring 438
 PREVIEW parameter 436, 446
 querying about a process 438
 querying the activity log 440
 recovering from an error 453
 viewing information about a process 438
IMPORT ADMIN command 445
IMPORT commands 438, 439
IMPORT NODE command 445, 452
IMPORT POLICY command 445
IMPORT SERVER command 445, 452
importing
 data 445
 data storage definitions 448, 450
 date of creation 451
 description of 435
 directing messages to an output file 449
 duplicate file spaces 451
 file data 451
 policy definitions 448
 server control data 450
 subfiles 284
 subsets of information 453
include-exclude file
 description of 16, 243
 for policy environment 240, 243
incremental backup
 file eligibility for 247
 full 247
 partial 248
incremental backup frequency, specifying 300
initial start date for schedule 373
initial start time for schedule 373
installing Tivoli Storage Manager xxi, 190
interface, application program
 client, registering 192
 compression option 192
 deletion option 193
 description of 3
 registering to server 192
interfaces to Tivoli Storage Manager 13
Internet xxi
introduction to Tivoli Storage Manager 3

J

Journal File System 127, 390

L

label
 checking media 90
 overwriting existing labels 84
 sequential storage pools 83, 129
 volume examples 85
 volumes using a library device 85
LABEL LIBVOLUME command
 identifying drives 84
 insert category 86
 labeling sequential storage pool volumes 84
 overwriting existing volume labels 84
 using a library device 85
 using a manual library 61
 using an automated library 65, 68, 73
 volume labeling examples 85
LAN-free data transfer
 client 37
 determining success of transfer 81
library
 349X 27
 ACSL (Automated Cartridge System Library Software) 28
 adding volumes 87
 auditing volume inventory 95
 automated 93
 configuration example 59, 63, 65
 defining 81
 deleting 100
 external 28
 full 94
 managing 99
 manual 27, 59, 96
 mode, random or sequential 50
 overflow location 125
 querying 99
 SCSI 27
 sharing (SAN) 73, 75
 type 27
 updating 99
 volume inventory 35
library client, shared library 37, 74, 76
library manager, shared library 37, 74, 76
license
 compliance 358
 features 355
 monitoring 358
 registering 356
 using 355
link recycling 219
location, volume
 changing 130
 overflow for storage pool 125
 querying volume 165
LOCK ADMIN command 226

LOCK NODE command 199
LOCK PROFILE command 330, 332
log mode
 normal 469, 471
 roll-forward 469, 471
 setting 469
logical devices 25, 45
logical volume, raw 44, 127, 129, 390
logical volume on client
 backup 238
 management class for 244
 policy for 246, 267
 process for backup 249
 restore 238
LOGPOOLSIZE option 401
LTO device type 105

M

machine characteristics 504
machine recovery information 505
macro
 commit individual commands 386
 continuation characters 384
 controlling command processing 386
 running 385
 scheduling on client 289
 substitution variables 385
 testing 386
 using 383
 writing commands 383
 writing comments 384
MACRO administrative command, using 196
magnetic disk devices 24, 43
managed server
 changing the configuration manager 336, 341
 communication setup 314
 deleting a subscription 338
 description 310
 managed objects 310, 335
 refreshing configuration information 339
 renaming 342
 returning managed objects to local control 340
 setting up 324
 subscribing to a profile 325, 335, 336, 337
management class
 assigning a default 262
 associating a file with 244
 binding a file to 244
 configuration 242
 controlling user access 241
 copying 251, 254
 default 242
 defining 254
 deleting 274
 description of 240, 241
 querying 272
 rebinding a file 245
 updating 245, 251, 255
 managing other TSM servers 309
 manual library device 59
 mapping a SAN drive for clients 80
 mapping devices to device drivers 51
 maximum extension 395
MAXSCRATCH parameter 123, 130, 181
media label
 checking 90
 for optical media 87
 for tape 84
 recording 84
media loss, recovery from 495
messages
 determining cause of ANR9999D message 419
 directing import messages to an output file 449
 for automated libraries 96
 getting help on 369
 mount, using the administrative client 96
 severe 419
migrating a file 239, 250
migration
 automatic, for HSM client
 demand 239
 files, eligible 250
 threshold 239
 using management class 250
 canceling the server process 171
 controlling by file age 142
 controlling start of, server 141
 copy storage pool, role of 146
 defining threshold for disk storage pool 141
 defining threshold for tape storage pool 144
 delaying by file age 142
 description, server process 139
 minimizing access time to migrated files 143
 monitoring thresholds for storage pools 169
 premigration for HSM client 239
 processes, number of 139
 providing additional space for server process 171
 reconciliation 239
 selective, for HSM client 239
 starting server process 138, 141
 stub file on HSM client 239
 threshold for a storage pool 139
mirrored volume
 description of 465
 querying 465
 viewing information about 465
mirroring
 advantages 463
 database 463
 defining volumes 465
 description of 18
 recovery log 460, 463
 recovery procedure 485
mobile client support 282
mode
 client backup 256
 library (random or sequential) 50
 scheduling 299
modified mode, description of 257

monitoring the TSM server 405

mount

- library 109
- query 98
- retention period 108
- wait period 108

mount limit 107

mount mode 96

mount operations 96

MOVE DATA command 176

MOVE DRMEDIA command 514

moving backup sets

- benefits of 280
- to another server 280

moving data

- from offsite volume in a copy storage pool 177
 - monitoring the movement of 179
 - procedure 177
 - requesting processing information 178
 - to another storage pool 177
 - to other volumes in same storage pool 176
- multiple servers, running 363

N

names of devices 52

network of TSM servers 10, 309

next storage pool 133, 138, 146, 169, 183

node, client

- adding 189
- amount of space used 173
- creating backup sets for 278
- file spaces, QUERY OCCUPANCY command 173
- finding tapes used by 168
- immediate processing 304
- locking 199
- managing registration 190, 198, 355
- options file 193
- performing operations for 277, 293, 298
- querying 199
- registering 192
- removing 199
- renaming 198
- scheduling operations for 286
- setting password authentication 229
- setting scheduling mode 300
- setting up subfile backups 283
- unlocking 199
- updating 198
- viewing information about 199

node privilege class

- description of 201
- granting 202

NOPREEMPT server option 367

NORETRIEVEDATE server option 147

NOTIFY SUBSCRIBERS command 330, 332

O

occupancy, querying 173

ODBC driver 410

offsite recovery media (for DRM)

- volumes
 - moving back onsite 513
 - sending offsite 512
 - states 511

offsite volume access mode 132

offsite volumes, moving data in a copy storage pool 177

one-drive library, volume reclamation 124, 155

open registration

- setting 191

operator privilege class

- description of 232
- granting 232
- revoking 226

optical device

- defining device class 105, 110
- device driver 51
- OPTICAL device type 110
- reclamation for media 155

option, server

- AUDITSTORAGE 359, 368
- BUFPOOLSIZE 400
- changing with SETOPT command 368
- COMMTIMEOUT 217, 219
- DEVCONFIG 474
- ENABLE3590LIBRARY 67
- EXPINTERVAL 265
- EXPQUIET 265
- IDLETIMEOUT 218, 219, 407
- LOGPOOLSIZE 401
- NOPREEMPT 367
- NORETRIEVEDATE 147
- RESTOREINTERVAL 221, 238, 265
- THROUGHPUTDATATHRESHOLD 219
- THROUGHPUTTIMETHRESHOLD 219
- TXNGROUPMAX 135
- VOLUMEHISTORY 473

option set, client

- adding client options to 215
- assigning clients to 215
- copying 216
- creating 215
- deleting 216
- deleting an option from 216
- requesting information about 216
- updating description for 216

options, querying

- BUFPOOLSIZE 401
- LOGPOOLSIZE 401
- VIRTUALMOUNTPOINT client option 230

options file, client 193

overflow location 125

owner authority, client 201, 202

P

- page, description of 399
- page shadowing, database server options 464
- password
 - resetting an administrative 224
 - setting authentication for a client 229
 - setting expiration 228
 - setting invalid limit 228
 - setting minimum length 229
- pending, volume state 165
- performance
 - cache, considerations for using 46, 146
 - concurrent client/server operation considerations 301
 - database or recovery log, optimizing 399
 - database read, increase with mirroring 463
 - file system effects on 44, 129
 - mobile client 283
 - storage pool volume 144, 484
 - volume frequently used, improve with longer mount retention 108
- period, specifying for an incremental backup 300
- point-in-time restore for clients, enabling 270
- policy
 - default 235
 - deleting 273
 - description of 240
 - distributing with enterprise management 270
 - effect of changing 263, 264
 - for application clients 267
 - for clients using SAN devices 268
 - for direct-to-tape backup 266
 - for logical volume backups 267
 - for point-in-time restore 270
 - for server as client 270
 - for space management 236, 250, 254
 - importing 448
 - managing 233
 - operations controlled by 238
 - planning 234
 - querying 271
- policy domain
 - assigning client node 264
 - changing 237
 - creating 253
 - deleting 275
 - description of 240
 - distributing via profile 270, 325
 - querying 273
 - updating 251, 253
- policy privilege class
 - description of restricted 231
 - granting restricted 231
 - revoking 226
- policy set
 - activating 264
 - changing, via the active policy set 237
 - copying 237, 251, 254
 - defining 254
 - deleting 274
 - description of 240
 - querying 273
- policy set (*continued*)
 - updating 254
 - validating 263, 264
- pool, storage
 - amount of space used 174
 - auditing a volume 487
 - backup and recovery 465
 - comparing primary and copy types 182
 - copy 121
 - creating a hierarchy 133
 - defining 123
 - defining for disk, example 125, 134
 - defining for tape, example 125, 134
 - deleting 183
 - description of 120
 - destination in copy group 255, 261
 - determining access mode 123, 181
 - determining maximum file size 124
 - determining whether to use collocation 124, 147, 181
 - enabling cache for disk 124, 146
 - estimating space for archived files on disk 160
 - estimating space for backed up files on disk 159
 - estimating space for disk 159
 - estimating space for sequential 160
 - estimating space in multiple 133
 - managing 119
 - monitoring 161
 - moving files 176
 - moving files between 177
 - next storage pool 133, 138, 146, 169, 183
 - overview 30
 - policy use 255, 261
 - primary 120
 - querying 161
 - random access 120
 - recovery log, effect on 387
 - renaming 180
 - restoring 467, 493
 - sequential access 120
 - updating 123
 - updating for disk, example 126, 134
 - using cache on disk 124, 146
 - viewing information about 161
- portable media
 - description of 277
 - restoring from 280
- preemption
 - mount point 367
 - volume access 367
- prefix, for recovery instructions 500
- prefix, for recovery plan file 500
- prefix, server 344
- premigration 239
- PREPARE command 506
- PREVIEW parameter 436, 446
- private category 67
- privilege class, administrator
 - analyst 232
 - description of 222
 - granting authority 222
 - operator 232

privilege class, administrator (*continued*)

- policy 231
- reducing 226
- revoking all 226
- storage 231, 232
- system 230

privilege class, policy

- description of restricted 231
- granting restricted 231
- revoking 226

process

- background 365
- canceling 367
- expiration 467
- number for migration 124, 139
- number for storage pool backup 467
- number for storage pool restore 483
- reclamation 152, 157

profile

- associating configuration information with 327
- changing 327, 330, 331
- default 327, 336
- defining 327, 329
- deleting 331, 332
- description 326
- getting information about 333
- locking 330
- problems with synchronization 341
- unlocking 330

programming interface notice 572

protecting your data 458

Q

- QUERY ACTLOG command 416, 440
- QUERY ADMIN command 224
- QUERY BACKUPSET command 281
- QUERY BACKUPSETCONTENTS command 281
- QUERY CONTENT command 166
- QUERY COPYGROUP command 271, 450
- QUERY DB command 398, 400
- QUERY DBBACKUPTRIGGER command 471
- QUERY DBVOLUME command 397, 465
- QUERY DEVCLASS command 437
- QUERY DOMAIN command 273
- QUERY DRIVE command 100
- QUERY ENABLED command 430
- QUERY EVENT command 296, 375
- QUERY FILESPACE command 204
- QUERY LIBRARY command 99
- QUERY LICENSE command 359
- QUERY LOG command 401
- QUERY LOGVOLUME command 397, 465
- QUERY MGMTCLASS command 272
- QUERY MOUNT command 98
- QUERY NODE command 199
- QUERY OCCUPANCY command 173, 174, 175
- QUERY OPTION command 408
- QUERY POLICYSET command 273

QUERY PROCESS command 171, 178, 366, 407, 438

QUERY REQUEST command 96

QUERY RESTORE command 221

QUERY RPFCONTENT command 508

QUERY RPFFILE 508

QUERY SCHEDULE command 288

QUERY SCRIPT command 381

QUERY SERVERGROUP command 346

QUERY SESSION command 217, 406

QUERY STATUS command 408

QUERY STGPOOL command 161, 169, 172

QUERY SUBSCRIPTION command 337

QUERY SYSTEM command 409

QUERY VOLHISTORY command 473

QUERY VOLUME command 162, 163, 179

querying for general information 163

querying policy objects 271

querying storage volumes 163

R

random mode for libraries 50

randomize, description of 302

raw logical volume 44, 127, 129, 390

read-only access mode 131

read/write access mode 131

rebinding

- description of 245

- file to a management class 245

recalling a file

- selective 239

- transparent 239

receiver 418

reclamation

- affect of collocation on 158

- delaying reuse of volumes 158, 467

- description of 15

- offsite volume 157

- setting a threshold for sequential storage pool 124, 152, 181

- threshold 15

- virtual volumes 155

- with single drive 155

reclamation storage pool 124

reclamation threshold, setting for sequential storage pool 124, 152, 181

RECONCILE VOLUMES command 352

recovering storage pools 465

recovering the database 477

recovery, disaster

- auditing storage pool volumes 491

- example recovery procedures 492

- general strategy 348, 457, 458

- media 506

- methods 348, 457

- providing 348, 457

- when to backup 458, 470

recovery instructions file 532

- recovery log
 - adding space to 394, 395
 - automating increase of 393
 - available space 389, 392
 - buffer pool 402
 - consistent database image 387
 - defining a volume 395
 - defining mirrored volumes 463
 - deleting a volume 399
 - deleting space 397
 - description of 18, 387
 - determining how much space is allocated 388, 392
 - estimating the amount of space needed 390
 - logical volume 388, 392
 - managing 387
 - mirroring 460, 463
 - monitoring space 388, 392
 - monitoring the buffer pool 402
 - optimizing performance 399
 - querying the buffer pool 401
 - reducing capacity 398
 - size of 469
 - space trigger 393
 - storage pool size effect 387
 - viewing information about 401
 - when to backup 458, 463, 470
- recovery log mode
 - normal 469, 471
 - roll-forward 469, 471
 - setting 469
- recovery plan file
 - creating 506
 - example 530
 - prefix 500
 - stanzas 528
- recycling links 219
- redbooks xxiii
- REDUCE DB command 398
- REDUCE LOG command 398
- REGISTER ADMIN command 222
- REGISTER LICENSE command 358
- REGISTER NODE command 202
- registering a workstation 192
- registration
 - description of 191
 - licensing for a client node 355
 - licensing for an administrator 355
 - managing client node 190, 198
 - setting for a client node 191
 - source server 192
- removable file system device
 - labeling requirements 63
 - support for 61, 111
- REMOVE ADMIN command 224
- REMOVE NODE command 199
- RENAME ADMIN command 227
- RENAME FILESPACE command 453
- RENAME NODE command 198
- RENAME SCRIPT command 382
- RENAME SERVERGROUP command 347
- RENAME STGPOOL command 180
- renaming an administrator ID 224
- reporting ANR9999D messages 419
- RESET BUFPOOL command 400
- RESET DBMAXUTILIZATION command 389, 392
- RESET LOGCONSUMPTION command 470
- RESET LOGMAXUTILIZATION command 389, 392
- resetting
 - administrative password 224
 - buffer pool statistic 400
 - database and recovery log volume utilization counter 392
 - user password expiration 228
- restartable restore session, client
 - canceling 221
 - interrupting, active 221
 - requesting information about 221
- restarting the server 365
- RESTORE STGPOOL command 467, 493
- restore to point-in-time, enabling for clients 270
- RESTORE VOLUME command 495
- RESTOREINTERVAL server option 221, 238, 265
- restoring a file 238
- restoring the database
 - point-in-time 477
 - to its most current state 482
- restricted policy privilege
 - granting 231
- restricted storage privilege
 - granting 232
- retain extra versions, description of 235, 257, 260
- retain only version, description of 235, 257, 260
- retention grace period
 - description of archive 253
 - description of backup 253
 - for backup sets 279
 - using archive 253
 - using backup 253
- RETEXTRA parameter 235, 257
- RETONLY parameter 235, 257
- retrieval date for files 147
- retrieving a file 238
- reuse of sequential volumes
 - delaying 158, 467
 - storage pool volumes 91
 - volume pending state 165
- roll-forward recovery
 - database backup trigger 482
 - mirroring recovery log 482
 - recovery log 482
- ROLLBACK command 386
- root user tasks
 - deactivate SNASVCMG mode sessions 220
 - free unused SNA LU6.2 links 219
- routing commands to servers 343
- RUN command 382

S

- SAN (storage area network)
 - client access to devices 37, 79

-
- SAN (storage area network) *(continued)*
 - Fibre Channel support 79
 - LAN-free data movement 37, 79
 - policy for clients using 268
 - sharing a library among servers 36, 73, 75
 - storage agent role 37
 - support summary 36, 73
 - schedule
 - associating client node with 287
 - checking the log file 294
 - coordinating 298
 - copying 294, 375
 - day of the week 373
 - defining 286, 373
 - deleting 294, 375
 - description of 285
 - expiration date 374
 - failed, querying 288, 297
 - frequency of service 373
 - initial start date 373
 - initial time 373
 - mode, setting 299
 - priority 374
 - querying 288
 - results of 296, 375
 - startup window 301, 373
 - uncertain status 298, 376
 - updating 373
 - viewing information about 288
 - schedule event
 - managing 296, 375
 - querying 296, 375
 - viewing information about 296, 375
 - scheduled operations, setting the maximum 301
 - scheduler workload, controlling 301
 - scheduling, central
 - client operations 277, 285, 293, 298
 - controlling the workload 301
 - coordinating 298
 - description of 17, 285
 - server operations 372
 - scheduling mode
 - client-polling 299
 - overview of 299
 - selecting 299
 - server-prompted 299
 - setting on a client node 300
 - setting on the server 299
 - scratch category, 349X library 67
 - scratch volume
 - deleting 128, 473
 - description 35
 - FILE volumes 46
 - number allowed in a storage pool 123, 181
 - using in storage pools 130
 - script, scheduling on client 289
 - script, server
 - continuation characters 378
 - copying 381
 - defining 377
 - deleting 382
 - script, server *(continued)*
 - EXIT statement 379
 - GOTO statement 379
 - IF clause 379
 - querying 381
 - renaming 382
 - routing commands in 344
 - running 382
 - substitution variables 378
 - updating 380
 - used with SNMP 423
 - SCSI library 27
 - SELECT command 410
 - selective backup 238, 248
 - selective recall 239
 - sending commands to servers 343
 - sequence number 215, 216
 - sequential mode for libraries 50
 - sequential storage pool
 - auditing a single volume in 490
 - auditing multiple volumes in 489
 - collocation 151
 - estimating space 160
 - migration threshold 144
 - reclamation 152
 - serialization parameter 235, 236, 256, 261
 - server
 - backing up subfiles on 282
 - canceling process 367
 - changing the date and time 365
 - description of 3
 - disabling access 220
 - enabling access 220
 - halting 364
 - importing subfiles from 284
 - managing operation 355
 - managing processes 365
 - messages 419
 - multiple instances 363
 - network of TSM 10, 309
 - options, adding or updating 368
 - prefix 344
 - querying about processes 366, 407
 - querying options 408
 - querying status 408
 - restarting 365
 - running multiple servers 363
 - setting the name 408
 - starting 359
 - stopping 364
 - viewing information about 408
 - viewing information about processes 366, 407
 - server console, description of 229
 - SERVER device type 348
 - server group
 - copying 347
 - defining 346
 - deleting 347
 - member, deleting 347
 - moving a member 347
 - querying 346

- server group *(continued)*
 - renaming 347
 - updating description 347
- server option
 - AUDITSTORAGE 359, 368
 - BUFPOOLSIZE 400
 - changing with SETOPT command 368
 - COMMTIMEOUT 217, 219
 - DEVCONFIG 474
 - ENABLE3590LIBRARY 67
 - EXPINTERVAL 265
 - EXPQUIET 265
 - IDLETIMEOUT 218, 219, 407
 - LOGPOOLSIZE 401
 - NOPREEMPT 367
 - NORETRIEVEDATE 147
 - RESTOREINTERVAL 221, 238, 265
 - THROUGHPUTDATATHRESHOLD 219
 - THROUGHPUTTIMETHRESHOLD 219
 - TXNGROUPMAX 135
 - VOLUMEHISTORY 473
- server-prompted scheduling 299
- server script
 - continuation characters 378
 - copying 381
 - defining 377
 - deleting 382
 - EXIT statement 379
 - GOTO statement 379
 - IF clause 379
 - querying 381
 - renaming 382
 - routing commands in 344
 - running 382
 - substitution variables 378
 - updating 380
 - used with SNMP 423
- server storage
 - client files, process for storing 4
 - concepts overview 4
 - considering user needs for recovering 41
 - deleting files from 184
 - evaluating 39
 - example 121
 - managing 4
 - monitoring 487
 - planning 39
 - protection, methods 458
 - tailoring definitions 450
 - using another TSM server 348
 - using disk devices 43
 - using the storage hierarchy 137
- server-to-server communications, establishing
 - enterprise configuration 314
 - enterprise event logging 314
 - virtual volumes 321
- server-to-server virtual volumes
 - reclaiming 155
 - using to store data 348
- session
 - canceling 218
- session *(continued)*
 - negative number 221
 - setting the maximum percentage for scheduled operations 301
- session, client
 - canceling 218
 - managing 217
 - querying 217, 406
 - recycling 219
 - viewing information about 217, 406
- SET ACCOUNTING command 431
- SET ACTLOGRETENTION command 417
- SET AUTHENTICATION command 229
- SET CLIENTACTDURATION command 304
- SET CONFIGMANAGER command 323, 326
- SET CONFIGREFRESH command 337
- SET CONTEXTMESSAGING command 419
- SET CROSSDEFINE command 316, 319
- SET DRMCHECKLABEL command 501
- SET DRMCOPYSTGPOOL command 499
- SET DRMCOURIERNAME command 501
- SET DRMDBBACKUPEXPIREDDAYS command 502
- SET DRMFILEPROCESS command 501, 502
- SET DRMINSTPREFIX command 500
- SET DRMNOTMOUNTABLE command 501
- SET DRMPLANPOSTFIX command 499
- SET DRMPLANPREFIX command 500
- SET DRMPRIMSTGPOOL command 499
- SET DRMRPFEXPIREDDAYS 508
- SET DRMVaultNAME command 502
- SET EVENTRETENTION command 298, 376
- SET INVALIDPWLIMIT command 228
- SET LICENSEAUDITPERIOD command 359
- SET LOGMODE command 472
- SET MAXCMDRETRIES command 303
- SET MAXSCHEDESESSIONS command 301
- SET PASSEXP command 228
- SET QUERYSCHEDPERIOD command 303
- SET RANDOMIZE command 302
- SET REGISTRATION command 191
- SET RETRYPERIOD command 304
- SET SCHEDMODES command 299
- SET SERVERHLADDRESS command 316, 319
- SET SERVERLLADDRESS command 316, 319
- SET SERVERNAME command 315, 316, 319, 368
- SET SERVERPASSWORD 315, 316, 319
- SET SUBFILE 282
- SET SUMMARYRETENTION 415
- SET WEBAUTHTIMEOUT command 228
- SETOPT command 368
- setting
 - clients to use subfile backup 283
 - compression 192
 - library mode 50
 - password 17, 228
- shared dynamic serialization, description of 256, 261
- shared library (SAN) 73, 75
- shared static serialization, description of 256, 261
- SNA LU6.2 219
- SNASVCMG session 219

-
- SNMP
 - agent 425
 - communications 425, 426
 - configuring 427
 - enabled as a receiver 418, 423
 - heartbeat monitor 418, 423
 - manager 425
 - subagent 425
 - source server 349
 - space
 - adding to the database or recovery log 395
 - deleting from the database or recovery log 397
 - planning how much to allocate 390
 - space-managed file 239
 - space trigger
 - database space 393
 - recovery log space 393
 - special file names 52
 - SQL 410
 - SQL activity summary table 415
 - standard management class, copying 255
 - standard storage management policies, using 235
 - start time, randomizing for a schedule 302
 - starting the server 359
 - startup window, description of 302
 - static serialization, description of 256, 261
 - status of a volume in an automated library 35
 - stopping the server 364
 - storage agent 37
 - storage area network (SAN)
 - client access to devices 37, 79
 - Fibre Channel support 79
 - LAN-free data movement 37, 79
 - policy for clients using 268
 - sharing a library among servers 36, 73, 75
 - storage agent role 37
 - support summary 36, 73
 - storage devices 105
 - storage hierarchy
 - defining in reverse order 125, 134
 - establishing 133
 - example 121
 - how TSM stores files in 134
 - next storage pool 133, 138, 146, 169, 183
 - staging data on disk for tape storage 137
 - Storage Management Analysis 430
 - storage management policies
 - description of 16, 240
 - managing 233
 - tailoring 251
 - using standard 235
 - storage occupancy, querying 173
 - storage pool
 - amount of space used 174
 - auditing a volume 487
 - backup and recovery 465
 - comparing primary and copy types 182
 - copy 121
 - creating a hierarchy 133
 - defining 123
 - defining for disk, example 125, 134
 - storage pool (*continued*)
 - defining for tape, example 125, 134
 - deleting 183
 - description of 120
 - destination in copy group 255, 261
 - determining access mode 123, 181
 - determining maximum file size 124
 - determining whether to use collocation 124, 147, 181
 - enabling cache for disk 124, 146
 - estimating space for archived files on disk 160
 - estimating space for backed up files on disk 159
 - estimating space for disk 159
 - estimating space for sequential 160
 - estimating space in multiple 133
 - managing 119
 - monitoring 161
 - moving files 176
 - moving files between 177
 - next storage pool 133, 138, 146, 169, 183
 - overview 30
 - policy use 255, 261
 - primary 120
 - querying 161
 - random access 120
 - recovery log, effect on 387
 - renaming 180
 - restoring 467, 493
 - sequential access 120
 - updating 123
 - updating for disk, example 126, 134
 - using cache on disk 124, 146
 - viewing information about 161
 - storage pool backup
 - full 465
 - incremental 465
 - storage privilege class
 - description of restricted 232
 - granting restricted 232
 - revoking 226
 - storage volume
 - auditing 487
 - contents 166
 - formatting random access 44, 129
 - information about 163
 - labeling sequential access 83, 129
 - monitoring use 162
 - overview 31
 - preparing sequential access 83, 129
 - stub file 239
 - subfile backups
 - deleting 284
 - description of 283
 - example of 283
 - expiring 284
 - restoring 284
 - subordinate storage pool 133
 - subscriber, deleting 342
 - subscription
 - defining 335, 337
 - deleting 338
 - scenario 336
-

substitution variables, using 378
swapping volumes in automated library 90
system privilege class
 description of 230
 granting 230
 revoking 226

T

tape
 exporting data 441
 finding for client node 168
 label prefix 108
 monitoring life 165
 planning for exporting data 437
 recording format 108
 reuse in storage pools 91
 scratch, determining use 123, 130, 181
 setting mount retention period 108
target server 349
technical publications, redbooks xxiii
threshold
 migration, for storage pool 139, 144
 reclamation 152
THROUGHPUTDATATHRESHOLD server option 219
THROUGHPUTTIMETHRESHOLD server option 219
Tivoli Decision Support 430
Tivoli event console 418, 421
Tivoli Space Manager
 archive policy, relationship to 250
 backup policy, relationship to 250
 description 239
 files, destination for 254
 migration of client files
 description 239
 eligibility 250
 policy for, setting 250, 254
 premigration 239
 recall of migrated files 239
 reconciliation between client and server 239
 selective migration 239
 setting policy for 250, 254
 space-managed file, definition 239
 stub file 239
Tivoli Storage Manager (TSM)
 introduction 3
 server network 10, 309
transactions, database 387, 388
transparent recall 239
trigger
 database space 393
 recovery log space 393
troubleshooting
 database errors (RSM) 71
TSM device drivers 51
tuning, server automatically 369
TXNBYTELIMIT client option 135
TXNGROUPMAX server option 135

type, device
 3570 107
 3590 107
 4MM 107
 8MM 107
 CARTRIDGE 107
 DISK 105
 DLT 107
 DTF 107
 ECARTRIDGE 107
 GENERICTAPE 107
 LTO 106
 OPTICAL 110
 QIC 107
 SERVER 107, 348, 349
 WORM 107
 WORM12 107
 WORM14 107

U

unavailable access mode
 description 132
 marked by server 98
uncertain, schedule status 298, 376
Unicode
 automatically renaming file space 207
 client platforms supported 204
 deciding which clients need enabled file spaces 205
 description of 204
 displaying Unicode-enabled file spaces 212
 example of migration process 211
 file space identifier (FSID) 212, 213
 how clients are affected by migration 210
 how file spaces are automatically renamed 208
 migrating client file spaces 206
 options for automatically renaming file spaces 206
unloading the database 402
UNLOCK ADMIN command 226
UNLOCK NODE command 199
UNLOCK PROFILE command 330, 332
unplanned shutdown 364
unrestricted policy privilege
 granting 231
unrestricted storage privilege
 granting 231
unusable space for database and recovery log 389
UPDATE ADMIN command 224
UPDATE BACKUPSET command 281
UPDATE CLIENTOPT command 216
UPDATE CLOPTSET command 216
UPDATE COPYGROUP command 255, 261
UPDATE DBBACKUPTRIGGER command 472
UPDATE DEVCLASS command 110
UPDATE DOMAIN command 253
UPDATE DRIVE command 100
UPDATE LIBRARY command 99
UPDATE LIBVOLUME command 36, 93
UPDATE MGMTCLASS command 255

UPDATE NODE command 198, 211, 215
 UPDATE POLICYSET command 254
 UPDATE RECOVERYMEDIA command 506
 UPDATE SCHEDULE command 373
 UPDATE SCRIPT command 380
 UPDATE SERVER command 321
 UPDATE VOLUME command 130
 URL
 client node 190
 usable space 389
 user exit 418
 user ID, administrative
 creating automatically 202
 description of 190
 preventing automatic creation of 203
 using the MAXNUMMP parameter to limit drives 81
 utilization, database and recovery log
 description of 389
 monitoring 389, 392

V

VALIDATE POLICYSET command 263
 variable, accounting log 432
 VARY command 45
 varying volumes on or off line 45
 VERDELETED parameter 235, 257
 VEREXISTS parameter 235, 257
 versions data deleted, description of 235, 257, 260
 versions data exists, description of 235, 257, 260
 virtual volumes, server-to-server
 reclaiming 155
 using to store data 348
 VIRTUALMOUNTPOINT client option 230
 volume capacity 109
 volume copy
 allocating to separate disks 463
 description of 463
 volume history backup, using to restore database 472, 478
 volume history files, establishing 403, 472
 volume history information, deleting 473
 VOLUMEHISTORY option 472
 volumes
 access, controlling 90
 access preemption 367
 adding to automated libraries 68
 allocating space for disk 44, 129
 assigning to storage pool 128
 auditing 95, 487
 auditing considerations 487
 automated library inventory 35
 capacity, compression effect 116
 checking in new volumes to library 87
 checking out 93
 contents, querying 166
 defining for database 395
 defining for recovery log 395
 defining to storage pools 130
 delaying reuse 158, 467

volumes (*continued*)
 deleting 184, 185, 473
 detailed report 167
 determining which are mounted 98, 438
 disk storage 130
 disk storage pool, auditing 489
 dismounting 98
 errors, read and write 164
 estimated capacity 164
 finding for client node 168
 inventory maintenance 90
 location 165
 managing 93
 monitoring life 165
 monitoring movement of data 179
 monitoring use 162
 mount retention time 108
 moving files between 176
 pending status 165
 private 35
 querying contents 166
 querying for general information 163
 random access storage pools 120, 130
 reclamation 155
 recovery using mirroring 485
 removing from a library 93
 returning to a library 94
 reuse delay 158, 467
 scratch, using 130
 scratch category 36
 sequential 130
 sequential storage pools 83, 129
 setting access mode 131
 standard report 166
 status, in automated library 35
 status, information on 164
 swapping 90
 updating 93, 130
 using private 35
 varying on and off 45

W

web administrative interface
 description 14
 setting authentication time-out value 228
 Web backup-archive client
 granting authority to 202
 remote access overview 200
 URL 190, 201
 Web sites xxi, xxiii
 wizard
 client configuration 194
 setup 194
 workstation, registering 192
 WORM device class
 defining 110
 maintaining volumes in a library 92
 reclamation of media 155



Program Number: 5698-TSM
5698-DRM



Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

GC35-0403-01



Spine information:

Tivoli Storage Manager for AIX Administrator's Guide,

Version 4 Release 2