
OpenVMS VAX Version 7.1 Upgrade and Installation Manual

Order Number: AA-QSBQB-TE

November 1996

This manual provides step-by-step instructions for upgrading and installing the OpenVMS VAX operating system.

Revision/Update Information: This is a new manual.

Operating System and Version: OpenVMS VAX Version 7.1

**Digital Equipment Corporation
Maynard, Massachusetts**

November 1996

Digital Equipment Corporation makes no representations that the use of its products in the manner described in this publication will not infringe on existing or future patent rights, nor do the descriptions contained in this publication imply the granting of licenses to make, use, or sell equipment or software in accordance with the description.

Possession, use, or copying of the software described in this publication is authorized only pursuant to a valid written license from Digital or an authorized sublicensor.

Digital conducts its business in a manner that conserves the environment and protects the safety and health of its employees, customers, and the community.

© Digital Equipment Corporation 1996. All rights reserved.

The following are trademarks of Digital Equipment Corporation: Bookreader, CDA, CI, DEC, DECdirect, DECdtm, DEC PHIGS, DECnet, DECset, DECterm, DECtp, DECwindows, DEQNA, Digital, Digital UNIX, EDCS, HSC, HSC50, HSC70, InfoServer, LAT, MANAGEWORKS, MicroVAX, MicroVAX II, MUXserver, OpenVMS, OpenVMS Volume Shadowing, PATHWORKS, Q-bus, RX01, RX33, RX50, TK, UETP, ULTRIX, VAX, VAX 4000, VAX 6000, VAX 8200, VAX 8250, VAX 8300, VAX 8350, VAX 8530, VAX 8550, VAX 8600, VAX 9000, VAX-11/730, VAX-11/750, VAX-11/780, VAX-11/785, VAX C, VAXBI, VAXcluster, VAXELN, VAXft, VAXlink, VAXserver, VAXset, VAXstation, VIDA, VMS, VR150, VR160, WPS-PLUS, XMI, XUI, and the DIGITAL logo.

The following are third-party trademarks:

Adobe, Adobe Illustrator, Display POSTSCRIPT, and POSTSCRIPT are registered trademarks of Adobe Systems Incorporated.

Microsoft, MS, and MS-DOS are registered trademarks, and Windows 95 and Windows NT are trademarks of Microsoft Corporation.

Motif, OSF, OSF/1, OSF/Motif, and Open Software Foundation are registered trademarks of the Open Software Foundation, Inc.

NetView is a registered trademark of International Business Machines Corporation.

OSI is a registered trademark of CA Management, Inc.

UNIX is a registered trademark in the United States and other countries, licensed exclusively through X/Open Company Limited.

X/Open is a trademark of X/Open Company Limited.

All other trademarks and registered trademarks are the property of their respective holders.

ZK6487

The OpenVMS documentation set is available on CD-ROM.

Contents

Preface	xiii
1 Overview of Installation and Upgrade Procedures	
1.1 Introduction	1-1
1.2 Important Information	1-1
1.2.1 DECnet-Plus	1-1
1.2.2 DECwindows Motif for OpenVMS—Minimum Version	1-2
1.2.3 MACRO32.EXE and Standalone Backup	1-3
1.2.4 Layered Product Availability	1-3
1.2.5 Restrictions	1-3
1.3 Definitions: A Few Key Terms	1-3
1.4 Locating Files on the Distribution Media	1-4
1.4.1 On Magnetic Tape	1-5
1.4.2 On Tape Cartridges	1-5
1.4.3 On Compact Disc	1-5
1.4.4 DECcmds and Monitoring Performance History (MPH) Files	1-5
1.4.5 Software Product Descriptions (SPDs)	1-5
1.5 What Happens During an Installation	1-6
1.5.1 When to Perform an Installation	1-6
1.5.2 How to Use the Installation Documentation	1-7
1.6 What Happens During an Upgrade	1-9
1.6.1 When to Perform an Upgrade	1-9
1.6.2 How to Use the Upgrade Documentation	1-9
1.7 Where to Go Next	1-10
2 Before Installing OpenVMS VAX Software	
2.1 Overview	2-1
2.2 Cautions and Restrictions	2-1
2.2.1 Cautions	2-1
2.2.2 Restrictions	2-2
2.3 Are You Ready to Install?	2-2
2.3.1 Hardware Components	2-2
2.3.2 Software Components	2-2
2.4 Preparing for an Installation	2-3
2.4.1 Preparing for a C2 System	2-3
2.4.2 Preparing for a VAXcluster Environment	2-3
2.4.3 Preparing Tape and Disk Drives	2-4
2.4.4 Information You Need During the Installation	2-5
2.5 Preinstallation Checklist	2-6

3 Installing the OpenVMS VAX Operating System

3.1	Overview	3-1
3.2	Booting Standalone BACKUP	3-1
3.2.1	Booting from Tape Cartridge	3-1
3.2.2	Booting from an InfoServer Device	3-2
3.2.3	Booting OpenVMS from the CD-ROM	3-3
3.3	Creating the System Disk	3-4
3.3.1	Step 1: Determine Device Names	3-4
3.3.2	Step 2: Load Distribution Media	3-4
3.3.3	Step 3: Transfer VMS071.B to Your System Disk	3-4
3.3.4	Step 4: Boot the New System Disk	3-6
3.3.5	Step 5: Specify the Volume Label	3-7
3.3.6	Step 6: Specify the Source Drive	3-7
3.3.7	Step 7: Select Optional OpenVMS Components	3-7
3.3.7.1	OpenVMS Library Files	3-8
3.3.7.2	OpenVMS Optional Files	3-8
3.3.7.3	Help Message Files	3-9
3.3.7.4	OpenVMS Management Station Files	3-9
3.3.8	Step 8: Choose DECwindows Support Options	3-10
3.3.9	Step 9: Select DECnet Product	3-11
3.3.10	Step 10: Verify Your Choices	3-12
3.3.11	Step 11: Install OpenVMS Options	3-12
3.3.11.1	Compact Disc	3-12
3.3.11.2	Tape Cartridges and 9-Track Open Reel Magnetic Tapes	3-12
3.4	Configuring a Cluster	3-13
3.5	Setting Passwords	3-14
3.6	Entering SCSNODE and SCSSYSTEMID Parameters	3-15
3.7	Postinstallation Tasks Described	3-15
3.8	Registering Licenses	3-16
3.8.1	Types of Licenses	3-16
3.8.2	How to Register Your Licenses	3-17
3.8.2.1	How to Register OpenVMS VAX Licenses	3-18
3.8.2.2	How to Register System Integrated Products	3-19
3.9	Time Zone and Time Differential Factor Information	3-20
3.9.1	Updating Time Zone Information	3-20
3.10	Installing DECnet-Plus	3-20
3.11	Running AUTOGEN	3-21

4 After Installing OpenVMS VAX

4.1	Overview	4-1
4.2	Verifying System Time	4-1
4.3	Registering Your Licenses	4-2
4.3.1	Where to Find More Information	4-2
4.4	Backing Up Your System Disk	4-2
4.5	Customizing the System	4-2
4.6	Configuring and Starting Networking Software	4-3
4.6.1	Configuring Your System	4-3
4.6.2	Editing SYSTARTUP_VMS	4-3
4.7	Testing the System with UETP Software	4-4
4.8	Decompressing System Libraries	4-4
4.9	Removing or Adding OpenVMS Files	4-6
4.10	Installing Layered Products	4-6
4.10.1	TCP/IP Services for OpenVMS	4-6

4.11	Backing Up the Customized System Disk	4-6
4.12	Running AUTOGEN	4-7
4.12.1	How AUTOGEN Works	4-7
4.12.2	When to Run AUTOGEN	4-7
4.13	Postinstallation Checklist	4-7

5 Before Upgrading OpenVMS VAX Software

5.1	Overview	5-1
5.2	Cautions and Restrictions	5-1
5.2.1	License Requirements	5-1
5.2.2	DECset Version 11 Debugger	5-2
5.2.3	Customized Security Environment	5-2
5.2.4	Operator and Accounting Logs	5-3
5.2.5	Special Testing and Debugging Files	5-3
5.2.6	Cluster Considerations	5-3
5.2.7	Save Set Location	5-3
5.2.8	System Disk Cautions	5-4
5.2.9	AUTOGEN Feedback Data	5-4
5.2.10	OpenVMS Version Requirements	5-4
5.2.11	DECwindows Motif Version Requirements	5-4
5.2.12	Shared System Dump Files	5-4
5.2.13	Layered Products	5-5
5.3	Are You Ready to Upgrade?	5-5
5.3.1	Hardware Components	5-5
5.3.2	Software Components	5-5
5.4	Examining AUTOGEN Feedback Data	5-5
5.4.1	Valid Feedback Data	5-6
5.4.2	How to Test Feedback Data	5-6
5.5	Performing Backup Tasks	5-6
5.5.1	How to Back Up the System Disk	5-6
5.5.2	How to Back Up Console Media	5-7
5.6	Preparing Your System Disk	5-7
5.6.1	Create a Nonshadowed System Disk	5-7
5.6.2	Boot the Backup Copy of Your System Disk	5-7
5.6.3	Copy UAF and Auditing Files to the System Disk	5-8
5.6.4	Rename the System Dump File	5-8
5.6.5	Analyze the System Disk	5-8
5.6.6	Check Page and Swap Files	5-8
5.6.7	Check for Free Blocks	5-9
5.6.8	Check Quotas and Limits	5-9
5.6.9	Set System Parameters	5-10
5.6.10	Check AGEN\$INCLUDE Files	5-11
5.6.11	Add Modified System Parameters to MODPARAMS.DAT	5-12
5.7	Preparing the System	5-12
5.7.1	Enable Auto Restart or Manual Reboot	5-12
5.7.2	Shut Down and Reboot the System	5-12
5.7.3	Prevent Interactive Logins	5-12
5.7.4	Check for DECnet	5-12
5.7.5	Check for Volume Shadowing	5-13
5.7.6	Stop Queues	5-13
5.8	Gathering Information for the Upgrade	5-14
5.9	Preupgrade Checklist	5-15

6 Upgrading a VAXcluster Environment

6.1	Overview	6-1
6.2	Concurrent and Rolling Upgrades	6-1
6.2.1	Concurrent Upgrades	6-1
6.2.2	Rolling Upgrades	6-1
6.3	Performing a Concurrent Upgrade	6-2
6.3.1	Concurrent Upgrade Procedure	6-2
6.4	Performing a Rolling Upgrade	6-3
6.4.1	Restrictions	6-3
6.4.2	Rolling Upgrade Procedure	6-3
6.5	Adding an OpenVMS VAX Version 7.1 Supported CPU	6-5

7 Upgrading the OpenVMS VAX Operating System

7.1	Overview	7-1
7.2	Preparing to Boot from [SYSF]	7-1
7.2.1	Modifying Boot Command Procedures	7-2
7.2.2	VAX 8200, 8250, 8300, and 8350 Computers	7-2
7.2.3	Configuring Devices	7-2
7.3	Beginning the Upgrade Procedure	7-2
7.3.1	Step 1: Load Distribution Media	7-3
7.3.2	Step 2: Upgrading from the InfoServer	7-3
7.3.3	Step 3: Start VMSINSTAL	7-3
7.3.4	Step 4: Back Up the System Disk	7-4
7.3.5	Step 5: Specify the Source Drive	7-4
7.3.6	Step 6: Enter Product Name	7-5
7.3.7	Step 7: Mount the First Volume	7-5
7.3.8	Step 8: Monitor Messages from VMSINSTAL	7-5
7.3.9	Step 9: Verify Date and Time	7-6
7.4	Upgrade Phase 1	7-6
7.4.1	Step 1: Specify Type of Upgrade	7-6
7.4.2	Step 2: Enter Passwords	7-6
7.4.3	Step 3: Choose Boot Method	7-7
7.4.4	Step 4: File Cleanup	7-8
7.4.5	Step 5: Select Optional OpenVMS Components	7-9
7.4.5.1	OpenVMS Library Files	7-9
7.4.5.2	OpenVMS Optional Files	7-10
7.4.5.3	Help Message Files	7-10
7.4.5.4	OpenVMS Management Station Files	7-10
7.4.6	Step 6: Choose DECwindows Support Options	7-11
7.4.7	Step 7: Select Networking Software	7-12
7.4.8	Step 8: Verify Your Choices	7-13
7.4.9	Step 9: Shut Down Your System	7-13
7.4.10	Step 10: Reboot the System	7-13
7.4.11	Step 11: Verify System Time	7-13
7.5	Upgrade Phase 2	7-14
7.5.1	What the Procedure Does	7-14
7.5.1.1	Mounting Additional Tape Cartridge and 9-Track Open Reel Magnetic Tape Volumes	7-14
7.6	Upgrade Phase 3	7-15
7.6.1	What the Procedure Does	7-15
7.7	Upgrade Phase 4	7-15
7.7.1	What the Procedure Does	7-15
7.7.2	What You Do	7-16

7.8	Upgrade Phase 5	7-16
7.9	Upgrade Phase 6	7-17
7.9.1	Restoring System Files	7-17
7.9.2	Registering Licenses	7-17
7.9.3	Updating Time Zone Information	7-18
7.9.4	Installing DECnet-Plus	7-18
7.9.5	Running AUTOGEN	7-19
7.9.6	Shutting Down the System	7-19
7.9.7	Booting Voting Nodes	7-20
7.9.8	Executing STARTUP	7-20
7.9.9	Logging In	7-20

8 After Upgrading OpenVMS VAX

8.1	Verifying System Time	8-2
8.2	Restoring the Preferred Node List	8-2
8.3	Replacing SYSUAF.DAT and VM\$AUDIT_SERVER.DAT	8-2
8.4	Examining AGEN\$PARAMS.REPORT	8-2
8.5	Checking the Size of System Files	8-3
8.6	Examining Your Command Procedures	8-3
8.7	Changing MODPARAMS.DAT	8-4
8.8	Updating Your Console Media	8-4
8.9	VAX 8530, 8550, 8810 (8700), 8820-N (8800) Computers	8-4
8.9.1	VAX-11/730, 750, 780, 785 and VAX 8200, 8250, 8300, 8350, 8600, 8650 Computers	8-5
8.9.2	VAX 9000 Computers	8-6
8.10	Decompressing the System Libraries	8-6
8.10.1	How to Decompress Libraries	8-7
8.11	Testing the System with UETP	8-8
8.12	Increasing Free Space on the System Disk	8-8
8.12.1	Using VM\$TAILOR and DECW\$TAILOR	8-8
8.12.2	Purging System Files	8-9
8.13	Restoring Your System Password Dictionary	8-9
8.14	Customizing DECwindows Support Software	8-9
8.15	Preparing to Run the OpenVMS Management Station	8-10
8.16	Installing Layered Products	8-10
8.16.1	TCP/IP Services for OpenVMS	8-10
8.17	Backing Up the System Disk	8-11
8.18	Running AUTOGEN	8-11
8.19	Postupgrade Checklist	8-12

9 Customizing DECwindows Support Software

9.1	Overview	9-1
9.2	Customizing the Server Startup	9-1
9.2.1	Assumptions	9-1
9.2.2	How to Override Incorrect Assumptions	9-2
9.3	Using Digital TCP/IP Services for OpenVMS	9-5
9.4	Using Other Transports with DECwindows	9-6
9.4.1	Writing a Transport Interface	9-6
9.4.2	Installing the Transport Interface Image	9-6
9.5	Using the Example Transport	9-6

10 Using VMSTAILOR and DECW\$TAILOR

10.1	Using VMSTAILOR	10-1
10.1.1	How VMSTAILOR Works	10-1
10.1.2	Removing OpenVMS VAX Files	10-3
10.1.3	Adding OpenVMS VAX Files	10-3
10.1.4	Sample Session	10-5
10.2	Using DECW\$TAILOR	10-6
10.2.1	How DECW\$TAILOR Works	10-6
10.2.2	DECwindows Files You Can Tailor	10-7
10.2.3	Removing DECwindows Files	10-7
10.2.4	Adding DECwindows Files	10-8
10.2.5	Sample Session	10-9

A Multiversion VAX Upgrade Process

A.1	Determine Your Path	A-1
A.2	Multiversion Upgrade Procedure	A-1
A.2.1	Before You Begin the Upgrade	A-2
A.2.2	Intermediate Upgrade	A-2
A.2.3	Final Upgrade	A-3
A.3	Specific Layered Product and Firmware Information	A-3
A.3.1	Layered Products	A-3

B License Management Notes

B.1	Overview	B-1
B.2	Registering Your Licenses	B-1
B.2.1	When to Register	B-1
B.2.2	How to Register	B-2
B.3	Using the License Unit Requirement Table (LURT)	B-3
B.4	License Management Facility Notes	B-6
B.5	Volume Shadowing for OpenVMS License	B-6
B.5.1	When to Register	B-7
B.5.2	Volume Shadowing Phase I and Phase II	B-7
B.5.3	Types of Licenses	B-7
B.6	Other System Integrated Product Licenses	B-7

C Booting from [SYSF] During an Upgrade

C.1	Booting Procedures	C-1
C.1.1	MicroVAX and VAXstation Computers	C-1
C.1.2	VAX 8530, 8550, 8810 (8700), 8820-N (8800) Computers	C-1
C.1.3	VAX 8820, 8830, and 8840 Computers	C-2
C.1.4	VAX-11/750, 8200, 8250, 8300, and 8350 Computers	C-2
C.1.5	VAX-11/730, 11/780, 11/785, 8600, and 8650 Computers	C-3
C.1.6	VAX 6000 Series	C-5
C.1.7	VAX 9000 Series	C-6

D OpenVMS VAX Save Set Subclasses

D.1	Save Set C Subclasses	D-1
D.2	Save Set D Subclasses	D-2
D.3	Save Set E Subclasses	D-2
D.4	Save Set F Subclasses	D-2

E DECwindows Display Server and Fonts Components

E.1	Table of Components	E-1
-----	---------------------------	-----

F NEW_OVER and NEW_UNDER Files

F.1	Where Files Are Installed	F-1
F.1.1	NEW_OVER Files	F-2
F.1.2	NEW_UNDER Files	F-2
F.1.3	Site-Specific Files	F-3

G Preparing to Use OpenVMS Management Station

G.1	Preparing Your OpenVMS System	G-1
G.1.1	Files Installed on Your OpenVMS System	G-2
G.1.2	Setting Up in a Mixed-Architecture Cluster Environment	G-2
G.1.3	Start the Server on Other Nodes	G-3
G.1.4	Update the Printer Database	G-3
G.1.5	Edit the System Files	G-4
G.1.6	Allow OpenVMS Management Station to Control the Printer Environment	G-4
G.1.7	Keep Your Printer Environment Up to Date	G-4
G.1.7.1	When Does TNT\$UTILITY.COM Run?	G-5
G.1.7.2	Do You Need to Run TNT\$UTILITY.COM Manually?	G-5
G.1.7.3	Are There Any Requirements for Running TNT\$UTILITY.COM?	G-6
G.1.8	Enabling Disk Quotas	G-6
G.1.9	Running Third-Party TCP/IP Stacks	G-6
G.1.10	Determining and Reporting Problems	G-6
G.2	Preparing Your PC	G-7
G.2.1	Required Memory and Disk Space	G-7
G.2.2	Required Software	G-7
G.2.3	TeamLinks Version 1.0 is Not Supported	G-8
G.2.4	Creating the Installation Media	G-8
G.2.5	Installing the OpenVMS Management Station Client Software on Your PC	G-9
G.2.5.1	Installation Directory	G-9
G.2.5.2	Installation Procedure	G-9
G.2.5.3	Recovering from Errors	G-10
G.2.5.4	Files Created on the PC	G-10
G.2.6	After Installing the Client Software on Your PC	G-11
G.2.6.1	Defining TCP/IP Nodes	G-12
G.2.6.2	DECnet Support	G-12
G.2.6.3	Procedure for Defining DECnet Nodes	G-12
G.2.7	PATHWORKS and Workgroup Administrator Support	G-12
G.2.8	POLYCENTER Manager on NetView for Windows NT, Version 3.0 ...	G-12
G.3	Getting Started with OpenVMS Management Station	G-13
G.3.1	Accessing Online Help	G-13

H Small Capacity System Disks

H.1	Overview	H-1
H.2	Limited Space Support	H-1
H.2.1	Limited Space Support Option	H-1
H.2.2	Configurations Affected	H-2
H.2.3	Dealing with a Small System Disk	H-2
H.3	Tailoring Considerations	H-2
H.3.1	Configuration Goals	H-3
H.3.2	Controlling the Size of Dump, Page, and Swap Files	H-3
H.3.3	Make a Backup Copy of Your System Disk	H-4
H.3.4	Analyze the System Disk	H-4
H.3.5	Tailoring Options	H-4
H.4	Installing OpenVMS VAX and DECwindows Motif	H-5
H.4.1	Install OpenVMS VAX Version 7.1	H-5
H.4.2	Install DECwindows Motif	H-5
H.5	Upgrading OpenVMS VAX and DECwindows Motif	H-6
H.5.1	Upgrading to OpenVMS VAX Version 7.1	H-6
H.6	Managing Single or Small System Disk Systems	H-6
H.6.1	System Dump File	H-7
H.6.2	Using PAGEFILE.SYS for the Dump File	H-7
H.6.3	Decompressing Libraries	H-8
H.6.4	Disabling Log File Creation	H-8
H.6.5	Accessing Example and Documentation Files	H-9
H.7	Managing Multiple Disk Systems	H-9
H.7.1	Alternate Page and Swap Files	H-9
H.7.2	Copying Dump Files	H-10
H.7.3	Offloading System Logs and Files	H-10
H.7.4	Offloading Nonessential Files	H-10

Glossary

Index

Examples

10-1	Sample VMSTAILOR Session	10-5
10-2	Sample DECWSTAILOR Session	10-9

Figures

1-1	Documentation Used to Perform an Installation	1-8
1-2	Documentation Used to Perform an Upgrade	1-10

Tables

2-1	VAXcluster Information for Installations	2-3
4-1	Sizes of Decompressed System Libraries	4-4
8-1	Sizes of Decompressed System Libraries	8-7
9-1	DECwindows Keymap	9-3
A-1	OpenVMS VAX Upgrade Version Matrix	A-1
B-1	First VMS or OpenVMS Version That Supports VAX Computers.....	B-2
B-2	License Unit Requirement Table (LURT)	B-3
E-1	DECwindows Display Server and Fonts Components	E-1
G-1	Prerequisite and Optional Software for PCs	G-7

Preface

This manual is your primary source for information about upgrading and installing the OpenVMS VAX Version 7.1 operating system. Before you attempt to install or upgrade the operating system, be sure to read all the release notes and cover letters (if any) included in your distribution kit.

If you received factory-installed software with your computer, read that user documentation first for information about starting up your system. Otherwise, use this manual for step-by-step instructions for performing an installation or an upgrade. When the instructions in this manual direct you to do so, refer to the upgrade and installation supplement for information specific to your VAX computer.

Intended Audience

If you are responsible for installing or upgrading the OpenVMS operating system and for performing related backup, shutdown, and startup procedures, read this manual before you install or upgrade to Version 7.1 of the OpenVMS VAX operating system.

Document Structure

The information in this manual is organized as follows:

- Chapter 1 provides an overview of the upgrade and installation procedures. It describes what happens during an installation or an upgrade, lists some changes and restrictions you should be aware of, and refers you to the appropriate documentation.
- Chapter 2 describes the tasks you must perform before installing the OpenVMS VAX operating system.
- Chapter 3 describes how to install Version 7.1 of the OpenVMS VAX operating system on a VAXcluster or a standalone VAX computer.
- Chapter 4 lists the tasks you should perform after you install the OpenVMS VAX operating system.
- Chapter 5 contains cautions, restrictions, and requirements for upgrading your VAX computer system and tells you how to prepare your system for an upgrade.
- Chapter 6 contains additional information for upgrading a VAXcluster environment.
- Chapter 7 describes the procedure for upgrading a standalone VAX computer.
- Chapter 8 lists the tasks you should perform after the upgrade.
- Chapter 9 describes how to customize DECwindows device support software.

- Chapter 10 describes how to use VMSTAILOR and DECW\$TAILOR to add or remove optional OpenVMS software.
- Appendix A provides a quick method of applying multiple upgrades to a VAX system.
- Appendix B provides notes and supplemental license management information to the upgrade and installation procedures.
- Appendix C describes how to boot from the [SYSF] directory on the different types of VAX computers.
- Appendix D lists the subclasses in the OpenVMS VAX optional save sets C, D, E, and F.
- Appendix E lists DECwindows display server and font files.
- Appendix F lists files installed either over or under the version numbers of existing files during an upgrade.
- Appendix G describes how to prepare your OpenVMS system and your PC to run the OpenVMS Management Station server and client software.
- Appendix H describes methods for managing small capacity system disks, including some specific recommendations for installing or upgrading to the OpenVMS VAX Version 7.1 operating system and the DECwindows Motif for OpenVMS Version 1.2–3 layered product.
- The Glossary defines commonly used terms.
- The Index provides a quick way to find information.

Related Documents

The following documents contain information associated with performing an upgrade or installation:

- The upgrade and installation supplement for your VAX computer—Provides supplemental information necessary during an installation or upgrade, such as booting the system and determining device names.
- *OpenVMS Version 7.1 Release Notes* —Describes changed and enhanced software features, software problems and restrictions, and changes to the documentation for Version 7.1 of the OpenVMS VAX operating system.
- *OpenVMS Version 7.1 New Features Manual*—Describes new software features for the OpenVMS Version 7.1 operating system.
- *OpenVMS Cluster Systems*—Describes the procedures for establishing and managing VAXcluster configurations.
- *OpenVMS License Management Utility Manual*—Provides information about registering and managing licenses on an OpenVMS VAX system.
- *OpenVMS Guide to System Security*—Describes security features provided by the OpenVMS VAX operating system, including criteria for C2 systems.
- *OpenVMS System Manager's Manual*—Provides task-oriented information about managing an OpenVMS system, including how to use the VMSINSTAL command procedure.
- *OpenVMS DCL Dictionary*—Provides detailed reference information and examples for all OpenVMS DCL commands.

- *OpenVMS System Management Utilities Reference Manual: M-Z*—Provides complete information about using the POLYCENTER Software Installation utility PRODUCT command.
- The hardware manuals supplied with your VAX computer provide detailed information about system hardware.

For additional information about the Open Systems Software Group (OSSG) products and services, access the Digital OpenVMS World Wide Web site. Use the following URL:

<http://www.openvms.digital.com>

Reader's Comments

Digital welcomes your comments on this manual.

Print or edit the online form SYSSHELP:OPENVMSDOC_COMMENTS.TXT and send us your comments by:

Internet	openvmsdoc@zko.mts.dec.com
Fax	603 881-0120, Attention: OSSG Documentation, ZKO3-4/U08
Mail	OSSG Documentation Group, ZKO3-4/U08 110 Spit Brook Rd. Nashua, NH 03062-2698

How To Order Additional Documentation

Use the following table to order additional documentation or information. If you need help deciding which documentation best meets your needs, call 800-DIGITAL (800-344-4825).

Telephone and Direct Mail Orders

Location	Call	Fax	Write
U.S.A.	DECdirect 800-DIGITAL 800-344-4825	Fax: 800-234-2298	Digital Equipment Corporation P.O. Box CS2008 Nashua, NH 03061
Puerto Rico	809-781-0505	Fax: 809-749-8300	Digital Equipment Caribbean, Inc. 3 Digital Plaza, 1st Street, Suite 200 P.O. Box 11038 Metro Office Park San Juan, Puerto Rico 00910-2138
Canada	800-267-6215	Fax: 613-592-1946	Digital Equipment of Canada, Ltd. Box 13000 100 Herzberg Road Kanata, Ontario, Canada K2K 2A6 Attn: DECdirect Sales
International	—	—	Local Digital subsidiary or approved distributor
Internal Orders	DTN: 264-4446 603-884-4446	Fax: 603-884-3960	U.S. Software Supply Business Digital Equipment Corporation 8 Cotton Road Nashua, NH 03063-1260

ZK-7654A-GE

Conventions

In this manual, every use of OpenVMS VAX means the OpenVMS VAX operating system.

Every use of DECwindows and DECwindows Motif refers to DECwindows Motif for OpenVMS software.

The following conventions are also used in this manual:

Ctrl/x A sequence such as Ctrl/x indicates that you must hold down the key labeled Ctrl while you press another key or a pointing device button.

PF1 x A sequence such as PF1 x indicates that you must first press and release the key labeled PF1, then press and release another key or a pointing device button.

Return In examples, a key name enclosed in a box indicates that you press a key on the keyboard. (In text, a key name is not enclosed in a box.)

...	A horizontal ellipsis in examples indicates one of the following possibilities: <ul style="list-style-type: none"> • Additional optional arguments in a statement have been omitted. • The preceding item or items can be repeated one or more times. • Additional parameters, values, or other information can be entered.
. . .	Vertical ellipsis points indicate the omission of items from a code example or command format; the items are omitted because they are not important to the topic being discussed.
()	In format descriptions, parentheses indicate that, if you choose more than one option, you must enclose the choices in parentheses.
[]	In format descriptions, brackets indicate optional elements. You can choose one, none, or all of the options. (Brackets are not optional, however, in the syntax of a directory name in an OpenVMS file specification, or in the syntax of a substring specification in an assignment statement.)
{ }	In format descriptions, braces surround a required choice of options; you must choose one of the options listed.
text style	This text style represents the introduction of a new term or the name of an argument, an attribute, or a reason. This style is also used to show user input in Bookreader versions of the manual.
<i>italic text</i>	Italic text emphasizes important information, indicates variables, and indicates complete titles of manuals. Italic text also represents information that can vary in system messages (for example, Internal error <i>number</i>), command lines (for example, /PRODUCER= <i>name</i>), and command parameters in text.
UPPERCASE TEXT	Uppercase text indicates a command, the name of a routine, the name of a file, or the abbreviation for a system privilege.
-	A hyphen in code examples indicates that additional arguments to the request are provided on the line that follows.
numbers	All numbers in text are assumed to be decimal, unless otherwise noted. Nondecimal radices—binary, octal, or hexadecimal—are explicitly indicated.

This manual often refers to products by their abbreviated names. For example, the VAX 8200, VAX 8250, VAX 8300, and VAX 8350 computers are referred to as the VAX 8200, 8250, 8300, 8350. The MicroVAX 2000 computer is referred to as the MicroVAX 2000, and so on.

Overview of Installation and Upgrade Procedures

1.1 Introduction

This chapter provides a general description of what happens during the installation and upgrade procedures, including information you should be aware of before you upgrade to or install the OpenVMS VAX Version 7.1 operating system.

This chapter also describes the contents of the distribution kit, tells you whether you should do an installation or an upgrade, and refers you to the appropriate documentation.

1.2 Important Information

Before you install or upgrade to OpenVMS VAX Version 7.1, you should review the information in this section.

1.2.1 DECnet-Plus

The OpenVMS VAX Version 7.1 kit includes the DECnet-Plus software. The DECnet Phase IV product is no longer part of the operating system installation and upgrade menus. During the OpenVMS VAX installation or upgrade procedure, you are given the option to install the DECnet-Plus product. Whether or not you chose to install DECnet-Plus, DECnet Phase IV will not be present on your system after you install or upgrade to OpenVMS VAX Version 7.1.

A kit containing the DECnet-Plus software is provided with the OpenVMS VAX Version 7.1 kit. In future releases, customers who do not receive the operating system installation kit on CD-ROM will need to purchase the DECnet-Plus media and documentation separately.

If you want to use the DECnet Phase IV product, a DECnet Phase IV kit is provided, which you can install after you have installed OpenVMS VAX Version 7.1. However, be aware that, if you install or reinstall DECnet Phase IV, you must purchase a separate support contract.

Note

If DECnet-Plus is installed on your system, you must remove that product before you install the DECnet Phase IV product. Both DECnet products cannot run at the same time.

Overview of Installation and Upgrade Procedures

1.2 Important Information

To install DECnet Phase IV, do the following after the OpenVMS VAX installation or upgrade is complete:

- If DECnet-Plus is installed on your system, use the PRODUCT REMOVE command to remove that product. (See *OpenVMS System Management Utilities Reference Manual: M-Z* for complete information about using the PRODUCT command.)
- Mount the distribution media that contains the DECnet Phase IV kit.
For example, if your OpenVMS VAX distribution media is on CD-ROM and you want to mount it on a local drive, DKA400, you would enter a command similar to the following:

```
$ MOUNT/OVER=ID DKA400
```

If you are using an InfoServer device, enter the following command to see if the device DAD0 is present on your system:

```
$ SHOW DEVICE DAD0
```

If DAD0 is *not* present, enter the following:

```
$ @SYS$STARTUP:ESS$STARTUP CLIENT
```

Once DAD0 is present, bind to the service and mount the CD. For example, if the service name is VAXVMS071, you would enter a command similar to the following:

```
$ MCR ESS$LADCP BIND VAXVMS071  
$ MOUNT/OVER=ID DAD$VAXVMS071
```

Now, invoke the POLYCENTER Software Installation utility and install DECnet Phase IV by entering a command similar to the following:

```
$ PRODUCT INSTALL DECNET_PHASE_IV /SOURCE=DKA400:[KITS.DECNET_PHASE_IV_KIT]
```

For DKA400, substitute the correct name for your source drive.

- If your distribution media is on TK50 tapes, mount the TK50 volume that contains the DECnet Phase IV kit.
For example, if the device name of your TK50 drive is MKA500, you would enter a command similar to the following:

```
$ MOUNT/OVER=ID MKA500:
```

Now, install the DECnet Phase IV product by entering a command similar to the following:

```
$ PRODUCT INSTALL DECNET_PHASE_IV /SOURCE=MKA500:
```

For MKA500:, substitute the correct name for your source drive.

For more information about the DECnet-Plus product, see the *OpenVMS Version 7.1 New Features Manual* and the *DECnet/OSI for OpenVMS Installation and Configuration*.

1.2.2 DECwindows Motif for OpenVMS—Minimum Version

For OpenVMS VAX Version 7.1, the minimum supported version of DECwindows Motif for OpenVMS is 1.2-3.

1.2.3 MACRO32.EXE and Standalone Backup

To build standalone backup onto tape, you must have the image MACRO32.EXE on your system disk. Do not tailor off the Macro libraries before building standalone backup onto tape.

1.2.4 Layered Product Availability

The most current information about layered product support is available in the Software Public Rollout Reports for OpenVMS. These reports are available from the OpenVMS World Wide Web site in the “literature” section. Use the following URL:

<http://www.openvms.digital.com>

If you do not have access to the Internet, you can find the operating system support information on any of the quarterly Software Products Libraries, in the following directory:

[README]SW_COMPAT_MATRIX.PS (.TXT)

1.2.5 Restrictions

Restrictions for OpenVMS VAX Version 7.1 include:

- The minimum memory requirement is 4 megabytes.
- The MA780 shared memory is not supported.
- You cannot install or upgrade to Version 7.1 of the OpenVMS VAX operating system on the following VAX computers and system disks:

<u>Computers</u>	MicroVAX I, VAXstation I, VAXstation 8000, VAX-11/725, and VAX-11/782
<u>System disks</u>	RK07, RL02, RC25, RD32, RD51, RD52, RD53, RZ22, and RZ23L.

- If your system uses a small-capacity system disk (less than 210 megabytes), the entire OpenVMS VAX Version 7.1 operating system *and* the complete DECwindows Motif for OpenVMS VAX layered product will not fit on your disk. Appendix H describes some methods that will enable you to install or upgrade to OpenVMS VAX Version 7.1 and DECwindows Motif for OpenVMS VAX on a small-capacity system disk.

Note that you can use the methods described in Appendix H to free up disk space on any system.

For more information about these restrictions, see the *OpenVMS Operating System for VAX and Alpha, Version 7.1 Software Product Description (SPD)*.

1.3 Definitions: A Few Key Terms

You should be familiar with the following key terms before performing an installation or upgrade:

<u>Term</u>	<u>Definition</u>
Distribution Media	The media containing the OpenVMS VAX operating system software. This software is supplied in a format that the computer cannot use until you perform an installation or upgrade.

Overview of Installation and Upgrade Procedures

1.3 Definitions: A Few Key Terms

Term	Definition
System Disk	The disk that contains (or will contain) the OpenVMS VAX operating system in a usable format. The installation or upgrade procedure converts the OpenVMS VAX operating system software to this usable format when transferring the software from the distribution media to the system disk.
Local Drive	A drive that is connected directly to a VAX computer. For example, a magnetic tape drive connected directly to a VAX computer is referred to as a local tape drive. If you have a standalone VAX computer, it is likely all the drives connected to your system are local drives.
InfoServer	A general-purpose disk storage server that allows you to use the distribution compact disc to install the operating system on remote client systems connected to the same LAN (local area network).
Source Drive	The drive that holds the distribution media during the upgrade or installation.
Target Drive	The drive that holds the system disk—or, for some files, the alternate disk—during the upgrade or installation.
HSC Drive	A drive connected to a hierarchical storage controller (HSC) device. For example, a magnetic tape drive connected to an HSC device is referred to as an HSC tape drive. The HSC is a self-contained, intelligent, mass storage subsystem that enables VAXcluster nodes to share Digital Storage Architecture (DSA) disks.

For definitions of other specialized terms used in this manual, see the Glossary at the end of this book.

1.4 Locating Files on the Distribution Media

The OpenVMS VAX files are stored on the distribution media as the following save sets:

Save Set Name	Description
VMS071.A	Required
VMS071.B	Required
VMS071.C	Library (optional)
VMS071.D	Optional (optional)
VMS071.E	Help Message (optional)
VMS071.F	OpenVMS Management Station software PC files (optional)

See Appendix D for descriptions of the file subclasses contained in the optional save sets.

The optional DECwindows support files are stored on the distribution media as the following save sets:

Overview of Installation and Upgrade Procedures

1.4 Locating Files on the Distribution Media

Save Set Name	Description
DECW071.C	Base support files
DECW071.D	Workstation support files
DECW071.E	75 dots-per-inch (dpi) font files
DECW071.F	100 dpi font files

1.4.1 On Magnetic Tape

The OpenVMS VAX Version 7.1 magnetic tape kit contains OpenVMS VAX software on four tapes. The first tape contains the required save sets VMS071.A and VMS071.B. The second tape contains the save set VMS071.C. The third tape contains save sets VMS071.D, VMS071.E, and VMS0701F. The fourth tape contains the DECwindows base support and workstation support files, and DEC AMDS files.

1.4.2 On Tape Cartridges

The OpenVMS VAX Version 7.1 TK50 tape kit contains OpenVMS VAX software on two tape cartridges. The first cartridge contains VMS071.A, VMS071.B, and VMS071.C save sets. The second cartridge contains standalone BACKUP, VMS071.D, VMS071.E, and VMS071.F save sets, DECwindows base support and workstation support files, and DEC AMDS files.

1.4.3 On Compact Disc

The OpenVMS VAX Version 7.1 compact disc kit contains all the save sets and DECwindows base and workstation support files on one compact disc. (For more information, see the *Guide to OpenVMS Version 7.1 CD-ROMs*.)

Note that you can install or upgrade the operating system from a local compact disc drive as well as from an InfoServer device.

1.4.4 DECamds and Monitoring Performance History (MPH) Files

The DECamds software is included as save sets AMDS071.A and AMDS071.B on the OpenVMS VAX distribution media. The save sets are located on the third magnetic tape volume, on the second tape cartridge, and on the compact disc in the [AMDS071] directory.

The Monitoring Performance History (MPH) kit is also included on the OpenVMS VAX distribution media. The MPH kit is located on the third magnetic tape, on the second tape cartridge, and on the compact disc in the [MPH] directory.

1.4.5 Software Product Descriptions (SPDs)

The following SPD files are located on the second tape cartridge of the TK50 distribution kit and the third tape of the magnetic tape distribution kit. These SPD files have been grouped into an OpenVMS BACKUP save set named VMS071_SPD.BCK. File names with the .PS extension are in PostScript format. File names with the .TXT extension are in plain ASCII text format.

DECNET_SPD.PS	<i>DECnet-Plus for OpenVMS VAX and Alpha, Version 7.1</i>
DECNET_SPD.TXT	
OVMS_71_SPD.PS	<i>OpenVMS Operating System for VAX and Alpha, Version 7.1</i>
OVMS_71_SPD.TXT	

Overview of Installation and Upgrade Procedures

1.4 Locating Files on the Distribution Media

RMS_SPD.PS RMS_SPD.TXT	<i>RMS Journaling for OpenVMS, Version 7.1</i>
CLUSTER_SPD.PS CLUSTER_SPD.TXT	<i>OpenVMS Cluster Software</i>
VOL_SHAD_SPD.PS VOL_SHAD_SPD.TXT	<i>Volume Shadowing for OpenVMS, Version 7.1</i>

To obtain all the SPD files and restore them to your current default directory, enter a BACKUP command using the following format:

```
BACKUP source-drive:VMS071_SPD.BCK /SAVE_SET *.*;*
```

For *source-drive*, substitute the name of the device that holds your distribution kit. For example, if your *source-drive* is a local magnetic tape drive with the device name MUAO, you would enter the following command:

```
$ BACKUP MUAO:VMS071_SPD.BCK/SAVE_SET *.*;*
```

To restore all the SPD files in PostScript format to your default directory, enter the following:

```
$ BACKUP MUAO:VMS071_SPD.BCK/SAVE_SET/SELECT=* .PS *.*;*
```

The following command restores the PostScript SPD file for the OpenVMS VAX and OpenVMS Alpha operating systems to your current default directory:

```
$ BACKUP MUAO:VMS071_SPD.BCK/SAVE_SET/SELECT=OVMS_71_SPD.PS *.*;*
```

If your distribution kit is on compact disk, the SPD files are located in the [DOCUMENTATION.V071] directory. For information about locating and printing these SPD files, see the *Guide to OpenVMS Version 7.1 CD-ROMs*.

1.5 What Happens During an Installation

When you install the OpenVMS VAX operating system, the installation procedure does the following:

- Initializes the system disk, overwriting its contents.
- Creates a system directory structure.
- Transfers the OpenVMS VAX files from the distribution media to the system disk. Some files can be transferred to an alternate disk.

1.5.1 When to Perform an Installation

Use the installation procedure under the following conditions:

- If your VAX computer is new (it has never had any version of the operating system running on it, including factory-installed software).
- If your VAX computer is running a previous version of the operating system and you want to overwrite the entire contents of the system disk (the OpenVMS VAX operating system, application software, and user files).
- If you are running a previous version of the operating system, but you cannot upgrade. For example, if you changed the names of system directories on the system disk, the upgrade procedure will not work correctly. You can either restore the system disk to its original directory structure, or you can reinstall the OpenVMS VAX operating system.

Overview of Installation and Upgrade Procedures

1.5 What Happens During an Installation

Caution: The installation procedure initializes the system disk, overwriting its contents. For this reason, use the installation procedure only on new VAX computers or if you want to destroy the contents of the system disk.


1.5.2 How to Use the Installation Documentation

This manual contains step-by-step instructions for performing an OpenVMS VAX installation. However, you will need to refer to several different documents before and during the installation. Figure 1-1 illustrates the major steps in an installation and the documents you will use to perform each step.

Overview of Installation and Upgrade Procedures

1.5 What Happens During an Installation

Figure 1-1 Documentation Used to Perform an Installation



ZK-9697-GE

1.6 What Happens During an Upgrade

When you upgrade the OpenVMS VAX operating system, the upgrade procedure does the following:

- Deletes and purges some OpenVMS VAX files on the system disk but leaves all the user files intact.
- Transfers the new OpenVMS VAX files from the distribution media to the system disk.

Note: The upgrade procedure puts the most recent versions of the OpenVMS VAX files in SYSSCOMMON.

- Merges some of the old OpenVMS files and the new OpenVMS VAX files and replaces others.

Certain OpenVMS VAX files are placed either over or under existing files (that is, they are given a version number above or below the version number of the existing file). This is done to protect any customizations to the files and results in having two versions of the file when the upgrade is completed. For more information, see Appendix F.

- Cleans up files and structures used only during the upgrade.
- Leaves your OpenVMS license and System Integrated Product (SIP) licenses intact.

You do not need to reinstall these licenses after you upgrade. (See Appendix B for detailed information about license management for OpenVMS VAX Version 7.1.)

1.6.1 When to Perform an Upgrade

In most cases, you can use the upgrade procedure to obtain a higher version of the OpenVMS VAX operating system. Unlike the installation procedure, the upgrade procedure does not initialize your system disk. This means you can get the latest version of the operating system and keep your user files and optional software files intact.


1.6.2 How to Use the Upgrade Documentation

This manual contains step-by-step instructions for performing an OpenVMS VAX upgrade. However, you will need to refer to several different documents before and during an upgrade. Figure 1-2 illustrates the major steps in an upgrade and the documents you will use to perform each step.

Overview of Installation and Upgrade Procedures

1.6 What Happens During an Upgrade

Figure 1–2 Documentation Used to Perform an Upgrade



ZK-9696-GE

1.7 Where to Go Next

If you are installing the OpenVMS VAX operating system, go to Chapter 2.

If you are upgrading the OpenVMS VAX operating system, go to Chapter 5.

Before Installing OpenVMS VAX Software

2.1 Overview

This chapter describes how to prepare for installing the OpenVMS VAX operating system, including:

- Being aware of the cautions and restrictions
- Ensuring your hardware is ready
- Ensuring your software distribution kit is complete
- Preparing for a C2 system
- Preparing for a VAXcluster environment
- Preparing your tape and disk drives
- Gathering the information you need to supply during the installation procedure
- Completing the preinstallation checklist

If you are an experienced system manager, you can use the checklist at the end of the chapter to complete all the necessary preinstallation tasks.

If you are a less-experienced system manager, you should read the entire chapter and then use the checklist to make sure you completed all the preinstallation tasks.

2.2 Cautions and Restrictions

Before you begin the installation procedure, note the following cautions and restrictions.

2.2.1 Cautions

The following cautions apply for Version 7.1 of the OpenVMS VAX operating system:

- The software installation procedure overwrites the contents of the system disk. Use the installation procedure only if your VAX computer is new or if you want to destroy the contents of the system disk. If your system disk contains files you want to save, you should *upgrade* to the new version of OpenVMS VAX. For an overview of the upgrade procedure, see Chapter 5.
- Do not attempt to use VMSINSTAL with OPTION G to transfer OpenVMS VAX save sets to another media type; doing so will produce an unusable system. Instead, you can use the DCL command COPY to transfer save sets to another media type.

Before Installing OpenVMS VAX Software

2.2 Cautions and Restrictions

If you move the save sets from the distribution media before beginning the installation, you must move them to the [000000] directory on a disk that is *not* the system disk; otherwise, the installation will fail.

2.2.2 Restrictions

The following restrictions apply for Version 7.1 of the OpenVMS VAX operating system:

- If your system contains DIGITAL Storage Systems Interconnect (DSSI) disks attached to a KFQSA controller, you will notice a change in the device names for DSSI disks attached to KFQSA controllers.

When you boot standalone BACKUP, it will display the devices on your system using the *new* device naming scheme. Use the new device names throughout the installation and after you complete the installation.

- If you want to use DECwindows software with OpenVMS VAX Version 7.1, you must purchase and install the DECwindows Motif for OpenVMS Version 1.2–3, or higher, layered product. For more information, see Section 1.2.1.

2.3 Are You Ready to Install?

Before you begin to install the OpenVMS VAX operating system, make sure you have all the required hardware and software components.

2.3.1 Hardware Components

Examine your hardware for the following:

- Make sure the hardware has been installed and checked for proper operation. For detailed information about the hardware, see the hardware manual for your VAX computer.
- Make sure you know how to turn on and operate your system components, including the system unit, console, monitor, drives, terminals, and printers. If necessary, read the manuals that came with these components.
- Set up your system to record the installation procedure on either a hardcopy terminal or a printer attached to the console terminal. If you do not do this, the screen messages will be lost. You will need a transcript in case there is a problem during the installation. For more information, see the upgrade and installation supplement for your computer.

2.3.2 Software Components

Examine your software for the following:

- Make sure you have all the items listed on the bill of materials (BOM) in the OpenVMS VAX distribution kit. If your kit is incomplete, notify Digital Software Supply, and request priority shipment of any missing items.
- Before installing the OpenVMS VAX operating system, review Appendix B of this manual for license management information, the *OpenVMS Version 7.1 New Features Manual*, the *OpenVMS Version 7.1 Release Notes*, and any cover letters included with your kit.
- Read the Before Installing OpenVMS section in the upgrade and installation supplement for your VAX computer, which describes tasks specific to your VAX computer that you must complete before beginning the installation.

2.4 Preparing for an Installation

Now that you have determined that your hardware and software components are ready, you can make the necessary preparations for installing the OpenVMS VAX operating system.

2.4.1 Preparing for a C2 System

Many of the security features provided by the OpenVMS VAX operating system are directed toward the criteria for a C2 system, as defined in the *Department of Defense Trusted Computer System Evaluation Criteria*, published by the U.S. Department of Defense Computer Security Center (DOD 5200.28-STD).

A C2 system is the shipped system that has been configured according to the guidelines in Appendix C of the *OpenVMS Guide to System Security*. Before installing OpenVMS VAX, become familiar with the requirements for operating an OpenVMS VAX system within the C2 framework.

2.4.2 Preparing for a VAXcluster Environment

If you are installing the OpenVMS VAX operating system in a VAXcluster environment, the installation procedure will ask you for information about your VAXcluster environment. Before proceeding, review *OpenVMS Cluster Systems*, which provides the information you will need to answer questions during the installation.

Note: Entering incorrect information during the installation can force you to repeat the entire installation procedure.

Table 2–1 lists the VAXcluster information you need and explains how to obtain that information. For a complete explanation, see *OpenVMS Cluster Systems*.

Table 2–1 VAXcluster Information for Installations

Information You Need	How to Get It
Type of configuration	Configuration types are distinguished by the interconnect device that the VAX computers in the cluster use to communicate with one another: Computer Interconnect (CI), Ethernet, DIGITAL Storage Systems Interconnect (DSSI), or FDDI (Fiber Distributed Data Interface).
DECnet node name and node address	Determined by the network or system manager for each VAX computer on the network. See your system or network manager for the DECnet node name and node address for the VAX computer on which you are installing the OpenVMS VAX operating system. See the <i>DECnet/OSI for OpenVMS Installation and Configuration</i> for more information.
Allocation class value	During the installation procedure you will be asked for the ALLOCLASS value of the VAX computer on which you are installing the OpenVMS VAX operating system. For example: Enter a value for MYNODE's ALLOCLASS parameter: Refer to <i>OpenVMS Cluster Systems</i> for the rules on specifying allocation class values. Note that, in a mixed-interconnect VAXcluster environment, the allocation class value cannot be zero. It has to be a value between 1 and 255. This is also true for any VAX computer that is connected to a dual-path disk. When you enter the allocation class value, the installation procedure uses it to automatically set the value of the system parameter ALLOCLASS.

(continued on next page)

Before Installing OpenVMS VAX Software

2.4 Preparing for an Installation

Table 2–1 (Cont.) VAXcluster Information for Installations

Information You Need	How to Get It
Quorum disk	See <i>OpenVMS Cluster Systems</i> to determine whether you want a quorum disk in the cluster.
Location for page and swap files	See <i>OpenVMS Cluster Systems</i> to determine where the page and swap files will be located for the system from which you are installing the OpenVMS VAX operating system software.
MOP servers, disk servers, tape servers	To establish either a local area or a mixed-interconnect cluster, determine which systems will be Maintenance Operations Protocol (MOP) servers, disk servers, and tape servers. Refer to <i>OpenVMS Cluster Systems</i> .
Cluster group number and cluster password	To establish either a local area or a mixed-interconnect cluster. <u>Cluster group number</u> : A number in the range from 1 to 4095 or from 61440 to 65535. <u>Cluster password</u> : Can range from 1 to 31 alphanumeric characters, including dollar signs (\$) and underscores (_).

2.4.3 Preparing Tape and Disk Drives

Prepare your tape and disk drives using the following steps:

1. Decide which drive will hold the distribution tape and which drive will hold the system disk. Determine the device names for each drive, and write these names on a piece of paper. You will need this information throughout the installation. If you need information about devices and device names, refer to the Before Installing the OpenVMS Operating System section in the upgrade and installation supplement for your VAX computer.

Note: Do not place the distribution media in the drive at this point.

2. Follow this step only if the **source drive** or **target drive** is attached to a hierarchical storage controller (HSC). Otherwise, go to step 3.

Make sure that both the CI and HSC devices are turned on and on line. Obtain the HSC name from the system manager, or use the following procedure:

- a. Press Ctrl/C at the HSC console terminal.
- b. Enter the following command at the HSC> prompt and press Return:

```
HSC> SHOW SYSTEM
```

The information displayed includes the name of the HSC. For example:

```
22-NOV-1996 15:00:00.00 Boot:12-NOV-1996 11:31:11.41 Up: 51:00
Version V350          System ID: %X000000011      Name: MUTT
```

```
.
```

```
DISK allocation class = 1 TAPE allocation class = 0
Start command file Disabled
```

```
SETSHO - Program Exit
```

For more information, see the *HSC User's Guide*.

3. Place a **scratch disk** in the drive for the system disk (unless the system disk is fixed).
4. Spin up the disk that will be the system disk but *do not* write protect it.

2.4.4 Information You Need During the Installation

During the installation, the procedure prompts you to supply certain information. To save time once the procedure begins, be sure you have the following information available. Remember, entering incorrect information during the installation could force you to repeat the entire installation procedure.

Required Information	Explanation
Passwords	You will be prompted to type passwords of at least 8 characters for the SYSTEM, SYSTEST, and FIELD accounts.
SCSNODE and SCSSYSTEMID parameters	<p>If you are installing a standalone system, you will be prompted to supply an SCSNODE name and an SCSSYSTEMID. The SCSNODE name must be a 1- to 6-character unique DECnet node name. The SCSSYSTEMID system parameter is calculated as follows:</p> $(\text{DECnet area} * 1024) + \text{node number}$ <p>Note that, if you are installing the operating system in a VAXcluster environment, the installation procedure does not prompt you to supply these parameters. It calculates the SCSNODE and SCSSYSTEMID based on the DECnet node name and node address that you supply earlier in the procedure.</p>
Optional components and OpenVMS Management Station files	<p>The installation procedure prompts you to specify whether you want to install the library (VMS071.C), optional (VMS071.D) OpenVMS components, and OpenVMS Management Station software PC files (VMS071.F). Appendix D lists the files included in these save sets.</p> <p>You can save some space on your system disk if you choose <i>not</i> to install these components, but be sure to review Appendix D before deciding.</p>
Location for Help Message utility	Save set VMS071.E contains the online Help Message utility, which you can install on your system disk or on an alternate disk. (However, if you copied the distribution kit to some other media from which you will be performing the installation, you cannot install this save set on that media.)

Before Installing OpenVMS VAX Software

2.4 Preparing for an Installation

Required Information	Explanation
DECwindows components	<p>The installation procedure prompts you to specify which of the following DECwindows components you want to install:</p> <ul style="list-style-type: none">• DECwindows base support (required for running DECwindows software), which includes:<ul style="list-style-type: none">– DECwindows transport– DECwindows keymaps• DECwindows workstation support (required for VAX workstations), which includes:<ul style="list-style-type: none">– DECwindows X11 display server– Graphics drivers– 75 dots/inch video fonts– 100 dots/inch video fonts (option available only if you select DECwindows workstation support) <p>You must install the DECwindows Motif for OpenVMS (previously called VMS DECwindows Motif) layered product if you want to run the DECwindows software. DECwindows Motif for OpenVMS Version 1.2–3 (or 1.2 if the VAXMOTF05_012 remedial kit is installed) is the minimum supported version for systems running OpenVMS VAX Version 7.1. If you do not know which version of DECwindows Motif you are currently running on your system, you can check by entering the following command:</p> <pre>\$ ANALYZE/IMAGE SYS\$LIBRARY:DECW\$XLIBSHR.EXE</pre> <p>Note: The DECwindows Motif for OpenVMS layered product does <i>not</i> have the DECwindows base and workstation support components. To get full DECwindows support, you must select the DECwindows components provided with the OpenVMS VAX kit and install the separate DECwindows Motif for OpenVMS layered product, which supports both Motif and XUI environments.</p>
PAK information	<p>The information listed on Product Authorization Keys (PAKs) for your OpenVMS VAX license and any system-integrated products you will run. The installation procedure gives you the opportunity to register any licenses you have. To register your licenses, you will need to enter the information listed on the PAK for each license.</p>

2.5 Preinstallation Checklist

Before you begin the installation, use the following checklist to make sure you have completed all of the tasks described in this chapter:

- Read the cautions and restrictions described at the beginning of this chapter.
- Make sure the hardware is installed and tested. (Described in the hardware manuals for your VAX computer.)
- Check the contents of your kit against the bill of materials (BOM).
- Read Appendix B of this manual, the *OpenVMS Version 7.1 New Features Manual*, the *OpenVMS Version 7.1 Release Notes*, and any cover letters included with your kit.
- Read Section 2.4.1 for special considerations about running the OpenVMS VAX operating system in a C2 environment if you intend to create a C2 compliant environment.

Before Installing OpenVMS VAX Software 2.5 Preinstallation Checklist

- Turn on the system. (Described in the upgrade and installation supplement for your VAX computer.)
- Set up your system to record the installation procedure. (Described in the upgrade and installation supplement for your VAX computer.)
- Read the Before Installing OpenVMS section in the upgrade and installation supplement for your VAX computer and perform the tasks described there.
- Make sure you have the most recent version of the console media if you have a VAX computer that uses console media. (Described in the upgrade and installation supplement for your VAX computer.)
- Determine whether you want a CI only, local area, or mixed-interconnect cluster if you are installing the OpenVMS VAX operating system on a VAX computer in a VAXcluster environment. (Described in *OpenVMS Cluster Systems*.)

You should have the following information, depending on the type of VAXcluster:

- CI Only VAXcluster: Get the allocation class value, DECnet node name, and DECnet node address for the computer. You also need to decide if you want a quorum disk and where the page and swap files for the system from which you are installing will be located.
 - Local Area and Mixed-Interconnect VAXclusters: Get the allocation class value, the DECnet node name, the DECnet node address, the cluster group number, and the cluster password. You also need to decide if you want a quorum disk and where the page and swap files for the system from which you are installing will be located.
- Prepare the disk and tape drives. (Described in Section 2.4.3.)
 - Make sure you have the following information (described in Section 2.4.4) available:
 - Passwords containing at least 8 characters for the SYSTEM, SYSTEST, and FIELD accounts.
 - SCSNODE and SCSSYSTEMID if you are installing a standalone system.
 - A list of optional OpenVMS VAX components you want to install.
 - A list of optional DECwindows support components you want to install.
 - Information listed on Product Authorization Keys (PAKs) for your OpenVMS VAX license and any system-integrated products you will run.

After you have performed all the tasks in the checklist, go to Chapter 3 to begin the installation.

Installing the OpenVMS VAX Operating System

3.1 Overview

During the installation procedure, OpenVMS VAX files are transferred from the distribution media to the system disk or, for certain files, to an alternate disk. The time required to complete an installation varies depending on your hardware configuration and on the distribution media you are using. In most cases, magnetic tapes and tape cartridges require more time than compact discs.

The following installation tasks are described in this chapter:

- Booting standalone BACKUP
- Creating the system disk
- Configuring a cluster
- Setting passwords
- Creating the rights database
- Registering licenses
- Running AUTOGEN

At certain points in the procedure you will need to refer to the upgrade and installation supplement for installation instructions that are specific to your VAX computer.

3.2 Booting Standalone BACKUP

Standalone BACKUP is a subset of the OpenVMS Backup utility (BACKUP). Because you boot it into main memory, standalone BACKUP executes outside the control of the operating system. You use standalone BACKUP to restore the *required* save sets from the distribution media to your system disk.

Standalone BACKUP is included in the OpenVMS VAX distribution kit. Each piece of media in the distribution kit has a label that indicates its contents. For example, there are two tape cartridges in a TK50 kit. Standalone BACKUP is on the second tape cartridge.

3.2.1 Booting from Tape Cartridge

If your distribution media is tape cartridges, complete the following steps to boot standalone BACKUP. (If you are using an InfoServer device, go to Section 3.2.2.)

1. Place the media that contains standalone BACKUP in the source drive or in the console drive.
2. Follow the instructions in the Booting Standalone BACKUP section of the upgrade and installation supplement for your VAX computer.

Installing the OpenVMS VAX Operating System

3.2 Booting Standalone BACKUP

3. After you boot standalone BACKUP, the system displays the following:

```
%BACKUP-I-IDENT, standalone BACKUP V6.2; the date is 22-NOV-1996 15:00
$
```

Note: If you have a tape cartridge kit, remove the tape cartridge 2/2 from the drive after you boot standalone BACKUP. Put the tape cartridge that contains the OpenVMS VAX operating system in the drive. The tape cartridge is labeled *VMS071 BIN TK50 1/2 VMS BINARY*.

After you have booted standalone BACKUP, go to Section 3.3.

3.2.2 Booting from an InfoServer Device

If you are using the InfoServer to boot standalone BACKUP from a compact disc, complete the following steps:

1. Insert the distribution compact disc into the drive.
2. Follow the instructions in the Booting Standalone BACKUP section of the upgrade and installation supplement for your VAX computer.
3. Enter your VAX processor boot command by using the designator for the Ethernet adapter in the boot path and, except for the VAX 9000 computer, add the /R5:100 qualifier to the boot command.

For example, on a VAX 6000 computer:

```
>>> B/R5:100/X:D/B:6 ET0
```

On VAX 9000 computers, standalone BACKUP resides on the console hard disk. Because the boot process is slightly different for each type of controller, each supported controller has a unique boot command procedure. Refer to the upgrade and installation supplement for your VAX 9000 computer for instructions for booting standalone BACKUP on your system.

4. During an InfoServer boot, the procedure prompts you for a file name that contains an initial system load (ISL) boot program instead of a virtual memory boot (VMB) program. Select one of the two files as follows:
 - ISL_SVAX_071
 - ISL_LVAX_071

Use the following table to determine which file name and boot path designator to use for your processor. Note that the VAX 9000 computer has the ISL file data built in its VMB image that runs from the console.

Processor Series	ISL File	Boot Path Designator
VAX 3000	ISL_SVAX_071	ESA0 (LANCE), XQA0 (DELQA)
VAX 4000	ISL_SVAX_071	EZA0 (SGEC), XQA0 (DELQA)
VAX 6000	ISL_LVAX_071	EXA0 (DEMNA), FXA0 (DEMFA), ETA0 (DEBNI) (DEBNA)
VAX 7000	ISL_LVAX_071	EXA0 (DEMNA), FXA0 (DEMFA)
VAX 10000	ISL_LVAX_071	EXA0 (DEMNA), FXA0 (DEMFA)
MicroVAX	ISL_SVAX_071	ESA0 (LANCE), XQA0 (DELQA)
VAXstation	ISL_SVAX_071	ESA0 (LANCE)

Installing the OpenVMS VAX Operating System 3.2 Booting Standalone BACKUP

Processor Series	ISL File	Boot Path Designator
VAXft 110, 310, 410, 610, and 612	ISL_SVAX_071	EPA0 (LANCE)

On a VAX 6000 computer, you would respond to the prompt as shown in the following example:

```
Loading system software.
```

```
Filename: ISL_LVAX_071
```

5. The InfoServer ISL program then displays the following menu:

```
Network Initial System Load Function  
Version 1.1
```

```
FUNCTION      FUNCTION  
ID  
1 - Display Menu  
2 - Help  
3 - Choose Service  
4 - Select Options  
5 - Stop
```

```
Enter a function ID value:
```

If you need more information, select function ID 2 for help.

6. After you boot standalone BACKUP, the system displays the following:

```
%BACKUP-I-IDENT, standalone BACKUP V6.2; the date is 22-NOV-1996 15:00  
$
```

After you have booted standalone BACKUP, go to Section 3.3.

3.2.3 Booting OpenVMS from the CD-ROM

If you are installing from the OpenVMS VAX operating system CD-ROM (your VAX computer supports booting from a local CD-ROM or from an InfoServer), you can use the full OpenVMS environment instead of the standalone BACKUP environment to transfer the VMS071.B save set to your target system disk. Although it may take slightly longer to boot OpenVMS than to boot standalone BACKUP, you might prefer the more robust OpenVMS environment. It provides a greater range of commands and utilities than the standalone BACKUP environment.

If you want to use the full OpenVMS environment, do the following:

1. Boot the CD-ROM and specify root 1. For example, from a local drive on a VAXstation 4000 computer:

```
>>> B/1000000 DKA400:
```

If you are booting from an InfoServer device, enter a command that specifies root 1. For example, on a VAX 6000 computer:

```
>>> B/R5:10000100/X:D/B:6 ET0
```

2. After you boot the OpenVMS CD-ROM, the system displays the following menu:

```
1) Execute DCL commands and procedures  
2) Shut down this system
```

Choose option 1 to execute DCL commands and procedures.

Installing the OpenVMS VAX Operating System

3.2 Booting Standalone BACKUP

Note that the system displays a triple dollar sign (\$\$\$) DCL prompt to indicate that you are in this specialized DCL environment.

3. Go to Section 3.3.3.

3.3 Creating the System Disk

You create an OpenVMS VAX Version 7.1 system disk by transferring OpenVMS VAX files from the distribution media to your system disk. (For certain files, you have the option to transfer the files to your system disk or to an alternate disk.)

To transfer the OpenVMS VAX files from the distribution kit to your system disk, perform the steps described in the sections that follow.

3.3.1 Step 1: Determine Device Names

If you have not already done so, determine the device names for the source drive, the target drive, and an alternate device if you will be using one. Write these names on a piece of paper. You will need this information throughout the installation. If either the source drive or the target drive is connected to an HSC, you also need the name of the HSC. (To determine the value for *hsc-name*, see Section 2.4.3 in Chapter 2.)

If you need more information about determining the device names for your system, refer to the upgrade and installation supplement for your VAX computer.

3.3.2 Step 2: Load Distribution Media

Each piece of media in the distribution kit has a label that indicates its contents. Place the media that contains the OpenVMS VAX operating system in the *source-drive*.

If your OpenVMS VAX distribution kit consists of more than one piece of media, insert the first piece of media in the *source-drive*. For example, if you have a TK50 tape cartridge kit, make sure the first tape is in the *source-drive*.

If you are installing from a compact disc, it is already in the drive.

3.3.3 Step 3: Transfer VMS071.B to Your System Disk

Enter a BACKUP command in the following format to transfer the VMS071.B save set to your system disk:

```
$ BACKUP/IMAGE/VERIFY [hsc-name] source-drive:VMS071.B/SAVE_SET-  
_ $ [hsc-name] target-drive:
```

Substitute the appropriate device names for *hsc-name* (if appropriate), *source-drive*, and *target-drive*. Make sure you put a colon (:) after each device name and that you use zeros rather than the letter "O" in the device names and in VMS071.

The square brackets ([]) indicate that you need the *hsc-name* only if the device is connected to an HSC.

For example, if your system has a *source-drive* that is a local TU80 magnetic tape drive with a device name of MUA0 and a *target-drive* that is an RA82 disk drive with a device name of DUA1, enter the following command and press the Return key:

```
$ BACKUP/IMAGE/VERIFY MUA0:VMS071.B/SAVE_SET DUA1:
```


Installing the OpenVMS VAX Operating System

3.3 Creating the System Disk

If your system has a *source-drive* that is a local tape cartridge drive with a device name of MUC6 or a *target-drive* that is an RA81 disk drive with a device name of DUA1 and an HSC name of YOURS, enter the following command and press Return:

```
$ BACKUP/IMAGE/VERIFY MUC6:VMS071.B/SAVE_SET YOURS$DUA1:
```

The procedure transfers the VMS071.B save set from the distribution kit to the system disk.¹ The amount of time this takes varies depending on the type of VAX computer and distribution media you have. During the process, the command displays the following message:

```
%BACKUP-I-STARTVERIFY, starting verification pass
```

This message indicates that the VMS071.B save set has been transferred to the system disk and the files are being checked for errors. If, instead, you see a message similar to the following, you might have the wrong volume of the distribution kit in the source drive:

```
% BACKUP-F-OPENIN, error opening MUA0:[000000]VMS071.B; as
input
- SYSTEM-W-NOSUCHFILE, no such file
.
.
.
```

If you do want to perform another standalone BACKUP operation, ensure the standalone BACKUP volume is online and ready. Enter "YES" to continue:

If the procedure displays the previous messages, remove the distribution volume from the drive and replace it with the correct volume as described in Step 2. Then type Yes, press Return, and repeat this step.

Completing the Transfer Operation

Complete the transfer of the VMS071.B save set to your system disk by performing one of the following operations:

- If you are using standalone BACKUP to transfer the VMS071.B save set, the procedure displays the following message, when it has completed checking files:

```
%BACKUP-I-PROCDONE, Operation completed. Processing finished at 22-NOV-1996 15:00.
If you do not want to perform another standalone BACKUP operation,
use the console to halt the system.
```

```
If you do want to perform another standalone BACKUP operation,
ensure the standalone application volume is online and ready.
Enter "YES" to continue:
```

Enter NO and go to step 4 (Section 3.3.4) to boot the new system disk.

- If you are using the specialized OpenVMS environment to transfer the VMS071.B save set, the system displays the triple dollar sign prompt (\$\$\$) DCL prompt after the BACKUP operation completes. Enter the command LOGOUT to return to the menu. For example:

```
$$$ LOGOUT
```

- 1) Execute DCL commands and procedures
- 2) Shut down this system

¹ The BACKUP command creates a system disk that includes a set of volume parameters provided by Digital, including CLUSTER_SIZE (disk access scheme). For more information, see the upgrade and installation supplement for your VAX computer.

Installing the OpenVMS VAX Operating System

3.3 Creating the System Disk

You can then choose option 2 to shut down the system in preparation for booting the new system disk, as described in step 4 (Section 3.3.4).

3.3.4 Step 4: Boot the New System Disk

Halt the system and boot the new system disk, as described in the upgrade and installation supplement for your VAX computer.

When the boot is completed, the procedure displays a message and prompts you to enter the date and time. Enter the date and time using the 24-hour clock format and press Return.

For example:

```
OpenVMS (TM) VAX Version 7.1 Major version id = 1 Minor version id = 0
      OpenVMS VAX V7.1 Installation Procedure
            Model: VAX 4000-300
            System device: RF73 - _DUA8
            Free blocks: 1170940
            CPU type: 11-01

* Please enter the date and time (DD-MMM-YYYY HH:MM):22-NOV-1996 15:35
*****
%SYSTEM-W-TZGMT, your local timezone has defaulted to GMT
%SYSTEM-I-SETTZ, to set your local timezone use:
      $ @SYSMANAGER:UCT$TIME_SETUP.COM
*****

STDRV-I-STARTUP, VMS startup begun at 22-NOV-1996 15:00:00.59
%SET-I-NEWAUDSERV, identification of new audit server process is 00000028
.
.
%OPCOM 22-NOV-1996 15:00:15.46 %OPCOM
Message from user JOB_CONTROL on POKIPC
%JBC-E-OPENERR, error opening SYS$COMMON:[SYSEXE]QMAN$MASTER.DAT

%OPCOM 22-NOV-1996 15:00:15.41 %OPCOM
Message from user JOB_CONTROL on POKIPC
-SYSTEM-W-NOSUCHFILE, no such file

LICENSE-F-EMTLDB, license database contains no license records
%LICENSE-E-NOAUTH, DEC VAX-VMS use is not authorized on this node
-%LICENSE-F-NOLICENSE, no license is active for this software product
-%LICENSE-I-SYSMGR, please see your system manager
Startup processing continuing...

%STDRV-I-STARTUP, VMS startup begun at 22-NOV-1996 15:03:00.00
```

Note

You can ignore the time zone message. The UTC\$TIME_SETUP.COM procedure runs during the final phase of the installation procedure.

The procedure also displays OPCOM messages from JOB_CONTROL stating the master queue file QMAN\$MASTER.DAT does not exist. You can ignore these messages. You will create the queue file later.

You can also ignore error messages stating that the OpenVMS VAX license is not registered. License registration occurs later in the procedure. For more information about registering your licenses, see Appendix B and the *OpenVMS License Management Utility Manual*.

Installing the OpenVMS VAX Operating System

3.3 Creating the System Disk

3.3.5 Step 5: Specify the Volume Label

The procedure prompts you to specify the volume label of the system disk. A volume label is the name the OpenVMS VAX operating system uses to refer to the system disk. You can press the Return key to accept the default volume label, OpenVMS071, or you can enter a volume label of your choice. The volume label can be 1 to 12 characters long; do not use spaces. For example:

If this system disk is to be used in a cluster with multiple system disks, then each system disk must have a unique volume label. Any nodes having system disks with duplicate volume labels will fail to boot into the cluster.

You can indicate a volume label of 1 to 12 characters in length. If you want to use the default name of OpenVMS071, press Return in response to the next question.

```
* Enter the volume label for this system disk [OpenVMS071]: SYSDSK1
```

3.3.6 Step 6: Specify the Source Drive

The procedure prompts you to specify which drive holds the distribution kit. Enter the device name for the source drive.

For example, if you are not using the InfoServer and the source drive is a magnetic tape drive with the device name MUA0, type MUA0 and press Return.

```
* Enter the name of the drive holding the OpenVMS distribution media: MUA0
* Is the OpenVMS media ready to be mounted? [N] YES
%MOUNT-I-MOUNTED, VMS071      mounted on _MUA0:
```

If you are not using the InfoServer, continue to Section 3.3.7.

If you are using an InfoServer, enter DAD1:

```
* Enter the volume label for this system disk [OpenVMS071]: SYSDSK1
* Enter name of drive holding the OpenVMS distribution media: DAD1:
```

The procedure then prompts you to:

```
* Enter the InfoServer service name [VAXVMS071]:
* Enter the InfoServer work group number [0]:
```

Press the Return key as a response to both of these prompts.

The InfoServer work group number was determined when you made a selection from the menu displayed by the InfoServer ISL program (refer to Section 3.2). If the answer to the group number is incorrect, the procedure displays the following:

InfoServer work group number must be in the range 0-1023.

The procedure then prompts you:

```
* Is the OpenVMS media ready to be mounted? [N]: Y
%MOUNT-I-MOUNTED, VMS071      mounted on _DAD1:
```

3.3.7 Step 7: Select Optional OpenVMS Components

The procedure displays information about OpenVMS VAX files that are optional and about the remaining amount of disk space. The information is similar to the following (block sizes might vary slightly):

Installing the OpenVMS VAX Operating System

3.3 Creating the System Disk

Select optional software you want to install. You can install one or more of the following OpenVMS or DECwindows components:

- o OpenVMS library - 53400 blocks
- o OpenVMS optional - 21200 blocks
- o OpenVMS Help Message - blocks
- o OpenVMS Management Station - 21200 blocks
- o DECwindows base support - 3800 blocks
- o DECwindows workstation support - 23500 blocks
 - 75 dots per inch video fonts - (included)
 - 100 dots per inch video fonts - 6000 blocks
- o DECnet-Plus networking - 85000 blocks

Space remaining on system disk: 1170752 blocks

You must indicate which of the options you want to install. If you require network support, you must select the OpenVMS library component.

Note that, if you do not install the optional components at this time, you can install them after the installation by using the VMSTAILOR or DECW\$TAILOR utility. However, the Help Message utility can be tailored on to the system disk only.

If you want to install Help Message on an alternate disk, you must install it now or install it *after* the installation procedure completes by entering the following BACKUP command:

```
BACKUP/VERIFY source-device:[000000]VMS071.E/SAVE_SET -  
target-device:[directory-name]
```

For *source-device*, enter the device name for the drive on which the distribution media is mounted. For *target-device*, enter the device name on which the alternate disk is mounted, and for *directory-name*, enter the name of the directory to which you are copying the files.

Also note that, for TK50 tape cartridges, it is quicker to install OpenVMS VAX software during the installation than to add software after the installation with a tailoring utility. For information about using VMSTAILOR, see Chapter 10.

To select the options you want to install, follow the instructions displayed by the procedure.

3.3.7.1 OpenVMS Library Files

The procedure displays the following message:

```
* Do you want to install the OpenVMS library files? (Y/N)
```

The file subclasses of the VMS071.C save set are listed in Appendix D. If you want to install the VMS071.C files, type Y (for YES) and press Return. If you require network support, you must select the OpenVMS library component. If you do *not* want to install the VMS071.C files, type N (for NO) and press Return.

3.3.7.2 OpenVMS Optional Files

The procedure displays the following message:

```
* Do you want to install the OpenVMS optional files? (Y/N)
```

The file subclasses of the VMS071.D save set are listed in Appendix D. If you want to install the VMS071.D files, type Y and press Return. If you do *not* want to install the VMS071.D files, type N and press Return.

Installing the OpenVMS VAX Operating System

3.3 Creating the System Disk

3.3.7.3 Help Message Files

The procedure displays the following message:

```
The Help Message utility (MSGHLP) provides online explanations
and user actions for OpenVMS messages in place of the hardcopy
OpenVMS System Messages and Recovery Procedures Reference Manual,
which is now separately orderable.
```

```
The MSGHLP database, MSGHLP$LIBRARY.MSGHLP$DATA,
consumes approximately 10200 blocks and will be
placed by default on your system disk in SYS$COMMON:[SYSHLP]
unless you specify an alternate device when prompted.
```

```
Users with limited disk space can access the MSGHLP database
on a read-only basis at DAD1:[HELP_MESSAGE].
```

* Do you want to install the MSGHLP database? (Y/N)

The Help Message utility is an online system for system messages documentation. You can install Help Message either on the system disk or on an alternate disk. If you want to install the Help Message files, type Y and press Return.

The procedure displays the following message:

```
You can install this database on your system disk in SYS$COMMON:[SYSHLP]
or on an alternate device. If you specify an alternate device, but no
directory, MSGHLP$LIBRARY.MSGHLP$DATA is placed in [HELP_MESSAGE]. When
prompted, take the default of the system disk or specify an alternate
device, using this format:
```

```
device:[directory]
```

* Where do you want to install the MSGHLP database?[SYS\$COMMON:[SYSHLP]] DUA1

The Help Message database is installed in the area you specify, and the system displays information similar to the following:

```
Space remaining on alternate device DUA1: 124532 blocks
```

3.3.7.4 OpenVMS Management Station Files

The procedure displays the following message:

```
The OpenVMS Management Station is a client-server application
that provides OpenVMS system management capabilities through a
client application on a personal computer (PC) running Microsoft
Windows. The server application runs on OpenVMS systems and is
automatically installed as part of the OpenVMS operating system.
```

```
This option provides the files used to create the installation media
for the PC client software. If you want to use the OpenVMS Management
Station, you must install these files on at least one OpenVMS system to
create the installation media, which can then be used to install the
PC client on one or more PCs.
```

```
Note: To use the OpenVMS Management Station on your PC, you must be
running Digital's PATHWORKS V5.0A for DOS and Windows (or V5.1)
software.
```

```
The OpenVMS Management Station optional files consume approximately 212000
blocks and will be placed on your system disk in SYS$COMMON:[TNT.CLIENT].
```

* Do you want to install the optional OpenVMS Management Station files? (Y/N)

```
Space remaining on system disk: 623240 blocks
```

If you want to use the OpenVMS Management Station software, you must install these files. After the installation procedure completes, follow the instructions in Appendix G to prepare your OpenVMS system and your PC to run the OpenVMS Management Station server and client software.

Installing the OpenVMS VAX Operating System

3.3 Creating the System Disk

3.3.8 Step 8: Choose DECwindows Support Options

Next, the procedure displays messages about the DECwindows components shipped with OpenVMS VAX Version 7.1.

Note

The OpenVMS VAX operating system no longer ships the VMS DECwindows product. The operating system now ships only the DECwindows base support and DECwindows workstation support components. To get full DECwindows support, you must also install the separate DECwindows Motif for OpenVMS (previously called VMS DECwindows Motif) layered product, which supports both Motif and XUI environments.

The DECwindows base support and DECwindows workstation support components are *not* shipped with the layered product. If you want to install these options, you must select them now or use the DECW\$TAILOR option after the installation procedure completes.

Before you indicate whether you want to install DECwindows support software, consider the following:

If you...	Then choose...
Intend to install the DECwindows Motif layered product	DECwindows base support.
Intend to install the DECwindows Motif layered product on a workstation or on a VAXcluster system that contains workstations	DECwindows base support and DECwindows workstation support.
Are <i>not</i> planning to install the DECwindows Motif layered product but are installing OpenVMS VAX on a workstation or on a VAXcluster that includes workstations	DECwindows base support and DECwindows workstation support.
Want to provide font files for X terminals	DECwindows base support and DECwindows workstation support.
Have a workstation monitor (for example, a VR150, VR160, or VR295) capable of displaying 100 dots/inch or a VAXstation 4000 series computer, which uses 100 dots/inch video fonts by default	DECwindows base support and DECwindows workstation support with the 100 dots/inch option. By selecting the workstation support files, you automatically get 75 dots/inch video font files, and you will be prompted to indicate if you want to install 100 dots/inch video font files.

The procedure displays the following:

```
You can select DECwindows support now, or you can use the DECW$TAILOR utility
to provide or remove DECwindows support after the installation.
```

```
Some media, TK50s in particular, can be very slow when tailoring on files.
You might want to provide DECwindows options now and tailor off unwanted files later.
```

```
NOTE: This kit does NOT contain full DECwindows.
      To obtain full DECwindows support, you must also install the
      separate layered product, DECwindows Motif for OpenVMS VAX.
      Version 1.2-3 is the minimum version of DECwindows Motif for OpenVMS VAX
      that can be used with OpenVMS VAX Version 7.1.
```

```
The DECwindows components provided in this kit require approximately
33300 blocks, broken down as follows:
```

Installing the OpenVMS VAX Operating System

3.3 Creating the System Disk

- o DECwindows base support - 3800 blocks
- o DECwindows workstation support - 23500 blocks
 - 75 dots per inch video fonts (included)
 - 100 dots per inch video fonts (optional) - 6000 blocks

You must select the DECwindows base support option if

- you plan to run DECwindows software, or
- you are installing this kit on
 - * a workstation or
 - * a VAXcluster that contains workstations, or
- you want to provide font files for Xterminals.

If you are installing this kit on a system that includes Xterminals and you do not select DECwindows base support, then you will have to use the DECW\$TAILOR utility to provide font files.

* Do you want the DECwindows base support? (Y/N)

Space remaining: 612725

You must select the DECwindows workstation support option if

- you are installing this kit on
 - * a workstation or
 - * a VAXcluster that contains workstations, or
- you want to provide font files for Xterminals.

If you are installing this kit on a system that includes Xterminals and you do not select DECwindows base support, then you will have to use the DECW\$TAILOR utility to provide font files.

* Do you want to provide DECwindows workstation support? (Y/N)

Space remaining: 591975

DECwindows workstation support includes the 75 dots per inch video fonts.

All DECwindows applications run with 75 dots per inch video fonts. By default, most systems start up with 75 dots per inch video fonts. Certain applications can take advantage of 100 dots per inch video fonts.

For the VAXstation 4000 series machine, 100 dots per inch video fonts are used by default. If you decide not to install 100 dots per inch video fonts, you must edit SYS\$MANAGER:DECW\$PRIVATE_SERVER_SETUP.COM to force 75 dots per inch video fonts to be the default. Otherwise, certain applications may not space text properly.

For instructions on how to configure your system with both 75 and 100 dots per inch video fonts, see the template command procedure SYS\$MANAGER:DECW\$PRIVATE_SERVER_SETUP.TEMPLATE.

*Do you want 100 dots per inch video fonts installed? (Y/N)

Space remaining: 541975

3.3.9 Step 9: Select DECnet Product

Next, the procedure displays messages describing the DECnet options. For more information, refer to Section 1.2.1.

Beginning with OpenVMS V7.1 DECnet-Plus is provided with the OpenVMS operating system. Digital strongly recommends that DECnet users install DECnet-Plus. DECnet Phase IV applications are supported by DECnet-Plus.

If you plan to install DECnet Phase IV do NOT select DECnet-Plus.

* Do you want to install DECnet-Plus. (Y/N) Y

Space remaining on system disk: 456975 blocks

If you want to install DECnet Phase IV, you must do so after the OpenVMS VAX installation procedure completes.

Installing the OpenVMS VAX Operating System

3.3 Creating the System Disk

3.3.10 Step 10: Verify Your Choices

The procedure displays a list of OpenVMS VAX and DECwindows support options you have selected and gives you the opportunity to change your mind before proceeding by displaying the following message:

* Is this correct? (Y/N)

If you answer No to this prompt, you can respecify the OpenVMS and DECwindows support options you want to install.

3.3.11 Step 11: Install OpenVMS Options

If you answer Yes to the prompt in step 9, the installation procedure begins restoring the OpenVMS options you have selected. After the installation has completed, you can use the VMSTAILOR utility to remove any optional OpenVMS files that you do not need. (For more information about using VMSTAILOR, see Chapter 10.)

This step in the procedure will vary, depending on whether your distribution kit is on compact disc, tape cartridges, or magnetic tapes.

3.3.11.1 Compact Disc

If your distribution kit is on compact disc, leave the disc in the drive. The procedure displays messages as it restores each of the OpenVMS options you have chosen to install.

3.3.11.2 Tape Cartridges and 9-Track Open Reel Magnetic Tapes

If your distribution kit is on TK50 tape cartridges or 9-track open reel magnetic tapes, you may be asked to mount additional volumes of the kit. In such a case, your system will display a message similar to the following:

Please mount volume <x> of the OpenVMS kit on <device>

where: <x> is the volume number and <device> is the cartridge tape drive or open reel tape drive.

After you respond to the prompt, the system displays one of the following messages:

- For a TK50 tape cartridge, the message is similar to the following:
* Is the volume labeled OVMS VAX V7.1 BIN TK50 2/2 ready to be mounted?
- For 9-track open reel tape, the message is similar to the following:
* Is the volume labeled OVMS VAX V7.1 BIN MT9 n/4 ready to be mounted?

where: *n/4* may be 2/4, 3/4 or 4/4.

To respond to either message, do the following:

1. Unload the volume currently in the drive.
2. Examine the remaining volumes and select the one with the label that matches the label specified in the prompt.
3. Load the volume and make the drive ready.
4. Answer YES to the question.

For information on which save sets are located on which tape volumes, Section 1.4.1 and Section 1.4.2.

Step 12: Install DECwindows Support Software

If you are installing DECwindows software, the procedure installs the DECwindows options that you specified and displays messages similar to the following:

```
Restoring DECwindows base support save set ...
%BACKUP-I-STARTVERIFY, starting verification pass

Restoring DECwindows workstation support save set ...
%BACKUP-I-STARTVERIFY, starting verification pass

Restoring DECwindows 75 dots per inch fonts save set ...
%BACKUP-I-STARTVERIFY, starting verification pass

Restoring DECwindows 100 dots per inch fonts save set ...
%BACKUP-I-STARTVERIFY, starting verification pass
```

The DECwindows support files are listed in Appendix E. After you finish the installation, you can use the DECwindows tailoring utility, DECW\$TAILOR, to remove the DECwindows files you do not need. For more information about removing files with DECW\$TAILOR, see Chapter 10.

If your distribution media is tape cartridges or magnetic tape, the procedure displays a message similar to the following after the DECwindows options you have selected have been successfully installed:

```
You can now remove the DECwindows distribution kit from MUA0:.
```

Remove the distribution media from the drive.

If your distribution media is compact disc leave it in the drive.

3.4 Configuring a Cluster

The installation procedure now displays information about cluster configuration. But, because there is no network present on the system at this point in the procedure, no cluster configuration work can actually be performed at this time.

In a cluster, you can run multiple systems sharing all files except PAGEFILE.SYS, SWAPFILE.SYS, SYSDUMP.DMP, and VAXVMSYS.PAR.

Cluster configuration cannot be done at this time because no network is present. In order to configure a cluster, you must FIRST do one or both of the following:

- o Install DECnet-Plus (or DECnet Phase IV), or
- o Execute SYS\$STARTUP:LAN\$STARTUP.COM by removing the comment delimiter ("!") from the line

```
$! @ SYS$STARTUP:LAN$STARTUP.COM
```

```
in SYS$MANAGER:SYSTARTUP_VMS.COM.
```

Then configure the cluster by executing the following command:

```
@SYS$MANAGER:CLUSTER_CONFIG.COM
```

Once the network is running on your system, you can execute the SYS\$MANAGER:CLUSTER_CONFIG.COM command procedure in configure your cluster. For more information about cluster configuration, see the *OpenVMS System Manager's Manual: Essentials*.

Installing the OpenVMS VAX Operating System

3.5 Setting Passwords

3.5 Setting Passwords

Next, the installation procedure prompts you to set passwords for the SYSTEM, SYSTEST, and FIELD accounts and uses this information to create a rights database.

When setting the passwords, remember:

- Passwords must be 8 characters or more.
- Passwords are not displayed by the system while you are entering them.
- Press Return after you enter each password.
- Each password is verified.

Use the following procedure to set passwords:

1. Supply the passwords when prompted by the installation procedure, as follows:

```
Now we will ask you for new passwords for the following accounts:
```

```
SYSTEM, SYSTEST, FIELD
```

```
Passwords must be a minimum of 8 characters in length. All passwords
will be checked and verified. Any passwords that can be guessed easily
will not be accepted.
```

```
* Enter password for SYSTEM:
* Re-enter for verification:
%UAF-I-MDFYMSG, user record(s) updated
%VMS-I-PWD_OKAY, account password for SYSTEM verified
```

```
* Enter password for SYSTEST:
* Re-enter for verification:
%UAF-I-MDFYMSG, user record(s) updated
%VMS-I-PWD_OKAY, account password for SYSTEST verified
```

```
The SYSTEST_CLIG account will be disabled. You must re-enable
it before running UETP but do not assign a password.
```

```
* Enter password for FIELD:
* Re-enter for verification:
%UAF-I-MDFYMSG, user record(s) updated
%VMS-I-PWD_OKAY, account password for FIELD verified
```

2. If there are no password errors, the procedure creates your rights database, and you can proceed to the next section.

If you enter a password incorrectly or if the password is too easy to guess, the procedure displays error messages similar to the following:

```
%VMS-I-PWD_INVALID, account password for SYSTEST is invalid
%VMS-I-PWD_WEAK, password is too easy to guess
```

```
Because of the preceding error, you must take action to secure this account.
You must either disable this account, change its password, or do both.
```

3. When the procedure asks if you want to disable the account, type N and press Return. When the procedure asks if you want to enter a new password, type Y and press Return. Then enter a new password. For example:

```
Do you want to disable this account (Y/N)? N
Do you want to change the account password (Y/N)? Y
You must now select a new primary password for the SYSTEST account. The
password you select must be at least 8 characters in length and cannot
be the same as the name of the account:
```

Installing the OpenVMS VAX Operating System

3.5 Setting Passwords

```
New password:
Verification:
%UAF-I-MDFYMSG, user record(s) updated
%VMS-I-PWD_SET, primary password for account SYSTEST set
```

4. When you have successfully set the passwords, the installation procedure creates your rights database, which lets you manage user access to the system, and displays the following message:

```
Creating RIGHTS database file, SYS$SYSTEM:RIGHTSLIST.DAT
Ignore any "-SYSTEM-F-DUPIDENT, duplicate identifier" errors
.
.
.
```

3.6 Entering SCSNODE and SCSSYSTEMID Parameters

If you are installing a standalone system, the procedure displays the following prompts:

- * Please enter SCSNODE name
- * Please enter SCSSYSTEMID

Enter the SCSNODE name and SCSSYSTEMID that you determined as part of the preinstallation tasks in Chapter 2.

If you are installing the operating system in a VAXcluster environment, you are not prompted to supply these parameters. The procedure calculates these parameters using the DECnet node name and node address you supplied earlier in the procedure.

3.7 Postinstallation Tasks Described

After the procedure creates the rights database, it displays messages describing postinstallation tasks you might want to perform.

Note that you do not perform these tasks now but *after* the installation completes.

The tasks displayed on your screen might vary from the following example, depending on what options you chose to install earlier in the procedure.

After the installation finishes, you might want to do one or more of the following tasks:

o DECOMPRESS THE SYSTEM LIBRARIES - To save space, many of the system libraries are shipped in a data-compressed format. If you have enough disk space, you can decompress the libraries for faster access. To data expand the libraries, type:

```
$ @SYS$UPDATE:LIBDECOMP.COM
```

If you do not decompress these libraries, you will experience slower response with the HELP and LINK commands.

o BUILD A STANDALONE BACKUP KIT - You can build a standalone backup kit using the procedure described in the upgrade and installation supplement supplied for your VAX computer.

o TAILOR THE SYSTEM DISK - You might want to review the files provided or not provided during this installation. If you find there are files you want to remove from the system disk (TAILOR OFF) or files you want to add (TAILOR ON), use the following utilities to perform the desired tailoring.

```
OpenVMS tailoring:          $ RUN SYS$UPDATE:VMSTAILOR
DECwindows tailoring:     $ RUN SYS$UPDATE:DECW$TAILOR
```

Installing the OpenVMS VAX Operating System

3.7 Postinstallation Tasks Described

Note: The tailor procedure cannot be used to TAILOR ON or to TAILOR OFF files located on an alternate device.

- o DEFINE A LOGICAL NAME - Define the logical name MSGHLP\$LIBRARY in your site-specific startup file to be: DUA1:[HELP_MESSAGE] to point to the new location of the MSGHLP database.

For more information about decompressing the system libraries, see Section 4.8 in Chapter 4. For information on using VMSTAILOR or DECW\$TAILOR, see Chapter 10.

After the messages about postinstallation tasks are displayed, the procedure displays a message similar to the following:

```
Continuing with OpenVMS VAX V7.1 installation procedure.  
Configuring all devices on the system...
```

Proceed to the next section for information about registering your licenses.

3.8 Registering Licenses

Before you can use the OpenVMS VAX operating system and its components, you must first register all licenses. If you do not register your licenses at this point in the procedure, you must register them immediately after the installation, *before* you perform the other postinstallation tasks.

3.8.1 Types of Licenses

The OpenVMS VAX operating system uses one of two different categories of licenses, depending on the hardware and software configuration used and currently supported. The two categories of operating system licenses for OpenVMS VAX are:

- VAX VMS licensing
- OpenVMS VAX licensing

The following table describes the types of licenses for each licensing category. Digital provides the proper license type with the purchase of the system. Not all license types are available for every system model.

Type of License	Description
VAX VMS Licenses	
Traditional License	Provides unlimited use to the users on a defined system. VAX VMS traditional licenses are sized to capacity according to system type.
Multi-User License	Provides use according to a specified number of concurrent users. This is an activity-based license. The Multi-user License gives you the right to use the operating system for up to the limit of users specified in the license. An operating system <i>user</i> is one who is logged in to the system or one who is using the operating system software by means other than login, or both. This license is available only on limited system models, primarily MicroVAX and VAX 4000 systems. Interactive use of VAX systems licensed with the Multi-user License can be increased by the addition of the OpenVMS VAX Individual User License ¹ for one or more users. For more information, refer to the description of the OpenVMS VAX Individual User License later in this table.

¹The OpenVMS VAX Individual User License is not supported by the VMS or OpenVMS VAX operating system releases prior to VMS Version 5.5.

Installing the OpenVMS VAX Operating System

3.8 Registering Licenses

Type of License	Description
VAX VMS Licenses	
VAX VMS Workstation License	<p>Provides use for a single user on a VAX workstation. This license type allows one direct login for the single user and then one additional login for system management purposes only.</p> <p>Additional interactive use of VAX workstations licensed with the VAX VMS Workstation License requires the addition of an OpenVMS VAX User License¹ for one or more users. For more information, refer to the description of the OpenVMS VAX Individual User License later in this table.</p>
File and Application Server License	<p>Provides for the noninteractive use of OpenVMS VAX. OpenVMS based VAXservers are sold with a File and Application Server License.</p> <p>The intent of an OpenVMS based VAXserver is to provide file, print, application, and compute <i>services</i> to <i>clients</i> who have remotely submitted their requests for these services. This license type also allows one direct login for system management purposes only.</p> <p>Additional interactive use of OpenVMS VAXservers licensed with the File and Application Server License requires the addition of an OpenVMS VAX User License¹ for one or more users. For more information, refer to the description of the OpenVMS VAX Individual User License later in this table.</p>
OpenVMS VAX Licenses	
OpenVMS VAX O/S Base License ²	<p>Provides the right to unrestricted, noninteractive use of the OpenVMS VAX operating system for the execution of remotely submitted requests for batch, print, application, and computing services, on a designated, single processor.</p> <p>No direct OpenVMS VAX operating system logins by users are permitted on the system. One direct login is allowed for system management purposes only.</p> <p>Interactive use of systems licensed with an OpenVMS VAX O/S Base License requires the addition of an OpenVMS VAX Individual User License¹ for one or more users.</p>
OpenVMS VAX Individual User License ¹	<p>Provides the right to interactively use the operating system by a specified, or unlimited, number of concurrent users on a designated, single processor. A user is one who is logged in to a processor or one who is interactively using the operating system software by means other than login, or both. An OpenVMS VAX O/S Base License, or any of the four types of VAX VMS Licenses, is a prerequisite for the OpenVMS VAX Individual User License.</p>

¹The OpenVMS VAX Individual User License is not supported by the VMS or OpenVMS VAX operating system releases prior to VMS Version 5.5.

²The OpenVMS VAX O/S Base License is not supported by the VMS or OpenVMS VAX operating system releases prior to VMS Version 5.5.

3.8.2 How to Register Your Licenses

You must register your licenses in the following order:

1. Register the OpenVMS VAX license for the VAX computer on which you have just installed the operating system. If you have a VAXcluster environment, you then register an OpenVMS VAX license for each additional VAX computer in the cluster that will boot off the system disk that you just created. Each registered OpenVMS VAX license must be assigned to one of the nodes for the cluster.

Installing the OpenVMS VAX Operating System

3.8 Registering Licenses

2. Register the licenses for any System Integrated Products (SIPs) that you purchased.

For more information about registering licenses, see the following:

- *OpenVMS License Management Utility Manual*, which provides:
 - Details about all LICENSE commands, error messages, and recovery procedures for licensing tasks
 - A description of VMSLICENSE.COM, with step-by-step instructions for registering licenses
 - Examples of license registration using VMSLICENSE.COM and LICENSE REGISTER commands
- Appendix B of this manual for notes and supplemental information concerning licenses

You can use the SYS\$UPDATE:VMSLICENSE.COM procedure to register a license for any Digital product that supplies a Product Authorization Key (PAK). Or, you can register licenses with the LICENSE REGISTER command. See the *OpenVMS License Management Utility Manual* for detailed information.

3.8.2.1 How to Register OpenVMS VAX Licenses

The installation procedure displays the following message:

```
If you have any Product Authorization Keys (PAKS) to register, you can
register them now.
```

```
* Do you want to register any Product Authorization Keys? (Y/N)
```

If you choose ...	Then ...
<i>Not</i> to register the licenses at this time	Do the following: <ol style="list-style-type: none">1. Type N and press Return.2. Go to Section 3.11.3. Remember that, after the installation, you must register your licenses <i>before</i> performing any other postinstallation tasks (see Chapter 4).
To register your licenses now	Do the following: <ol style="list-style-type: none">1. Type Y and press Return.2. Be sure you have a copy of your PAK for each license you will register.3. Go to the next section to begin the licensing procedure.

By typing Y (Yes) to register your licenses now, you invoke the SYS\$UPDATE:VMSLICENSE.COM procedure, which displays the following message:

Installing the OpenVMS VAX Operating System

3.8 Registering Licenses

OpenVMS License Management Utility Options:

1. REGISTER a Product Authorization Key
2. AMEND an existing Product Authorization Key
3. CANCEL an existing Product Authorization Key
4. LIST Product Authorization Keys
5. MODIFY an existing Product Authorization Key
6. DISABLE an existing Product Authorization Key
7. DELETE an existing Product Authorization Key
8. COPY an existing Product Authorization Key
9. MOVE an existing Product Authorization Key
10. ENABLE an existing Product Authorization Key
11. SHOW the licenses loaded on this node
12. SHOW the unit requirements for this node

99. Exit this procedure

Type '?' at any prompt for a description of the information requested. Press Ctrl/Z at any prompt to return to this menu.

Enter one of the above choices [1]

Select the appropriate options (beginning with 1, as shown) until you have successfully registered all required PAKs.

3.8.2.2 How to Register System Integrated Products

After you register the OpenVMS VAX license, you must register the license for any of the following System Integrated Products (SIPs) you have purchased:

- VAXcluster
(LMF Product Name: VAXCLUSTER)
- DECnet-Plus

There are two DECnet-Plus licenses:

- The end node license named DVNETEND
- The routing node license named DVNETRTG

All routing nodes must have a routing license. Each end node can have either an end node license or a routing license. If neither license is registered and activated, DECnet does not start and your use is limited to local DECnet only (SET HOST 0). If DECnet-Plus for OpenVMS is running when you register your license, you must stop and then restart it.

You can control which VAXcluster nodes have access to each license. Using the LICENSE MODIFY/INCLUDE=(node-name[,node-name,...]) command, you can assign licenses to nodes and limit access as needed. For example, you can assign a routing node license to only one VAXcluster node and assign the end node licenses to the remaining VAXcluster nodes. If you choose this approach, make sure you assign a license to each end node license. Specify include lists for each license of the same type. For details, see the *OpenVMS License Management Utility Manual*.

- RMS Journaling for OpenVMS
(LMF Product Name: RMSJNL)

On systems that do not have registered and loaded journaling licenses, users cannot write to any files marked for journaling.

- Volume Shadowing for OpenVMS
(LMF Product Name: VOLSHAD)

You must register and load a license for Volume Shadowing for OpenVMS on each node using volume shadowing, including satellites in a VAXcluster system.

Installing the OpenVMS VAX Operating System

3.9 Time Zone and Time Differential Factor Information

3.9 Time Zone and Time Differential Factor Information

At this point in the installation, the procedure asks you for time zone information that is used for providing local time zone support.

3.9.1 Updating Time Zone Information

For local time zone support to work correctly, the installation procedure must set the time zone that accurately describes the location you want to be considered as your default time zone. Usually, this is the time zone in which your system is running. In addition, your system must be correctly configured to use a valid OpenVMS time differential factor (TDF).

The procedure displays a series of time zone menus and prompts you to make selections from those menus. The first menu is the main time zone menu. Select the time zone that best describes your location. If you do not select a time zone, the default is Greenwich Mean Time (GMT).

Some time zone choices cause an additional menu to be displayed. This happens when the time zone you select has subcomponents. For example, if you choose the United States (US) time zone from the main menu, a second menu displays the specific time zones within the United States. You then select the menu item that best represents your local time zone.

The procedure then prompts you for the TDF. The TDF is the difference between your system time and Coordinated Universal Time (UTC), which is an international standard for measuring time of day. You can choose from the following options:

- Exit the time zone procedure without setting a TDF
- Set a TDF
- Display the TDF for your local time zone

For more information about TDF and local time zone support, see the *OpenVMS System Manager's Manual*

If you chose to install DECnet-Plus earlier in the installation procedure, see Section 3.10.

If you chose *not* to install DECnet-Plus, go to Section 3.11.

3.10 Installing DECnet-Plus

Earlier in the procedure, you were asked whether you wanted to install the DECnet-Plus product. If you answered Yes, the procedure will now install the DECnet-Plus product.

The procedure displays a message similar to the following and prompts you for information it needs to install the DECnet-Plus product. In this example, the kit is being installed from an InfoServer device, DAD1.

```
DECnet-Plus will now be installed.
```

```
Media containing the DECnet-Plus kit must be available.
```

```
If you are installing OpenVMS from an InfoServer (DAD1)
or local CD-ROM, there is a DECnet-Plus kit on the CD-ROM.
```

```
If you are installing from a cartridge tape (TK50) or
from an open reel tape, you should have a DECnet-Plus kit
on cartridge tape or open reel tape.
```


Installing the OpenVMS VAX Operating System

3.10 Installing DECnet-Plus

An appropriate DECnet-Plus kit may also be available on the Consolidated Distribution CD-ROM, or you may have a separate DECnet-Plus kit.

NOTE: You may choose any available media for the DECnet-Plus kit. It is NOT NECESSARY to use the same type of media that contained the OpenVMS kit.

If you do not have a DECnet-Plus kit available, or if you have decided NOT to install/upgrade DECnet-Plus, you can bypass the DECnet-Plus installation by entering "EXIT" for the "name of drive holding the DECnet-Plus kit".

- * Enter name of drive holding the DECnet-Plus kit: DAD1:
- * Enter the InfoServer service name: OTHER_PRODS
- * Enter the InfoServer work group number [0]:

The following product has been selected:
DEC VAXVMS DECNET_OSI V7.1

DEC VAXVMS DECNET_OSI V7.1: DECnet-Plus V7.1 for OpenVMS VAX

Copyright © Digital Equipment Corporation 1996. All rights reserved.

Digital Equipment Corporation

This product requires one of two PAKs: DVNETEND or DVNETRTG.

Do you want all the default values for this product? [YES]

Do you want to view the values? [NO]

Execution phase starting ...

The following product will be installed:

DEC VAXVMS DECNET_OSI V7.1

Portion done: 0%...10%...20%...30%...40%...80%...90%...100%

The following product has been installed:

DEC VAXVMS DECNET_OSI V7.1

.
.
.

To complete the installation procedure, continue on to the next section, Section 3.11.

3.11 Running AUTOGEN

The remaining portion of the installation procedure runs AUTOGEN to evaluate your hardware configuration and estimate typical workloads. AUTOGEN then sets system parameters, the sizes of page, swap, and dump files, and the contents of VMSIMAGES.DAT. When AUTOGEN finishes and the system has rebooted, the installation procedure is complete.

The installation procedure runs AUTOGEN, as follows:

1. The installation procedure displays a series of messages similar to the following:

```
Running AUTOGEN to compute new SYSTEM parameters ...
```

```
%AUTOGEN-I-BEGIN, GETDATA phase is beginning.
```

```
%AUTOGEN-I-NEWFILE, A new version of SYS$SYSTEM:PARAMS.DAT has been created.
```

```
    You may wish to purge this file.
```

```
%AUTOGEN-I-END, GETDATA phase has successfully completed.
```

```
.  
.  
.
```

```
%AUTOGEN-I-BEGIN, REBOOT phase is beginning.
```

If you need to create or modify the size of the pagefile or swapfile, use the SYSMAN utility. For more information, see the *OpenVMS System Manager's Manual: Essentials*.

Installing the OpenVMS VAX Operating System

3.11 Running AUTOGEN

2. After AUTOGEN finishes, the procedure displays a series of shutdown messages that begin like this:

The system is shutting down to allow the system to boot with the generated site-specific parameters and installed images.

The system will automatically reboot after the shutdown and the upgrade will be complete.

```
SHUTDOWN -- Perform an Orderly System Shutdown
```

3. After the system shuts down, the procedure tries to reboot the new system disk. If the system does not reboot automatically, reboot it manually.

For example, suppose you have a VAX-11/780 computer and the system disk is on an RA60 disk drive with a unit number of one. Enter the following command and press Return:

```
>>> B DUA1
```

For information on booting, refer to the upgrade and installation supplement for your VAX computer. Then return to this manual.

4. After the system reboots, the procedure displays the following message:

```
OpenVMS VAX Version V7.1 Major version id = 1 Minor version id = 0
```

```
*****
```

```
OpenVMS VAX V7.1
```

```
You have SUCCESSFULLY installed the OpenVMS VAX operating system.
```

```
The system is now executing the STARTUP procedure. Please wait for the completion of STARTUP before logging in to the system.
```

```
*****
```

Note: If you did not register your OpenVMS VAX license as described in Section 3.8, the procedure displays warning messages that the OpenVMS license must be registered. Be sure to register this license when the installation procedure finishes. For more information, see Appendix B and the *OpenVMS License Management Utility Manual*.

Finally, the procedure displays informational messages and accounting information. For example:

```
%SET-I-INTSET, login interactive limit = 64, current interactive value = 0
SYSTEM      job terminated at 22-NOV-1996 16:54:24.71
```

```
Accounting information:
Buffered I/O count:      859      Peak working set size:      565
Direct I/O count:       478      Peak virtual size:          2570
Page faults:            5003     Mounted volumes:             0
Charged CPU time: 0 00:00:19.33  Elapsed time:                0 00:00:41.24
```

At this point the OpenVMS VAX operating system is running.

5. Press the Return key. The system asks you for the user name and password. Log in to the SYSTEM account so you can perform certain postinstallation tasks. For example:

```
Welcome to OpenVMS VAX V7.1
Username: SYSTEM
Password:
.
.
.
Welcome to OpenVMS VAX Version V7.1
```

Installing the OpenVMS VAX Operating System

3.11 Running AUTOGEN

If you forget the password, follow the instructions for performing an emergency startup in the *OpenVMS System Manager's Manual: Essentials*.

6. There are several postinstallation tasks you must perform before you can use the system. These tasks are described in Chapter 4.

After Installing OpenVMS VAX

4.1 Overview

After you have installed the OpenVMS VAX operating system, you need to perform several important tasks to prepare the system for operation. This chapter describes the following postinstallation tasks in the order you perform them:

- Verifying system time
- Registering licenses
- Backing up your system disk
- Customizing your system
- Configuring and starting networking software
- Testing the system
- Decompressing system libraries
- Removing unwanted files
- Installing layered products
- Backing up the customized system disk
- Running AUTOGEN
- Completing the postinstallation checklist

If you are an experienced system manager, you can use the checklist at the end of the chapter to complete the necessary postinstallation tasks.

If you are a system manager with less OpenVMS VAX experience, you should read the entire chapter and then use the checklist to make sure you have completed all the postinstallation tasks.

4.2 Verifying System Time

During the installation, the procedure prompted you to enter the date and time. Now that you have installed your system, verify that the system time is correct by entering the following command:

```
$ SHOW TIME
```

The system displays the date and time. If the time is not correct, reset it by entering the command SET TIME using the following format:

```
SET TIME=dd-mmm-yyyy:hh:mm:ss
```

For example:

```
$ SET TIME=22-NOV-1996:18:35:30
```

After Installing OpenVMS VAX

4.3 Registering Your Licenses

4.3 Registering Your Licenses

The installation procedure gave you the opportunity to register any software product licenses. If you did not register your OpenVMS VAX license at that time, you must do so before you can use the OpenVMS VAX operating system. You must also register the licenses for any of the following System Integrated Products you have purchased:

- VAXcluster
- DECnet-Plus
- OpenVMS RMS Journaling
- Volume Shadowing for OpenVMS

4.3.1 Where to Find More Information

For step-by-step instructions about registering licenses, see the *OpenVMS License Management Utility Manual* and Appendix B of this manual, which provides supplemental information.

4.4 Backing Up Your System Disk

Now that you have spent time installing the operating system, you should protect your work by making a backup copy of the system disk in case you have any problems while customizing it. Digital recommends that you perform the following operations:

- Make a standalone BACKUP kit on the system disk and on removable media
- Perform a standalone BACKUP of your system disk

You should back up your system disk again after you have customized it.

For complete information about these operations, see the upgrade and installation supplement for your VAX computer.

4.5 Customizing the System

You can customize the system to meet the specific needs of your site. In addition, if your VAX computer is part of a VAXcluster environment, you must prepare the cluster environment and configure the cluster.

For instructions about customizing your system, refer to the following:

- Read the chapter on booting in the upgrade and installation supplement for your VAX computer. This chapter explains the different ways to boot the system. It also tells you how to shut down the system.
- If the computer is part of a VAXcluster environment, read *OpenVMS Cluster Systems* for further information about setting up a cluster.
- Read the *OpenVMS System Manager's Manual: Essentials* for instructions on customizing and using your system. You will find information about the following tasks:
 - Editing the template files SYCONFIG.COM, SYLOGICALS.COM, SYLOGIN.COM, and SYSTARTUP_VMS.COM
 - Starting the queue manager and creating a queue database. (If you are installing on a VAXcluster system with multiple system disks, see the *OpenVMS Cluster Systems* for additional instructions.)
 - Setting up user accounts

- Adjusting system parameters
- If you plan to use either the DECnet-Plus product included on the OpenVMS VAX Version 7.1 kit or the DECnet Phase IV layered product, read Section 4.6 and perform the steps described there. If you are installing the DECnet-Plus software, you should also refer to the DECnet-Plus installation and configuration documentation.
- If you installed DECwindows support software, there are several steps you must take to customize your DECwindows environment. Depending on your configuration, these tasks might include:
 - Customizing the server startup
 - Using the Transmission Control Protocol/Internet Protocol (TCP/IP) as a DECwindows transport
 - Using transports for DECwindows other than those supplied by DigitalSee Chapter 9 for complete instructions for customizing your DECwindows support software.
- If you installed the optional OpenVMS Management Station files, see Appendix G for information about preparing your OpenVMS system and your PC to use this application.

4.6 Configuring and Starting Networking Software

In local area and mixed-interconnect VAXcluster systems, DECnet software provides both system management functions and cluster communications, such as remote booting operations. DECnet software ensures that system managers can access all VAXcluster computers from a single terminal.

You can use the DECnet-Plus software included on the OpenVMS VAX Version 7.1 kit, or you can install the DECnet Phase IV layered product.

Both of these products require that you run a configuration procedure to configure the network. If you choose to run the DECnet Phase IV product, you must also edit your system startup file as described in Section 4.6.2.

4.6.1 Configuring Your System

After you have registered your DECnet license, execute one of the following interactive configuration procedures:

- For the DECnet Phase IV software, run `SYSSMANAGER:NETCONFIG.COM`. (See the *DECnet for OpenVMS Guide to Networking* for more information.)
- For the DECnet-Plus for OpenVMS layered product, run `SYSSMANAGER:NET$CONFIGURE.COM`. (See the *DECnet-Plus for OpenVMS Installation and Basic Configuration* for more information.)

4.6.2 Editing SYSTARTUP_VMS

If you plan to run DECnet-Plus, you do not need to edit this file because DECnet will start automatically.

If you plan to run DECnet Phase IV, after you start the queue manager, edit the commands in `SYSSCOMMON:[SYSMGR]SYSTARTUP_VMS.COM` that pertain to networking, so that DECnet starts automatically when your system is booted. Choose one of the following commands to start the network and remove the comment delimiter (!) from that command:

After Installing OpenVMS VAX

4.6 Configuring and Starting Networking Software

```
$! IF F$SEARCH("SYS$SYSTEM:NETACP.EXE") .NES. "" THEN @SYS$MANAGER:STARTNET
$! IF F$SEARCH("SYS$SYSTEM:NETACP.EXE") .NES. "" THEN SUBMIT SYS$MANAGER:STARTNET.COM
```

Both of the previous commands perform the same task. However, the first command executes STARTNET.COM and delays further processing until the procedure is completed; the second submits STARTNET.COM to a batch queue and continues executing SYSTARTUP_VMS.COM. If you plan to run both DECnet Phase IV and DECwindows Motif for OpenVMS VAX, you must also edit SYS\$COMMON:[SYSMGR]SYSTARTUP_VMS.COM to add a comment delimiter (!) immediately following the dollar-sign (\$) in the DEFINE DECW\$IGNORE_DECNET command as follows:

```
$! DEFINE DECW$IGNORE_DECNET TRUE
```

If you are not going to start DECnet Phase IV or have not yet started it, this command tells DECwindows not to wait for DECnet.

4.7 Testing the System with UETP Software

UETP software is a user environment test package that tests whether the OpenVMS VAX operating system is installed correctly. As part of the postinstallation procedure, you should run UETP to verify your installation.

Note that UETP needs at least 1200 free blocks on the system disk and is available only if you installed the optional save set VMS071.D. If you did not install the optional save set, you can add the UETP files to your system using VMSTAILOR.

For information about using VMSTAILOR see Chapter 10.

For complete information about UETP, see the *OpenVMS System Manager's Manual: Tuning, Monitoring, and Complex Systems*.

4.8 Decompressing System Libraries

Decompressing the system libraries gives the system faster access to them. You can decompress all the system libraries or just some of them. Table 4–1 gives the approximate number of blocks consumed by each library after decompression.

Table 4–1 Sizes of Decompressed System Libraries

Library	Blocks	Library	Blocks
HELPLIB.HLB	9108	EDFHLP.HLB	102
STARLET.OLB	8442	TPUHELP.HLB	1038
VAXCCURSE.OLB	102	ACLEDT.HLB	102
VAXCRTL.OLB	477	INSTALHLP.HLB	102
VAXCRTLG.OLB	102	LATCP\$HELP.HLB	240
DECCURSE.OLB	102	MNRHELP.HLB	102
DECCRTL.OLB	183	PATCHHELP.HLB	102
DECCRTL.G.OLB	102	PHONEHELP.HLB	102
ERFLIB.TLB	105	SDA.HLB	111
STARLETSD.TLB	4800	SHWCLHELP.HLB	150

(continued on next page)

After Installing OpenVMS VAX 4.8 Decompressing System Libraries

Table 4-1 (Cont.) Sizes of Decompressed System Libraries

Library	Blocks	Library	Blocks
MAILHELP.HLB	273	SYSGEN.HLB	393
EDTHELP.HLB	231	TECO.HLB	102
DBG\$UIHELP.HLB	408	UAFHELP.HLB	372
DBG\$HELP.HLB	1986	EVE\$HELP.HLB	1197
EXCHNGHLP.HLB	117	EVE\$KEYHELP.HLB	147
NCPHELP.HLB	537	STARLET.MLB	2502
ANLRMSHLP.HLB	102	LIB.MLB	2229
DISKQUOTA.HLB	102		

The additional amount of disk space required to decompress all the system libraries is about 13,500 blocks. To find out how much disk space you have, enter the following command and press the Return key:

```
$ SHOW DEVICE SYS$SYSDEVICE
```

To decompress the system libraries, you run LIBDECOMP.COM by logging in to the SYSTEM account, entering the following command, and pressing Return:

```
$ @SYS$UPDATE:LIBDECOMP.COM
```

The following information is displayed:

```

OpenVMS Library Decompression Utility

 1  HELPLIB.HLB          14  NCPHELP.HLB          27  PATCHHELP.HLB
 2  STARLET.OLB         15  SDA.HLB              28  PHONEHELP.HLB
 3  ACLEDT.HLB          16  SHWCLHELP.HLB       29  LIB.MLB
 4  ANLRMSHLP.HLB      17  SYSGEN.HLB           30  STARLET.MLB
 5  DBG$HELP.HLB       18  ANALAUDIT$HELP.HLB  31  STARLETSD.TLB
 6  DBG$UIHELP.HLB    19  SYSMANHELP.HLB      32  ERFLIB.TLB
 7  DISKQUOTA.HLB     20  TFF$TFUHELP.HLB     33  VAXCCOURSE.OLB
 8  EDFHLP.HLB         21  EXCHNGHLP.HLB       34  VAXCRTL.OLB
 9  INSTALHLP.HLB     22  TPUHELP.HLB          35  VAXCRTLG.OLB
10  LATCP$HELP.HLB    23  EVE$HELP.HLB         36  IMAGELIB.OLB
11  MAILHELP.HLB      24  EVE$KEYHELP.HLB     37  DECCOURSE.OLB
12  MNRHELP.HLB       25  UAFHELP.HLB          38  DECCRTL.OLB
13  EDTHELP.HLB       26  TECO.HLB             39  DECCRTLG.OLB

      A  ALL libraries to be decompressed
      E  EXIT this procedure

```

* Enter letter or number(s) of libraries to be decompressed
(Separate multiple entries with a comma):

Enter the appropriate letter or the numbers of the libraries you want to decompress. To decompress all libraries, the process takes approximately one half hour.

If you prefer, you can execute LIBDECOMP interactively or as a batch job. If you use either of these methods, you can decompress up to 8 libraries each time you execute LIBDECOMP by listing the names of the libraries you want to decompress as parameters on the command line. (You can decompress all the libraries by omitting the /PARAMETERS qualifier.) Be sure to separate the library names with commas and do not include the file extension. For example, to decompress the VAXCRTL.OLB, DISKQUOTA.HLB, and LIB.MLB libraries as a batch job, enter the following command:

After Installing OpenVMS VAX

4.8 Decompressing System Libraries

```
$ SUBMIT/NOTIFY/PARAMETERS=(VAXCTRL, DISKQUOTA, LIB) -  
_ $ SYSSUPDATE:LIBDECOMP
```

To decompress these same libraries interactively, enter the following command:

```
$ @SYSSUPDATE:LIBDECOMP VAXCTRL DISKQUOTA LIB
```

Note that, when you type the command for a batch job, you separate the library names with commas and enclose the list within parentheses. You do not use commas or parentheses on the interactive command line.

4.9 Removing or Adding OpenVMS Files

To remove unwanted OpenVMS VAX files from the system disk, use VMSTAILOR or DECW\$TAILOR. For example, if you are not running DECnet software, use VMSTAILOR to remove the files associated with DECnet.

Note

You cannot use VMSTAILOR to remove files installed on an alternate device from save set VMS071.E.

For complete information about using VMSTAILOR and DECW\$TAILOR to remove optional OpenVMS VAX software, see Chapter 10.

4.10 Installing Layered Products

Back up your system disk and then use either the VMSINSTAL command procedure or the POLYCENTER Software Installation utility to install layered products on your system.

For additional information about installing layered products, see the *OpenVMS System Manager's Manual*.

4.10.1 TCP/IP Services for OpenVMS

If you installed the Digital TCP/IP Services for OpenVMS software during the installation or if you choose to install it now as a layered product, note that you must also install the mandatory security update kit included with this release.

The Digital TCP/IP Kit and the mandatory Security Update Kit are available in the following directory on the OpenVMS VAX CD-ROM:

```
[TCPIP_VAX_041]
```

If you choose to install the Digital TCP/IP Services for OpenVMS software, you must install both kits.

4.11 Backing Up the Customized System Disk

Now that you have spent time installing and customizing the operating system, protect your work by making a standalone backup copy of the system disk. For complete information about these operations, see the upgrade and installation supplement for your VAX computer.

4.12 Running AUTOGEN

When you installed the OpenVMS VAX operating system, the procedure executed AUTOGEN to set the values of system parameters and the sizes of the page and swap files according to the system's workload.

In many cases, AUTOGEN can improve system performance by using dynamic feedback information from the running system. As a postinstallation task, you should run AUTOGEN again using the feedback mechanism to make further adjustments to system parameters.

4.12.1 How AUTOGEN Works

When AUTOGEN runs, it uses the parameter values in SYSSYSTEM:MODPARAMS.DAT. Note that hardcoded values in MODPARAMS.DAT affect AUTOGEN's calculations of the feedback parameters. For AUTOGEN to properly calculate minimum default values, you should replace the hardcoded values in MODPARAMS.DAT with MIN_ values. If you need to modify the parameter values calculated by AUTOGEN, you can use AUTOGEN to change the hardcoded values in MODPARAMS.DAT.

For information about using AUTOGEN, see the *OpenVMS System Manager's Manual: Essentials*.

4.12.2 When to Run AUTOGEN

After installing the operating system, run AUTOGEN again using the following procedure:

1. After 24 hours of operation, run AUTOGEN in feedback mode and reboot the system.
2. Run AUTOGEN in this same way, again, two working days later.

Note: For large memory systems such as the VAX 9000 computer, AUTOGEN's initial parameter calculations are conservative. To obtain parameter values that match your system workload, you can run AUTOGEN in feedback mode a number of times. For more information, see the upgrade and installation supplement for your computer.

3. Digital recommends that you run AUTOGEN from SAVPARAMS through TESTFILES on a weekly basis and examine AGEN\$PARAMS.REPORT to determine the need for additional changes.

After you run AUTOGEN following the first 24 hours of system operation (step 1), review the checklist in Section 4.13 to confirm that you have completed all the tasks described in this chapter.

4.13 Postinstallation Checklist

Use the following checklist to make sure you perform all the necessary postinstallation tasks.

- Verify the system time. (Described in Section 4.2.)
- Register your licenses if you did not do so during the installation procedure. (Described in Appendix B of this manual and in the *OpenVMS License Management Utility Manual*.)
- Build a standalone BACKUP kit on the system disk and on removable media. (Described in the upgrade and installation supplement for your computer.)

After Installing OpenVMS VAX

4.13 Postinstallation Checklist

- Back up the system disk as a safeguard before customizing the system. (Described in the upgrade and installation supplement for your computer.)
- Customize the system. (Described in Section 4.5.)
- Configure and start your networking software. (Described in Section 4.6.)
- Run UETP (the User Environment Test Package) to test the system. (Described in *OpenVMS System Manager's Manual: Tuning, Monitoring, and Complex Systems*.)
- Decompress the system libraries using LIBDECOMP.COM. (Described in Section 4.8.)
- Remove unwanted files from the system disk using the OpenVMS tailoring utility. (Described in Chapter 10.)
- Install layered products.
- Back up the system disk after you have customized it. (Described in the upgrade and installation supplement for your computer.)
- Run AUTOGEN after the system has been running for at least 24 hours to collect feedback information. (Described in Section 4.12.)

Before Upgrading OpenVMS VAX Software

5.1 Overview

Before you begin an upgrade, you need to perform several important tasks to prepare the system. This chapter describes what you need to know and do to prepare for an upgrade, including:

- Being aware of the cautions and restrictions
- Making sure your hardware is ready and your software distribution kit is complete
- Examining AUTOGEN feedback data
- Backing up your system disk
- Preparing your system disk
- Preparing your system
- Gathering the information for the upgrade procedure
- Completing the preupgrade checklist

If you are an experienced system manager, you can use the checklist at the end of this chapter to complete the necessary preupgrade tasks.

If you are system manager with limited OpenVMS VAX experience, you should read the entire chapter and then use the checklist to make sure you have completed all the preupgrade tasks.

5.2 Cautions and Restrictions

This section provides important information that you need to be aware of before you upgrade your system. If you attempt to upgrade your system without following these cautions and restrictions, the upgrade could fail or your upgraded system might not perform as expected.

5.2.1 License Requirements

To upgrade to OpenVMS Version 7.1, you must have an appropriate license. Digital's software licenses grant the right to use the current version of a product or any previous version of the product at the time of purchase. If you have an OpenVMS license prior to Version 7.1 and are not covered by a Software Product Services agreement, which includes the right to use new versions (RTNV), you must purchase an Update License before upgrading to OpenVMS Version 7.1.

If you do not have an Update License, please contact your Digital account representative who will assist you in obtaining the correct Product Authorization Key (PAK) needed to access the OpenVMS operating system.

Before Upgrading OpenVMS VAX Software

5.2 Cautions and Restrictions

5.2.2 DECset Version 11 Debugger

If you have the DECset Version 11 layered product installed on your system, you must remove the @DEBUG\$STARTUP.COM command from the system startup procedure. The debugger shipped with OpenVMS VAX Version 7.1 is a superset of the debugger that was shipped with the DECset Version 11 software. Removing the @DEBUG\$STARTUP.COM command will cause the debugger shipped with OpenVMS VAX Version 7.1 to be the default system debugger.

To remove the @DEBUG\$STARTUP.COM command *before* you upgrade the operating system software, perform the following steps:

1. Log in to an account with system privileges.
2. Using the editor of your choice, open the SYS\$STARTUP:SYSTARTUP_VMS.COM file and search for the following command:

```
$ @DEBUG$STARTUP
```

Delete the command and any parameters. (The command might have an optional parameter of either VMS or DECSET.)

3. Exit from the file, saving the change.

If you do not remove this command before you upgrade the operating system software, you must remove it after the upgrade, and you must deassign the logicals that were defined by DEBUG\$STARTUP.COM by performing the following steps:

1. Log in to the account that you used to perform the upgrade.
2. Enter the following commands:

```
$ DEASSIGN/SYSTEM DEBUG  
$ DEASSIGN/SYSTEM DEBUGSHR  
$ DEASSIGN/SYSTEM DEBUGUIHR  
$ DEASSIGN/SYSTEM DBGTBKMSG  
$ DEASSIGN/SYSTEM DBG$HELP  
$ DEASSIGN/SYSTEM DBG$UIHELP  
$ DEASSIGN/SYSTEM DEBUGAPPCLASS  
$ DEASSIGN/SYSTEM VMSDEBUGUIL
```

3. Using the editor of your choice, open the SYSTARTUP_VMS.COM file and search for the following command:

```
$ @DEBUG$STARTUP
```

Delete the command and any parameters. (The command might have an optional parameter of either VMS or DECSET.)

4. Exit from the file, saving the change.

5.2.3 Customized Security Environment

The Version 7.1 upgrade procedure provides new files and directories in the directory [VM\$COMMON...]. If you had any special protections and access control lists (ACLs) before the upgrade, you need to reapply them to reestablish the security environment you had previously established. For more information on creating and maintaining a secure environment, see the *OpenVMS Guide to System Security*.

5.2.4 Operator and Accounting Logs

The upgrade procedure deletes all the operator and accounting logs. To save these files, move them to a user directory before you start the upgrade.

5.2.5 Special Testing and Debugging Files

Before you perform an upgrade, remove or rename any special testing or debugging files that you might have in any of the SYSSSPECIFIC: or SYSSSYSROOT: directories. Files in these directories are used in place of the files in SYSSCOMMON: directories.

As a minimum, you should check the following directories:

```
SYSSSYSROOT: [SYSEXE]  
SYSSSYSROOT: [SYS$LDR]
```

Because the upgrade procedure affects the SYSSCOMMON: directories and does not check or alter the contents of the SYSSSPECIFIC: or SYSSSYSROOT: directories, any testing or debugging files that you have in these directories remain there unchanged until you remove or rename them. If you do not remove or rename these files, your system might behave in an unpredictable manner.

5.2.6 Cluster Considerations

The following cautions apply when you are upgrading a cluster system:

- The upgrade procedure does *not* work across the network. The network is not available during the upgrade, so you must have the save sets available locally or on the InfoServer.
- If the node you are upgrading is a cluster member, the upgrade procedure checks the previously set values of several system parameters at the beginning of the upgrade (see Section 7.3.) If any of the values are less than that required to upgrade to OpenVMS VAX Version 7.1, you are given the choice of continuing or canceling the upgrade. If you choose to continue the upgrade, the entire upgrade might not be completed and the cluster might be left in a hung state.
- Before you start the upgrade procedure in a VAXcluster environment, you must shut down all the nodes that boot from the system disk you are upgrading, including the node you perform the upgrade on.

5.2.7 Save Set Location

If you move the OpenVMS VAX save sets from the distribution media to the system disk or some other disk before beginning the upgrade, the save sets must be in the [000000] directory of the disk, or the upgrade will fail.

Do not attempt to use VMSINSTAL with OPTION G to transfer OpenVMS VAX save sets to another media type; doing so will produce an unusable system. Instead, you can use the DCL command COPY to transfer save sets to another media type.

Before Upgrading OpenVMS VAX Software

5.2 Cautions and Restrictions

5.2.8 System Disk Cautions

The following cautions apply to the system disk:

- If you changed the names of system directories on your system disk, the upgrade procedure will not work correctly. Restore your system disk to a standard directory structure before you attempt an upgrade.
- You must not move the system disk or the distribution kit from one drive to another during the upgrade.
- You cannot upgrade a shadowed system disk. If your system disk is part of a shadow set, you must create a nonshadowed system disk before beginning the upgrade.

Also, if you copy the distribution media to another disk, that disk must be a nonshadowed disk.

For more information, see the manual *Volume Shadowing for OpenVMS*.

- If you elect not to install optional components, the upgrade procedure removes existing files for those components from the system disk. You can install optional files during the upgrade or later using VMSTAILOR.

Note that, while some optional files can be placed on an alternate device, you cannot tailor files on or off an alternate device.

5.2.9 AUTOGEN Feedback Data

If you use your AUTOGEN feedback data, you should save this information before rebooting the system with minimum startup to begin the upgrade. For more information, see Section 5.4.

5.2.10 OpenVMS Version Requirements

Before you can upgrade to OpenVMS VAX Version 7.1, your system must be running at least Version 6.1 of the OpenVMS operating system. For example, you can upgrade a system disk to Version 7.1 of the OpenVMS VAX operating system from any of the following versions (or related hardware releases):

OpenVMS VAX Version 6.1
OpenVMS VAX Version 6.2
OpenVMS VAX Version 7.0

5.2.11 DECwindows Motif Version Requirements

If you want to use DECwindows software with OpenVMS VAX Version 7.1, you must be running Version 1.2–3 or higher of the DECwindows Motif for OpenVMS layered product.

For more information, see Section 1.2.1.

5.2.12 Shared System Dump Files

If you have a shared system dump file in `SYSS$COMMON:[SYSEXE]`, the shared dump file cannot have the name `SYSDUMP.DMP`. If you have a shared system dump file with this name, Digital recommends that you rename it to `SYSS$COMMON:[SYSEXE]SYSDUMP_COMMON.DMP`.

5.2.13 Layered Products

The upgrade procedure is designed so that you should not have to reinstall most layered products after the upgrade. However, you might need to reinstall certain layered products because of product-specific installation procedures.

If a layered product is available yet exhibits unexpected behavior once Version 7.1 of the OpenVMS VAX operating system is running, check the *OpenVMS Version 7.1 Release Notes* for possible layered-product restrictions.

5.3 Are You Ready to Upgrade?

Before you begin to upgrade the OpenVMS VAX operating system, be sure you have all the required hardware and software components.

5.3.1 Hardware Components

Examine your hardware for the following:

- Make sure your hardware has been checked for proper operation. To perform a successful upgrade, you must understand the basic operations of the VAX computer that you are upgrading. Refer to the upgrade and installation supplement for your VAX computer. If you have a VAXcluster environment, refer to *OpenVMS Cluster Systems*.
- Set up your system to record the upgrade procedure on either a hardcopy terminal or a printer attached to the console terminal. If you do not do this, the screen messages will be lost. You will need a transcript in case there is a problem during the upgrade. For more information, see the upgrade and installation supplement for your VAX computer.
- Have scratch console media (media that does not contain files you want to save) available for the following VAX computers:

VAX 8600, 8650
VAX 8200, 8250, 8300, 8350
VAX-11/730
VAX-11/750
VAX-11/780, 785

For example, if you have a VAX-11/780 or VAX-11/785 computer, you need a scratch RX01 floppy diskette.

5.3.2 Software Components

Examine your software for the following:

- Make sure you have all the items listed on the bill of materials (BOM) in the OpenVMS distribution kit. If your kit is incomplete, notify Digital Software Supply, and request priority shipment of any missing items.
- Before upgrading the OpenVMS VAX operating system, read Appendix B of this manual, the *OpenVMS Version 7.1 New Features Manual*, the *OpenVMS Version 7.1 Release Notes*, and any cover letters included with your kit.

5.4 Examining AUTOGEN Feedback Data

After the upgrade is finished, AUTOGEN runs. If it finds valid feedback data on your system, it tries to use AUTOGEN feedback.

Before Upgrading OpenVMS VAX Software

5.4 Examining AUTOGEN Feedback Data

5.4.1 Valid Feedback Data

Feedback data is produced by the SAVPARAMS phase of AUTOGEN and is stored in SYSS\$SYSTEM:AGENS\$FEEDBACK.DAT. Valid feedback data is defined as follows:

- The system was up for at least 24 hours when the feedback data was gathered.
- The feedback data is not over 30 days old.

If your feedback data is not valid, AUTOGEN will run without feedback (all previous feedback-generated parameters will be replaced by the AUTOGEN NOFEEDBACK calculations).

5.4.2 How to Test Feedback Data

To ensure that AUTOGEN feedback will run after the upgrade, do the following:

1. Check the validity of your current feedback data by entering the following command:

```
$ @SYS$UPDATE:AUTOGEN GETDATA TESTFILES
```

This command is for test purposes and does not result in the modification of system parameters or changes to the page and swap files. If your current feedback is valid, AUTOGEN will use it during the upgrade, and you can proceed to the next section.

If your current feedback data is invalid, AUTOGEN will issue several warnings. If you get these warnings, go to step 2.

2. If your current feedback is invalid, you can generate new feedback data (assuming your system was up for at least 24 hours). Enter the following command:

```
$ @SYS$UPDATE:AUTOGEN SAVPARAMS TESTFILES
```

This command is for test purposes and does not result in the modification of system parameters or changes to the page and swap files. Again, AUTOGEN warns you if the feedback data just produced is invalid.

3. If you follow steps 1 or 2 and your current feedback data is valid, AUTOGEN uses your current feedback-generated parameters during the upgrade. Your current feedback-generated parameters will not be lost during the upgrade.

5.5 Performing Backup Tasks

Digital recommends that you make a standalone backup copy of the system disk and, if your configuration allows it, upgrade the *backup copy*. If there are problems, you will still have a working system disk.

5.5.1 How to Back Up the System Disk

To make a backup copy of the system disk, follow the instructions in the upgrade and installation supplement for your VAX computer. If you do not have a removable system disk, back up your system disk to tape and restore the image backup to the system disk. This eliminates disk fragmentation on the system disk and creates contiguous free disk blocks required for the upgrade. (The upgrade can fail if there are not sufficient contiguous free blocks.) Store the backup tapes in a safe place.

5.5.2 How to Back Up Console Media

If you have one of the following VAX computers, you also must make a backup copy of the console media:

VAX-11/730
VAX-11/750
VAX-11/780, 785
VAX 8200, 8250, 8300, 8350, 8600, 8650

To make a backup copy of the console media, use the `SYS$UPDATE:CONSCOPY.COM` procedure, as described in the upgrade and installation supplement for your VAX computer. Use the backup copy of the console media during the upgrade procedure. The upgrade procedure updates the console media for you.

If your VAX computer uses one of the following console media, you did not receive a new standalone BACKUP kit with your OpenVMS VAX distribution kit:

TU58 tape cartridge
RX33 diskette
RX50 diskette
RX01 diskette
RL02 disk cartridge

Before beginning the upgrade, make sure you have a standalone BACKUP kit on one of these media. If you do not have one, create a standalone BACKUP kit using the `STABACKIT.COM` procedure as described in the upgrade and installation supplement for your VAX computer.

Note

You cannot build standalone BACKUP on TU58 or RX01 console media because the OpenVMS VAX Version 7.1 kit is too large. If your VAX computer uses a TU58 or RX01, build a standalone BACKUP kit before upgrading and retain the backup copies for use with future versions of OpenVMS VAX.

5.6 Preparing Your System Disk

To prepare the system disk for the upgrade, log in to the SYSTEM account and, depending on your configuration, complete some or all of the tasks described in the sections that follow.

5.6.1 Create a Nonshadowed System Disk

If you are using a volume-shadowed system disk, you must create a nonshadowed system disk to upgrade. Follow the instructions in the *Volume Shadowing for OpenVMS* manual to prepare a nonshadowed system disk for the upgrade.

5.6.2 Boot the Backup Copy of Your System Disk

If you need to boot the backup copy of your system disk or if you are upgrading a VAXcluster environment, enter the following command (otherwise, go to the next step):

```
$ @SYS$SYSTEM:SHUTDOWN
```

Before Upgrading OpenVMS VAX Software

5.6 Preparing Your System Disk

When the procedure asks if an automatic system reboot should be performed, press Return for NO. If you are a VAXcluster member, choose the CLUSTER_SHUTDOWN option. When the procedure is finished, halt the system as described in the upgrade and installation supplement for your VAX computer.

If applicable, remove the system disk and replace it with the backup copy.

Boot the system from the backup copy of the system disk. If you do not know how to boot the system, refer to the upgrade and installation supplement for your VAX computer.

Log in to the SYSTEM account.

5.6.3 Copy UAF and Auditing Files to the System Disk

The current copies of the SYSUAF.DAT and the VMSSAUDIT_SERVER.DAT files must be on the system disk; otherwise, you cannot proceed with the upgrade.

If you have moved your copy of SYSUAF.DAT to another location, copy it to the SYSSCOMMON:[SYSEXE] directory for the duration of the upgrade.

If you have moved your copy of VMSSAUDIT_SERVER.DAT to another location, copy it to the SYSSCOMMON:[SYSMGR] directory.

Note that, if you are doing a rolling upgrade, the shared version of SYSUAF.DAT is not updated.

Move any files that you do not want changed into a user directory.

5.6.4 Rename the System Dump File

If you have a shared system dump file in SYSSCOMMON:[SYSEXE], the shared dump file cannot have the name SYSDUMP.DMP. If you have a shared system dump file with this name, Digital recommends that you rename it to SYSSCOMMON:[SYSEXE]SYSDUMP-COMMON.DMP.

5.6.5 Analyze the System Disk

To analyze the system disk for inconsistencies and errors in the file structure, enter the following command:

```
$ ANALYZE/DISK_STRUCTURE SYS$SYSDEVICE
```

The following message represents normal behavior; you can ignore it:

```
%ANALDISK-I-OPENQUOTA, error opening QUOTA.SYS
```

If you find any other errors on the system disk, repair the errors by entering the following command:

```
$ ANALYZE/DISK_STRUCTURE/REPAIR SYS$SYSDEVICE
```

Refer to the *OpenVMS System Management Utilities Reference Manual* for more information on the ANALYZE/DISK_STRUCTURE command.

5.6.6 Check Page and Swap Files

Digital recommends that the page file be located on the system disk in SYSSSPECIFIC:[SYSEXE] for the upgrade.

The swapfile (SWAPFILE.SYS) does not need to be located on the system disk for the upgrade, but if it is located on the system disk, the file must be located in SYSSSPECIFIC:[SYSEXE].

Before Upgrading OpenVMS VAX Software

5.6 Preparing Your System Disk

If the upgrade procedure finds the page files and swap files in the common directory, it will move them to the system-specific directory before continuing.

The page file must be at least 4600 blocks. If the upgrade procedure detects fewer than 4600 blocks, it displays a message that gives you the option of continuing the upgrade or exiting the procedure and increasing the size of the page file. If you get this message, Digital recommends that you exit the procedure, increase the page file to at least 4600 blocks, and restart the upgrade procedure.

To check the size of your page file and enter a new size if needed, use the following procedure:

1. To determine the size of the page file, enter the following command:

```
$ @SYS$UPDATE:SWAPFILES
```

The procedure displays the size of the page file and asks you to enter a new value, as follows:

Enter new size for paging file:

If the page file (PAGEFILE.SYS) size is greater than 4600 blocks, press the Return key. If it is less than 4600 blocks, enter 4600 and press Return.

2. If the swap and dump files are on the system disk, the procedure displays the sizes of each file. To keep the current values, press Return after each prompt.

If the swap file is not on the system disk, the procedure asks if you want to create one. You do not need swap and dump files on the system disk for the upgrade procedure. Enter the appropriate response for your system.

If you changed the size of the page file or created a swap file, a message is displayed that tells you to reboot the system. Do not reboot now. You will reboot later.

5.6.7 Check for Free Blocks

Check the system disk to make sure there is enough room for the upgrade. To determine whether you have enough room, enter the following command:

```
$ SHOW DEVICE SYS$SYSDEVICE
```

To upgrade the OpenVMS VAX *required* files, the minimum number of free blocks required is 48,950. Even if you plan to upgrade the OpenVMS *library* or *optional* files, you might not need more than 48,950 free blocks because many files are deleted as the upgrade progresses, thus freeing up additional space.

5.6.8 Check Quotas and Limits

Use the Authorize utility (AUTHORIZE) to make sure the SYSTEM account has sufficient quotas and limits. To check and, if necessary, modify quota and limit values, do the following:

1. Enter the following commands:

```
$ SET DEFAULT SYS$SYSTEM  
$ RUN AUTHORIZE  
UAF> SHOW SYSTEM
```

AUTHORIZE displays the SYSTEM account's quota and limit values.

Before Upgrading OpenVMS VAX Software

5.6 Preparing Your System Disk

2. Compare the values displayed on your screen to the following minimum required values:

Quota or Limit Name	Minimum Value
Open file quota (FILLM)	300
Buffered I/O limit (BIOLM)	18
Direct I/O limit (DIOLM)	18
AST limit (ASTLM)	24
Enqueue quota (ENQLM)	200
Buffered byte quota count (BYTLM)	32768†

†If you are using an InfoServer device to upgrade your system, increase the value of BYTLM to 33150

3. If necessary, adjust the quota and limit values in your SYSTEM account so that they are equal to or greater than the minimum required values.

To change the value for a quota or limit, enter the MODIFY SYSTEM command using the following format:

```
MODIFY SYSTEM/limit=new_value
```

For example:

```
UAF> MODIFY SYSTEM/DIOLM=18
```

4. Exit the Authorize utility by entering the following command:

```
UAF> EXIT
```

5. If you adjusted the values for any of the SYSTEM account quotas or limits, log out and log back in to have the new values take effect.

5.6.9 Set System Parameters

During the upgrade procedure, the system is shut down and rebooted a number of times. You must boot the system minimum (STARTUP_P1 set to MIN) before you begin the upgrade (see Section 5.7). This prevents startup of certain system integrated products and layered products on the system during each reboot. To set the system parameter STARTUP_P1 to MIN, enter the following commands:

```
$ RUN SYS$SYSTEM:SYSMAN
SYSMAN> PARAMETERS USE CURRENT
SYSMAN> PARAMETERS SET STARTUP_P1 "MIN"
SYSMAN> PARAMETERS WRITE CURRENT
SYSMAN> EXIT
```

Make sure the system parameters SCSNODE and SCSSYSTEMID are defined on your system. To determine whether these parameters are defined on your system, enter the following commands:

```
$ RUN SYS$SYSTEM:SYSMAN
SYSMAN> PARAMETERS SHOW SCSNODE
SYSMAN> PARAMETERS SHOW SCSSYSTEMID
```

If SCSNODE and SCSSYSTEMID are not set correctly, enter the following commands where *node* is a 1- to 6-character unique DECnet node name and *systemid* is (DECnet area * 1024) + node number:

Before Upgrading OpenVMS VAX Software 5.6 Preparing Your System Disk

```
SYSMAN> PARAMETERS USE CURRENT
SYSMAN> PARAMETERS SET SCSNODE "node"
SYSMAN> PARAMETERS SET SCSSYSTEMID systemid
SYSMAN> PARAMETERS WRITE CURRENT
```

.
.
.

Make sure the system parameter VMS5 is set to 0. If your system has a KFQSA controller, the VMS5 parameter might have been set to a nonzero value for a previous upgrade. The VMS5 parameter is reserved for Digital's use only.

To check the value of the VMS5 parameter, enter the following commands:

```
$ RUN SYS$SYSTEM:SYSMAN
SYSMAN> PARAMETERS USE CURRENT
SYSMAN> PARAMETERS SHOW VMS5
Parameter Name      Current  Default  Minimum  Maximum Unit  Dynamic
-----
VMS5                1        0        0        -1
```

If the current value of VMS5 is not 0, set it to 0 by entering the following commands:

```
SYSMAN> PARAMETERS USE CURRENT
SYSMAN> PARAMETERS SET VMS5 0
SYSMAN> PARAMETERS WRITE CURRENT
SYSMAN> EXIT
```

If you used the Snapshot facility to boot your current system with a system snapshot image, you must change the BOOT_STYLE system parameter to 0 before you can perform an upgrade. To change the BOOT_STYLE system parameter to 0, enter the following commands:

```
$ RUN SYS$SYSTEM:SYSMAN
SYSMAN> PARAMETERS USE CURRENT
SYSMAN> PARAMETERS SET BOOT_STYLE 0
SYSMAN> PARAMETERS WRITE CURRENT
SYSMAN> EXIT
$
```

You can reexecute the Snapshot command procedure (SYSSMANAGER:SNAPSHOT.COM) after the upgrade is completed, as described in the *OpenVMS System Manager's Manual: Essentials*.

5.6.10 Check AGEN\$INCLUDE Files

During an upgrade, user disks are not mounted and SYLOGICALS.COM is not invoked, so AUTOGEN can access only data files that are on the system disk and whose file specification includes a logical name that is shipped as part of the OpenVMS operating system. Therefore, if you use AGEN\$INCLUDE in SYSS\$SYSTEM:MODPARAMS.DAT to point to data files that are not on the system disk, follow these steps before you perform an upgrade:

1. Copy any files that you want AUTOGEN to include to a directory on the system disk.
2. For each file that you move, change the file specification on the AGEN\$INCLUDE line in SYSS\$SYSTEM:MODPARAMS.DAT to point to the new location of the file on the system disk.

If you do not move referenced data files to the system disk, AUTOGEN uses whatever information is available during the upgrade and parameters might be set to values considerably different from what you intend.

Before Upgrading OpenVMS VAX Software

5.6 Preparing Your System Disk

5.6.11 Add Modified System Parameters to MODPARAMS.DAT

Any system parameter values that you modified and *did not* enter in MODPARAMS.DAT are lost during the upgrade. To retain the values of these parameters, enter their names in MODPARAMS.DAT and the value that AUTOGEN needs to add to the default minimum value.

For example, if you modified GBLPAGES by 128 pages above the default, add the following line to SYS\$SYSTEM:MODPARAMS.DAT:

```
ADD_GBLPAGES=128
```

When AUTOGEN runs after the upgrade, it uses the values in MODPARAMS.DAT.

Section 5.7 tells you how to get your system ready for an upgrade.

5.7 Preparing the System

To prepare the system for the upgrade, use the procedure described in the following rdsections.

5.7.1 Enable Auto Restart or Manual Reboot

If your computer uses console media, set the computer to restart automatically. For some VAX computers this means setting one or more switches. For others, this means entering certain console mode commands. To determine how to enable auto restart, refer to the upgrade and installation supplement for your VAX computer.

If you have a system that does not use console media, set your system so you can reboot it manually. For more information, refer to the upgrade and installation supplement for your VAX computer.

5.7.2 Shut Down and Reboot the System

Shut down and reboot the system to activate any system parameters that you changed (STARTUP_P1, for example). To shut down the system, enter the following command:

```
$ @SYS$SYSTEM:SHUTDOWN
```

When the procedure asks if an automatic system reboot should be performed, type Y (for YES) and press the Return key.

After the system reboots, log in to the SYSTEM account.

5.7.3 Prevent Interactive Logins

To prevent users from logging in to the system during the upgrade, enter the following command:

```
$ SET LOGINS/INTERACTIVE=0
```

5.7.4 Check for DECnet

To determine whether your system is running DECnet for OpenVMS software, enter the following command:

```
$ SHOW LOGICAL SYS$NODE
```


Before Upgrading OpenVMS VAX Software

5.7 Preparing the System

If the system displays the following message, DECnet is not running on your system and you can proceed to Section 5.7.6:

```
%SHOW-S-NOTRAN, no translation for logical name SYS$NODE
```

If the system responds with a translation for SYS\$NODE, then DECnet is running on your system.

If you set STARTUP_P1 to MIN as described in Section 5.6.9, DECnet should not be running. To set STARTUP_P1 to MIN, repeat all of the preceding steps beginning with Section 5.6.9. Note that you must shut down and reboot the system for any changes you make to system parameters to take effect.

5.7.5 Check for Volume Shadowing

Phase I (controller-based) shadowing is no longer available. Phase II (host-based) shadowing is designed to fully replace phase I shadowing with significantly enhanced features.

If you have volume shadowing installed on your system but are unsure which phase, you can enter the following commands:

```
$ RUN SYS$SYSTEM:SYSMAN
SYSMAN> PARAMETERS USE CURRENT
SYSMAN> PARAMETERS SHOW SHADOWING
```

If the SHADOWING parameter is 1 or 3, then you have phase I shadowing currently loaded on your system. For information about migrating to phase II, see *Volume Shadowing for OpenVMS*.

At the beginning of an upgrade, the procedure checks the setting of the SHADOWING system parameter. If you have not migrated to phase II and the procedure detects the presence of phase I shadowing, it displays the following message and asks if you want to continue the upgrade:

```
The SHADOWING system parameter (currently set to 1) specifies
phase I of volume shadowing, which is no longer available as of
OpenVMS VAX Version 6.1. If you continue with this upgrade, volume
shadowing will not be present on your system after the upgrade has
completed. Please consult the Volume Shadowing for OpenVMS manual
for instructions about moving to phase II of volume shadowing.
```

```
* Do you want to continue the upgrade?
```

At that point, you can exit the upgrade procedure, follow the instructions in *Volume Shadowing for OpenVMS* for migrating to phase II shadowing, and restart the upgrade procedure from the beginning. If you continue with the upgrade without migrating to phase II, volume shadowing will not be present on your system after the upgrade has completed.

5.7.6 Stop Queues

To stop all batch and print queues on the node you are upgrading, enter the following command:

```
$ STOP/QUEUES/ON_NODE
```

It is not necessary to stop queues on nodes that you are not upgrading.

Before Upgrading OpenVMS VAX Software

5.8 Gathering Information for the Upgrade

5.8 Gathering Information for the Upgrade

At different points during the upgrade, the procedure prompts you to supply information. To save time once the procedure begins, be sure you have the following information readily available. Remember, entering incorrect information during the upgrade could force you to repeat the entire upgrade procedure.

Required Information	Explanation
Device names	You will need to specify the device names for the drives that will hold the distribution media and the system disk.
Passwords	You will be prompted to type passwords of at least 8 characters for the SYSTEM, SYSTEST, and FIELD accounts.
Optional components and OpenVMS Management Station files	<p>The upgrade procedure prompts you to specify whether you want to install the library (VMS071.C), optional (VMS071.D) OpenVMS components, and OpenVMS Management Station software PC files (VMS071.F). Appendix D lists the files included in these save sets.</p> <p>You can save some space on your system disk if you choose <i>not</i> to install these components, but be sure to review Appendix D before deciding.</p>
Location for Help Message utility	Save set VMS071.E contains the online Help Message utility, which you can install on your system disk or on an alternate disk. (However, if you copied the distribution kit to some other media from which you will be performing the installation, you cannot install this save set on that media.)
DECwindows components	<p>The installation procedure prompts you to specify which of the following DECwindows components you want to install:</p> <ul style="list-style-type: none">• DECwindows base support (required for running DECwindows software), which includes:<ul style="list-style-type: none">– DECwindows transport– DECwindows keymaps• DECwindows workstation support (required for VAX workstations), which includes:<ul style="list-style-type: none">– DECwindows X11 display server– Graphics drivers– 75 dots/inch video fonts– 100 dots/inch video fonts (option available only if you select DECwindows workstation support)

Note that you must install the DECwindows Motif for OpenVMS (previously called VMS DECwindows Motif) layered product if you want to run the DECwindows software. DECwindows Motif for OpenVMS Version 1.2–3 (or 1.2 if the VAXMOTF05_012 remedial kit is installed) is the minimum supported version for systems running OpenVMS VAX Version 7.1. If you do not know which version of DECwindows Motif you are currently running on your system, you can check by entering the following command:

```
$ ANALYZE/IMAGE SYS$LIBRARY:DECW$XLIBSHR.EXE
```

Also note that the layered product does *not* have the DECwindows base and workstation support components. To get full DECwindows support, you must select the DECwindows components provided with the OpenVMS VAX Version 7.1 kit and install the separate DECwindows Motif for OpenVMS VAX layered product, which supports both Motif and XUI environments.

Before Upgrading OpenVMS VAX Software

5.8 Gathering Information for the Upgrade

Required Information	Explanation
PAK information	The information listed on Product Authorization Keys (PAKs) for any new products you will register. You do not need to register your OpenVMS VAX license or the licenses for any System Integrated Products (SIPs) you are already running.

5.9 Preupgrade Checklist

Before you begin the upgrade procedure, use the following checklist to make sure you have completed all the necessary preupgrade tasks.

- Read the *OpenVMS Version 7.1 New Features Manual*, the *OpenVMS Version 7.1 Release Notes*, and any cover letters that came with your kit.
- Read the cautions and restrictions described at the beginning of this chapter and in Chapter 1.
- Make sure you have enough free blocks for the upgrade. You need at least 48,950 free blocks for the required files to start the upgrade. (Described in Section 5.6.) The entire upgrade requires about 163,000 blocks.
- Set up your system to record the upgrade procedure on either a hardcopy terminal or a printer attached to the console terminal. If you do not do this, the screen messages will be lost. You will need a transcript in case there is a problem during the upgrade. For information on how to connect a hardcopy device to your console to record the procedure, see the upgrade and installation supplement for your VAX computer.
- Check your AUTOGEN feedback information to be sure it is valid before rebooting the system. (Described in Section 5.4.)
- Make a backup copy of the system disk and, if applicable, of the console media. (Described in the upgrade and installation supplement for your computer.)
- If, in previous versions, your distribution kit provided standalone BACKUP on one of the following media types, make sure you have created a standalone BACKUP kit on one of the following media types:
 - RX33
 - TU58
 - RX50
 - RX01
 - RL02(Described in Section 5.5.)
- Make sure SYSUAF.DAT is in the SYS\$COMMON:[SYSEX] and VMS\$AUDIT_SERVER.DAT is in the SYS\$COMMON:[SYSMGR] directory. (Described in Section 5.6.)
- Make sure SWAPFILE.SYS (if it is located on the system disk) and PAGEFILE.SYS are in the SYS\$SPECIFIC:[SYSEX] directory. (Described in Section 5.6.)
- Make sure the page file is at least 4600 blocks. (Described in Section 5.6.)
- If you have a shared system dump file in SYS\$COMMON:[SYSEX], make sure the shared file is not named SYSDUMP.DMP. (Described in Section 5.6.)

Before Upgrading OpenVMS VAX Software

5.9 Preupgrade Checklist

- If your system disk is part of a shadow set, create a nonshadowed system disk to upgrade. (Described in *Volume Shadowing for OpenVMS*.)
- Make sure the SYSTEM account has sufficient quotas and limits. (Described in Section 5.6.)
- Set the appropriate system parameters and make sure that STARTUP_P1 is set to MIN. (Described in Section 5.6.)
- Define the system parameters SCSNODE and SCSSYSTEMID. (Described in Section 5.6.)
- If your system has a KFQSA controller, make sure the VMS5 parameter is set to 0. (Described in Section 5.6.)
- Check the location of your AGEN\$INCLUDE files. (Described in Section 5.6.10.)
- Set up the system to restart automatically. (Described in the upgrade and installation supplement for your VAX computer.)
- Shut down and reboot the system from which you will perform the upgrade. If you are upgrading a VAXcluster, shut down all computers that boot from the system disk you are upgrading.
- Set interactive logins to 0.
- Shut down DECnet for OpenVMS software. (Described in Section 5.7.)
- Migrate to phase II volume shadowing if you are currently using phase I. (Described in Section 5.7.)
- Stop all batch and print queues on the node you are upgrading. (Described in Section 5.7.)
- Make sure you have the following information (described in Section 5.8) available:
 - The device names of the drives that will hold the system disk and the distribution media.
 - Passwords of at least 8 characters for the SYSTEM, SYSTEST, and FIELD accounts.
 - A list of optional OpenVMS VAX components you want to install.
 - A list of optional DECwindows components you want to install.
 - The information listed on Product Authorization Keys (PAKs) for any new product licenses you will register.
- Create a command procedure to be used when booting from [SYSF]. See Appendix C.

To upgrade a standalone system, go to Chapter 7.

To upgrade a VAXcluster environment, go to Chapter 6.

Upgrading a VAXcluster Environment

6.1 Overview

This chapter describes how to upgrade a VAXcluster environment. Refer to *OpenVMS Cluster Systems* for more detailed information on VAXcluster environments.

If your cluster environment has both VAX and Alpha systems, you should also refer to the *Migrating an Environment from OpenVMS VAX to OpenVMS Alpha*.

6.2 Concurrent and Rolling Upgrades

There are two types of cluster upgrades: concurrent and rolling. The type of upgrade you use depends on whether you want to maintain the availability of the cluster during the upgrade and whether you have more than one system disk.

6.2.1 Concurrent Upgrades

During a concurrent upgrade, you must shut down the entire cluster and upgrade each system disk. No one can use the cluster until you upgrade each system disk and reboot each VAX computer. If all systems in the VAXcluster environment are booted from one system disk, you must perform a concurrent upgrade.

Note

For OpenVMS VAX Version 7.1 concurrent upgrades, all nodes in the cluster must be running at least OpenVMS VAX Version 6.1. (See Section 5.2.10 for more information.)

To perform a concurrent upgrade, go to Section 6.3.

6.2.2 Rolling Upgrades

During a rolling upgrade, you can keep some of the VAX computers in the cluster running while you upgrade others (you must have more than one system disk). The cluster runs temporarily with different versions of the operating system.

Note

For OpenVMS VAX Version 7.1 rolling upgrades, all nodes in the cluster must be running at least OpenVMS VAX Version 6.1. (See Section 5.2.10 for more information.)

To perform a rolling upgrade, go to Section 6.4.

Upgrading a VAXcluster Environment

6.3 Performing a Concurrent Upgrade

6.3 Performing a Concurrent Upgrade

You perform a concurrent upgrade by shutting down the entire cluster, upgrading each system disk, and rebooting each VAX computer in the cluster. When the cluster reboots, each VAX computer will be running the upgraded version of the operating system. Users cannot access the cluster until you upgrade each system disk and reboot each VAX computer.

6.3.1 Concurrent Upgrade Procedure

To perform a concurrent upgrade, use the following procedure:

1. Shut down the entire cluster by logging in to the SYSTEM account on each node *locally*, entering the following command, and choosing the CLUSTER_SHUTDOWN option:

```
$ @SYS$SYSTEM:SHUTDOWN
```

2. If you have only one system disk for your cluster, go to step 3. If you have more than one system disk, select one to upgrade.

Caution

You cannot use the system disk that you usually use as the quorum disk to hold the save sets from the distribution kit.

3. Perform a conversational boot of a single VAX computer from the system disk you will be upgrading. For more information about the conversational boot procedure, refer to the upgrade and installation supplement for your VAX computer.

At the SYSBOOT> prompt, use the SHOW VOTES and SHOW EXPECTED_VOTES command to display the current values of the parameters. Write these values down because you will need to restore them later. Set the VOTES and EXPECTED_VOTES values to 1 by entering the following commands:

```
SYSBOOT> USE CURRENT
SYSBOOT> SET VOTES 1
SYSBOOT> SET EXPECTED_VOTES 1
SYSBOOT> CONTINUE
```

4. Upgrade the system disk, using the procedure in Chapter 7.
5. If you have only one system disk, go to step 6. If you have more than one system disk, shut down the system that you just upgraded. Then repeat steps 2 through 4 to upgrade each system disk in the cluster. When you finish upgrading all of the system disks, go to step 6.
6. Reboot each computer in the VAXcluster environment.
7. Complete the postupgrade procedures described in Chapter 8.

6.4 Performing a Rolling Upgrade

During a rolling upgrade, you upgrade each system disk individually, allowing old and new versions of the operating system to run together temporarily in the same cluster. Clusters running two versions of the operating system are called mixed-version clusters. Because rolling upgrades allow mixed-version clusters, the systems that you are not upgrading remain available.

6.4.1 Restrictions

The following restrictions apply to rolling upgrades:

- Digital recommends that all VAX computers in a cluster run the same version of the operating system. Mixed-version clusters are supported *only* for the purpose of upgrading the entire cluster incrementally. Digital further recommends that all VAX systems in a VAXcluster run the latest version of the OpenVMS VAX operating system.
- A rolling upgrade does not apply when all systems boot from a single system disk. When all systems boot from a single system disk, perform a concurrent upgrade using the procedure described in Section 6.3.
- During the rolling upgrade, the queuing system is disabled on the nodes being upgraded. The queuing system on the other nodes should be unaffected by the upgrade as long as a `START/QUEUE/MANAGER/ON=(upgrade node . . .)` command is not executed. A `START/QUEUE/MANAGER` command could attempt to move the queue manager process to the node being upgraded if the `/ON` qualifier indicates that it is one of the preferred nodes. If the queue manager attempts to run on the node being upgraded, the queuing system will hang on the entire cluster.

If your startup file contains a `START/QUEUE/MANAGER/ON=(upgrade node1, node2 . . . noden)` command, do not boot in any nonupgrading nodes until you have removed that command from the startup file. Booting in a node will cause the queuing system to hang on the cluster if the `START/QUEUE/MANAGER/ON=(upgrade node, . . .)` command is executed. When the upgrade has completed, you can add the command back to the startup file.

If the cluster queuing system hangs during the upgrade, it is most likely caused by the queue manager attempting to run on the upgrading node. To clear the condition, move the queue manager to a node you are not upgrading by entering the following command:

```
START/QUEUE/MANAGER/ON=(nonupgrading node1,-  
node2 . . . noden)
```

6.4.2 Rolling Upgrade Procedure

To perform a rolling upgrade follow these steps:

1. Check the votes and make adjustments to maintain the proper quorum so the cluster can continue to operate throughout the upgrade. (*OpenVMS Cluster Systems* describes this procedure in detail.)
2. Select a system disk to upgrade.
3. Shut down all VAX computers booting from the system disk that you are upgrading, except for the computer that you will use to apply the upgrade.

Upgrading a VAXcluster Environment

6.4 Performing a Rolling Upgrade

VAX computers that do not boot from the system disk that you are upgrading remain available to users.

- a. Log in to the SYSTEM account on the VAX computer you are shutting down.
- b. Enter the following command:

```
$ @SYS$SYSTEM:SHUTDOWN.COM
```

- c. On one of the VAX computers that is still running, enter the following command:

```
$ SET CLUSTER/EXPECTED_VOTES
```

- d. Repeat steps a through c for each VAX computer requiring a shutdown.

This procedure lets one VAX computer continue running from the system disk (assuming computers running from different system disks supply enough votes to sustain cluster quorum).

4. If proper quorum is not maintained at any time during the upgrade procedure, the shutdown procedure will hang the cluster. If the cluster hangs during a shutdown, enter the following commands on the system console of a CPU that is still a cluster member:

```
$ Ctrl/P  
>>> H  
>>> D/I 14 C  
>>> C  
IPC> Q  
IPC> Ctrl/Z
```

5. Upgrade the system disk using the procedure in Chapter 7.

Caution

The upgrade procedure requires exclusive access to the drive that holds the distribution media. Do not mount the distribution media on other nodes.

6. During phase 1 of the upgrade, the procedure will ask if you are performing a rolling upgrade. If you enter Y, the procedure asks you several questions to determine if all system disks in the cluster (other than the one you are upgrading) are running at least OpenVMS VAX Version 6.1. For example:

```
* Are the other system disks running OpenVMS V6.1 or higher?
```

All systems in the cluster must be running at least OpenVMS VAX Version 6.1 to perform the rolling upgrade. Type Y and press the Return key.

7. When the upgrade has completed, reboot each VAX computer that boots from the system disk you have just upgraded.
8. Perform the postupgrade tasks described in Chapter 8.
9. Repeat steps 2 through 7 for each system disk you are upgrading. Once you have performed tasks a through d in step 3, you do not need to perform them again.

6.5 Adding an OpenVMS VAX Version 7.1 Supported CPU

If you need to add a new CPU supported by OpenVMS VAX Version 7.1 to an existing Version 6.1 VAXcluster, Digital supports two options, listed in the following preferred order:

1. Upgrade the entire cluster to OpenVMS VAX Version 7.1 and bring the new CPU in as a member.
2. If you need to keep some systems in the cluster at OpenVMS VAX Version 6.1, you must upgrade a system disk in the cluster to Version 7.1 using the rolling upgrade procedure and then boot the new CPU into the cluster using that system disk.

Upgrading the OpenVMS VAX Operating System

7.1 Overview

This chapter explains the procedure for upgrading a single OpenVMS VAX system disk, including:

- How to prepare for booting from the [SYSF] directory
- How to configure devices
- How to begin the upgrade
- What the procedure does and what you are asked to do during the six phases of the upgrade

You must complete each phase of the upgrade procedure. On most VAX computers the upgrade procedure continues automatically from phase to phase. Read the screen displays carefully and, if you need to reboot your VAX computer manually, refer to the upgrade and installation supplement for your VAX computer and Appendix C of this manual.

The time required to complete an upgrade varies depending on your hardware configuration and on the distribution media you are using. In most cases, magnetic tapes and tape cartridges require more time than compact discs.

Before you begin the upgrade procedure, read the overview of the upgrade procedure described in Chapter 1 and complete the preupgrade tasks described in Chapter 5. If you are upgrading a VAXcluster, you must also read Chapter 6.

7.2 Preparing to Boot from [SYSF]

During the upgrade procedure, you are asked to boot the system from the [SYSF] directory on the system disk. The [SYSF] directory is a root directory created on the system disk by the upgrade procedure. It temporarily holds the system files used in the upgrade until the procedure moves the files to their permanent location. The upgrade procedure then removes the [SYSF] directory from the system disk.

If you do not know how to boot from [SYSF], read the upgrade and installation supplement for your VAX computer and Appendix C of this manual.

Ignore any error messages after the first reboot that indicate an invalid dump header version. These messages are normal and are to be expected.

Upgrading the OpenVMS VAX Operating System

7.2 Preparing to Boot from [SYSF]

7.2.1 Modifying Boot Command Procedures

Some VAX computers require a special command procedure to boot from [SYSF]. If you are performing an upgrade on one of the following VAX computers you must modify the boot command procedures, DEFBOO and *dddGEN* before beginning the upgrade procedure:

VAX 8530, 8550, 8700, 8810, 8820-N
VAX 8820, 8830, 8840

To modify the boot command procedures, exit from the OpenVMS VAX operating system (but do not shut it down) and enter the appropriate console mode. Make copies of DEFBOO and *dddGEN* before you modify them. Name the copies DEFBOO.SAV and *dddGEN*.SAV.

The upgrade and installation supplement for your VAX computer describes the procedures for copying and modifying DEFBOO and *dddGEN*. Use these procedures to modify DEFBOO and *dddGEN* so that they specify [SYSF] as the directory from which to boot.

In DEFBOO, change the DEPOSIT command that sets boot flags in register 5 (R5) as follows:

```
DEPOSIT R5=F0000000
```

In *dddGEN*, change the DEPOSIT command as follows:

```
DEPOSIT R5 F0000001
```

7.2.2 VAX 8200, 8250, 8300, and 8350 Computers

If you are upgrading a VAX 8200, 8250, 8300, or 8350 computer, you must create a boot command procedure that allows you to boot from the [SYSF] directory before beginning the upgrade. The upgrade and installation supplement for your VAX computer describes how to create this boot command procedure.

7.2.3 Configuring Devices

Because you rebooted your system with minimum startup, the system did not automatically configure all devices. However, you might need access to some of the devices to perform the upgrade.

To make sure you can access the devices that might be needed for the upgrade, run SYSGEN to reconfigure the devices on the system and run STARTUP CONFIGURE by entering the following commands:

```
$ RUN SYS$SYSTEM:SYSGEN
SYSGEN> AUTOCONFIGURE ALL
SYSGEN> EXIT
$ @SYS$SYSTEM:STARTUP CONFIGURE
```

7.3 Beginning the Upgrade Procedure

This section describes how to start the upgrade procedure using VMSINSTAL. You can type a question mark (?) for help at any time while running VMSINSTAL.

The instructions refer to the *source drive* and the *target drive*, where:

- The source drive is the drive that holds the distribution kit.
- The target drive is the drive that holds the system disk.

Upgrading the OpenVMS VAX Operating System 7.3 Beginning the Upgrade Procedure

7.3.1 Step 1: Load Distribution Media

Put the distribution compact disc or tape in the source drive. If your OpenVMS VAX distribution kit contains several tapes, put the first one in the drive. The paper labels on the tapes indicate the order in which you use them.

If you are not using an InfoServer device, go to Section 7.3.3.

If you are using an InfoServer device, proceed to the next step.

7.3.2 Step 2: Upgrading from the InfoServer

If upgrading from an InfoServer device, perform the following steps:

1. Start the InfoServer Client software by entering the following command:

```
$ @SYS$STARTUP:ESS$STARTUP CLIENT
```

The CLIENT parameter loads the client driver, ESS\$DADDRIVER.EXE, and the InfoServer transport driver, ESS\$LASTDRIVER.EXE.

2. As the startup procedure executes, it displays the following messages:

```
%LASTCP-I-VERSION, LASTDRIVER X1.5 is stopped  
%LASTCP-I-ADAINIT, Initializing adapter xxx for LASTDRIVER  
%LASTCP-I-STARTED, LASTDRIVER X1.5 started on node yyy
```

3. After you start the InfoServer Client software, you must make the compact disc drive accessible to your system by completing the following steps:

- a. Insert the distribution compact disc in the compact disc drive connected to the InfoServer.

- b. Enter the following commands:

```
$ RUN SYS$SYSTEM:ESS$LADCP  
LADCP> BIND/CONNECT/SYSTEM VAXVMS071  
%LADCP-I-BIND, service bound to logical unit DAD$VMS071 (_DADn:)  
LADCP> EXIT
```

Make note of the device name `_DADn:` in the previous display. You will have to specify this device name during the upgrade.

7.3.3 Step 3: Start VMSINSTAL

To start VMSINSTAL, use the following procedure:

1. Log in to the SYSTEM account.
2. Enter the following command:

```
$ @SYS$UPDATE:VMSINSTAL
```

VMSINSTAL displays a message similar to the following, depending on which version of the operating system is currently running on your system:

```
OpenVMS VAX Software Product Installation Procedure V7.0  
It is 22-NOV-1996 at 15:00.00.00  
Enter a question mark (?) at any time for help.
```

VMSINSTAL checks your system's account quotas. If it finds account quotas that are less than it expects, VMSINSTAL displays a message similar to the following:

Upgrading the OpenVMS VAX Operating System

7.3 Beginning the Upgrade Procedure

```
%VMSINSTAL-W-LOWQUOTA, The following account quotas may be too low.
-VMSINSTAL-W-LOWQUOTA, If you want to modify these account quotas, type NO to
-VMSINSTAL-W-LOWQUOTA, the next question, modify the appropriate quotas, log out
-VMSINSTAL-W-LOWQUOTA, then log back in and restart this procedure.
```

BYTLM: currently 32512; minimum expected 32768

* Do you want to continue anyway [NO]?

You should have verified that your SYSTEM account quotas were sufficient before beginning the upgrade. (See Section 5.6.8 for the minimum required values and for instructions for modifying quotas and limits.)

To modify the account quotas now, do the following:

1. Type No and press the Return key.
2. Modify the account quotas you want to change.
3. Log out of the SYSTEM account; then log back in so that the new quotas will be in effect.
4. Restart VMSINSTAL.

To continue the upgrade without modifying the account quotas, type Yes and press the Return key.

7.3.4 Step 4: Back Up the System Disk

The procedure displays the following message:

```
* Are you satisfied with the backup of your system disk [YES]?
```

If you have made a standalone backup of the system disk, press Return and go to Section 7.3.5.

If you have not made a standalone image backup of the system disk, do the following:

1. Type N (for No) and press Return. VMSINSTAL ends and the dollar-sign prompt (\$) is displayed.
2. Back up the system disk as described in the upgrade and installation supplement for your VAX computer.
3. After you have made a backup of the system disk, start the upgrade procedure again.

7.3.5 Step 5: Specify the Source Drive

VMSINSTAL asks for the name of the drive that holds the distribution media:

```
* Where will the distribution volumes be mounted:
```

Enter the device name of the source drive. For example, if you have a VAX 6000 series computer that has a TK70 with a device name of MUC6, type *MUC6* and press the Return key.

If the drive is connected to an HSC, enter the HSC name and the device name of the drive separated by a dollar sign (\$). (If you do not enter the device name in this manner, it will cause a failure in Phase 2.) For example, if the HSC name is MUTT and the device name is MUA0, enter the following and press Return:

```
* Where will the distribution volumes be mounted: MUTT$MUA0
```

If you are not using an InfoServer device, proceed to Section 7.3.6.

Upgrading the OpenVMS VAX Operating System

7.3 Beginning the Upgrade Procedure

If you are upgrading from a compact disc drive connected to an InfoServer, the device name is `DADn`. The `n` part of the device name was displayed when you bound to the distribution compact disc as previously described in Section 7.3.2.

If `VMSINSTAL` displays an error message, make sure the drive is connected and set up properly. Enter the name again. If `VMSINSTAL` displays another error message, use the following procedure to verify the device name:

1. Press `Ctrl/Y` to exit from `VMSINSTAL`.
2. Enter the `SHOW DEVICE` command to make sure you have the correct device name.
3. Restart the upgrade procedure from Section 7.3.3.

If `VMSINSTAL` does not display an error message, proceed to Section 7.3.6.

7.3.6 Step 6: Enter Product Name

When `VMSINSTAL` displays the following message, type `VMS071` and press the Return key. Make sure that you use the number zero (not the letter "O") when you type `VMS071`. For example:

```
* Products: VMS071
```

When the procedure displays the following message, press Return:

```
* Enter installation options you wish to use (none):
```

7.3.7 Step 7: Mount the First Volume

`VMSINSTAL` displays a message similar to the following:

```
Please mount the first volume of the set on _MUA0.
```

When the procedure displays the following message, type `Y` (for Yes) `S`) and press Return:

```
* Are you ready? Y
```

The procedure displays messages similar to the following:

```
%MOUNT-I-MOUNTED, VMS071 mounted on _MUA0:
```

```
The following products will be processed:
```

```
OpenVMS V7.1
```

After a slight pause, the procedure displays a message similar to the following:

```
Beginning installation of OpenVMS V7.1 at 15:05
```

```
%VMSINSTAL-I-RESTORE, Restoring product saveset A...
```

7.3.8 Step 8: Monitor Messages from `VMSINSTAL`

The upgrade procedure displays several important messages that provide you with the following information:

- What `VMSINSTAL` is doing.
- Notes, suggestions, and restrictions about various parts of the upgrade.
- Status of the upgrade.

Upgrading the OpenVMS VAX Operating System

7.3 Beginning the Upgrade Procedure

Read these messages carefully to decide whether or not you need to interrupt the upgrade procedure. An interruption is allowed before Phase 1. The procedure displays the following message:

```
* Do you want to continue? (Y/N):
```

To continue the upgrade, type Yes and press the Return key.

To interrupt the upgrade, do the following:

1. Type No and press Return.
2. If prompted for another product, type EXIT to exit from VMSINSTAL.

7.3.9 Step 9: Verify Date and Time

The procedure displays the current date and time. If the date and time are correct, type Yes. If they are incorrect, type No. Enter the correct date and time using the 24-hour clock format and press Return. For example:

```
PLEASE ENTER DATE AND TIME (DD-MMM-YYYY HH:MM) 22-NOV-1996 15:10
```

7.4 Upgrade Phase 1

This section describes Phase 1 of the upgrade. During this phase, you provide passwords for system accounts and select OpenVMS options, and the procedure restores the files in the OpenVMS *required* save set (VMS071.B).

At the end of this phase, the procedure shuts down your VAX computer. If your computer uses console media when booting and the boot file was modified as described in Section 7.2, the system should reboot automatically. Otherwise, you must reboot manually from the SYSF directory.

7.4.1 Step 1: Specify Type of Upgrade

At the beginning of Phase 1, the procedure displays a message similar to the following:

```
Upgrade Phase 1 22-NOV-1996 15:11:17.05
```

```
* Are you performing a rolling upgrade? (Y/N):
```

If you are performing a concurrent upgrade or an upgrade on a standalone system, type No and press the Return key.

If you are performing a rolling upgrade, type Yes and press Return. The procedure will ask you several questions to determine if all system disks in the cluster (other than the one you are upgrading) are running at least OpenVMS VAX Version 6.0. Follow the instructions in Section 6.4.

7.4.2 Step 2: Enter Passwords

To ensure system security, the upgrade procedure requires you to enter passwords for the SYSTEM, SYSTEST, and FIELD accounts before continuing. Passwords must contain at least 8 characters; they are not displayed by the system. Press Return after you enter each password and it will be verified. For example:

To help provide a more secure system, you are asked to enter passwords for key system accounts. Passwords must be a minimum of 8 characters in length. You can enter new or existing passwords.

```
Enter passwords for the following accounts:
```

```
SYSTEM, SYSTEST, FIELD
```


Upgrading the OpenVMS VAX Operating System

7.4 Upgrade Phase 1

```
* Enter password for SYSTEM:
* Re-enter for verification:
%UAF-I-MDFYMSG, user record(s) updated
%VMS-I-PWD_OKAY, account password for SYSTEM verified

* Enter Password for SYSTEST
* Re-enter for verification:
%UAF-I-MDFYMSG, user record(s) updated
%VMS-I-PWD_OKAY, account password for SYSTEST verified

    The SYSTEST_CLIG account will be disabled. You must re-enable
    it before running UETP but do not assign a password.

%UAF-I-MDFYMSG, user record(s) updated

Enter password for FIELD:
Re-enter for verification:
%UAF-I-MDFYMSG, user record(s) updated
%VMS-I-PWD-OKAY, account password for FIELD verified
```

If you enter a password incorrectly or if the password is too easy to guess, the procedure displays error messages similar to the following:

```
%VMS-W-PWD-INVALID, account password for FIELD is invalid
%VMS-I-PWD-WEAK, password is too easy to guess
```

Because of the preceding error, you must take action to secure this account. You must either disable this account, change its password, or do both.

When the procedure asks if you want to disable the account, type No and press the Return key. When the procedure asks if you want to enter a new password, type Yes and press Return. Then enter a new password. For example:

```
Do you want to disable the account (Y/N)? N
Do you want to change the account password (Y/N)? Y
You must now select a new primary password for the FIELD account. The
password you select must be at least 8 characters in length and cannot be
the same as the name of the account.
```

```
New password:
Verification:
%UAF-I-MDFMSG, user record(s) updated
%VMS-I-PWD-SET, primary password for account FIELD set
```

After you have correctly entered the passwords, the procedure does the following:

- Checks the account quotas in the DEFAULT, SYSTEM, and various other accounts and modifies them if necessary
- Turns off quotas on the system disk
- Stops OPCOM
- Stops the error formatter (ERRFMT)

7.4.3 Step 3: Choose Boot Method

If your VAX computer is *not* one of the following, go to Section 7.4.4.

```
VAX-11/730
VAX-11/750
VAX-11/780
VAX 8200, 8250, 8300, 8350
VAX 8600, 8650
VAX 9000
```

Upgrading the OpenVMS VAX Operating System

7.4 Upgrade Phase 1

If your VAX computer is included in the preceding list, the procedure can temporarily modify the DEFBOO.COM (or DEFBOO.COM if you have a VAX 8600 computer) to boot from the [SYSF] directory. During Phase 4 of the upgrade, the procedure restores the DEFBOO.COM (or DEFBOO.COM) file that is set up to boot from the current system disk and system root.

The procedure displays a message similar to the following (*except for VAX-11/730, 11/780, and 8600 computers*):

* Do you want to boot from the [console media]?

If you prefer to boot your system manually from the [SYSF] directory or if you are booting directly from a local system disk, type No, press the Return key, and go to Section 7.4.4 to continue the upgrade.

Type Yes and press Return if one of the following is true:

- You want to boot from the console media.
- Your computer is a VAX-11/730, 11/780, or 8600.
- You are using a CI750.

The procedure prompts you to insert the console media in the drive. Insert the backup copy of the console media into the drive and do not remove it from the drive until the upgrade has been completed. Make sure the console media is write enabled.

7.4.4 Step 4: File Cleanup

The procedure does the following:

- Checks for the location of the SYS\$TIMEZONE.DAT file, which must now must be in the SYS\$COMMON:[SYSEXE] directory. If the procedure finds this file in some other directory, it deletes it from that directory. Later, during the final phase of the upgrade, the procedure prompts you for the information it needs to create a SYS\$TIMEZONE.DAT file in the SYS\$COMMON:[SYSEXE] directory.
- Renames files found in SYS\$SPECIFIC:[SYSMGR] and in SYS\$COMMON:[SYSMGR] by adding _OLD_SPECIFIC to the file extensions. For example, [SYSMGR]LOGIN.COM becomes [SYSMGR]LOGIN.COM_OLD_SPECIFIC. (The file extensions are restored during Phase 6 of the upgrade procedure.)
- Cleans up the system disk by purging all accounting data files, operator logs, and the directory SYSERR. The procedure also deletes all JNL files in the root directory and its subdirectories.
- Builds the directory tree [SYSF] and deletes the OpenVMS VAX and DECwindows files that are not needed to reboot during Phase 2 of the upgrade.

As the procedure performs each of these tasks, it displays messages describing what is being done. When this step is completed, the procedure displays a message similar to the following:

```
File cleanup complete - 22-NOV-1996 15:29:41.92
```

7.4.5 Step 5: Select Optional OpenVMS Components

The procedure displays information about optional OpenVMS VAX files and the remaining amount of disk space. The information is similar to the following (block sizes might vary slightly):

Select optional software you want to install. You can install one or more of the following OpenVMS or DECwindows components:

- o OpenVMS library - 53400 blocks
- o OpenVMS optional - 21200 blocks
- o OpenVMS Help Message - 10200 blocks
- o OpenVMS Management Station - 21200 blocks
- o DECwindows base support - 3800 blocks
- o DECwindows workstation support - 23500 blocks
 - 75 dots per inch video fonts - (included)
 - 100 dots per inch video fonts - 6000 blocks
- o DECnet-Plus networking - 85000 blocks

Space remaining on system disk: 682440 blocks

You must indicate which of the options you want to install. If you require network support, you must select the OpenVMS library component.

Note that, if you do not install the optional OpenVMS components at this time, you can install them after the upgrade by using the VMSTAILOR and DECW\$TAILOR utilities. However, the Help Message utility and the three reference manuals can be tailored on to the system disk only. If you do not choose the Help Message files or the three manuals at this point in the procedure and want them on an alternate device, you will not be able to use VMSTAILOR to restore them later. If you want to install Help Message on an alternate disk *after* the installation procedure completes, you can use the BACKUP command, as follows:

```
BACKUP/VERIFY source-device:[000000]VMS071.E/SAVE_SET-  
target-device:[directory-name]
```

For *source-device*, enter the device name for the drive on which the distribution media is mounted. For *target-device*, enter the device name on which the alternate disk is mounted, and for *directory*, enter the name of the directory to which you are copying the files.

Also note that, for TK50 tape cartridges, it is quicker to install OpenVMS VAX software during the upgrade than to add software after the upgrade with a tailoring utility. For information about using VMSTAILOR, see Chapter 10. To select the options you want to install, follow the instructions displayed by the procedure.

7.4.5.1 OpenVMS Library Files

The procedure displays the following message:

```
* Do you want to install the OpenVMS library files? (Y/N)
```

The file subclasses of the OpenVMS *library* (VMS071.C) save set are listed in Appendix D. If you want to install the VMS071.C files, type Yes and press Return. If you require network support, you must select the OpenVMS library component. If you do *not* want to install the VMS071.C files, type No and press Return.

Upgrading the OpenVMS VAX Operating System

7.4 Upgrade Phase 1

7.4.5.2 OpenVMS Optional Files

The procedure displays the following message:

```
* Do you want to install the OpenVMS optional files? (Y/N)
```

The file subclasses of the OpenVMS *optional* (VMS071.D) save set are listed in Appendix D. If you want to install the VMS071.D files, type Yes and press Return. If you do *not* want to install the VMS071.D files, type No and press Return.

7.4.5.3 Help Message Files

The procedure displays the following message:

```
The Help Message utility (MSGHLP) provides online explanations
and user actions for OpenVMS messages in place of the hardcopy
OpenVMS System Messages and Recovery Procedures Reference Manual,
which is now separately orderable.
```

```
The MSGHLP database, MSGHLP$LIBRARY.MSGHLP$DATA, consumes
approximately 10200 blocks and will be placed by default
on your system disk in SYS$COMMON:[SYSHLP] unless you specify an
alternate device when prompted.
```

```
Users with limited disk space can access the MSGHLP database
on a read-only basis at DAD1:[HELP_MESSAGE].
```

```
* Do you want to install the MSGHLP database? (Y/N)
```

The Help Message utility is an online system for system messages documentation. You can install Help Message either on the system disk or on an alternate disk. If you want to install the Help Message files, type Yes and press Return.

The procedure displays the following message:

```
You can install this database on your system disk in SYS$COMMON:[SYSHLP]
or on an alternate device. If you specify an alternate device, but no
directory, MSGHLP$LIBRARY.MSGHLP$DATA is placed in [HELP_MESSAGE]. When
prompted, take the default of the system disk or specify an alternate
device using this format:
```

```
device:[directory]
```

```
* Where do you want to install the MSGHLP database? [SYS$COMMON:[SYSHLP]] DUA1
```

The Help Message database is installed in the area you specified, and the system displays information similar to the following:

```
%MOUNT-I-MOUNTED, VMS071      mounted on DUA1
      Space remaining on alternate device DUA1:: 124532 blocks
```

7.4.5.4 OpenVMS Management Station Files

The procedure displays the following message:

```
The OpenVMS Management Station is a client-server application
that provides OpenVMS system management capabilities through a
client application on a personal computer (PC) running Microsoft
Windows. The server application runs on OpenVMS systems and is
automatically installed as part of the OpenVMS operating system.
```

```
This option provides the files used to create the installation media
for the PC client software. If you want to use the OpenVMS Management
Station, you must install these files on at least one OpenVMS system to
create the installation media, which can then be used to install the
PC client on one or more PCs.
```

```
Note: To use the OpenVMS Management Station on your PC, you must be
running Digital's PATHWORKS V5.0A for DOS and Windows (or V5.1) software.
```

```
The OpenVMS Management Station optional files consume approximately 21200
blocks and will be placed on your system disk in SYS$COMMON:[TNT.CLIENT].
```

Upgrading the OpenVMS VAX Operating System

7.4 Upgrade Phase 1

* Do you want to install the optional OpenVMS Management Station files? (Y/N)

Space remaining on system disk: 623240 blocks

If you want to use the OpenVMS Management Station software, you must install these files. After the upgrade procedure completes, follow the instructions in Appendix G to prepare your OpenVMS system and your PC to run the OpenVMS Management Station server and client software.

7.4.6 Step 6: Choose DECwindows Support Options

Next, the procedure displays messages about the DECwindows components shipped with OpenVMS VAX Version 7.1.

The OpenVMS VAX operating system no longer ships the OpenVMS DECwindows product. The operating system now ships only the DECwindows base support and DECwindows workstation support components. To get full DECwindows support, you must also install the separate DECwindows Motif for OpenVMS VAX (previously called VMS DECwindows Motif) layered product, which supports both Motif and XUI environments.

Note that the DECwindows base support and DECwindows workstation support components are *not* shipped with the DECwindows Motif for OpenVMS layered product. If you want to install these options, you must select them now or use the DECW\$TAILOR option after the installation procedure completes.

Before you indicate whether you want to install DECwindows support software, consider the following:

If you...	Then choose...
Intend to install the DECwindows Motif layered product	DECwindows base support.
Intend to install the DECwindows Motif layered product on a workstation or on a VAXcluster system that contains workstations	DECwindows base support and DECwindows workstation support.
Are <i>not</i> planning to install the DECwindows Motif layered product but are installing OpenVMS VAX on a workstation or on a VAXcluster that includes workstations	DECwindows base support and DECwindows workstation support.
Want to provide font files for X terminals	DECwindows base support and DECwindows workstation support.
Have a workstation monitor (for example, a VR150, VR160, or VR295) capable of displaying 100 dots/inch or a VAXstation 4000 series computer, which uses 100 dots/inch video fonts by default	DECwindows base support and DECwindows workstation support with the 100 dots/inch option. By selecting the workstation support files, you automatically get 75 dots/inch video font files, and you will be prompted to indicate if you want to install 100 dots/inch video font files.

The procedure displays the following:

You can select DECwindows support now, or you can use the DECW\$TAILOR utility to provide or remove DECwindows support after upgrade.

Some media, TK50s in particular, can be very slow when tailoring on files. You might want to provide DECwindows options now and tailor off unwanted files later.

Upgrading the OpenVMS VAX Operating System

7.4 Upgrade Phase 1

NOTE: This kit does NOT contain full DECwindows.
To obtain full DECwindows support, you must also install the separate layered product, DECwindows Motif for OpenVMS VAX. Version 1.2-3 is the minimum version of DECwindows Motif for OpenVMS VAX that can be used with OpenVMS VAX Version 7.1.

The DECwindows components provided in this kit require approximately 29350 blocks, broken down as follows:

- o DECwindows base support - 3800 blocks
- o DECwindows workstation support - 23500 blocks
 - 75 dots per inch video fonts (included)
 - 100 dots per inch video fonts (optional) - 6000 blocks

You must select the DECwindows base support option if

- you plan to run DECwindows software, or
- you are installing this kit on
 - * a workstation or
 - * a VAXcluster that contains workstations, or
- you want to provide font files for Xterminals.

If you are installing this kit on a system that includes Xterminals and you do not select DECwindows base support, then you will have to use the DECW\$TAILOR utility to provide font files.

* Do you want the DECwindows base support? (Y/N)

Space remaining: 619640

You must select the DECwindows workstation support option if

- you are installing this kit on
 - * a workstation or
 - * a VAXcluster that contains workstations, or
- you want to provide font files for Xterminals.

If you are installing this kit on a system that includes Xterminals and you do not select DECwindows base support, then you will have to use the DECW\$TAILOR utility to provide font files.

* Do you want to provide DECwindows workstation support? (Y/N)

Space remaining: 598890

DECwindows workstation support includes the 75 dots per inch video fonts.

All DECwindows applications run with 75 dots per inch video fonts. By default, most systems start up with 75 dots per inch video fonts. Certain applications can take advantage of 100 dots per inch video fonts.

For the VAXstation 4000 series machine, 100 dots per inch video fonts are used by default. If you decide not to install 100 dots per inch video fonts, you must edit SYS\$MANAGER:DECW\$PRIVATE_SERVER_SETUP.COM to force 75 dots per inch video fonts to be the default. Otherwise, certain applications may not space text properly.

For instructions on how to configure your system with both 75 and 100 dots per inch video fonts, see the template command procedure SYS\$MANAGER:DECW\$PRIVATE_SERVER_SETUP.TEMPLATE.

*Do you want 100 dots per inch video fonts installed? (Y/N)

Space remaining: 593890

7.4.7 Step 7: Select Networking Software

Next, the procedure displays messages describing the DECnet options. For more information, refer to Section 1.2.1.

Beginning with OpenVMS V7.1 DECnet-Plus is provided with the OpenVMS operating system. Digital strongly recommends that DECnet users install DECnet-Plus. DECnet Phase IV applications are supported by DECnet-Plus.

If you plan to install DECnet Phase IV do NOT select DECnet-Plus.

* Do you want to install DECnet-Plus. (Y/N) Y

Space remaining on system disk: 508890 blocks

7.4.8 Step 8: Verify Your Choices

The procedure displays a list of OpenVMS VAX and DECwindows support options that you have chosen and gives you the opportunity to change your mind before proceeding by displaying the following message:

```
* Is this correct? (Y/N)
```

If you answer Yes to this prompt, the procedure restores the OpenVMS required save set (VMS071.B) and purges the page, swap, dump, and authorization files.

If you answer No to this prompt, you can respecify the OpenVMS VAX and DECwindows options that you want to install. The procedure restores the DECwindows components you have chosen during Phase 2.

7.4.9 Step 9: Shut Down Your System

After several minutes, the upgrade procedure indicates that the system will shut down to reboot the partially upgraded OpenVMS VAX system and displays information about how to reboot the system.

On certain VAX computers, the procedure displays the following message:

```
* Press RETURN to shutdown system:
```

Once you have read the information displayed on the screen, press Return to begin the shutdown.

7.4.10 Step 10: Reboot the System

If your system uses console media, it should automatically reboot from the SYSF directory when the shutdown is complete. If you have a MicroVAX or if your system does not reboot from SYSF, halt the system and boot from the [SYSF] directory. For most MicroVAX and VAXstation computers, use the BOOT command in the following format and substitute the device name of the system disk for *ddcu*:

```
>>> B/F0000000 ddcu
```

If the system fails to boot, you can boot into SYSBOOT by entering the following:

```
>>> B/F0000001 ddcu
```

For more information on booting your computer from the SYSF directory, see the upgrade and installation supplement for your VAX computer.

7.4.11 Step 11: Verify System Time

When the system reboots, it displays a message similar to the following:

```
OpenVMS VAX Version V7.1 Major version id = 1 Minor version id = 0
System time is: 22-NOV-1996 15:54:08.30
.
.
.
* Is that correct? (Y/N/?)
```

If ...	Then ...
You want to redisplay the time	Type a question mark (?) and press Return.

Upgrading the OpenVMS VAX Operating System

7.4 Upgrade Phase 1

If . . .	Then . . .
The system time displayed by the procedure is correct	Type Yes and press Return.
The system time displayed by the procedure is incorrect	Type No and press Return. The procedure prompts you to enter the correct date and time.

7.5 Upgrade Phase 2

At the beginning of Phase 2, the procedure displays a message similar to the following:

```
Continuing with OpenVMS VAX V7.1 Upgrade Procedure.
      Upgrade Phase 2          22-NOV-1996 15:55:42.57
*****
%SYSTEM-W-TZGMT, your local timezone has defaulted to GMT
%SYSTEM-I-SETTZ, to set your local timezone use:
      $ @SYS$MANAGER:UTC$TIME_SETUP.COM
*****
On MIN or UPGRADE system startup - CLUE is not run.
.
.
.
      22-NOV-1996 15:57:00.59
```

You can ignore the time zone message. The UTC\$TIME_SETUP.COM procedure runs during the final phase of the upgrade procedure.

7.5.1 What the Procedure Does

During Phase 2, the upgrade procedure restores the rest of the library (C), optional (D), Help Message (E), and OpenVMS Management Station software (F) save sets and DECwindows support files if you elected to install them.

7.5.1.1 Mounting Additional Tape Cartridge and 9-Track Open Reel Magnetic Tape Volumes

If your distribution kit is on TK50 tape cartridges or 9-track open reel magnetic tapes, you may be asked to mount additional volumes of the kit. In such a case, your system will display a message similar to the following:

Please mount volume <x> of the OpenVMS kit on <device>

where: <x> is the volume number and <device> is the cartridge tape drive or open reel tape drive.

After you respond to the prompt, the system displays one of the following messages:

- For a TK50 tape cartridge, the message is similar to the following:
* Is the volume labeled OVMS VAX V7.1 BIN TK50 2/2 ready to be mounted?
- For 9-track open reel tape, the message is similar to the following:
* Is the volume labeled OVMS VAX V7.1 BIN MT9 n/4 ready to be mounted?
where: n/4 may be 2/4, 3/4 or 4/4.

To respond to either message, do the following:

1. Unload the volume currently in the drive.

2. Examine the remaining volumes and select the one with the label that matches the label specified in the prompt.
3. Load the volume and make the drive ready.
4. Answer YES to the question.

For information on which save sets are located on which tape volumes, Section 1.4.1 and Section 1.4.2.

7.6 Upgrade Phase 3

At the beginning of Phase 3, the procedure displays a message similar to the following:

```
Continuing with OpenVMS VAX V7.1 Upgrade Procedure
      Upgrade Phase 3                22-NOV-1996 16:45:18.35
```

7.6.1 What the Procedure Does

During Phase 3, the upgrade procedure does the following:

1. Merges the OpenVMS VAX distributed files that are commonly edited by system managers with new OpenVMS VAX files.
2. Merges all the miscellaneous user files in the old system directories into a new set of system directories, temporarily called SYSF.SYSEXEXE, SYSF.SYSMGR, SYSF.SYSLIB, and so on.
3. Removes the directory entries for page, swap, dump, and authorization files from the old directory tree.
4. Deletes all the remaining accounting data files, operator logs, and all files in the SYSERR directory.
5. Merges the old and new versions of the following files: HELP, DCLTABLES, IMAGELIB.OLB, and STARLET.OLB.
6. Moves all remaining files from the old directory tree [VMSSCOMMON] to the new directory tree.
7. Deletes the old directory tree [VMSSCOMMON].

7.7 Upgrade Phase 4

At the beginning of Phase 4, the procedure displays a message similar to the following:

```
Continuing with OpenVMS VAX V7.1 Upgrade Procedure.
      Upgrade Phase 4                22-NOV-1996 17:14:34.12
```

7.7.1 What the Procedure Does

During Phase 4, the upgrade procedure does the following:

1. Corrects back pointers for system directories.
2. Shuts down the system.
3. Reboots the system, or requires that you manually reboot the system.

Upgrading the OpenVMS VAX Operating System

7.7 Upgrade Phase 4

7.7.2 What You Do

If the procedure requires that you manually reboot the system from the original system root (usually SYS0), do the following:

1. If you are upgrading a VAX 8530, 8550, 8810, or 8820-N computer, do the following:
 - a. Restore the original copies of DEFBOO and *dddGEN* to boot from the original root directory.
 - b. In the preupgrade procedure (Chapter 5), you made copies of the boot command procedures, DEFBOO.SAV and *dddGEN.SAV*. To restore the original names to these files, enter the following commands and press the Return key after each one:

```
>>> EXIT
$ COPY DEFBOO.SAV DEFBOO.COM
$ COPY dddGEN.SAV dddGEN.COM
```

2. For most MicroVAX and VAXstation computers, use the BOOT command in the following format and substitute the device name of the system disk for *ddcu*:

```
>>> B ddcu
```

If the system fails to boot, you can boot into SYSBOOT by entering the following:

```
>>> B/1 ddcu
```

For more information about booting your system, see the upgrade and installation supplement for your VAX computer.

When the system reboots, the procedure displays a message similar to the following:

```
OpenVMS VAX Version 7.1 Major version id = 1 Minor version id = 0
```

After the system reboots, the procedure continues with upgrade Phase 5. Do not move the system disk to a different drive. The system disk must remain in the same drive for the procedure to continue with Phase 5.

7.8 Upgrade Phase 5

At the beginning of Phase 5, the procedure displays a message similar to the following:

```
Continuing with OpenVMS VAX V7.1 Upgrade Procedure.
```

```
Upgrade Phase 5          22-NOV-1996 17:45:24.03
```

During Phase 5, the upgrade procedure does the following:

1. Deletes the temporary [SYSF] directory tree.
2. Cleans up files used only during the upgrade procedure.
3. Converts all VAXVMSSYS.PAR parameter files found in system roots to Version 7.1 format.
4. Displays messages listing tasks that you can perform after the upgrade procedure is completed. These tasks are described in Chapter 8.

7.9 Upgrade Phase 6

At the beginning of Phase 6, the procedure displays a message similar to the following:

```
Continuing with OpenVMS VAX V7.1 Upgrade Procedure.  
      Upgrade Phase 6      22-NOV-1996 17:45:25.03  
  
Configuring all devices on the system...
```

7.9.1 Restoring System Files

The procedure restores SYSSSPECIFIC and SYSSCOMMON versions of the following system files that were renamed with .COM_OLD_SPECIFIC and .DAT_OLD_SPECIFIC extensions during Phase 1:

```
SYSTARTUP_VMS.COM  
SYCONFIG.COM  
SYPAGSWPFILES.COM  
SYSECURITY.COM  
SYSHUTDOWN.COM  
SYLOGIN.COM  
LOGIN.COM  
SYLOGICALS.COM  
AGENSNEW_SATELLITE_DEFAULTS.DAT  
AGENSNEW_NODE_DEFAULTS.DAT  
LATSSYSTARTUP.COM  
TFFSSTARTUP.COM
```

You might not have site-specific versions of all of these files. The procedure will display a message listing each file as it is restored.

You might receive any of the following network messages, which can be ignored:

```
%NCP-W-UNRCMP, Unrecognized component, Object
```

Or:

```
%NCP-I-SUCCESS, Success  
Object = X$X0  
%NML-I-RECDELETE, Database entry deleted
```

7.9.2 Registering Licenses

The upgrade procedure also gives you the opportunity to register any additional licenses.

The procedure displays the following message:

```
If you have Product Authorization Keys (PAKs) to register, you can  
register them now.
```

```
* Do you want to register any Product Authorization Keys? (Y/N):
```

You do not have to reregister your OpenVMS VAX license or licenses for the following system integrated products:

```
VAXclusters  
DECnet-Plus  
RMS Journaling  
Volume Shadowing
```

If you want to register a *new* Product Authorization Key, type Yes and press the Return key. Otherwise, type No and press Return.

Upgrading the OpenVMS VAX Operating System

7.9 Upgrade Phase 6

For more information on registering licenses, see the description of VMSLICENSE.COM in Appendix B and in the *OpenVMS License Management Utility Manual*.

7.9.3 Updating Time Zone Information

At this point in the upgrade, the procedure checks for the presence of time zone and time differential factor (TDF) files on your system. If it does not find one or the other of these files, the procedure prompts you for information to be used for providing local time zone support.

For local time zone support to work correctly, the upgrade procedure must set the time zone that accurately describes the location you want to be considered as your default time zone. Usually, this is the time zone in which your system is running. In addition, your system must be correctly configured to use a valid OpenVMS time differential factor (TDF).

The procedure displays a series of time zone menus and prompts you to make selections from those menus. The first menu is the main time zone menu. Select the time zone that best describes your location. If you do not select a time zone, the default is Greenwich Mean Time (GMT).

Some time zone choices cause an additional menu to be displayed. This happens when the time zone you select has subcomponents. For example, if you choose the United States (US) time zone from the main menu, a second menu displays the specific time zones within the United States. You then select the menu item that best represents your local time zone.

The procedure then prompts you for the TDF. The TDF is the difference between your system time and Coordinated Universal Time (UTC), which is an international standard for measuring time of day. You can choose from the following options:

- Exit the time zone procedure without setting a TDF
- Set a TDF
- Display the TDF for your local time zone

For more information about TDF and local time zone support, see the *OpenVMS System Manager's Manual*.

7.9.4 Installing DECnet-Plus

Earlier in the procedure, you were asked whether you wanted to install the DECnet-Plus product. If you answered Yes, the procedure now installs it.

Note that, if DECnet-Plus (formerly DECnet/OSI) is already installed on your system and if the installed version is the same as or higher than the version supplied with OpenVMS VAX Version 7.1, then DECnet-Plus is *not* reinstalled, and the procedure displays the following message:

```
DECnet--Plus is already installed.
```

If DECnet-Plus is not already installed on your system, the procedure displays a message similar to the following and prompts you for information it needs to install the DECnet-Plus product. In this example, the kit is being installed from an InfoServer device, DAD1.

Upgrading the OpenVMS VAX Operating System 7.9 Upgrade Phase 6

DECnet-Plus will now be installed.

Media containing the DECnet-Plus kit must be available.

If you are installing OpenVMS from an InfoServer (DAD1) or local CD-ROM, there is a DECnet-Plus kit on the CD-ROM.

If you are installing from a cartridge tape (TK50) or from an open reel tape, you should have a DECnet-Plus kit on cartridge tape or open reel tape.

An appropriate DECnet-Plus kit may also be available on the Consolidated Distribution CD-ROM, or you may have a separate DECnet-Plus kit.

NOTE: You may choose any available media for the DECnet-Plus kit. It is NOT NECESSARY to use the same type of media that contained the OpenVMS kit.

- * Enter name of drive holding the DECnet-Plus kit: DAD1:
- * Enter the InfoServer service name: OTHER PRODS
- * Enter the InfoServer work group number [0]:

The following product has been selected:
DEC VAXVMS DECNET_PLUS V7.1

*** DEC VAXVMS DECNET_PLUS V7.1: DECnet-Plus V7.1 N3_H for OpenVMS VAX
Copyright) Digital Equipment Corporation 1996. All rights reserved.

Digital Equipment Corporation

This product requires one of two PAKs: DVNETEND or DVNETRTG.

Do you want all the default values for this product? [YES]

Do you want to view the values? [NO]

Execution phase starting ...

The following product will be installed:

DEC VAXVMS DECNET_PLUS V7.1

Portion done: 0%...10%...20%...30%...40%...80%...90%...100?

The following product has been installed:

DEC VAXVMS DECNET_PLUS V7.1

7.9.5 Running AUTOGEN

Next, the procedure displays the following message and runs AUTOGEN:

Running AUTOGEN to compute the new SYSTEM parameters...

If AUTOGEN encounters any problems, it displays the following message:

```
%AUTOGEN-W-REPORT, Warnings were detected by AUTOGEN. Please review the
information given in the file SYS$SYSTEM:AGEN$PARAMS.REPORT.
```

If AUTOGEN displays this message, be sure to check AGEN\$PARAMS.REPORT as one of your postupgrade tasks. This task is described in Section 8.4.

7.9.6 Shutting Down the System

After AUTOGEN finishes, the procedure displays a sequence of shutdown messages that begins like this:

The system is shutting down to allow the system to boot with the generated site-specific parameters and installed images.

The system will automatically reboot after the shutdown and the upgrade will be complete.

```
SHUTDOWN -- Perform an Orderly System Shutdown
```

```
.  
. .  
.
```

Upgrading the OpenVMS VAX Operating System

7.9 Upgrade Phase 6

The system shuts down and will reboot automatically if your system is set up to do so. If the system does not reboot automatically, reboot it manually. For more information on booting your system, see the upgrade and installation supplement for your VAX computer.

7.9.7 Booting Voting Nodes

If you are upgrading a standalone system, go to the next step.

If you are upgrading a VAXcluster system, the system might hang when you try to reboot the upgraded system disk. This is because the total cluster value is less than the cluster quorum value. To remedy this situation, boot voting members that run from the system disk you just upgraded. (For more information about quorum values and voting members, see *OpenVMS Cluster Systems*.) All nodes that are booted at this time will run AUTOGEN and reboot.

7.9.8 Executing STARTUP

After the system reboots, the procedure displays the following message:

```
*****
OpenVMS VAX V7.1
You have SUCCESSFULLY installed the OpenVMS operating system.
The system is now executing the STARTUP procedure. Please
wait for the completion of STARTUP before logging in to the
system.
*****
```

Finally, the procedure displays informational messages as well as accounting information. For example:

```
%STDRV-I-STARTUP, OpenVMS startup begun at 22-NOV-1996 18:27:30
.
.
%SET-I-INTSET, login interactive limit=64, current interactive value = 0
SYSTEM      job terminated at 22-NOV-1996 18:30:00.00
Accounting information:
Buffered I/O count:      133   Peak working set size:      401
Direct I/O count:       12    Peak virtual size:      2379
Page faults:           325   Mounted volumes:      0
Charged CPU time 0 00:00:55.23 Elapsed time      0 00:01:31.24
```

At this point the OpenVMS VAX operating system is running.

7.9.9 Logging In

Press the Return key. The system asks for the user name and password. Log in to the SYSTEM account so that you can perform the postupgrade procedures described in Chapter 8.

```
Welcome to OpenVMS VAX V7.1
Username: SYSTEM
Password:
.
.
.
```

If you forget the password, follow the instructions for performing an emergency startup in the *OpenVMS System Manager's Manual: Essentials*.

Proceed to Chapter 8 to perform the required postupgrade tasks.

After Upgrading OpenVMS VAX

After you upgrade the OpenVMS VAX operating system, you need to perform several important tasks before you can use the system. This chapter describes the following tasks in the order you perform them:

- Verifying system time
- Restoring the preferred node list
- Replacing SYSUAF.DAT and VMSSAUDIT_SERVER.DAT
- Examining AGEN\$PARAMS.REPORT
- Checking the size of system files
- Examining your command procedures
- Changing MODPARAMS.DAT
- Updating your console media
- Decompressing system libraries
- Testing the system with UETP, the user environment test package
- Increasing free space on your system disk
- Purging system files
- Restoring your modifications to the system password dictionary
- Customizing DECwindows support software
- Preparing to run the OpenVMS Management Station software
- Installing layered products
- Backing up the system disk
- Running AUTOGEN
- Completing the postupgrade checklist

If you are an experienced system manager, you can use the checklist at the end of this chapter to complete the necessary postupgrade tasks.

If you are a less-experienced system manager, you should read the entire chapter and then use the checklist to make sure you have completed all the postupgrade tasks.

After Upgrading OpenVMS VAX

8.1 Verifying System Time

8.1 Verifying System Time

During the upgrade, the procedure displayed the system time and gave you the opportunity to enter the correct time if the displayed time was incorrect.

Now that you have upgraded your system, verify that the system time is correct by entering the following command:

```
$ SHOW TIME
```

The system displays the date and time.

If the time displayed by your system is not correct, reset it by entering the command SET TIME using the following format:

```
SET TIME=dd-mmm-yyyy:hh:mm:ss
```

For example:

```
$ SET TIME=22-NOV-1996:18:35:30
```

8.2 Restoring the Preferred Node List

After the upgrade completes, the queuing system on the upgraded nodes is enabled, and you must restore the preferred node list for the queue manager.

To restore the preferred node list, enter the following command from any node:

```
START/QUEUE/MANAGER/ON=(node1, node2 . . . noden)
```

For **node1**, **node2**, and so forth, supply the names of the nodes—separated by commas—that you want to restore to the preferred node list.

8.3 Replacing SYSUAF.DAT and VMSSAUDIT_SERVER.DAT

If you permanently store the SYSUAF.DAT and VMSSAUDIT_SERVER.DAT files on the system disk, go to Section 8.4.

If you do not permanently store SYSUAF.DAT and VMSSAUDIT_SERVER.DAT on the system disk, you copied them to the system disk before you did the upgrade. During upgrade procedure, these files were updated.

Note

If you did a rolling upgrade, the shared version of SYSUAF.DAT was not updated.

To replace the updated files, copy the updated versions of SYSUAF.DAT and VMSSAUDIT_SERVER.DAT from the system disk to the directory where you usually keep them.

8.4 Examining AGEN\$PARAMS.REPORT

When AUTOGEN runs, it writes informational and, if necessary, warning messages to the file SYSSYSTEM:AGEN\$PARAMS.REPORT. You can view the contents of this report file to examine these messages.

After Upgrading OpenVMS VAX 8.4 Examining AGEN\$PARAMS.REPORT

To display AGEN\$PARAMS.REPORT on your screen, enter the following command and press the Return key:

```
$ TYPE SYS$SYSTEM:AGEN$PARAMS.REPORT
```

If the report includes a message similar to the following, you can modify the size of the PAGE, SWAP, or DUMP file:

```
*****  
%AUTOGEN-W-DSKSPC, The disk on which DISK$OpenVMS071:[SYS0.SYSEXE]PAGEFILE.SYS  
  resides would be over 95% full if it were modified to hold 20000  
  blocks.  
*****
```

For more information about modifying the sizes of the PAGE, SWAP, and DUMP files, see Section 8.5.

8.5 Checking the Size of System Files

AUTOGEN sets the following files at sizes appropriate for your system:

```
[SYSEXE]SYSDUMP.DMP  
[SYSEXE]PAGEFILE.SYS  
[SYSEXE]SWAPFILE.SYS
```

For special workloads or configurations, you can specify different sizes for these files. Check the sizes of these files to be sure they meet your needs. Log in to the SYSTEM account and enter the following command:

```
$ @SYS$UPDATE:SWAPFILES
```

For more information, see the *OpenVMS System Manager's Manual: Essentials*.

8.6 Examining Your Command Procedures

The upgrade procedure places a new version of WELCOME.TXT on your system disk. If your system uses a site-specific version of this file, you must modify the new version of the file with your changes.

The upgrade procedure restores your site-specific version of the following files with *.COM_OLD_SPECIFIC extensions:

```
SYSTARTUP_VMS.COM  
SYCONFIG.COM  
SYPAGSWPFILES.COM  
SYSECURITY.COM  
SYSHUTDOWN.COM  
SYLOGIN.COM  
LOGIN.COM  
SYLOGICALS.COM  
LAT$SYSTARTUP.COM  
TFF$SYSTARTUP.COM
```

The upgrade procedure provides new templates for some of these files with the .TEMPLATE extension. The new templates can include features that are not in your site-specific files. Check the templates against your site-specific files and edit your files as necessary.

Remember, you do not need a START/QUEUE/MANAGER command in your startup file because the queue manager automatically starts up when you boot the system.

After Upgrading OpenVMS VAX

8.7 Changing MODPARAMS.DAT

8.7 Changing MODPARAMS.DAT

Review the file SYS\$SYSTEM:MODPARAMS.DAT. The upgrade procedure created a new version of this file. The old version is named SYS\$SYSTEM:MODPARAMS.DAT_OLD. Modify the new file, if necessary, for your system.

If you are upgrading a VAXcluster, you must update the MODPARAMS.DAT file for each VAX computer that boots from the system disk. Make sure the EXPECTED_VOTES value is correct. The value is the sum of all VOTES in the cluster. For example, if there are five VAX computers in the cluster, and each has one VOTE, the value is five. As you reboot each VAX computer, AUTOGEN runs automatically. The cluster forms when you have booted enough computers to attain cluster quorum.

For more information, refer to the *OpenVMS System Manager's Manual: Tuning, Monitoring, and Complex Systems*.

8.8 Updating Your Console Media

If your computer does not use console media, skip this section and go to Section 8.10.

If your computer uses console media, you must copy the Version 7.1 VMB.EXE onto your system's console media. The procedure for accomplishing this differs depending on the VAX series computer you have. Follow the instructions in the section that applies to your VAX computer.

8.9 VAX 8530, 8550, 8810 (8700), 8820-N (8800) Computers

If you upgraded a VAX 8530, 8550, 8810 (8700), or 8820-N (8800) computer, do the following:

1. Place a blank RX50 diskette in one of the console diskette drives. The console refers to the upper (or left-hand) diskette drive as DZ1 while the OpenVMS VAX operating system refers to it as CSA1. The console refers to the lower (or right-hand) drive as DZ2 while the OpenVMS VAX operating system refers to it as CSA2.
2. Make sure the diskette drives have been connected to the OpenVMS VAX operating system, as follows:

```
$ SHOW DEVICE CSA
Device      Device      Error      Volume
Name        Status      Count      Label
CSA0:      (SYSTEM)   Online     0
CSA1:      (SYSTEM)   Online     0
CSA2:      (SYSTEM)   Online     0
```

If the drives are not connected, the following message is displayed:

```
%SYSTEM-W-NOSUCHDEV, no such device available
```

If this message is displayed, enter the following commands (you need CMKRNL privilege):

```
$ RUN SYS$SYSTEM:SYSGEN
SYSGEN> CONNECT CONSOLE
SYSGEN> EXIT
```

3. To initialize the diskette, enter a command in the following format:

```
$ INITIALIZE/STRUCTURE=1 device-name: volume-label
```

After Upgrading OpenVMS VAX

8.9 VAX 8530, 8550, 8810 (8700), 8820-N (8800) Computers

Substitute *CSA1* or *CSA2* for *device-name*. Substitute a 1- to 12-character name for *volume-label*. For example:

```
$ INITIALIZE/STRUCTURE=1 CSA1: V61CONSOLE
```

4. Enter the following commands to mount the diskette, create the required directories, and copy the new VMB.EXE to the diskette. Substitute *CSA1* or *CSA2* for *device-name*.

```
$ MOUNT/OVERRIDE=ID device-name:  
$ CREATE/DIRECTORY device-name: [TRANSFER]  
$ COPY SYS$SYSTEM:VMB.EXE device-name: [TRANSFER]
```

5. Once you have copied all the files, enter the following command to dismount the diskette. (Leave the diskette in the drive.) Substitute *CSA1* or *CSA2* for *device-name*.

```
$ DISMOUNT device-name:
```

6. To enter console mode, press Ctrl/P. To exit from the console program, enter the following command:

```
>>> EXIT
```

7. Open the diskette drive door, pause for a moment, and close it. The red indicator light will flash.

8. To copy VMB.EXE from the diskette to the console fixed disk drive, enter the following command:

```
$ COPY DZu: [TRANSFER]VMB.EXE LB0: [CONSOLE]
```

Substitute *DZ1* or *DZ2* for *DZu*.

The fixed drive in the console is known by two names, *DW2* and *LB0*. Most console files are stored using the name *LB0*. If the system displays a message that describes a protection violation on the output device, copy the files using the device name *DW2* rather than *LB0*.

9. When you have finished copying the files, remove the diskette from the drive.
10. Restart the console program by entering the following command and pressing Return:

```
$ RUN CONTROL
```

11. Return to the operating system by entering the following command and pressing Return:

```
>>> SET TERMINAL PROGRAM
```

8.9.1 VAX-11/730, 750, 780, 785 and VAX 8200, 8250, 8300, 8350, 8600, 8650 Computers

If you upgraded a VAX-11/730, 750, 780, 785 and VAX 8200, 8250, 8300, 8350, 8600, or 8650 computer, follow the instructions in this section.

The procedure does the following:

- Checks to see if you have enough space for the new VMB.EXE
- Copies the new VMB.EXE to the console media
- Updates the *BOOT58* file for the VAX-11/750, 8200, 8250, 8300 and 8350 computers

After Upgrading OpenVMS VAX

8.9 VAX 8530, 8550, 8810 (8700), 8820-N (8800) Computers

To update the console media, use the following procedure:

1. Log in to the SYSTEM account.
2. Enter the following commands to check if there is enough space for the new VMB.EXE. You need 120 blocks. If you are updating a VAX-11/730 system, use CSA2 for *device-name*; if you are updating one of the other VAX computers, use CSA1 for *device-name*.

```
$ RUN SYS$SYSTEM:SYSGEN
SYSGEN> CONNECT CONSOLE
SYSGEN> EXIT
$ EXCHANGE DIRECTORY device-name:VMB.EXE

Directory of RT-11 volume TINES$CSA1:      22-NOV-1996 18:40
      VMB.EXE      80  22-NOV-1996

Total of 1 file, 80 blocks.  Free space 43 blocks, largest 23.
```

If the size of the current VMB, plus the free space, does not equal at least 120 blocks, delete unneeded files on the console until you have 120 blocks available. In the above example, the size of the current VMB.EXE (80 blocks) plus the free space (43 blocks) equals 123 blocks, so files do not have to be deleted.

3. Enter the following command and press the Return key:

```
$ @SYS$UPDATE:UPDATE_CONSOLE.COM
```

4. If you are updating the console medium for a VAX 8600 or VAX 8650 computer, the new VMB.EXE is copied onto the console medium.

If you are updating the console medium for one of the other VAX computers, the procedure uses the EXCHANGE procedure to copy the contents of the existing console medium, merge the new files onto the copy of the console medium, and create a new version of the console medium. When the computer is ready to create the new version, it displays a message asking you to insert a scratch tape cassette or diskette. Take out the original console medium and insert a new one.

8.9.2 VAX 9000 Computers

VAX 9000 computers use a special version of VMB.EXE named VMB9AQ.EXE. The upgrade procedure automatically copies a new version of this file to the console hard disk. However, if for some reason you need to update the console hard disk, use the UPDATE_CONSOLE.COM command procedure described for the VAX-11/730, 750, 780, 785 and VAX 8200, 8250, 8300, 8350, 8600, 8650 computers. The device name for the VAX 9000 console hard disk is CSA1.

8.10 Decompressing the System Libraries

Decompressing the system libraries gives the system faster access to the libraries. You can decompress all the system libraries or just some of them. Table 8-1 gives the approximate number of blocks consumed by each library after decompression.

After Upgrading OpenVMS VAX 8.10 Decompressing the System Libraries

Table 8–1 Sizes of Decompressed System Libraries

Library	Blocks	Library	Blocks
HELPLIB.HLB	9108	EDFHLP.HLB	102
STARLET.OLB	8442	TPUHELP.HLB	1038
VAXCCURSE.OLB	102	ACLEDT.HLB	102
VAXCTRL.OLB	477	INSTALHLP.HLB	102
VAXCTRLG.OLB	102	LATCP\$HELP.HLB	240
DECCURSE.OLB	102	MNRHELP.HLB	102
DECCRTL.OLB	183	PATCHHELP.HLB	102
DECCRTLG.OLB	102	PHONEHELP.HLB	102
ERFLIB.TLB	105	SDA.HLB	111
STARLETSD.TLB	4800	SHWCLHELP.HLB	150
MAILHELP.HLB	273	SYSGEN.HLB	393
EDTHELP.HLB	231	TECO.HLB	102
DBG\$UIHELP.HLB	408	UAFHELP.HLB	372
DBG\$HELP.HLB	1986	EVE\$HELP.HLB	1197
EXCHNGHLP.HLB	117	EVE\$KEYHELP.HLB	147
NCPHELP.HLB	537	STARLET.MLB	2502
ANLRMSHLP.HLB	102	LIB.MLB	2229
DISKQUOTA.HLB	102		

The additional amount of disk space required to decompress all system libraries is about 13,500 blocks. To find out how much disk space you have, enter the following command and press the Return key:

```
$ SHOW DEVICE SYS$SYSDEVICE
```

8.10.1 How to Decompress Libraries

You execute the LIBDECOMP.COM command procedure to decompress the system libraries. To run LIBDECOMP, log in to the SYSTEM account, enter the following command, and press Return:

```
$ @SYS$UPDATE:LIBDECOMP.COM
```

The following information is displayed:

```

OpenVMS Library Decompression Utility

 1 HELPLIB.HLB          14 NCPHELP.HLB          27 PATCHHELP.HLB
 2 STARLET.OLB          15 SDA.HLB              28 PHONEHELP.HLB
 3 ACLEDT.HLB           16 SHWCLHELP.HLB       29 LIB.MLB
 4 ANLRMSHLP.HLB        17 SYSGEN.HLB          30 STARLET.MLB
 5 DBG$HELP.HLB         18 ANALAUDIT$HELP.HLB 31 STARLETSD.TLB
 6 DBG$UIHELP.HLB       19 SYSMANHELP.HLB      32 ERFLIB.TLB
 7 DISKQUOTA.HLB        20 TFF$TFUHELP.HLB     33 VAXCCURSE.OLB
 8 EDFHLP.HLB           21 EXCHNGHLP.HLB       34 VAXCTRL.OLB
 9 INSTALHLP.HLB        22 TPUHELP.HLB          35 VAXCTRLG.OLB
10 LATCP$HELP.HLB       23 EVE$HELP.HLB         36 IMAGELIB.OLB
11 MAILHELP.HLB         24 EVE$KEYHELP.HLB     37 DECCURSE.OLB
12 MNRHELP.HLB          25 UAFHELP.HLB          38 DECCRTL.OLB
13 EDTHELP.HLB          26 TECO.HLB             39 DECCRTLG.OLB

A ALL libraries to be decompressed
E EXIT this procedure

```

After Upgrading OpenVMS VAX

8.10 Decompressing the System Libraries

* Enter letter or number(s) of libraries to be decompressed
(Separate multiple entries with a comma):

Enter the appropriate letter or the numbers of the libraries you want to decompress. To decompress all libraries, the process takes approximately one half hour.

If you prefer, you can execute LIBDECOMP interactively or as a batch job. If you use either of these methods, you can decompress up to 8 libraries each time you execute LIBDECOMP by listing the names of the libraries you want to decompress as parameters on the command line. (You can decompress all the libraries by omitting the /PARAMETERS qualifier.) Be sure to separate the library names with commas and do not include the file extension. For example, to decompress the VAXCTRL.OLB, DISKQUOTA.HLB, and LIB.MLB libraries as a batch job, enter the following command:

```
$ SUBMIT/NOTIFY/PARAMETERS=(VAXCTRL, DISKQUOTA, LIB) -  
_ $ SYS$UPDATE:LIBDECOMP
```

To decompress these same libraries interactively, enter the following command:

```
$ @SYS$UPDATE:LIBDECOMP VAXCTRL DISKQUOTA LIB
```

Note that, when you type the command for a batch job, you separate the library names with commas and enclose the list within parentheses. You do not use commas or parentheses on the interactive command line.

8.11 Testing the System with UETP

UETP, the user environment test package, is a software package that tests whether the OpenVMS VAX operating system is installed correctly. As part of the postupgrade procedure, you should run UETP to verify your upgrade.

Note that UETP needs at least 1200 free blocks on the system disk and is available only if you installed the optional save set VMS071.D. If you did not install the optional save set, you can add the UETP files to your system using VMSTAILOR. For information about using VMSTAILOR, see Chapter 10.

For complete information about UETP, see the *OpenVMS System Manager's Manual: Tuning, Monitoring, and Complex Systems*.

8.12 Increasing Free Space on the System Disk

This section describes how to increase the amount of free space on your system disk. You can gain free space by removing optional OpenVMS VAX files that you do not need from the system disk or by purging old versions of some system files.

8.12.1 Using VMSTAILOR and DECW\$TAILOR

To remove files you do not need from the system disk, use VMSTAILOR. For example, if you are not running DECnet for OpenVMS, you do not need the network support files. For complete information about using VMSTAILOR to remove files, see Chapter 10.

If you are running DECwindows Motif, use DECW\$TAILOR to add or remove DECwindows base support, workstation support, and fonts.

Note

Files installed on alternate devices cannot be tailored.

8.12.2 Purging System Files

In most cases, you can purge the following OpenVMS system files to free space on your system disk. However, before you purge any of these files, read Appendix F to make sure you do not purge a file version you might want to keep.

```
SYS$SYSTEM:SHUTDOWN.COM  
SYS$SYSTEM:STARTUP.COM  
SYS$LIBRARY:ENCRYP$HR.EXE  
SYS$LIBRARY:*RTL*.EXE  
SYS$LIBRARY:*SHR.EXE  
SYS$MANAGER:EDTINI.EDT  
SYS$MANAGER:DBL$STRUP.COM  
SYS$MANAGER:*.TEMPLATE  
SYS$EXAMPLES:XAD$RIVER.MAR  
SYS$LIBRARY:CDD$SHR.EXE  
SYS$LIBRARY:EPC$FACILITY.TLB  
SYS$MESSAGE:EPC$MESSG.EXE  
SYS$STARTUP:VMS$LAYERED.DAT
```

To purge a file, enter the PURGE command followed by the file specification. For example:

```
$ PURGE SYS$SYSTEM:SHUTDOWN.COM
```

8.13 Restoring Your System Password Dictionary

The OpenVMS VAX operating system screens potential passwords for acceptability. The DCL command SET PASSWORD takes the user's proposed password, converts it to lowercase (if necessary), and compares it to entries in a system dictionary. If the proposed password is found in the dictionary, it is rejected as a valid user password, and the user must suggest another. Many system managers modify the system password dictionary to include words of significance to their site.

During the upgrade, the procedure replaces the existing system password dictionary with a new one. If you had modified the dictionary and want to restore your local additions, you must merge the file containing your additions with the new system file.

To add your site-specific passwords to the new system password dictionary, enable SYS\$PRV and merge your local additions by entering the following commands, where LOCAL_PASSWORD_DICTIONARY.DATA is the file that contains your additions:

```
$ SET PROCESS/PRIVILEGE=SYS$PRV  
$ CONVERT/MERGE/PAD LOCAL_PASSWORD_DICTIONARY.DATA -  
_ $ SYS$LIBRARY:VMS$PASSWORD_DICTIONARY.DATA
```

8.14 Customizing DECwindows Support Software

If you have installed DECwindows support software, there are several steps that you can take to customize the DECwindows environment. Depending on your configuration, DECwindows customization tasks include the following:

- Customizing the server startup
- Using the Transmission Control Protocol/Internet Protocol (TCP/IP) as a DECwindows transport
- Using transports for DECwindows other than those supplied by Digital

After Upgrading OpenVMS VAX

8.14 Customizing DECwindows Support Software

Go to Chapter 9 for complete instructions for customizing your DECwindows support software.

After you complete the tasks described in Chapter 9, return to this chapter to continue with the remaining postupgrade tasks.

8.15 Preparing to Run the OpenVMS Management Station

The OpenVMS Management Station client-server software provides OpenVMS system management capabilities through a client application on a personal computer (PC) running Microsoft Windows.

When you upgraded your OpenVMS system, the OpenVMS Management Station server files were automatically installed on your OpenVMS system disk. However, to obtain *complete* support, you had to select the OpenVMS Management Station client software files during the OpenVMS upgrade procedure. Those files are required for creating the installation media that you use to install the client software on your PC.

Appendix G provides complete instructions for preparing your OpenVMS system and your PC to run the OpenVMS Management Station software.

Note

If you did *not* select the optional OpenVMS Management Station client software files during the installation or upgrade, you must add these files to your OpenVMS system disk before you follow the instructions in Appendix G. Use the OpenVMS Version 7.1 distribution media and VMSTAILOR to add the OpenVMS Management Station files to your system. (For information about using VMSTAILOR, see Chapter 10.)

8.16 Installing Layered Products

Back up your system disk and then use either the VMSINSTAL command procedure or the POLYCENTER Software Installation utility to install layered products on your system.

For additional information about installing layered products, see the *OpenVMS System Manager's Manual*.

8.16.1 TCP/IP Services for OpenVMS

If you installed the Digital TCP/IP Services for OpenVMS software during the installation or if you choose to install it now as a layered product, note that you must also install the mandatory security update kit included with this release.

The Digital TCP/IP Kit and the mandatory Security Update Kit are available in the following directory on the OpenVMS VAX CD-ROM:

[TCPIP_VAX_041]

If you choose to install the Digital TCP/IP Services for OpenVMS software, you must install both kits.

8.17 Backing Up the System Disk

Digital recommends that you protect your work by performing the following operations:

- Use `SYSS$UPDATE:CONSCOPY.COM` to back up the console media (if applicable).
- Make a standalone BACKUP kit on removable media and on the system disk. If your console media is a TU58 tape cartridge or an RX01 diskette, use the standalone BACKUP copy you made before you began the upgrade. (See Section 5.5.2.)
- Back up the system disk.

For complete information about these operations, see the upgrade and installation supplement for your VAX computer.

8.18 Running AUTOGEN

When you upgraded the OpenVMS VAX operating system, the procedure executed AUTOGEN to set the values of system parameters and the sizes of the page and swap files according to the system's workload.

In many cases, AUTOGEN can improve system performance by using dynamic feedback information from the running system. As a postinstallation task, you should run AUTOGEN again using the feedback mechanism to make further adjustments to system parameters.

When AUTOGEN runs after an upgrade, it uses the parameter values in `SYSS$SYSTEM:MODPARAMS.DAT`. Note that hardcoded values in `MODPARAMS.DAT` affect AUTOGEN's calculations of the feedback parameters. For AUTOGEN to properly calculate minimum values, you should replace the hardcoded values in `MODPARAMS.DAT` with `MIN_` values. The `MIN_` prefix specifies the minimum value to which a parameter can be set by AUTOGEN.

If you are not satisfied with the parameter settings calculated by AUTOGEN, you can modify the parameter values by editing `MODPARAMS.DAT` as explained in the *OpenVMS System Manager's Manual: Tuning, Monitoring, and Complex Systems*.

After you have upgraded the operating system, run AUTOGEN again using the following procedure:

1. After 24 hours of operation, run AUTOGEN in feedback mode and reboot the system.
2. Run AUTOGEN in this same way, again, two working days later.

Note

For the VAX 9000 computer, AUTOGEN's initial parameter calculations are conservative. To obtain parameter values that match your system workload, you can run AUTOGEN in feedback mode a number of times. For more information, see the upgrade and installation supplement for your VAX 9000 computer.

After Upgrading OpenVMS VAX

8.18 Running AUTOGEN

3. Digital recommends that you run AUTOGEN from SAVPARAMS through TESTFILES on a weekly basis and examine AGEN\$PARAMS.REPORT to determine the need for additional changes.

For information about using AUTOGEN, see the *OpenVMS System Manager's Manual: Tuning, Monitoring, and Complex Systems*.

8.19 Postupgrade Checklist

Use the following checklist to make sure you perform all the necessary postupgrade tasks.

- Verify the system time. (Described in Section 8.1.)
- Restore the preferred node list for the queue manager. (Described in Section 8.2.)
- Replace SYSUAF.DAT and VMS\$AUDIT_SERVER.DAT. (Described in Section 8.3.)
- Examine AUTOGEN output stored in the file AGEN\$PARAMS.REPORT. (Described in Section 8.4.)
- Examine the command procedure templates supplied with OpenVMS VAX Version 7.1. (Described in Section 8.6.)
- Examine MODPARAMS.DAT? (Described in Section 8.7.)
- Update your console media. (Described in Section 8.8.)
- Decompress the system libraries using LIBDECOMP.COM. (Described in Section 8.10.)
- Run UETP (the user environment test package) to test the system. (Described in *OpenVMS System Manager's Manual: Tuning, Monitoring, and Complex Systems*.)
- Remove unwanted files and check the sizes of system files. (Described in Section 8.12.)
- Restore your local additions to the system password dictionary. (Described in Section 8.13.)
- Customize your DECwindows environment. (Described in Section 8.14.)
- Build a standalone BACKUP kit. (Described in Section 8.17.)
- Back up the console media. (Described in Section 8.17.)
- Install layered products.
- Back up the system disk. (Described in the upgrade and installation supplement for your computer.)
- Run AUTOGEN and reboot the system after the first 24 hours of operation. (Described in Section 8.18.)

Customizing DECwindows Support Software

9.1 Overview

This chapter describes how you can customize DECwindows support software. The DECwindows components provided on the OpenVMS VAX kit supply DECwindows base support and workstation support files only. If you have not installed either of these DECwindows components on your system, skip this chapter.

Depending on your configuration, DECwindows customization tasks include the following:

- Customizing the server startup
- Using the Transmission Control Protocol/Internet Protocol (TCP/IP) as a DECwindows transport
- Using transports with DECwindows other than those supplied by Digital

Note that the OpenVMS VAX operating system no longer includes the VMS DECwindows product. To get full DECwindows support, you must also install the separate DECwindows Motif for OpenVMS VAX layered product, which supports both the Motif and XUI environments.

9.2 Customizing the Server Startup

By default, the DECwindows server no longer logs successful connect/disconnect messages to the `DECW$SERVER_#_ERROR.LOG` file. To enable these messages, define the symbol `DECW$SERVER_CONNECT_LOG` in the `DECW$PRIVATE_SERVER_SETUP.COM` file to be "T" and restart the server. Note that abnormal or unsuccessful connect/disconnect messages are still logged by the server.

9.2.1 Assumptions

The startup command procedures automatically determine most of the configuration variables for the DECwindows display server. However, there are items that the command procedures cannot determine, so they make the following assumptions:

- The startup procedures normally assume that you have a 75 dots/inch monitor (such as a VR260 or VR290). However, if you are installing on a VAXstation 4000, the startup procedures assume that you have a 100 dots/inch monitor.
- If you have a GPX, SPX, or LCG workstation, the startup procedures assume that you have a color monitor.
- The startup procedures normally assume that you have a North American keyboard layout (you have an LK201-AA or an LK201-LA keyboard). If you are installing on a VAXstation 4000, the startup procedures assume that you have an LK401-AA keyboard.

Customizing DECwindows Support Software

9.2 Customizing the Server Startup

- The startup procedures assume that the server will use only DECnet software and local transports.

9.2.2 How to Override Incorrect Assumptions

If any of these assumptions is incorrect, you must override them as follows:

1. Make a copy of the file SYSSMANAGER:DECW\$PRIVATE_SERVER_SETUP.TEMPLATE and rename it to a .COM file type. The comments in this file show how to customize individual workstations by adding a section of DCL commands for each workstation. You can also add DCL commands to the common section of the server startup file. By doing this, you ensure that the customizations you make affect all workstations that use the server startup file.

2. If your screen supports 100 dots/inch, add the following line:

```
$ DECW$SERVER_DENSITY == "100"
```

Add this line to the section for each workstation that has a 100 dots/inch monitor, or add it to the common section for all workstations (if all the workstations have 100 dots/inch monitors).

3. If you have upgraded to a VAXstation 4000 but still have a 75 dots/inch monitor, add the following line:

```
$ DECW$SERVER_DENSITY == "75"
```

4. The section for any workstation with color graphics and a monochrome screen should contain the following lines:

```
$ DECW$COLOR == "FALSE"  
$ DECW$BITONAL == "FALSE"
```

5. To override the default keyboard layout, determine the correct name from the model number of your LK201 keyboard, as follows:

- a. Turn the keyboard upside down, and look for a label that specifies the model number. The model number should be in a format similar to LK201-xx.

If the model number is listed as LK201 without any additional characters, the information you need is on another part of the label. Look for a number that has the following format:

```
nn-nnnnn-xx.
```

- b. Use the xx part of this number to choose a keymap name from Table 9-1. The table is arranged based on the dialect that each keyboard is designed for. Choose the keymap ending in _DP for the data processing keyboard layout, or the keymap ending in _TW for the typewriter layout.

Customizing DECwindows Support Software 9.2 Customizing the Server Startup

Table 9–1 DECwindows Keymap

Dialect	Model	DECwindows Keymap Name
Austrian/German	LK201-(AG,LG,BG,MG)	AUSTRIAN_GERMAN_LK201LG_DP
		AUSTRIAN_GERMAN_LK201LG_TW
	LK201-(NG,PG)	AUSTRIAN_GERMAN_LK201NG_DP
AUSTRIAN_GERMAN_LK201NG_TW		
Belgian/French	LK401-(AG)	AUSTRIAN_GERMAN_LK401AG_TW
		LK201-(AP,LP,BP,MP)
Belgian/French	LK401-(AP)	BELGIAN_FRENCH_LK201LP_TW
		BELGIAN_FRENCH_LK401AP_DP
British	LK201-(AE,LE,BE,ME)	BELGIAN_FRENCH_LK401AP_TW
		BRITISH_LK201LE_DP
British	LK401-(AA,PA)	BRITISH_LK201LE_TW
		BRITISH_LK401AA_DP
Canadian/French	LK201-(AC,LC,BC,MC)	BRITISH_LK401AA_TW
		CANADIAN_FRENCH_LK201LC_DP
Canadian/French	LK401-(AC,LC,BC,MC)	CANADIAN_FRENCH_LK201LC_TW
		CANADIAN_FRENCH_LK401AC_DP
Czech	LK201-(ED,RD,FD)	CANADIAN_FRENCH_LK401AC_TW
		CZECH_LK401AV
Danish	LK401-(AD,LD,BD,MD)	DANISH_LK401AV
		DANISH_LK201LD_DP
Danish	LK201-(ED,RD,FD)	DANISH_LK201LD_TW
		DANISH_LK201RD_DP
Danish	LK401-(AD,LD,BD,MD)	DANISH_LK201RD_TW
		DANISH_LK401AD_DP
Dutch	LK201-(AH,LH,BH,MH)	DANISH_LK401AD_TW
		DUTCH_LK201LH_DP
Finnish	LK201-(NH,PH)	DUTCH_LK201LH_TW
		DUTCH_LK201NH
Finnish	LK401-(NH,PH)	DUTCH_LK401AH
		FINNISH_LK201LF_DP
Finnish	LK201-(AF,LF,BF,MF)	FINNISH_LK201LF_TW
		FINNISH_LK201NX_DP
Finnish	LK401-(AF,LF,BF,MF)	FINNISH_LK201NX_TW
		FINNISH_LK401AF_DP
Flemish	LK201-(AB,LB,BB,MB)	FINNISH_LK401AF_TW
		FLEMISH_LK201LB_DP
Flemish	LK401-(AB,LB,BB,MB)	FLEMISH_LK201LB_TW
		FLEMISH_LK401AB_DP
		FLEMISH_LK401AB_TW

(continued on next page)

Customizing DECwindows Support Software

9.2 Customizing the Server Startup

Table 9–1 (Cont.) DECwindows Keymap

Dialect	Model	DECwindows Keymap Name
Hungarian	LK401-(BQ)	HUNGARIAN_LK401_BQ
Icelandic	LK201-(AU,LU,BU,MU)	ICELANDIC_LK201LU_DP
		ICELANDIC_LK201LU_TW
Italian	LK201-(AI,LI,BI,MI)	ITALIAN_LK201LI_DP
		ITALIAN_LK201LI_TW
Italian	LK401-(AI,LI,BI,MI)	ITALIAN_LK401AI_DP
		ITALIAN_LK401AI_TW
North American	LK201-(AA,LA,BA,MA)	NORTH_AMERICAN_LK201LA
North American	LK401-(AA,LA,BA,MA)	NORTH_AMERICAN_LK401AA
Norwegian	LK201-(AN,LN,BN,MN)	NORWEGIAN_LK201LN_DP
		NORWEGIAN_LK201LN_TW
		NORWEGIAN_LK201RN_DP
		NORWEGIAN_LK201RN_TW
Norwegian	LK401-(AN,LN,BN,MN)	NORWEGIAN_LK401AN_DP
		NORWEGIAN_LK401AN_TW
Polish	LK401-(BP)	POLISH_LK401_BP
Portuguese	LK201-(AV,LV,BV,MV)	PORTUGUESE_LK201LV
Portuguese	LK401-(AV,LV,BV,MV)	PORTUGUESE_LK401AV
Russian	LK401-(BT)	RUSSIAN_LK401_BT
Slovakian	LK401-(CZ)	SLOVAK_LK401_CZ
Spanish	LK201-(AS,LS,BS,MS)	SPANISH_LK201LS_DP
		SPANISH_LK201LS_TW
Spanish	LK401-(AS,LS,BS,MS)	SPANISH_LK401AS_DP
		SPANISH_LK401AS_TW
Swedish	LK201-(AM,LM,BM,MM)	SWEDISH_LK201LM_DP
		SWEDISH_LK201LM_TW
		SWEDISH_LK201NM_DP
		SWEDISH_LK201NM_TW
Swedish	LK401-(AM,LM,BM,MM)	SWEDISH_LK401AM_DP
		SWEDISH_LK401AM_TW
Swiss/French	LK201-(AK,LK,BK,MK)	SWISS_FRENCH_LK201LK_DP
		SWISS_FRENCH_LK201LK_TW
Swiss/French	LK401-(AK,LK,BK,MK)	SWISS_FRENCH_LK401AK_DP
		SWISS_FRENCH_LK401AK_TW
Swiss/German	LK201-(AL,LL,BL,ML)	SWISS_GERMAN_LK201LL_DP
		SWISS_GERMAN_LK201LL_TW
Swiss/German	LK401-(AL,LL,BL,ML)	SWISS_GERMAN_LK401AL_DP
		SWISS_GERMAN_LK401AL_TW

(continued on next page)

Table 9–1 (Cont.) DECwindows Keymap

Dialect	Model	DECwindows Keymap Name
Combined US/UK	LK201-(EE,RE,PE)	UK_LK201RE
		US_LK201RE
Combined US/UK	LK401-(EE,RE,PE)	UK_LK401AA
		US_LK401AA

- c. After you choose a keymap name, modify the server startup file. For example, to change the keyboard layout to a Dutch typewriter layout, add the following line to the server startup file:

```
$ DECW$DEFAULT_KEYBOARD_MAP == "DUTCH_LK201LH_TW"
```

Add a line similar to this for each workstation that does not have a North American keyboard layout, or add it to the common section for all workstations (if all the workstations use the same keyboard layout).

6. To add support for the Transmission Control Protocol/Internet Protocol (TCP/IP) transport using the DEC TCP/IP Services for OpenVMS product, add the following line:

```
$ DECW$SERVER_TRANSPORTS == "DECNET,LOCAL,TCPIP"
```

Add this line to the section for each workstation that will be using TCP/IP, or add it to the common section for all workstations.

To include support for other transports, add the last part of the transport image name to the list of transports. For example, suppose you want to add support for a customer-written transport that has the following image name:

```
SYSSSHARE:DECW_TRANSPORT_FOO
```

You would add the following line:

```
$ DECW$SERVER_TRANSPORTS == "DECNET,LOCAL,FOO"
```

7. Reboot the workstations for which you customized the server startup.
8. Customize security as described in the *Using DECwindows Motif for OpenVMS* manual.

After you start the server, a per-server logical name table is created on your system but is not added to the default logical name table search lists.

9.3 Using Digital TCP/IP Services for OpenVMS

DECwindows contains support for the TCP/IP transport. This support requires Digital TCP/IP Services for OpenVMS, a Digital layered product. Before you can use the DECwindows TCP/IP transport interface, you must install Digital TCP/IP Services for OpenVMS.

Note

Other vendors' implementation of TCP/IP transports use different call interfaces. For this reason, DECwindows support for TCP/IP is compatible only with Digital TCP/IP Services for OpenVMS.

Customizing DECwindows Support Software

9.3 Using Digital TCP/IP Services for OpenVMS

You can conserve memory and process slots by configuring Digital TCP/IP Services for OpenVMS software for the minimum DECwindows requirement to support the X protocol. DECwindows only requires that INET_ACP be running. DECwindows does not require that the NFS server, the FTPD server, or the remote terminal servers be running.

For more information about TCP/IP concepts, see the *Digital TCP/IP Services for OpenVMS: Management* manual.

For information on how to configure the TCP/IP software, see the *Digital TCP/IP Services for OpenVMS: Installation and Basic Configuration* manual.

9.4 Using Other Transports with DECwindows

DECwindows supports DECnet-Plus, local, and TCP/IP transports. However, you can use other transports, such as new transports for layered products and transports from third-party vendors, with DECwindows by writing a DECwindows transport interface layer.

9.4.1 Writing a Transport Interface

For information about writing a transport interface, see the *VMS DECwindows Transport Manual*.

The transport interface image's filename must have the following format where *name* is the unique transport name:

DECW\$TRANSPORT_name (for transports supplied by Digital)
DECW_TRANSPORT_name (for customer-written transports)

9.4.2 Installing the Transport Interface Image

Install the image as a protected image in the SYSS\$SHARE directory (as defined by an executive mode logical name). Digital recommends that you install the image by adding the following line to SYSS\$MANAGER:SYSTARTUP_VMS.COM:

```
$ INSTALL CREATE SYSS$SHARE:DECW_TRANSPORT_name/OPEN/SHARED-  
/HEADER_RESIDENT/PROTECTED
```

You can also include this command in a startup file that SYSTARTUP_VMS calls.

To use this transport with the DECwindows server, customize the server startup as described in Section 9.2.

9.5 Using the Example Transport

DECwindows has an example transport interface based upon the Digital TCP/IP Services for OpenVMS layered product. It is similar to the DECwindows TCP/IP transport interface, except it includes its own source files and it uses a different port number (5000). You can run the example transport interface simultaneously with the TCP/IP transport interface.

If you have installed Digital TCP/IP Services for OpenVMS software, you can install and use the example transport by doing the following:

1. Copy the example transport to the SYSS\$SHARE directory as follows:

```
$ COPY DECW$EXAMPLES:DECW$TRANSPORT_EXAMPLE.EXE SYSS$SHARE:/PROT=W:RE
```

2. Add the following line to SYSS\$MANAGER:SYSTARTUP_VMS.COM:

```
$ INSTALL CREATE SYSS$SHARE:DECW$TRANSPORT_EXAMPLE /OPEN /SHARED-  
/HEADER_RESIDENT /PROTECTED
```


Customizing DECwindows Support Software

9.5 Using the Example Transport

3. Customize the private server startup as described in Section 9.2 for TCP/IP, except use the transport name "EXAMPLE". For example, you could add the following line:

```
$ DECW$SERVER_TRANSPORTS == "DECNET,LOCAL,TCPIP,EXAMPLE"
```

4. Reboot the workstation, or restart DECwindows.
5. Customize TCP/IP security as described in the *Using DECwindows Motif for OpenVMS* manual, but use the transport name "EXAMPLE" instead of "TCPIP".
6. Create a DECterm window on the workstation and enter the following command:

```
$ SET DISPLAY /CREATE /NODE=your_node /TRANSPORT=EXAMPLE
```

Substitute the node name of your workstation for *your_node*.

Remember that the same transport must be running on both the client and server. It is not necessary, however, for the client and the server to be on the same system.

7. Run any DECwindows application from the DECterm window. It will now use the example transport to display graphics on your workstation screen. For example, you would enter the following command to run the clock:

```
$ RUN SYS$SYSTEM:DECW$CLOCK
```

Using VMSTAILOR and DECW\$TAILOR

This chapter describes how to add or remove optional OpenVMS VAX files and DECwindows support files from your system disk using VMSTAILOR and DECW\$TAILOR. You will need your OpenVMS VAX software media kit to tailor on files. Any site-specific customization that has been done to a class will be lost when that class is tailored off.

10.1 Using VMSTAILOR

To add or remove unwanted OpenVMS VAX files from the system disk, use VMSTAILOR. For example, if you are not running DECnet for OpenVMS, and you do not need the network support files, you can remove those files using VMSTAILOR. If you later decide you want to run DECnet for OpenVMS, you can add the necessary files at any time using VMSTAILOR and your OpenVMS VAX distribution media. (Note that you cannot tailor files on or off an alternate device.)

10.1.1 How VMSTAILOR Works

VMSTAILOR has three phases:

1. VMSTAILOR asks if you want to tailor your system by adding files (tailor on) or by deleting files (tailor off).
2. If you choose to tailor files on, VMSTAILOR lists each class of OpenVMS VAX files and asks if you want to include them on the system disk. If you choose to tailor files off, VMSTAILOR lists each class of files and asks if you want to delete them from the system disk.
3. VMSTAILOR adds or deletes the files you indicated from the system disk. If you are tailoring files on, you must load your OpenVMS VAX distribution media in a drive available to the system. If your distribution media consists of more than one piece, put the first piece of the media into the drive.

The following is a list of classes and subclasses of OpenVMS VAX files that can be added or deleted by using VMSTAILOR. For a complete list of OpenVMS VAX files and their functions, see the *OpenVMS System Manager's Manual: Tuning, Monitoring, and Complex Systems*.

- Network Support
 - Incoming Remote File Access files
 - Incoming Remote Terminal files
 - Network Test files
 - Remote Task Loading
- Programming Support
 - Debugger utility (DEBUG)
 - Image Dump utility (ANALYZE/PROCESS_DUMP)
 - RMS Analyze and FDL Editor utilities (ANALYZE/RMS, ANALYZE/FDL)

Using VMSTAILOR and DECW\$TAILOR

10.1 Using VMSTAILOR

- Message utility (MESSAGE)
- Object and Shareable Image libraries
- MACRO libraries
- MACRO assembler
- SDL intermediary form of STARLET.MLB
- Fortran required files
- VAX C object libraries

- OpenVMS RMS Journaling Files
- System Programming Support
 - Files-11 ODS-1, ISO 9660, High Sierra ACPs
 - Monitor utility
 - Delta/XDelta debugger
 - System Dump Analyzer utility (ANALYZE/SYSTEM, ANALYZE/CRASH)
 - System Symbol Table file (SYS.STB)
 - Miscellaneous Symbol Table files
- Secure User's Environment
 - File Access Control List utilities
 - Print and Batch Queue utilities
 - Input Queue Symbiont (Card Reader)
 - Accounting Log Report Generator utility
 - DECdtm
- Utilities
 - Mail utility
 - DUMP utility
 - RUNOFF utility
 - Phone utility
 - OpenVMS Help library
 - OpenVMS System Messages Help Library
 - Foreign Terminal Support
 - LAT-11 terminal server (via Ethernet)
 - Standalone BACKUP
 - Error Log Report Generator utility (ANALYZE/ERROR)
 - DECTPU utility
 - Terminal Fallback facility
 - TECO editor
 - EDT documentation
 - National Character Set utility (NCS)
- VMS Workstation Support (VWS)
 - Workstation device support
- BLISS require files
- Miscellaneous Files
 - System map
 - LPA-11 support
- User Environment Test Package
- Example Files

10.1.2 Removing OpenVMS VAX Files

To remove unwanted files using VMSTAILOR, perform the following steps:

1. Log in to the SYSTEM account.
2. Enter the following command and press the Return key:

```
$ RUN SYS$UPDATE:VMSTAILOR
```

VMSTAILOR displays a description of the VMSTAILOR program and displays the following message:

```
Do you want to tailor files "ON" or "OFF"?
```

3. Enter OFF to remove unwanted files and press the Return key.

The VMSTAILOR program lists each group, or *class*, of files and its size in blocks. Files are grouped according to their function. For example, all the files required for network support are in one class. A file class is made up of many smaller groups called *subclasses*. You can eliminate an entire class of files, or you can eliminate one or more of its subclasses. For example:

```
CLASS - Network support
      Size of entire class (with subclasses): 1499
      Size of common files required for any subclass: 1249
      Do you wish to select the entire class (default = NO)?
      .
      .
      .
```

4. Decide which file classes or subclasses you do not need to support your system. The VMSTAILOR program displays step-by-step instructions. Follow these instructions to specify which classes or subclasses of files you want to remove.
5. VMSTAILOR deletes the files you selected and displays the names of those files. After it finishes, AUTOGEN runs automatically to make the adjustments that are necessary after system files are deleted. AUTOGEN also reboots the system.

Caution

To cancel VMSTAILOR during the first and second phases, press Ctrl/C, Ctrl/Y, or Ctrl/Z. Canceling VMSTAILOR during the third phase can cause a partially tailored disk.

For a description of each phase, see Section 10.1.1.

10.1.3 Adding OpenVMS VAX Files

To add optional OpenVMS VAX files that you previously removed, or that you chose not to install during the OpenVMS VAX installation procedure, do the following:

1. Log in to the SYSTEM account.
2. Load your distribution media in a drive available to the system. For example, if your distribution media is on a TK50 tape cartridge, load the first tape cartridge in a TK50 drive that is available to the system. Make sure the drive is on line and ready.

Using VMSTAILOR and DECW\$TAILOR

10.1 Using VMSTAILOR

If you are adding files from a compact disc on an InfoServer, first determine whether the SYSGEN parameter SCSNODE is defined on your system (see Section 5.6) or start the DECnet software, and then refer to step 2 of Section 7.3.

3. Enter the following command and press the Return key:

```
$ RUN SYS$UPDATE:VMSTAILOR
```

VMSTAILOR displays a description of the VMSTAILOR program and displays the following message:

```
Do you want to tailor files "ON" or "OFF"?
```

4. Enter ON to add files and press the Return key.

The VMSTAILOR program lists each group, or *class*, of files and its size in blocks. Files are grouped according to their function. For example, all the files required for network support are in one class. A file class is made up of many smaller groups called *subclasses*. You can add an entire class of files, or you can add one or more of its subclasses. For example:

```
CLASS - Network support
      Size of entire class (with subclasses): 1499
      Size of common files required for any subclass: 1249
      Do you wish to select the entire class (default = NO)?
.
.
.
```

5. Decide which file classes or subclasses you need to add. VMSTAILOR displays step-by-step instructions. Follow these instructions to specify which classes or subclasses of files you want to add.
6. VMSTAILOR adds the files you specified and displays the names of the files. After the files have been added, AUTOGEN runs automatically to make the adjustments that are necessary after system files are added. AUTOGEN also reboots the system.

Caution

To cancel VMSTAILOR during the first and second phases, press Ctrl/C, Ctrl/Y, or Ctrl/Z. Canceling VMSTAILOR during the third phase can cause a partially tailored disk.

For a description of each phase, see Section 10.1.1.

After adding files to the system disk, apply any updates that affect them. OpenVMS VAX update procedures create a .TXT file that contains a description of patched files. This file usually has the following format: SYS\$UPDATE:VMSUn06n.TXT.

For example, suppose you do not need the OpenVMS Phone utility (PHONE) and you run VMSTAILOR to remove those files. Later, you decide you want to use Phone. Run VMSTAILOR to return the Phone files to the system disk; then, apply any OpenVMS VAX update that has occurred since Version 7.1 that affected the Phone utility.

10.1.4 Sample Session

Example 10-1 shows how to add all Network Support files and selected Programming Support files to a system disk.

Example 10-1 Sample VMSTAILOR Session

```
$ RUN SYS$UPDATE:VMSTAILOR
.
.
.
Do you want to tailor files "ON" or "OFF"? ON
TAILOR-ON
-----
You will now be prompted with a list of the classes and subclasses
of OpenVMS VAX files that are optional. The size of each class and subclass is included
in the list. This will help you decide whether or not you want to add
a class or subclass to your system.

Under some classes, there is a set of common files that is required in order
for any subclasses to work. These files are added when you ask
for either the entire class or any of its subclasses.

Total size of the system disk is 2376153 blocks.
Total space used on the system disk is 2241252 blocks.
Total space left on the system disk is 134901 blocks.

CLASS - Network support
      Size of entire class (with subclasses): 1499
      Size of common files required for any subclass: 1249
      Do you wish to select the entire class (default = NO)? YES

CLASS - Programming Support
      Size of entire class (with subclasses): 14706
      Size of common files required for any subclass: 0
      Do you wish to select the entire class (default = NO)?
      Do you wish to select any of its subclasses (default = NO)? )YES
      Select the subclasses that you wish to provide:
      SUBCLASS - Debugger utility (DEBUG) (4690 blocks) [NO]: YES
      SUBCLASS - Image Dump utility (ANALYZE/PROCESS_DUMP) (48 blocks) [NO]: YES
      SUBCLASS - RMS Analyze and FDL Editor utilities (ANALYZE/RMS, ANALYZE/FDL) -
      (374 blocks) [NO]:YES
      SUBCLASS - Message utility (MESSAGE) (49 blocks) [NO]:
      SUBCLASS - Object and Shareable Image libraries (4311 blocks) [NO]: YES
      SUBCLASS - Macro libraries (2293 blocks) [NO]:
      SUBCLASS - Macro assembler (457 blocks) [NO]:
      SUBCLASS - SDL intermediary form of STARLET.MLB (1957 blocks) [NO]:
      SUBCLASS - FORTRAN require files (51 blocks) [NO]:
      SUBCLASS - VAX-C object libraries (471 blocks) [NO]:

CLASS - RMS journaling files
      Size of entire class (with subclasses): 155
      No subclasses in this tailor class.
      Do you wish to select the entire class (default = NO)?

CLASS - System programming Support
      Size of entire class (with subclasses): 2286
      Size of common files required for any subclass: 93
      Do you wish to select the entire class (default = NO)?
      Do you wish to select any of its subclasses (default = NO)?
```

(continued on next page)

Using VMSTAILOR and DECW\$TAILOR

10.1 Using VMSTAILOR

Example 10–1 (Cont.) Sample VMSTAILOR Session

```
CLASS - Secure User's Environment
  Size of entire class (with subclasses): 919
  Size of common files required for any subclass: 0
  Do you wish to select the entire class (default = NO)?

  Do you wish to select any of its subclasses (default = NO)?

.
.
.
Files have been selected
Do you wish to add all of the options selected? YES
Creating temporary command file, please wait...
* Enter device containing OpenVMS distribution media: mua0:

.
.
.
```

10.2 Using DECW\$TAILOR

You can use DECW\$TAILOR to add or remove some or all DECwindows X11 display server, base support, and fonts files from the system disk. For example, if you are not planning to use the DECwindows PEX (PHIGS Extensions to X) support, you can remove those files. Later, if you decide you want DECwindows programming support, you can add the files to the system disk using DECW\$TAILOR and your DECwindows distribution media. You cannot tailor files on or off an alternate device.

Note

To add or remove VMS DECwindows Motif files, refer to the *DECwindows Motif Version 1.2–3 for OpenVMS Installation Guide*. DECW\$TAILOR will only tailor on or off those DECwindows display server, base support, and font files, with the exception of the required files, supplied on the OpenVMS VAX kit.

10.2.1 How DECW\$TAILOR Works

DECW\$TAILOR has three phases:

- DECW\$TAILOR asks if you want to tailor your system by adding files (tailor on) or by deleting files (tailor off).
- If you choose to tailor files on, DECW\$TAILOR lists each class of DECwindows files and asks if you want to include them on the system disk. If you choose to tailor files off, DECW\$TAILOR lists each class of DECwindows files and asks if you want to delete them from the system disk.
- DECW\$TAILOR adds or deletes the files you indicated from the system disk. If you are tailoring files on, you must load your DECwindows distribution media in a drive that is available to the system. For example, if your OpenVMS VAX distribution kit is on a TK50 tape cartridge, load the second tape cartridge, which contains the DECwindows support files, into a TK50 drive that is available to the system.

10.2.2 DECwindows Files You Can Tailor

The following is a list of classes and subclasses of DECwindows files that you can add or delete using DECW\$TAILOR. For a list of DECwindows files and their functions, see Appendix E.

- DECwindows base support files—If you plan to install the separate DECwindows Motif for OpenVMS VAX layered product, you must add the base support files.
- DECwindows workstation support files—If you are installing DECwindows support on a workstation or in a cluster that includes workstations or if you intend to install the DECwindows Motif for OpenVMS VAX layered product, you need the workstation support files. Otherwise, you do not need them.

Note

If you tailor device support files ON or OFF, the system reboots.

- 100 dots/inch video font files—By default, some workstation monitors (for example, a VR150, VR160, or VR295) display 100 dots/inch, which gives you a more readable display when you run DECwindows applications. If your workstation monitor cannot display 100 dots/inch fonts (for example, a VR260 or VR290), you can save disk space by not selecting this option. For more information about the capabilities of your particular monitor, see the owner's guide for your monitor.
- 75 dots/inch video font files—If your workstation monitor cannot display 75 dots/inch, you can save disk space by not selecting this option. For more information about the capabilities of your particular monitor, see the owner's guide for your monitor.

10.2.3 Removing DECwindows Files

To remove DECwindows files from the system disk, do the following:

1. Log in to the SYSTEM account.
2. Type the following command, and press Return:

```
$ RUN SYS$UPDATE:DECW$TAILOR
```

DECW\$TAILOR displays information about the DECW\$TAILOR program and displays the following message:

```
Do you want to tailor files "ON" or "OFF"?
```

3. Type OFF to remove unwanted files, and press Return.

The DECW\$TAILOR program lists each group, or *class*, of files and its size in blocks. Files are grouped according to their function. For example, all the files required for DECwindows device support are in one class. A file class is made up of many small subclasses. You can eliminate an entire class of files, or you can eliminate one or more of its subclasses. For example:

```
CLASS - DECwindows workstation support files
      Size of entire class (with subclasses): 14301
      Size of common files required for any subclass: 8937
      Do you wish to select the entire class (default = NO)?
      .
      .
      .
```

Using VMSTAILOR and DECW\$TAILOR

10.2 Using DECW\$TAILOR

4. Decide which file classes or subclasses you need to add. DECW\$TAILOR displays step-by-step instructions. Follow these instructions to specify which of the classes or subclasses you want to remove.
5. DECW\$TAILOR deletes the files you selected and displays the names of those files. If you deleted device support files, the system automatically shuts down and reboots.

Caution

To cancel DECW\$TAILOR during the first and second phases, press Ctrl/C, Ctrl/Y, or Ctrl/Z. Canceling DECW\$TAILOR during the third phase can cause a partially tailored disk.

For a description of each phase, see Section 10.2.1.

10.2.4 Adding DECwindows Files

To install DECwindows device support and font files after the OpenVMS VAX installation or to add optional DECwindows files that you previously chose not to install or that you removed, do the following:

1. Log in to the SYSTEM account.
2. Load the OpenVMS VAX distribution media containing the DECwindows save sets in a drive available to your system. For example, if your distribution media is a TK50 tape cartridge, load the second tape cartridge into a TK50 drive that is available to the system. Make sure the drive is on line and ready.

If you are adding files from a compact disc on an InfoServer, first determine whether the SYSGEN parameter SCSNODE is defined on your system (see Section 5.6) or start the DECnet software, and then refer to step 2 of Section 7.3 in Chapter 7.

3. Enter the following command, and press Return:

```
$ RUN SYS$UPDATE:DECW$TAILOR
```

DECW\$TAILOR displays information about the DECW\$TAILOR program, and displays the following message:

```
Do you want to tailor files "ON" or "OFF"?
```

4. Type ON to add files, and press Return.

The DECW\$TAILOR program lists each group, or *class*, of files and its size in blocks. Files are grouped according to their function. For example, all the files required for DECwindows device support are in one class. A file class is made up of many small subclasses. You can add an entire class of files, or you can add one or more of its subclasses. For example:

```
CLASS - DECwindows workstation support files
      Size of entire class (with subclasses): 14301
      Size of common files required for any subclasses: 8937
      Do you wish to select the entire class (default = NO)?
      .
      .
      .
```

5. Decide which file classes or subclasses you do not need to support your system. The DECW\$TAILOR program displays step-by-step instructions. Follow these instructions to specify which of the classes or subclasses you want to add.
6. DECW\$TAILOR installs the files you selected and displays the names of those files. If you added device support files, the system automatically shuts down and reboots.

Caution

To cancel DECW\$TAILOR during the first and second phases, press Ctrl/C, Ctrl/Y, or Ctrl/Z. Canceling DECW\$TAILOR during the third phase can cause a partially tailored disk. For a description of each phase, see Section 10.2.1.

After adding files to the system disk, apply any updates that affect them. For example, suppose you delete the Version 7.1 DECwindows 100 dots/inch video font files. Later on, you are able to use the 100 dots/inch fonts, so you run DECW\$TAILOR to return the files to the system disk. You must then apply any OpenVMS VAX update that has occurred since Version 7.1 that affected the 100 dots/inch video font files. OpenVMS VAX update procedures create a .TXT file that contains a description of modified files. This file is usually named with the following format: SYSS\$UPDATE:VMSUn05n.TXT¹.

10.2.5 Sample Session

Example 10–2 illustrates how to add the files for DECwindows 100 dots/inch font files.

Example 10–2 Sample DECW\$TAILOR Session

```
$ RUN SYS$UPDATE:DECW$TAILOR
.
.
.
Do you want to tailor files "ON" or "OFF"? ON
TAILOR-ON
-----
You will now be prompted with a list of the classes and subclasses
of DECwindows files that are optional. The size of each class and subclass is
included in the list. This will help you decide whether or not you want to add
a class or subclass to your system.

Under some classes, there is a set of common files that is required in order
for any subclasses to work. These files are added when you ask
for either the entire class or any of its subclasses.

Total size of the system disk is 2376153 blocks.
Total space used on the system disk is 1728072 blocks.
Total space left on the system disk is 648081 blocks.

CLASS - DECwindows base support files
      Size of entire class (with subclasses): 3363
```

(continued on next page)

¹ Examine this file to determine if the update patched the 100 dots/inch font files

Using VMSTAILOR and DECW\$TAILOR

10.2 Using DECW\$TAILOR

Example 10–2 (Cont.) Sample DECW\$TAILOR Session

```
No subclasses in this tailor class.
Do you wish to select the entire class (default = NO)?

CLASS - DECwindows workstation support files
  Size of entire class (with subclasses): 12376
  Size of common files required for any subclass: 8916
  Do you wish to select the entire class (default = NO)? NO
  Do you wish to select any of its subclasses (default = NO)?

CLASS - 75 dots per inch video font files
  Size of entire class (with subclasses): 4537

  No subclasses in this tailor class.
  Do you wish to select the entire class (default = NO)?

CLASS - 100 dots per inch video font files
  Size of entire class (with subclasses): 3693
  No subclasses in this tailor class.
  Do you wish to select the entire class (default = NO)? YES

Files have been selected
Do you wish to add all of the options selected? YES
Creating temporary command file, please wait...
* Enter device containing DECwindows distribution media: MUA0:
.
.
.
```

Multiversion VAX Upgrade Process

This appendix provides you with an express method and easy to follow set of directions to apply multiple OpenVMS VAX version upgrades to your current system.

Note

By following these directions, the time that you spend on upgrading your VAX computer from Version 5.5-2 to Version 7.1 can be significantly reduced.

A.1 Determine Your Path

Your first step is to determine which upgrade path you need to perform Table A-1 lists the recommended upgrade paths to reach OpenVMS VAX Version 7.1.

Table A-1 OpenVMS VAX Upgrade Version Matrix

Current Version	Intermediate Version(s)	Final Version
5.5-2	6.1	7.1
6.0	6.1 or 6.2	7.1
6.1	¹	7.1
6.2	¹	7.1
7.0	¹	7.1

¹No intermediate version needed.

A.2 Multiversion Upgrade Procedure

This procedure refers to an intermediate upgrade and final upgrade. An **intermediate upgrade** is defined as a version of the operating system that you need to install to reach your final version. .

The **final upgrade** is the version of the operating system that you want to be running on your system at the end of this process.

Important

You should not plan to stay at the intermediate version. If you do need to upgrade to and run the intermediate version, please use the normal upgrade procedure located in the specific version installation manual.

Multiversion VAX Upgrade Process

A.2 Multiversion Upgrade Procedure

A.2.1 Before You Begin the Upgrade

Before you begin the multiversion upgrade, you need to perform the following steps:

1. Locate the OpenVMS VAX software kits for the versions that you need.
2. Review the layered products on your system to determine the minimum supported version of each layered product to be installed on your final operating system version.
 - Determine which layered products you want to run on your system. See the web page at the following URL:
<http://www.service.digital.com/openvms>
 - For information about specific layered products, see Section A.3.

A.2.2 Intermediate Upgrade

Follow these steps to perform an intermediate upgrade of your OpenVMS VAX operating system.

1. Review your mixed-cluster version environment. Digital recommends that you upgrade all of your systems to the same version prior to performing a multiversion upgrade.
2. Review the firmware running on your system. For information about specific layered products, see Section A.3.
3. Review the version-specific documentation. Digital recommends that you read the New Features, Release Notes, Installation Guide manuals and Software Product Description available in your software kit.
4. Review the preupgrade checklist located in the Installation Guide.
5. Perform the upgrade.

Important

For the intermediate upgrade, install only the base operating system. Do not install any options. By installing only the base operating system, the time that you spend on upgrading your VAX computer during this intermediate upgrade can be reduced by 40 percent.

6. Perform the postupgrade checklist located in the Installation Guide.
7. If you are performing multiple intermediate upgrades, repeat steps 3-7 as necessary.
8. You have completed the intermediate phase of the multiversion upgrade procedure. Proceed to Section A.2.3 to apply the final upgrade phase of this procedure .

A.2.3 Final Upgrade

Follow these steps to perform the final upgrade of your OpenVMS VAX operating system.

1. Review the version-specific documentation. Digital recommends that you read the New Features, Release Notes, Installation Guide manuals and Software Product Description available in your software kit.
2. Perform the preupgrade checklist located in the Installation Guide.
3. Perform the complete upgrade and select the optional files that you need for your final version.
4. Perform the postupgrade checklist located in the Installation Guide.
5. Upgrade the layered products on your system based on your review of layered products in Section A.2.1. See the web page at the following URL:

<http://www.service.digital.com/openvms>

A.3 Specific Layered Product and Firmware Information

This section provides specific information about the following layered products and firmware:

- BASEstar
- Debugger

A.3.1 Layered Products

This section contains information about layered products.

BASEstar Classic Domain

A BASEstar Classic domain that consists of BASEstar Classic for OpenVMS VAX Versions 3.2 and 3.3 is fully supported on OpenVMS Version 7.1, as long as you have obtained the kits through normal support channels.

However, on Alpha systems you need to be running BASEstar Classic Version 3.4. This means that any BASEstar Classic domain consisting of both VAX and Alpha systems can only have the VAX systems upgraded to OpenVMS Version 7.1 at this time.

Debugger Graphical User Interface (GUI)

In order to run the Debugger Graphical User Interface (GUI) on OpenVMS Version 7.1, you must be running the DECwindows Motif for OpenVMS layered product. See Section 1.2.2 for information about DECwindows Motif.

License Management Notes

B.1 Overview

This appendix contains supplemental information to the license instructions given in the installation and upgrade procedures and in the *OpenVMS License Management Utility Manual*. Although most of the information in this appendix pertains to managing OpenVMS and System Integrated Product (SIP) licenses, some of the information pertains to managing layered product licenses.

This appendix covers the following information:

- Registering your licenses
- Using the License Unit Requirement Table (LURT)
- License Management Facility (LMF) notes
- Volume Shadowing for OpenVMS license
- Other System Integrated Product (SIP) licenses

B.2 Registering Your Licenses

This section provides an overview of the license registration procedure.

B.2.1 When to Register

After you install the OpenVMS VAX operating system, you must register an OpenVMS VAX license. An OpenVMS VAX license lets you use the operating system. You must also register the licenses for any of the following SIPs you have purchased:

- VAXclusters
- DECnet-Plus
- OpenVMS RMS Journaling
- Volume Shadowing for OpenVMS

After you upgrade the OpenVMS VAX operating system, in most cases there is no need to reregister licenses for the operating system or for SIPs.

In addition to the OpenVMS VAX operating system and the SIPs, many layered products—including DECwindows Motif for OpenVMS VAX—that run on OpenVMS VAX Version 7.1 also require license registration. See the *OpenVMS License Management Utility Manual* for a full explanation of license registration.

License Management Notes

B.2 Registering Your Licenses

B.2.2 How to Register

To register a license, you need to obtain a Product Authorization Key (PAK). A typical PAK is a piece of paper provided by Digital Equipment Corporation that contains the appropriate information to authorize access to software on a VAX computer or in a VAXcluster environment. You can obtain a PAK from a Digital representative the same way as you obtain software.

See Table B-1 for a complete list of the versions of the OpenVMS VAX operating system and the VAX computers that were first supported by these versions.

Table B-1 First VMS or OpenVMS Version That Supports VAX Computers

VMS Version	First Computer Support
Version 5.0	VAX 6000 Model 2 _{xx} , VAX 8820-8840
Version 5.0-2A	MicroVAX 3300/3400
Version 5.1	VAX 6000 Model 3 _{xx} , MicroVAX 3800/3900
Version 5.1-B	VAXstation 3100, Model 30/40
Version 5.1-1	VAXstation 3520/3540
Version 5.2	VAX 6000 Model 4 _{xx} , MicroVAX 3100
Version 5.2-1	VAXstation 3100, Model 38/48
Version 5.3	No CPUs introduced
Version 5.3-1	No CPUs introduced
Version 5.3-2	VAX 4000 Model 300
Version 5.4	VAXstation 3100 Model 76, VAX 9000, VAX 6000 Model 5 _{xx} , VAXft 310
Version 5.4-1	No CPUs introduced
Version 5.4-2	VAX 4000 Model 200
Version 5.4-3	VAXft Models 410, 610, 612
Version 5.5	VAXstation 4000 VLC, MicroVAX 3100 Models 30, 40, and 80, VAX 6000 Model 600, VAX 4000 Model 500, VAXstation 4000 Model 60, and VAXft Model 110
Version 5.5-2	VAX 4000 Model 100, VAXstation 4000 Models 90 and 100, MicroVAX 3100 Model 90, VAX 4000 Model 400, VAX 4000 Model 600, VAX 7000 Model 600, and VAX 10000 Model 600
Version 5.5-2H4	VAX 4000 Models 100A, 500A, 600A, and 700A
Version 5.5-2HF	VAXft Model 810
OpenVMS Version	First Computer Support
Version 6.0	VAX 7000 Models 650 and 660, VAX 10000 Models 600 and 650
Version 6.1	VAX 7000 Model 7 _{xx}
Version 6.2	VAX 4000 Model 106A, MicroVAX 3500 Model 95A, MicroVAX 3100 Model 96, VAXstation 4000 Model 96

B.3 Using the License Unit Requirement Table (LURT)

Many PAKs contain a table name in the availability or activity fields. This name refers to a column in the License Unit Requirement Table (LURT). (For more information about using the LURT, see the *OpenVMS License Management Utility Manual*.)

Table B-2 has seven lettered columns (A, B, C, D, E, F, and I; G and H are reserved by Digital and therefore are not listed). The numbers listed in these columns indicate the number of license units required for each processor listed in the System Marketing Model column. For example, if your PAK specifies *availability = F*, you would require 100 license units to load the license on a VAX-11/780 computer, or 4800 license units to load the license on a VAX 9000-430 computer.

Note that some PAKs specify MOD_UNITS in the options field. The MOD_UNITS option allows the system manager to use the DCL command LICENSE MODIFY /UNITS to temporarily increase the size of the PAK. This permits a product to be used, in certain emergency situations, on a processor larger than the processor size specified in the license. Check your license terms and conditions before modifying license units. Reset the PAK size to its original size after the emergency situation is resolved.

Table B-2 License Unit Requirement Table (LURT)

System Marketing Model	License Types by Code						
	OpenVMS				SIP	LP	
	A	B	C	D	E	F	I
VAX-11/730	10	NA	NA	NA	230	50	50
VAX 11/750	12	NA	NA	NA	230	100	100
VAX 11/780, 785	13	NA	NA	NA	230	100	100
VAX 6000-210, 6000-310	58	NA	NA	NA	230	300	300
VAXft 110	60	NA	NA	NA	230	100	100
VAXft 310, 410, 610, 810	58	NA	NA	NA	230	300	300
VAX 6000-220, 6000-320, 6000-410	69	NA	NA	NA	230	600	600
VAX 6000-230, 6000-330, 6000-510	81	NA	NA	NA	400	900	900
VAX 6000-240, 6000-340, 6000-350, 6000-420, 7000-610, 10000-610	93	NA	NA	NA	400	1200	1200

Key to License Type Codes and Values

- A—OpenVMS Capacity or OpenVMS Unlimited or Base
- B—OpenVMS Server
- C—OpenVMS Concurrent user
- D—OpenVMS Workstations
- E—System integrated products
- F—Layered products
- G—Reserved (not listed)
- H—OpenVMS reserved (not listed)
- I—Layered products
- NA—Not applicable

(continued on next page)

License Management Notes

B.3 Using the License Unit Requirement Table (LURT)

Table B-2 (Cont.) License Unit Requirement Table (LURT)

System Marketing Model	License Types by Code						
	OpenVMS				SIP	LP	
	A	B	C	D	E	F	I
VAX 6000-540, 6000-640	170	NA	NA	NA	600	2400	2400
VAX 6000-550, 6000-650	195	NA	NA	NA	600	2400	2400
VAX 6000-560, 6000-660	220	NA	NA	NA	600	2400	2400
VAX 6000-610	81	NA	NA	NA	400	1200	1200
VAX 8200, 8250	20	NA	NA	NA	230	100	100
VAX 8300, 8350	25	NA	NA	NA	230	200	200
VAX 8500	63	NA	NA	NA	230	400	400
VAX 8530	65	NA	NA	NA	230	400	400
VAX 8550, 8700, 8810	72	NA	NA	NA	400	600	600
VAX 8600, 8650	28	NA	NA	NA	230	400	400
VAX 8800, 8820	93	NA	NA	NA	400	1200	1200
VAX 8830, 6000-360, 6000-430, 6000-520, 6000-620	119	NA	NA	NA	600	1800	1800
VAX 7000-620, 10000-620	145	NA	NA	NA	600	1800	1800
VAX 6000-440, 6000-450, 6000-460, 6000-530	143	NA	NA	NA	600	2400	2400
VAX 7000-630, 10000-630,	167	NA	NA	NA	600	2400	2400
VAX 7000-640, 10000-640,	197	NA	NA	NA	600	2400	2400
VAX 6000-630, 9000-210, 9000-410	143	NA	NA	NA	600	2400	2400
VAX 9000-420	241	NA	NA	NA	800	4800	4800
VAX 9000-430	330	NA	NA	NA	800	4800	4800
VAX 9000-440	386	NA	NA	NA	800	4800	4800
VAX 7000-710, 810	93	NA	NA	NA	230	600	600
VAX 7000-720, 820	193	NA	NA	NA	230	600	600
VAX 7000-730, 830	293	NA	NA	NA	230	600	600
VAX 7000-740, 840	393	NA	NA	NA	230	600	600
VAX 7000-750, 850	493	NA	NA	NA	230	600	600
VAX 7000-760, 860	593	NA	NA	NA	230	600	600
MicroVAX II	18	NA	100	NA	230	50	50

Key to License Type Codes and Values

- A—OpenVMS Capacity or OpenVMS Unlimited or Base
- B—OpenVMS Server
- C—OpenVMS Concurrent user
- D—OpenVMS Workstations
- E—System integrated products
- F—Layered products
- G—Reserved (not listed)
- H—OpenVMS reserved (not listed)
- I—Layered products
- NA—Not applicable

(continued on next page)

License Management Notes

B.3 Using the License Unit Requirement Table (LURT)

Table B–2 (Cont.) License Unit Requirement Table (LURT)

System Marketing Model	License Types by Code						
	OpenVMS				SIP	LP	
	A	B	C	D	E	F	I
MicroVAX 2000, 3100-10e, 3100-20e, 3100-30, 3100-40, 3100-80	18	NA	100	NA	230	20	20
MicroVAX 3100-90, 3100-96, 3100-96A	60	NA	100	NA	230	20	20
MicroVAX 3500, 3600, 3800, 3900, 4000-200	60	NA	100	NA	230	200	200
MicroVAX 3300, 3400, 4000-100, 4000-106A	60	NA	100	NA	230	100	100
VAX 4000-100, 4000-106	60	NA	100	NA	230	100	100
VAX 4000-300, 4000-400, 4000-500A, 4000-600A, 4000-700A, 4000-706A	60	NA	100	NA	230	300	300
VAX 4000-500, 4000-600	60	NA	100	NA	400	900	900
VAXstation II, II/GPX	NA	NA	NA	100	50	10	10
VAXstation 2000, 2000/GPX	NA	NA	NA	100	50	10	10
VAXstation 3100, 3200, 3500, 3520, 3540, 4000-60, 4000 VLC, 4000-90, 4000-96	NA	NA	NA	100	50	10	10
VAXserver 2000	NA	52	NA	NA	50	10	10
VAXserver 3300, 3400, 3500, 3600, 3900, 4000-200, 4000-300	NA	100	NA	NA	50	10	10
VAXserver 6000-210, 6000-310	NA	1443	NA	NA	230	200	200
VAXserver 6000-220, 6000-320, 6000-410, 6000-420	NA	1737	NA	NA	230	400	400
VAXserver 6000-510	NA	600	NA	NA	230	400	400
VAXserver 6000-520	NA	890	NA	NA	230	400	400
VAXserver 9000-110, 9000-310	143	143	NA	NA	600	900	900
VAXserver 9000-320	241	241	NA	NA	800	1200	1200
VAXserver 9000-330	330	330	NA	NA	800	1200	1200
VAXserver 9000-340	386	386	NA	NA	800	1200	1200

Key to License Type Codes and Values

- A—OpenVMS Capacity or OpenVMS Unlimited or Base
- B—OpenVMS Server
- C—OpenVMS Concurrent user
- D—OpenVMS Workstations
- E—System integrated products
- F—Layered products
- G—Reserved (not listed)
- H—OpenVMS reserved (not listed)
- I—Layered products
- NA—Not applicable

License Management Notes

B.4 License Management Facility Notes

B.4 License Management Facility Notes

The following list is offered to help new users with some common concerns and questions regarding the License Management Facility (LMF).

- If you do not have a valid OpenVMS VAX license that is registered and activated, the system displays a warning message as part of system startup and restricts system use to the operator's console, OPA0.
- If a checksum error is displayed when you register a license, check *all* the fields of data that you entered, including the checksum itself.
- After your PAKs are registered, they are activated (loaded) automatically as part of each system startup.
- If an OpenVMS VAX availability license is registered with insufficient license units for the specified VAX computer, the system displays a warning message at system startup but allows normal system use at the console level only.
- If an OpenVMS VAX activity license is registered with insufficient license units to meet your user requirements, the system displays the following message when the user (process) attempts to log in:

```
%LICENSE-F-EXCEEDED, licensed product has exceeded current license limits
```

A user can always log in to the operator's console, OPA0, however.

- The default LICENSE database is located in the file SYSSCOMMON:[SYSEXE]LMF\$LICENSE.LDB. You can move the database, although Digital does not recommend doing so. If you move the database, you must either define the logical name LMF\$LICENSE at the system level to point to the new database or use the /DATABASE=*filespec* qualifier with all LICENSE commands. To redirect LMF to another database location on a more permanent basis, add the following line to the command procedure SYSSMANAGER:SYLOGICALS.COM:

```
$ DEFINE/SYSTEM LMF$LICENSE device:[directory]LMF$LICENSE.LDB
```

If you specify a device other than SYSSSYSDEVICE, you must also mount the specified disk from the SYLOGICALS.COM command procedure.

- Each VAX VMS and OpenVMS VAX Base license is restricted to a single node for permanent PAKs. You must assign a System Communications Services (SCS) name to the license when you register with the VMSLICENSE.COM command procedure, or you must enter a LICENSE MODIFY/INCLUDE=*node-name* command after you register the license. Although you can successfully activate an unassigned OpenVMS VAX license on a standalone system, you cannot activate one in a VAXcluster environment.

Note that the SCS node name is not necessarily the DECnet node name. SCSNODE is a system parameter; it can be a maximum of 6 alphabetic characters.

B.5 Volume Shadowing for OpenVMS License

The following paragraphs describe Volume Shadowing for OpenVMS licenses.

B.5.1 When to Register

After you *install* OpenVMS VAX Version 7.1, you *must* register your Volume Shadowing for OpenVMS license before you can use Volume Shadowing. If you *upgraded* to OpenVMS VAX Version 7.1, you do not need to reregister this license.

B.5.2 Volume Shadowing Phase I and Phase II

In the past, volume shadowing has offered two modes of operation: phase I and phase II. The original implementation of shadowing, phase I, was HSC controller based. The newer implementation, phase II, is host based and provides performance superior to phase I.

With the release of OpenVMS VAX Version 6.2, phase I Volume Shadowing is no longer available. Refer to the *Volume Shadowing for OpenVMS* manual for instructions about moving from phase I to phase II.

B.5.3 Types of Licenses

Two types of Volume Shadowing licenses are valid for OpenVMS VAX Version 7.1:

- Capacity license—If you are using this type of license, you must have one license for each node in a cluster that is accessing shadowed data.
- Per-disk license—If you are using this type of license, you must have one license for every disk contained in the shadow set.

For information about OpenVMS VAX Version 7.1 changes to per-disk licensing for Volume Shadowing, refer to Section 1.2.1.

See the *Volume Shadowing for OpenVMS* manual for more information about these two licenses.

B.6 Other System Integrated Product Licenses

After you *install* OpenVMS VAX Version 7.1, you *must* register licenses for any system integrated product. If you *upgraded* to OpenVMS VAX Version 7.1, you do not need to reregister licenses for system integrated products.

Booting from [SYSF] During an Upgrade

C.1 Booting Procedures

You must boot from the [SYSF] root during phases 2, 3, and 4 of the upgrade procedure. Different VAX computers require that you use different booting procedures. This appendix describes how to boot the various VAX computers from [SYSF].

Go to the section that describes your VAX computer and follow the instructions for booting from [SYSF]. If you need more information about booting, refer to the upgrade and installation supplement for your VAX computer.

C.1.1 MicroVAX and VAXstation Computers

The information in this section applies to the following VAX computers:

VAXstation II, VAXstation II/GPX, and MicroVAX II
VAXstation 2000 and MicroVAX 2000
VAXstation 3100 and MicroVAX 3100 series
VAXstation 3200 and 3500
VAXstation 3520 and 3540
VAXstation 4000
VAXft 110, 310, 410, 610, and 612
MicroVAX 3300, 3400, 3500, 3600, 3800, and 3900

To boot from [SYSF], enter the BOOT command in the following format and press the Return key:

```
>>> B/F0000000 device-name
```

Substitute the device name of the system disk for *device-name*.

C.1.2 VAX 8530, 8550, 8810 (8700), 8820-N (8800) Computers

To boot from [SYSF], use the following procedure:

1. Press Ctrl/P. Enter the following command at the console-mode prompt (>>>) and press the Return key:

```
>>> HALT
```

2. Enter the BOOT command at the console-mode prompt (>>>) in the following format:

```
>>> B dddn /R5:F0000000
```

Substitute BCI, BDA, or UDA for *ddd*. Substitute the unit number of the drive holding the system disk for *n*.

Booting from [SYSF] During an Upgrade

C.1 Booting Procedures

C.1.3 VAX 8820, 8830, and 8840 Computers

To boot from [SYSF], use the following procedure:

1. Enter the following command at the PS-OS-0> prompt and press Return:

```
PS-OS-0> HALT/CPU=ALL
```
2. Enter the BOOT command at the PS-CIO-0> prompt in the following format:

```
PS-CIO-0> B dddn /R5=F0000000
```

Substitute BCI or BDA for *ddd*. Substitute the unit number of the drive holding the system disk for *n*.

C.1.4 VAX-11/750, 8200, 8250, 8300, and 8350 Computers

To boot from [SYSF], create a command procedure named SYFBOO.CMD before the upgrade is started.

To create SYFBOO.CMD, use the following procedure:

Note

This procedure assumes that you have installed and booted the OpenVMS VAX operating system and are logged in to the SYSTEM account.

1. Log in to the SYSTEM account.
2. Make sure that the console media is in the console drive.
3. To connect the console drive to the system, enter the following commands and press the Return key after each one:

```
$ RUN SYS$SYSTEM:SYSGEN
SYSGEN> CONNECT CONSOLE
SYSGEN> EXIT
```

4. Use the Exchange utility to copy the appropriate boot command procedure from the console media to your current directory on the system disk. If the system disk is on an HSC drive and you have created DEFBOO.CMD, enter the following command and press Return:

```
$ EXCHANGE COPY CSA1:DEFBOO.CMD *
```

On the VAX-11/750 computer, if the system disk is on a local drive, copy the boot command procedure that matches the drive that holds the system disk. For example, suppose the system disk is on an RP06 drive and has a controller designation of A and a unit number of one. Enter the following command and press the Return key:

```
$ EXCHANGE COPY CSA1:DA1BOO.CMD *
```

5. Edit the boot command procedure. Change the line that deposits a value in register 5 (R5). This line contains the comment *!software boot flags*. The value is a hexadecimal number with eight digits. For example:

```
D/G R5 0 !software boot flags
```

Change the left-most digit of the value to reflect the name of the root directory from which you want to boot. For example, to boot from the [SYSF] root directory, change the line as follows:

```
D/G/L R5 F0000000 !designated root is SYSF
```

Booting from [SYSF] During an Upgrade

C.1 Booting Procedures

6. Rename the boot command procedure to SYFBOO.CMD. For example, if the boot command procedure is DEFBOO.CMD, enter the following command and press the Return key:

```
$ RENAME DEFBOO.CMD SYFBOO.CMD
```

7. Use the Exchange utility to copy SYFBOO.CMD back to the console media. Enter the following command and press Return:

```
$ EXCHANGE COPY SYFBOO.CMD CSA1:SYFBOO.CMD
```

8. When the copy operation completes, enter the following command and press Return:

```
$ DISMOUNT CSA1
```

9. To secure the console media from unauthorized access, you must enter the following command and press Return:

```
$ MOUNT/FOREIGN/SYSTEM/NOWRITE/NOASSIST CSA1
```

To boot from [SYSF], use the following procedure:

1. Make sure the console media is in the console drive. On the VAX-11/750 computers, make sure the keylock switch is set to LOCAL. Set the BOOT DEVICE switch to position A.

On the VAX 8200 computer, set the upper keylock switch to ENABLE and the lower keylock switch to HALT.

2. Press Ctrl/P.
3. On the VAX-11/750 computer, enter the following command and press the Return key:

```
>>> B/800 DDA0
```

On the VAX 8200 computer, enter the following command at the console-mode prompt (>>>) and press Return:

```
>>> B/R5:800 CSA1
```

4. At the BOOT58> prompt, enter the following command:

```
BOOT58> @SYFBOO.CMD
```

C.1.5 VAX-11/730, 11/780, 11/785, 8600, and 8650 Computers

To boot from [SYSF], create a command procedure named SYFBOO.CMD (for VAX-11/730, 11/780, and 11/785 computers) or SYFBOO.COM (for VAX 8600 and 8650 computers) before the upgrade is started.

To create SYFBOO.CMD or SYFBOO.COM, use the following procedure:

Note

This procedure assumes that you have installed and booted the OpenVMS VAX operating system and are logged in to the SYSTEM account.

1. Log in to the SYSTEM account.
2. Make sure that the console media is in the console drive. On the VAX 8600 computer, make sure the TERMINAL CONTROL switch is set to LOCAL.

Booting from [SYSF] During an Upgrade

C.1 Booting Procedures

3. To connect the console drive, enter the following commands and press the Return key after each one:

```
$ RUN SYS$SYSTEM:SYSGEN
SYSGEN> CONNECT CONSOLE
SYSGEN> EXIT
```

4. Use the Exchange utility to copy DEFBOO.CMD (for VAX-11/730, 11/780, and 11/785 computers) or DEFBOO.COM (for VAX 8600 and 8650 computers) from the console media to your current directory on the system disk. On the VAX-11/780, 11/785, and 8600 computers, enter a command similar to the following and press Return:

```
$ EXCHANGE COPY CSA1:DEFBOO.CMD *
```

On the VAX-11/730 computer, enter the following command and press the Return key:

```
$ EXCHANGE COPY CSA2:DEFBOO.CMD *
```

5. Edit DEFBOO.CMD or DEFBOO.COM. Change the line that deposits a value in register 5 (R5). On the VAX-11/730, 11/780, and 11/785 computers, this line contains the comment *!software boot flags*. On the VAX 8600, this line contains the comment *!Use R5 for optional boot control flags [SYSB.]*. The value is a hexadecimal number with eight bits. For example:

```
DEPOSIT R5 10000000      !software boot flags
```

Change the left-most digit of the value to reflect the name of the root directory from which you want to boot. For example, to boot from [SYSF], change the line as follows:

```
DEPOSIT R5 F0000000      !software boot flags
```

6. Rename DEFBOO.CMD to SYFBOO.CMD (or DEFBOO.COM to SYFBOO.COM), as follows:

```
$ RENAME DEFBOO.CMD SYFBOO.CMD
```

7. Use the Exchange utility to copy SYFBOO.CMD or SYFBOO.COM to the console media. On the VAX-11/780, 11/785, and 8600 computers, enter a command similar to the following:

```
$ EXCHANGE COPY SYFBOO.CMD CSA1:SYFBOO.CMD
```

On the VAX-11/730 computer, enter the following command and press the Return key:

```
$ EXCHANGE COPY SYFBOO.CMD CSA2:SYFBOO.CMD
```

8. When you are finished, enter a command similar to the following and press Return:

```
$ DISMOUNT CSA1
```

9. To secure the console media from unauthorized access, you must enter a command similar to the following and press Return:

```
$ MOUNT/FOREIGN/SYSTEM/NOWRITE/NOASSIST CSA1
```

To boot from [SYSF] during an upgrade, use the following procedure:

1. Make sure the console media is in the console drive. On the VAX-11/730, 11/780, and 11/785 computers, make sure the keylock switch is set to LOCAL. On the VAX 8600, make sure the TERMINAL CONTROL switch is set to LOCAL.

Booting from [SYSF] During an Upgrade

C.1 Booting Procedures

2. Press Ctrl/P. On the VAX-11/780, 11/785, and 8600 computers, enter the HALT command at the console-mode prompt (>>>) and press the Return key:

```
>>> HALT
```

3. Use SYFBOO.CMD to boot from [SYSF]. Enter the following command and press Return:

```
>>> B SYF
```

C.1.6 VAX 6000 Series

To boot from [SYSF], use the following procedure:

1. If you have a CIBCA-A adapter and are booting over the CI, insert the console tape cartridge in the console drive.
2. Press Ctrl/P to put the system in console mode.
3. Enter the BOOT command in the following format:

```
>>> BOOT /R5:F0000000 /XMI:a /BI:b [/R3:c] [/NODE:d] DUu
```

where:

- *a* is the XMI node number of the system disk.
- *b* is the VAXBI node number of the system disk.
- *c* pertains to volume shadowing. This qualifier is not required unless you are using volume shadowing. For more information, see the *Volume Shadowing for OpenVMS* manual.
- *d* is the HSC node number of the node being accessed. The /NODE qualifier is not necessary if you are booting from a local disk. The HSC node number is in hexadecimal. You can deposit a maximum of two HSC node numbers (if two HSCs are available).
- *u* is the unit number of the drive holding the system disk.

For example, suppose you want to boot from [SYSF] on an HSC disk with a unit number of one and your system has the following configuration:

- The disk is connected to the VAXBI at node 2.
- The VAXBI you are using is connected to the XMI at node 3.
- The disk is available to two HSCs, node numbers 0E and 02.

Enter the following command and press the Return key:

```
>>> BOOT/R5:F0000000/XMI:3/BI:2/NODE:0E02 DU1
```

Booting from [SYSF] During an Upgrade

C.1 Booting Procedures

C.1.7 VAX 9000 Series

The upgrade procedure automatically updates DEFBOO.CMD to boot from [SYSF]. If you want to boot a VAX 9000 computer manually from [SYSF] however, you must set up DEFBOO.CMD to boot from the system disk and perform the following procedure:

1. Press Ctrl/P to obtain the console prompt.
2. Enter the following BOOT commands:

```
>>> I/K
>>> BOOT/NOSTART
>>> DEPOSIT R5 F0000000
>>> CONTINUE
```

3. If you set up DEFBOO.CMD properly, the system will boot from the SYSF directory on the system disk and continue with the upgrade procedure.

If the system does not boot, enter the SHOW CONFIGURATION console command and verify that DEFBOO.CMD contains the correct information for your configuration. For more information, see the *OpenVMS VAX Upgrade and Installation Supplement: VAX 9000 Series*.

OpenVMS VAX Save Set Subclasses

This appendix lists the file subclasses contained in the following save sets:

- VMS070.C—Library save set
- VMS070.D—Optional save set
- VMS070.E—Help Message save set
- VMS070.F—OpenVMS Management Station save set

D.1 Save Set C Subclasses

The following files are contained in the Library save set:

- Network support
 - Incoming Remote File Access files
 - Incoming Remote Terminal files
 - Network Test files
 - Remote Task Loading
- Programming Support
 - Debugger utility (DEBUG)
 - Image Dump utility (ANALYZE/PROCESS_DUMP)
 - RMS Analyze and FDL Editor utilities (ANALYZE/RMS, ANALYZE/FDL)
 - Message utility (MESSAGE)
 - Object and Shareable Image libraries
 - MACRO libraries
 - MACRO assembler
 - SDL intermediary form of STARLET.MLB
 - Fortran required files
 - VAX C object libraries
 - X/Open transport interface libraries
 - OpenVMS RMS journaling files
- System programming Support
 - Files-11 ODS-1, ISO 9660, High Sierra ACPs
 - Monitor utility
 - Delta/XDelta debugger
 - System Dump Analyzer utility (ANALYZE/SYSTEM, ANALYZE/CRASH)
 - System Symbol Table file (SYS.STB)
 - Miscellaneous symbol table files
- Secure User's Environment
 - File Access Control List utilities
 - Print and Batch Queue utilities
 - Input Queue Symbiont (Card Reader)

OpenVMS VAX Save Set Subclasses

D.1 Save Set C Subclasses

Accounting Log Report Generator utility
DECdtm

- Utilities
 - Mail utility
 - DUMP utility
 - RUNOFF utility
 - Phone utility
 - OpenVMS Help library
 - Foreign Terminal Support
 - LAT-11 terminal server (via Ethernet)
 - Standalone backup
 - Error Log Report Generator utility (ANALYZE/ERROR)
 - DECTPU
 - Terminal Fallback Facility
 - National Character Set utility (NCS)
 - C language internationalization utilities
- TECO editor
- EDT documentation
- OpenVMS workstation support
- Workstation device support

D.2 Save Set D Subclasses

The following files are contained in the Optional save set:

- Miscellaneous files
- System map
- LPA-11 support
- BLISS required files
- UETP (the User Environment Test Package)
- Example files

D.3 Save Set E Subclasses

The following files are contained in the Help Message save set:

- Help Message database

D.4 Save Set F Subclasses

The following files are contained in the OpenVMS Management Station save set:

- OpenVMS Management Station software PC files

DECwindows Display Server and Fonts Components

This appendix provides a list of files provided by the DECwindows base and workstation support components included on the OpenVMS VAX distribution kit.

E.1 Table of Components

Table E-1 contains the name of the DECwindows display server and fonts components, the directory where the component can be found, a brief description of what the component does, and one of the following component classifications:

- BASE—Indicates that the component is part of all installations.
- WS—Indicates that the component is part of the workstation support.
- FONT—Indicates the component is part of the fonts component.

Table E-1 DECwindows Display Server and Fonts Components

File	Purpose	Component Class
Files in DECW\$KEYMAP Directory		
DECW\$KEYMAP		BASE
Files in SYS\$LOADABLE_IMAGES Directory		
GAADRIVER.EXE	VAXstation II/GPX driver	WS
GABDRIVER.EXE	VAXstation 2000/GPX driver	WS
GBBDRIVER.EXE	VAXstation 35x0 driver	WS
GCADRIVER.EXE	VAXstation II monochrome device driver	WS
GCBDRIVER.EXE	VAXstation 2000 monochrome device driver	WS
GEBDRIVER.EXE	Scanproc graphics device driver	WS
GECDRIVER.EXE	Spxg/gt graphics device driver	WS
GFBDRIVER.EXE	Low-cost graphics device driver	WS
IEDRIVER.EXE	Input extension driver	WS
IKDRIVER.EXE	Keyboard decoder driver	WS
IMDRIVER.EXE	Mouse decoder driver	WS
INDRIVER.EXE	Common input function driver	WS
WSDRIVER.EXE	Set display driver	BASE

(continued on next page)

DECwindows Display Server and Fonts Components

E.1 Table of Components

Table E-1 (Cont.) DECwindows Display Server and Fonts Components

File	Purpose	Component Class
Files in SYSSYSTEM Directory		
DECW\$FONTCOMPILER.EXE	Font compiler image	FONT
DECW\$MKFONTDIR.EXE	Font utility to generate list of fonts and paths	FONT
DECW\$SERVER_MAIN.EXE	Server main image	WS
DECW\$SETSHODIS.EXE	SHOW DISPLAY command image	BASE
Files in DECW\$FONT Directory		
See <i>VMS DECwindows Xlib Programming Volume</i>	DECwindows fonts	WS
Files in DECW\$EXAMPLES Directory		
DECW\$FONT_ALIAS_CHARTER.DAT	Example alias file for Charter fonts	FONT
DECW\$FONT_ALIAS_CHARTER_100DPI.DAT	Example alias file for 100 dpi Charter fonts	FONT
DECW\$FONT_ALIAS_FILENAMES.DAT	Brief alias name list for shipped fonts	FONT
DECW\$FONT_ALIAS_KANJI.DAT	Example alias file for Kanjifonts	FONT
DECW\$FONT_ALIAS_LUCIDA.DAT	Example alias file for Lucida fonts	FONT
DECW\$FONT_ALIAS_LUCIDA_100DPI.DAT	Example alias file for 100 dpi Lucida fonts	FONT
Files in SYS\$LIBRARY Directory		
DECW\$DRIVER.MLB	Driver macro library	WS
DECW\$FONTCOMPILER.CLD	CLD for font compile commands	FONT
DECW\$SERVER_DDX_GA.EXE	Server color device support shareable image	WS
DECW\$SERVER_DDX_GB.EXE	Server color device support shareable image	WS
DECW\$SERVER_DDX_GC.EXE	Server monochrome device support shareable image	WS
DECW\$SERVER_DDX_GE.EXE	Server scanproc device-dependent shareable image	WS
DECW\$SERVER_DDX_GF.EXE	Server low-cost graphics device-dependent shareable image	WS
DECW\$SERVER_DIX.EXE	Server device independent support	WS
DECW\$SERVER_XINPUT_IE.EXE	Input extension for handling nonstandard input devices	WS
DECW\$SESSIONSHRP.EXE	Support routines for DECwindows Session Manager	BASE
DECW\$SVEXT_ADOBE_DPS_EXTENSION.EXE	Display PostScript server extension image	WS
DECW\$SVEXT_D2DX_EXTENSIONS.EXE	DECwindows 2D extensions	WS
DECW\$SVEXT_DEC_XTRAP.EXE	Input and event recording and playback extension	WS

(continued on next page)

DECwindows Display Server and Fonts Components E.1 Table of Components

Table E-1 (Cont.) DECwindows Display Server and Fonts Components

File	Purpose	Component Class
Files in SYS\$LIBRARY Directory		
DECW\$SVEXT_MULTI_BUFFERING.EXE	DECwindows multi-buffering extension	WS
DECW\$SVEXT_X3D_PEX.EXE	Phigs Extension to X (PEX) for 3D	WS
DECW\$SVEXT_X3D_PEX_GB.EXE	PEX for 35x0 systems	WS
DECW\$SVEXT_X3D_PEX_GB_UCODE.EXE	PEX microcode for 35x0 systems	WS
DECW\$SVEXT_X3D_PEX_GE.EXE	PEX for scanproc systems	WS
DECW\$SVEXT_X3D_PEX_STP.EXE	PEX for scanproc systems with geometry processor	WS
DECW\$SVEXT_X3D_PEX_STP_UCODE.EXE	PEX microcode for scanproc systems with geometry processor	WS
DECW\$SVEXT_X3D_PEX_VCFB.EXE	PEX color frame buffer (software PEX)	WS
DECW\$SVEXT_XIE.EXE	DECwindows imaging extension	WS
DECW\$SVEXT_XINPUTEXTENSION.EXE	DECwindows input extension	WS
DECW\$STRANSPOrt_COMMON.EXE	Common transport shareable image	BASE
DECW\$STRANSPOrt_DECNET.EXE	DECnet transport image	BASE
DECW\$STRANSPOrt_LOCAL.EXE	Local transport image	BASE
DECW\$STRANSPOrt_TCPIP.EXE	TCP/IP transport image	BASE
DECW\$XPORTCOM.H	Common transport definitions	BASE
DECW\$XPORTCOM.MAR	Common transport definitions	BASE
DECW\$XPORTCOM.R32	Common transport definitions	BASE
DECW\$XPORTDEF.H	Transport definitions	BASE
DECW\$XPORTDEF.MAR	Transport definitions	BASE
DECW\$XPORTDEF.R32	Transport definitions	BASE
DECW\$XPORTMAC.R32	Transport BLISS macros	BASE
DECW\$XPORTMSG.R32	Transport message symbols	BASE
XDP\$MASTERDPSVM.DAT	Display PostScript support file	WS
Files in SYS\$MANAGER Directory		
DECW\$DEVICE.COM	Device detection and configuration	BASE
DECW\$DEVICE_GE.COM	Scanproc device detection and configuration	WS
DECW\$DEVICE_GF.COM	Low-cost graphics device detection and configuration	WS
DECW\$DEVICE_GG.COM	Scanproc turbo device detection and configuration	WS
DECW\$RGB.DAT	Definitions of the color names used by the XStoreNamedColor and XAllocNamedColor requests	WS
DECW\$STARTSERVER.COM	Server initialization and startup	WS

(continued on next page)

DECwindows Display Server and Fonts Components

E.1 Table of Components

Table E-1 (Cont.) DECwindows Display Server and Fonts Components

File	Purpose	Component Class
Files in SYSSMESSAGE Directory		
DECWSTRANSPORTMSG.EXE	Transport message image	BASE
Files in SYS\$UPDATE Directory		
DECWSMKFONDIR.COM	Command file to invoke DECWSMKFONDIR.EXE font utility	FONT

NEW_OVER and NEW_UNDER Files

This appendix lists files installed either over or under existing files during an upgrade.

F.1 Where Files Are Installed

During an upgrade, the procedure replaces certain files that exist on your system with new versions of those files from the OpenVMS VAX distribution kit. For some system files, the upgrade procedure does not replace your existing system files, which might contain customizations for your site. Instead, the procedure retains your existing file and installs the new file from the kit at a version number higher or at a version number lower than your existing file.

You can use the DCL command `DIFFERENCES` to compare the contents of your existing files and the contents of the new files provided by OpenVMS VAX Version 7.1. Enter the command using the following syntax:

```
DIFFERENCES/OUTPUT=filespec existing_filename new_filename
```

The `/OUTPUT` qualifier causes the `DIFFERENCES` command to write the list of differences to the output file you specify. This output file will have the default file type `.DIF`. For more information about using the `DIFFERENCES` command, refer to the *OpenVMS DCL Dictionary*.

New files that the procedure installs at a version number higher than your existing files are referred to as **new_over** files. You must use these files at least until you complete the upgrade. After you have upgraded your system, you can add your customizations to these files.

New files installed at a version number lower than the existing files are referred to as **new_under** files. This allows you to continue to use your existing files during and after the upgrade.

If you purge a `new_over` file, you are left with the new version of the file provided by the distribution kit, and any customizations you might have made to the existing file will be lost. If you purge a `new_under` file, you are left with the file that existed before the upgrade.

In addition to the `new_over` and `new_under` files, there are certain files that are intended to contain your site-specific modifications. During an upgrade, the old versions of these files are retained if they were present before the upgrade. The new version of the file is installed only if no old version is present on your system. With the exception of `TFF$STARTUP.COM`, there is a corresponding `.TEMPLATE` file for each of the site-specific files. The new version of the `.TEMPLATE` file replaces the old version.

NEW_OVER and NEW_UNDER Files

F.1 Where Files Are Installed

F.1.1 NEW_OVER Files

During an upgrade, the following new files are installed over (that is, at a version number higher than) the existing files:

```
[SYSEXE]SHUTDOWN.COM
[SYSEXE]STARTUP.COM
[SYSHLP]HELPLIB.HLB
[SYSLIB]ADARTL.EXE
[SYSLIB]BASRTL.EXE
[SYSLIB]BASRTL2.EXE
[SYSLIB]BLAS1RTL.EXE
[SYSLIB]COBRTL.EXE
[SYSLIB]DBLRTL.EXE
[SYSLIB]DCLTABLES.EXE
[SYSLIB]ENCRYPHR.EXE
[SYSLIB]FORRTL.EXE
[SYSLIB]FORRTL2.EXE
[SYSLIB]IMAGELIB.OLB
[SYSLIB]LBRSHR.EXE
[SYSLIB]LIBRTL.EXE
[SYSLIB]LIBRTL2.EXE
[SYSLIB]MTHRTL.EXE
[SYSLIB]PASRTL.EXE
[SYSLIB]PLIRTL.EXE
[SYSLIB]PPLRTL.EXE
[SYSLIB]RPGRTL.EXE
[SYSLIB]SCNRTL.EXE
[SYSLIB]STARLET.OLB
[SYSLIB]UVMTHRTL.EXE
[SYSLIB]VAXCRTL.EXE
[SYSLIB]VAXCRTLG.EXE
[SYSLIB]VBLAS1RTL.EXE
[SYSLIB]VMSRTL.EXE
[SYSLIB]VMTHRTL.EXE
[SYSMGR]DBLSTRTUP.COM
[SYSMGR]WELCOME.TEMPLATE
[SYSMGR]WELCOME.TXT
```

F.1.2 NEW_UNDER Files

During an upgrade, the following new files are installed under (that is, at a version number lower than) the existing files:

```
[SY$LDR]VMS$SYSTEM_IMAGES.DATA
[SY$STARTUP]ESS$LAST_STARTUP.DAT
[SY$STARTUP]VMS$LAYERED.DAT
[SYSEXE]VMS$IMAGE_VERSION.DAT
[SYSLIB]CDDSHR.EXE
[SYSLIB]EPC$FACILITY.TLB
[SYSLIB]EPC$SHR.EXE
[SYSLIB]UISSHR.EXE
[SYSMMSG]EPC$MSG.EXE
```

F.1.3 Site-Specific Files

The following files are intended to contain site-specific modifications. Note that, with the exception of TFF\$STARTUP.COM, there is a corresponding .TEMPLATE file for each of these files. The new version of the .TEMPLATE file replaces the old version.

[SYSEXE]SYSUAF.DAT
[SYSMGR]AGEN\$NEW_NODE_DEFAULTS.DAT
[SYSMGR]AGEN\$NEW_SATELLITE_DEFAULTS.DAT
[SYSMGR]LAT\$SYSTARTUP.COM
[SYSMGR]LOGIN.COM
[SYSMGR]SYCONFIG.COM
[SYSMGR]SYLOGICALS.COM
[SYSMGR]SYLOGIN.COM
[SYSMGR]SYPAGSWPFILES.COM
[SYSMGR]SYSECURITY.COM
[SYSMGR]SYSHUTDOWN.COM
[SYSMGR]SYSTARTUP_VMS.COM
[SYSMGR]TFF\$STARTUP.COM

Preparing to Use OpenVMS Management Station

This appendix describes how to prepare your OpenVMS system and your PC to run the OpenVMS Management Station server and client software.

The OpenVMS Management Station is a client-server application that provides OpenVMS system management capabilities through a client application on a personal computer (PC) running Microsoft Windows.

During the OpenVMS VAX installation or upgrade procedure, the OpenVMS Management Station server files are automatically installed on your OpenVMS system disk. However to obtain *complete* support, you must also select the OpenVMS Management Station client software files during the OpenVMS installation or upgrade procedure. Those files are required to create the installation media that you use to install the client software on your PC.

If you did *not* select the OpenVMS Management Station component during the installation or upgrade, you must add those files to your OpenVMS system disk before you follow the instructions in this appendix. Use the OpenVMS VAX distribution media and VMSTAILOR to add the OpenVMS Management Station files to your system. (For information about using VMSTAILOR, see Chapter 10.)

G.1 Preparing Your OpenVMS System

You must prepare your OpenVMS system to run the server software so that your system can properly interact with the PC running the client software. The procedures include the following:

- Set up within a mixed-architecture cluster environment (if applicable).
- Start the server on other nodes.
- Update the printer database.
- Edit the system files.
- Allow OpenVMS Management Station to control the printer environment.
- Keep your printer environment up to date.
- Check if running third-party TCP/IP stacks.
- Recover from a failure.
- Determine and report problems.

Preparing to Use OpenVMS Management Station

G.1 Preparing Your OpenVMS System

G.1.1 Files Installed on Your OpenVMS System

The following files are created on your OpenVMS system when the OpenVMS Management Station server is installed:

- SYS\$SYSTEM:TNT\$SERVER.EXE
- SYS\$STARTUP:TNT\$STARTUP.COM
- SYS\$STARTUP:TNT\$SHUTDOWN.COM
- SYS\$STARTUP:TNT\$UTILITY.COM
- SYS\$TEST:TNT\$IVP.COM
- SYS\$COMMON:[SYSTEST.TNT]TNT\$SERVER_IVP.EXE
- SYS\$HELP:TNTV20.RELEASE_NOTES

These optional files are created when you install PC installation media files:

- SYS\$COMMON:[TNT.CLIENT]DISKIMAG.EXE
- SYS\$COMMON:[TNT.CLIENT]TNTCLID1.IMG
- SYS\$COMMON:[TNT.CLIENT]TNTCLID2.IMG
- SYS\$COMMON:[TNT.CLIENT]TNTCLID3.IMG
- SYS\$COMMON:[TNT.CLIENT]TNTCLID4.IMG
- SYS\$COMMON:[TNT.CLIENT]TNTCLID5.IMG
- SYS\$COMMON:[TNT.CLIENT]TNTCLID6.IMG

These files are created when the server is started:

- SYS\$COMMON:[SYSEXE]TNT\$UADB.DAT
- SYS\$COMMON:[SYSEXE]TNT\$ACS.DAT
- SYS\$COMMON:[SYSEXE]TNT\$JOURNAL.TNT\$TRANSACTION_JOURNAL

G.1.2 Setting Up in a Mixed-Architecture Cluster Environment

The OpenVMS Management Station server creates three main configuration files:

- TNT\$UADB.DAT
- TNT\$ACS.DAT
- TNT\$JOURNAL.TNT\$TRANSACTION_JOURNAL

In a common-environment cluster with one common system disk, you use a common copy of each of these files located in the SYS\$COMMON:[SYSEXE] directory on the common system disk, or on a disk that is mounted by all cluster nodes. No further action is required.

However, to prepare a common user environment for an OpenVMS Cluster system that includes more than one common VAX system disk or more than one common Alpha system disk, you must coordinate the files on those disks.

Rules: The following rules apply:

- Disks holding common resources must be mounted early in the system startup procedure, such as in the SYLOGICALS.COM procedure.
- You must ensure that the disks are mounted with each cluster reboot.

Preparing to Use OpenVMS Management Station

G.1 Preparing Your OpenVMS System

Follow these steps to coordinate files:

1. Decide where to locate the files. In a cluster with multiple system disks, system management is much easier if the common system files are located on a single disk that is not a system disk.
2. Copy TNT\$UADB.DAT, TNT\$ACS.DAT, and TNT\$JOURNAL.TNT\$TRANSACTION_JOURNAL to a location other than the system disk.
3. Edit the file SYSS\$COMMON:[SYSMGR]SYLOGICALS.COM *on each system disk* and define logical names that specify the location of the cluster common files.

Example: If the files will be located on \$1\$DJA16, define logical names as follows:

```
$ DEFINE/SYSTEM/EXEC TNT$ACS -
_ $ $1$DJA16: [VMS$COMMON.SYSEXEC] TNT$ACS.DAT

$ DEFINE/SYSTEM/EXEC TNT$UADB -
_ $ $1$DJA16: [VMS$COMMON.SYSEXEC] TNT$UADB.DAT

$ DEFINE/SYSTEM/EXEC TNT$JOURNAL -
_ $ $1$DJA16: [VMS$COMMON.SYSEXEC] TNT$JOURNAL.TNT$TRANSACTION_JOURNAL
```

4. To ensure that the system disks are mounted correctly with each reboot, follow these steps:
 1. Copy the SYS\$EXAMPLES:CLU_MOUNT_DISK.COM file to the [VMS\$COMMON.SYSMGR] directory, and edit it for your configuration.
 2. Edit SYLOGICALS.COM and include commands to mount, with the appropriate volume label, the system disk containing the shared files.

Example: If the system disk is \$1\$DJA16, include the following command:

```
$ @SYS$SYSDEVICE: [VMS$COMMON.SYSMGR] CLU_MOUNT_DISK.COM -
_ $ $1$DJA16: volume-label
```

G.1.3 Start the Server on Other Nodes

If you plan to run OpenVMS Management Station on more than one node in an OpenVMS Cluster without a reboot, you need to start the software on those nodes. Enter the following command:

```
$ @SYS$STARTUP:TNT$STARTUP.COM
```

If you are performing an upgrade or a reinstallation and OpenVMS Management Station is already running on the node, add the RESTART parameter to the startup command, as follows:

```
$ @SYS$STARTUP:TNT$STARTUP.COM RESTART
```

G.1.4 Update the Printer Database

When you installed OpenVMS Management Station, the installation started the OpenVMS Management Station server on the installation node and created an initial version of the printer database file TNT\$ACS.DAT. However, this initial version of the database might not contain complete device and queue information for your OpenVMS Cluster system.

Preparing to Use OpenVMS Management Station

G.1 Preparing Your OpenVMS System

To complete the database, first start the OpenVMS Management Station server on each node in your cluster. The instances of the server communicate with each other to determine device and queue information, and the server must be running on each node for this communication to take place.

Once you have started the server on each node, run the following procedure to update the printer database:

```
$ @SYS$STARTUP:TNT$UTILITY UPDATE PRINTERS
```

G.1.5 Edit the System Files

To start the OpenVMS Management Station server from your system startup files, insert the following line into your system startup procedures (usually `SYSS$MANAGER:SYSTARTUP_VMS.COM`) after both the Queue Manager and network are started, but before `ENABLE AUTOSTART/QUEUES`.

```
$ @SYS$STARTUP:TNT$STARTUP BOOT
```

(The best place for this is immediately prior to the `ENABLE AUTOSTART /QUEUES` command.)

Note

Remove any other invocations of `TNT$STARTUP` you might have added in previous releases of the OpenVMS Management Station.

OpenVMS Management Station cannot start until the network has started. If you start your network using a batch process, OpenVMS Management Station might start before the batch process completes and the network is started.

Add the following command line to the system shutdown file, `SYSS$MANAGER:SYSHUTDOWN.COM`:

```
$ @SYS$STARTUP:TNT$SHUTDOWN.COM
```

G.1.6 Allow OpenVMS Management Station to Control the Printer Environment

Placing the server startup before `ENABLE AUTOSTART/QUEUES` in the system startup procedure allows the server to start any queues not already started by your existing DCL command procedures.

It is not necessary to remove your existing queue startup DCL procedures immediately. The OpenVMS Management Station server will recognize that you started a queue with your command procedures and will assume that you want it that way.

As you become familiar with the server's management ability, you can remove or comment out the DCL commands and procedures that perform these tasks and allow OpenVMS Management Station to control your printer environment.

G.1.7 Keep Your Printer Environment Up to Date

The OpenVMS Management Station server installation creates a file named `SYSS$STARTUP:TNT$UTILITY.COM`. This command procedure scans the OpenVMS system and updates the database of known printers, queues, and related devices. `TNT$UTILITY.COM` runs at regular intervals to keep the database files synchronized with the actual system.

Preparing to Use OpenVMS Management Station

G.1 Preparing Your OpenVMS System

G.1.7.1 When Does TNT\$UTILITY.COM Run?

The TNT\$UTILITY.COM procedure runs:

- As part of the OpenVMS Management Station installation.
- When you specifically invoke it.
- At periodic intervals as a background thread. Two logical names control how often it runs:

Logical Name	Description
TNT\$PRINTER_RECON_INTERVAL	How often TNT\$UTILITY.COM should run, in minutes, from when the server was last started on this node. If you do not define this logical, the default value is 1440 minutes (24 hours).
TNT\$PRINTER_RECON_INTERVAL_MIN	The minimum number of minutes that must elapse before TNT\$UTILITY.COM should run again, starting from when the database was last updated. If you do not define this logical, the default value is 60 minutes (1 hour).

You can think of these logicals as meaning “run TNT\$UTILITY.COM this often (TNT\$PRINTER_RECON_INTERVAL), but make sure this much time has elapsed since the database was last updated (TNT\$PRINTER_RECON_INTERVAL_MIN).”

Because you can run TNT\$UTILITY.COM yourself, and because the OpenVMS Management Station server also updates the database, the TNT\$PRINTER_RECON_INTERVAL_MIN logical prevents the database from being updated more frequently than is actually needed.

If you want to change the defaults for one of these logicals, define the logical on all nodes on which the OpenVMS Management Station server is running.

G.1.7.2 Do You Need to Run TNT\$UTILITY.COM Manually?

If you use OpenVMS Management Station to make all of the changes to your printer configuration, the configuration files are immediately modified to reflect the changes and you probably do not need to specifically run TNT\$UTILITY.COM. TNT\$UTILITY.COM runs at periodic intervals as a background thread to make sure that the database is kept up to date.

However, if you or someone else uses DCL to make a change — for example, if you use the DELETE /QUEUE command to delete a queue — the configuration files will not be synchronized. In this case, the OpenVMS Management Station client will advise you to run TNT\$UTILITY.COM to resynchronize the database.

Run the following procedure on one node in the cluster to make the database match your system:

```
$ @SYS$STARTUP:TNT$UTILITY.COM UPDATE PRINTERS
```

For example, if you or someone else used DCL to delete a queue, you need to delete that queue from the database. TNT\$UTILITY.COM assumes that your system is set up and running the way that you want it to, so you should fix any problems before you run TNT\$UTILITY.COM.

Preparing to Use OpenVMS Management Station

G.1 Preparing Your OpenVMS System

G.1.7.3 Are There Any Requirements for Running TNT\$UTILITY.COM?

You need the SYSNAM privilege to run TNT\$UTILITY.COM.

TNT\$UTILITY.COM connects to the OpenVMS Management Station server on the current OpenVMS system to determine device and queue information. Therefore, the OpenVMS Management Station server must be running on the node where you run TNT\$UTILITY.COM.

The OpenVMS Management Station server then connects to the other OpenVMS Management Station servers in the OpenVMS Cluster to determine device and queue information. It is generally a good idea to keep the OpenVMS Management Station server running on the other nodes in an OpenVMS Cluster to keep the database up to the minute.

However, if the OpenVMS Management Server is not able to connect to the OpenVMS Management Station server on a given node, it uses the known information about that OpenVMS node from the database. That is, in the absence of a valid connection to that OpenVMS node, the information in the database is assumed to be correct.

G.1.8 Enabling Disk Quotas

Before installing OpenVMS Management Station, you might have disabled disk quotas on the SYSTEM disk. If so, you should reenble the quotas and then rebuild to update quota information by entering the following commands:

```
$ RUN SYS$SYSTEM:DISKQUOTA
DISKQUOTA> ENABLE
DISKQUOTA> REBUILD
DISKQUOTA> EXIT
```

G.1.9 Running Third-Party TCP/IP Stacks

Digital TCP/IP Services for OpenVMS Version 3.2 or higher is the only supported TCP/IP stack. Additional stacks have not been tested. However, TCP/IP stacks that are 100% compliant with the QIO interface for TCP/IP Services for OpenVMS should also work. (Contact your TCP/IP vendor for additional information and support issues.)

For the best chance of success, check the following:

- Make sure that the QIO service (for example, UCXQIO) is enabled.
- For TCPware, also make sure that TCPware's UCX\$IPC_SHR.EXE is an installed image.

G.1.10 Determining and Reporting Problems

If you encounter a problem while using OpenVMS Management Station, please report it to Digital. Depending on the nature of the problem and the type of support you have, you can take one of the following actions:

- If your software contract or warranty agreement entitles you to telephone support, call Digital.
- If the problem is related to OpenVMS Management Station documentation, use the Internet address printed in front of this book to send us your comments.

G.2 Preparing Your PC

During the OpenVMS Version 7.1 installation or upgrade procedure, you selected the OpenVMS Management Station client software files to be installed on your OpenVMS system disk (or you added them later using the DCL command `PRODUCT RECONFIGURE VMS`). After you have prepared your OpenVMS system to run the server software, you must next prepare your PC to run the client software.

This section includes the following information:

- Required memory and disk space
- Required software
- TeamLinks support
- Creating the installation media
- Installing the client software
- Getting started using OpenVMS Management Station

G.2.1 Required Memory and Disk Space

Your PC requires 8 MB of random-access memory (RAM) and 11.5 MB of free disk space to install the OpenVMS Management Station client software.

G.2.2 Required Software

Table G–1 describes the software that must be installed on your PC before installing OpenVMS Management Station.

Table G–1 Prerequisite and Optional Software for PCs

Prerequisite Products	Purpose
Microsoft Windows NT Version 3.51 <i>or</i> Microsoft Windows 95 <i>or</i> Microsoft Windows Version 3.1 <i>or</i> Microsoft Windows for Workgroups Version 3.11	Operating system
Optional Products	Purpose
PATHWORKS Version 5.1 for DOS and Windows client software	Integrate with PATHWORKS, DECnet support
ManageWORKS Workgroup Administrator, Version 2.2	ManageWORKS integration
Your TCP/IP stack	IP connections

PATHWORKS for Windows 95 and any version of Windows NT prior to Version 3.51 are not officially supported.

Preparing to Use OpenVMS Management Station

G.2 Preparing Your PC

G.2.3 TeamLinks Version 1.0 is Not Supported

If Version 1.0 of TeamLinks is installed on your PC, the OpenVMS Management Station PC installation program will ask whether to update the XTI library component of TeamLinks.

If you answer No, the OpenVMS Management Station installation terminates. However, if you allow OpenVMS Management Station to update the XTI library, Version 1.0 of TeamLinks will no longer work.

The version of the XTI library included with Version 1.0 of TeamLinks does not allow TCP/IP connections from your PC and is not supported in this version of OpenVMS Management Station. If you want to utilize both TCP/IP connections and TeamLinks, you must upgrade to a higher version of TeamLinks.

G.2.4 Creating the Installation Media

Create the PC installation media using the following procedure.

Note: You need six formatted 3-1/2-inch, high-density floppy disks.

1. For PCs running TCP/IP, at the MS-DOS prompt use the FTP utility on the PC to copy the files by entering commands similar to the following:

```
C:\> cd temp-dir
C:\temp> ftp
ftp> open node
Connected to node
Username: username
Password: password
User logged in.
ftp> cd sys$common:[tnt.client]
ftp> type bin
ftp> mget *.*
```

where *node*, *username*, and *password* are the access control information for an account on the OpenVMS system, and *temp-dir* is the name of the temporary directory.

2. For PCs running DECnet, at the MS-DOS prompt use the NFT utility on the PC to copy the files by entering the following command:

```
C:\> NFT COPY /BLOCK node"username password":.SYS$COMMON:
[TNT.CLIENT]*.* \temp-dir
```

where *node*, *username*, and *password* are the access control information for an account on the OpenVMS system, and *temp-dir* is the name of the temporary directory. The node name must be defined in the PC's network database.

3. Insert a formatted floppy disk in the 3-1/2-inch floppy disk drive (A in this example). At the MS-DOS prompt, type the following MS-DOS command:

```
C:\> \temp-dir\DISKIMAG \temp-dir\TNTCLID1.IMG A:
```

where *temp-dir* is the temporary directory used in step 2.

When the DISKIMAG program returns to the MS-DOS prompt, remove the floppy disk and label it "Disk 1—Setup."

4. Repeat this process for TNTCLID2.IMG through TNTCLID6.IMG
5. You can delete the files DISKIMAG.EXE and TNTCLID1.IMG through TNTCLID6.IMG from *temp-dir* after creating the floppy disks.

G.2.5 Installing the OpenVMS Management Station Client Software on Your PC

This section provides the following information:

- How to install the OpenVMS Management Station client on a PC
- How to recover from errors during the installation
- How to define DECnet nodes after the installation
- The names of the files that are created on your PC after the installation
- How to access online help to get started using OpenVMS Management Station

G.2.5.1 Installation Directory

The installation procedure allows you to select the installation directory, and suggests \VMSTNT as the default.

Do not install OpenVMS Management Station into the PATHWORKS or ManageWORKS Workgroup Administrator directories. If you do want to configure PATHWORKS or ManageWORKS Workgroup Administrator to load OpenVMS Management Station, see Section G.2.7.

G.2.5.2 Installation Procedure

Follow these steps to install OpenVMS Management Station client:

1. Start your PC as you usually do.
2. Insert disk 1 in your floppy disk drive.
3. Enter the Windows environment and click on the Program Manager icon.
4. In the Menu bar of the Program Manager program group, click on File, and then choose Run from the pull-down menu.

Result: The Run dialog box appears.

5. In the Run dialog box, type:

```
A:\SETUP.EXE
```

where A: is the name of the floppy disk drive.

6. Click on the OK button to start the installation.

Result: A dialog box containing the message “Initializing setup, please wait...” appears. You are then prompted to continue.

7. To proceed with the installation, click on the Next button.

Note: You can stop the installation at any time by clicking on the Cancel button.

As the installation progresses, the system displays a status bar indicating what percentage of the installation is done. Also displayed is a reminder to read the OpenVMS Management Station Read Me file for important information.

8. When you are prompted by a dialog box message, remove disk 1 from the disk drive and insert disk 2. Click on OK.

Repeat this process for the remaining disks.

Preparing to Use OpenVMS Management Station

G.2 Preparing Your PC

G.2.5.3 Recovering from Errors

If an error occurs during installation, you will receive an error message describing the problem. This information can help you determine the cause of the problem. An error can occur during the installation if one or more of the following conditions exist:

- The operating system version is incorrect.
- The prerequisite software version is incorrect.
- Disk space and memory necessary for successful installation are inadequate.

G.2.5.4 Files Created on the PC

The following files (with their directory names) are created on your PC after the OpenVMS Management Station client software is installed:

- OpenVMS Management Station directory (usually \VMSTNT)
 - VMSACNT.DLL
 - VMSACNT.HLP
 - VMSCLU.DLL
 - VMSCUSCT.DLL
 - VMSINFRA.DLL
 - VMSMGMT.DLL
 - VMSMGMT.HLP
 - VMSMSCRL.DLL
 - VMSNODE.DLL
 - VMSPRINT.HLP
 - VMSSCOPE.HLP
 - VMSTAB.DLL
 - VMSTIMEL.DLL
 - VMSUAOMM.DLL
 - CLASS.IDX
 - CLASS.POD
 - CONTAIN.DLL
 - CONTAIN.IDX
 - CONTAIN.POD
 - DISPATCH.DLL
 - MWBROWSE.DLL
 - MW_OEM.DLL
 - MW_OEM2.DLL
 - MW_OEM3.DLL
 - OMMLIB.DLL
 - OBJECT.POD

Preparing to Use OpenVMS Management Station

G.2 Preparing Your PC

- OBJECT.IDX
- POD.DLL
- PRMAKTPL.EXE
- PWMGMT.EXE
- PWMGMT.HLP
- PWMGMT.INI
- PWSHELL.DLL
- SVN.DLL
- SVNVIEW.DLL
- XMEM.DLL
- Windows directory (usually \WINDOWS)
 - XTIDNW.DLL
 - XTILIB.DLL
 - XTIWINS.DLL
 - VMSTNT.INI
- Windows systems directory (usually \WINDOWS\SYSTEM)
 - CTL3DV2.DLL
 - COMPOBJ.DLL
 - MFC250.DLL
 - MFCO250.DLL
 - MFCOLEUI.DLL
 - OLE2.DLL
 - OLE2DISP.DLL
 - OLE2NLS.DLL
 - STORAGE.DLL

G.2.6 After Installing the Client Software on Your PC

OpenVMS Management Station allows you to use both the TCP/IP and DECnet transports to establish connections.

You can have a mix of DECnet and TCP/IP connections, all DECnet connections, or all TCP/IP connections. OpenVMS Management Station does not have any DECnet dependencies and can run in a TCP/IP-only environment. Note that Windows NT and Windows 95 support TCP/IP connections only.

You do need to make sure that your PC can connect to the primary-server systems, as described in the following sections. OpenVMS Management Station connects your PC to the primary-server system and then routes management operations to the target systems.

Preparing to Use OpenVMS Management Station

G.2 Preparing Your PC

G.2.6.1 Defining TCP/IP Nodes

If you select the TCP/IP transport, your host's file or name server must be able to resolve the IP name or address of all primary-server systems. If you can successfully ping the primary-server systems from your PC, then this condition is met.

G.2.6.2 DECnet Support

If you want to use DECnet connections, PATHWORKS Version 5.1 for DOS and Windows must be installed somewhere on the PC and listed in the PC's path statement.

Define the DECnet node names and network addresses of primary-server OpenVMS systems that you want to manage.

G.2.6.3 Procedure for Defining DECnet Nodes

Follow these steps to define DECnet nodes:

Step	Action
1	At the MS-DOS prompt, invoke the NCP utility as follows: C:\> NCP
2	At the NCP> prompt, type the following command: NCP> DEFINE NODE <i>addrs</i> NAME <i>name</i> where <i>addrs</i> is the DECnet address and <i>name</i> is the DECnet node name. Example: NCP> DEFINE NODE 19.208 NAME ISTAR
3	At the NCP prompt, type EXIT and press Return to exit the operation.

G.2.7 PATHWORKS and Workgroup Administrator Support

You no longer need the PATHWORKS client software to run OpenVMS Management Station. OpenVMS Management Station installs into its own directory and includes all of the ManageWORKS components it needs to run.

If you happen to have PATHWORKS or ManageWORKS Workgroup Administrator installed, both will continue to function independently of OpenVMS Management Station.

You can configure PATHWORKS Version 5.1 for DOS and Windows or the ManageWORKS Workgroup Administrator Version 2.2 to load the OpenVMS Management Station software if you want to.

To do this, run the ManageWORKS Setup application and use the Browse feature to select the file ARGUS.MMI in the VMSTNT directory. Refer to the ManageWORKS online help for step-by-step instructions.

G.2.8 POLYCENTER Manager on NetView for Windows NT, Version 3.0

You can launch OpenVMS Management Station from POLYCENTER Manager on NetView for Windows NT, Version 3.0. To do this, copy the file VMSTNT.REG from the temporary directory (or disk 1 if you requested client media) to the following directory:

```
\usr\ov\registration\c\
```

Note that NetView can be installed only on an NTFS partition.

G.3 Getting Started with OpenVMS Management Station

All information about getting started, setting up, and using OpenVMS Management Station is contained in online help and the *OpenVMS Management Station Overview and Release Notes*.

G.3.1 Accessing Online Help

Follow these steps to access the OpenVMS Management Station online help:

1. Open the OpenVMS Management Station program group.
2. Click on the OpenVMS Management Help icon for instructions on how to get started.

Small Capacity System Disks

H.1 Overview

This appendix describes some methods you can use to manage small capacity system disks, along with some specific recommendations for installing or upgrading to OpenVMS VAX Version 7.1 and DECwindows Motif for OpenVMS VAX Version 1.2–3 on an RZ24, RA80, or RM80 system disk. (These recommendations will also work for Versions 1.1 and 1.2 of the DECwindows Motif for OpenVMS VAX layered product.)

Note that you can use the methods described in this appendix to free disk space on any space-constrained system.

H.2 Limited Space Support

As the OpenVMS VAX operating system and associated layered products continue to develop and mature, their sizes have grown so that previously acceptable system disk devices might now have insufficient capacity for the desired computing environment. Support for added features, conformance to standards, addition of online documentation, and especially, support for a graphical user environment (specifically, DECwindows Motif) have contributed to this growth. Although a single-user workstation system might be perceived as entry level, it does, in fact, have an increased need for system disk capacity to handle the desired graphical environment.

H.2.1 Limited Space Support Option

In the past, when the OpenVMS VAX operating system grew too large for a specific disk type, that disk was no longer supported as a system device. The OpenVMS VAX Version 7.1 operating system and the DECwindows Motif for OpenVMS VAX Version 1.2–3 layered product cannot fit, in total, on an RZ24 disk device.

However, to preserve the investment in some user configurations, a *limited space support* option has been introduced that will allow the RZ24 to continue to be used as a system disk but with some features removed. For the most part, these features include new online documentation, programming examples, and programming support files. The most important mechanisms used to provide this environment are the OpenVMS VAX and DECwindows tailoring facilities, VMSTAILOR and DECW\$TAILOR. (For more information about these facilities, see Chapter 10.)

The limited space support option means that, although the disk (in this case, the RZ24) is supported as a system device, you must take some explicit action to not install or to remove some portions of the product so the remainder will fit. This option gives small, resource-constrained system users a choice between investing in new hardware or continuing with existing hardware but with (possibly) reduced capabilities.

Small Capacity System Disks

H.2 Limited Space Support

H.2.2 Configurations Affected

The RZ24 disk is now too small for the full OpenVMS VAX Version 7.1 and DECwindows Motif for OpenVMS VAX Version 1.2–3 kits, regardless of user configuration. Other disk devices, such as the RZ24 and RD54 disks, will need to be closely monitored, depending on the system environment and user configuration.

The general disk space guideline for OpenVMS VAX plus DECwindows Motif for OpenVMS VAX Version 1.2–3 is a system disk of at least 213 megabytes (or about 377,000 disk blocks). For nonworkstation, single-user systems, this guideline can be reduced to about 125 megabytes because DECwindows support is not necessary. For timesharing systems, a larger disk is usually necessary due to the need for many layered products and applications. For VAXcluster systems, a larger system disk capacity is also usually required. See the VAXcluster SPD for details.

For specific information about disk space requirements and supported system disks, see the OpenVMS VAX SPD.

While the absolute minimum disk space requirements can make base system support available, layered products, applications, and user files usually make it necessary to manage even large capacity system disks carefully. Therefore, some of the following techniques and ideas can be useful for a broader range of users than can be listed by hardware type.

H.2.3 Dealing with a Small System Disk

You can solve small system disk configuration problems three ways:

- Upgrade your hardware to a larger capacity disk device.
- Add additional hardware disk devices (one or more) to the system and redistribute the software contents.
- Reduce the software contents on the existing disk device.

Upgrading hardware might have the highest monetary cost, but has the benefits of a full environment and the simplest and fastest upgrade mechanism. Adding additional hardware (or using existing extra hardware) can require less money, but requires more time and effort for setting up and maintaining the environment. Reducing the software contents requires the lowest capital expense but, by necessity, removes some features, documentation, or capabilities.

If your major constraint is fiscal, you might want to investigate the tailoring recommendations first. If time or simplicity are more important, you might want to purchase a larger system disk.

H.3 Tailoring Considerations

Most of this appendix describes the mechanisms for reducing the software contents on the existing disk device, mostly by tailoring. There are also some hints for multiple disk systems. There is nothing specific to recommend for upgrading the hardware device, except that moving up in a single large increment is much more effective than several smaller ones.

The target device in the following sections is the RZ24 disk, which has 209 megabytes of disk space. However, you can use these methods on any system that is tight on system disk space.

H.3.1 Configuration Goals

The basic configuration goal for the limited space support option is for an environment that is not used for programming. Typically, this would be a system with a few user applications or a turnkey system. It is possible to build a viable system with a single programming language environment (notably, the C language); however, the space used for this support and for the compiler reduces the amount of available user space.

There are some mechanisms and techniques common to any space-constrained system both for installing new systems and for upgrading existing systems. One of the most important considerations is to reduce the disk space consumption of the normal, ongoing system environment before doing an upgrade or as soon as possible during or after an installation. Some methods for accomplishing this are discussed in Section H.6 and in Section H.7.

Note that, during an upgrade or installation, there will be a period of time when the windowing software is likely to be unavailable. This means that, on a workstation, your monitor will function only as an operator console, and you will not be able to use screen-oriented editors.

H.3.2 Controlling the Size of Dump, Page, and Swap Files

One of the primary things to control is the sizing of the dump, page, and swap files in AUTOGEN. The tailoring facilities automatically use AUTOGEN to reboot the system, adjusting anything that the tailoring might have affected. Because AUTOGEN normally includes existing disk space in calculating the sizes for these files, unexpected results can occur when tailoring removes some files and AUTOGEN increases the size of others. Fixing the size of these files by adding appropriate lines to the file SYSSSYSTEM:MODPARAMS.DAT will prevent this from occurring during an upgrade or after an installation (and, possibly, while installing layered products).

The following values are suggested as generous for an upgrade:

```
PAGEFILE = 38000  
SWAPFILE = 13500  
DUMPFIL = 0
```

If your system has been running successfully with smaller values, use those instead.

If your windowing system is unavailable, you will not be able to use a screen-oriented editor to add these lines to the SYSSSYSTEM:MODPARAMS.DAT file. You can use the COPY command to add lines to the end of the text file as follows:

```
$ COPY SYSSSYSTEM:MODPARAMS.DAT, SYS$INPUT: SYSSSYSTEM:MODPARAMS.DAT   
newparam1 = value1   
newparam2 = value2   

```

Note

To be able to use the delete key more effectively when typing input to the console, set the operator terminal to be a scope (assuming it is not a hardcopy device). To set the console terminal to be a scope, enter the following command:

```
$ SET TERM/SCOPE/PERM _OPA0:
```

Small Capacity System Disks

H.3 Tailoring Considerations

H.3.3 Make a Backup Copy of Your System Disk

It is important to make a backup copy of your system disk before any system software upgrade. When tailoring and system environment options must be used to fit the required software on the device, it is even more important to make a backup copy before you begin and at major milestones during the procedure. This gives you a fallback to a *last good* position in the event that a subsequent step produces undesired side effects (especially when tailoring software off of the disk) or fails due to unexpectedly running out of space.

H.3.4 Analyze the System Disk

The space used on the system disk might include files that have been only partially deleted (usually, because they were still open when an attempt was made to delete them). To recover this space, enter the following command:

```
$ ANALYZE/DISK/REPAIR SYS$$SYSDEVICE:
```

Continue to use the ANALYZE/DISK/REPAIR command after every reboot or before each major step to be sure that all free blocks are available for the upgrade procedure to use.

H.3.5 Tailoring Options

The installation and upgrade procedures (for both OpenVMS VAX Version 7.1 and DECwindows Motif) let you select optional software to install or upgrade only by save set. The tailoring facilities are capable of finer granularity and can usually select files in smaller groups within the save sets.

In the case of DECW\$MOTIF_TAILOR, the save sets and tailoring groups are the same. Additionally, DECW\$MOTIF_TAILOR can only tailor off. To add files, you must either use the installation or upgrade procedures or use the OpenVMS Backup utility (BACKUP) manually to select the desired files. For the VMSTAILOR and DECW\$TAILOR utilities, the tailorable options are subsets of the installation and upgrade save sets and can be tailored either on or off. If there is sufficient space to take an entire save set, it is usually faster to select it during the procedure and then tailor off the undesired pieces, rather than tailor them on later.

If you are doing an upgrade and have a large area of user application files or a large database that is not part of the OpenVMS VAX operating system or DECwindows Motif layered product but resides on the system disk, it might be convenient to back up that data to a separate piece of media, delete it from the system disk before the upgrade, and then restore it after the upgrade. The blocks can be used in the interim, and you can save time and effort in the tailoring and upgrade process.

You can decrease the time needed to perform the tailoring and upgrade tasks by disabling highwater marking on the system disk. To disable highwater marking, enter the following command:

```
$ SET VOLUME/NOHIGHWATER SYS$$SYSDEVICE:
```

Depending on the system security you require, you might want to leave highwater marking permanently disabled. Otherwise, you can restore it by entering the following command:

```
$ SET VOLUME/HIGHWATER SYS$$SYSDEVICE:
```

H.4 Installing OpenVMS VAX and DECwindows Motif

In general, installing OpenVMS VAX Version 7.1 and DECwindows Motif for OpenVMS VAX Version 1.2–3 is easier than doing an upgrade because there are no user files on the disk when you perform the installation. However, because the total size of the two kits is larger than the capacity of the RZ24 disk, you cannot select some options and you might have to do some tailoring.

H.4.1 Install OpenVMS VAX Version 7.1

By itself, the entire OpenVMS VAX Version 7.1 distribution kit fits on the RZ24 system disk. So, the easiest approach might be to select both the library and optional save sets, then use the VMSTAILOR and DECW\$TAILOR utilities to increase the free space before installing the DECwindows Motif layered product.

If you plan to run DECnet for OpenVMS, be sure to select the library save set. If you do not perform system programming or BLISS programming, do not have an LPA11 device, do not need any of the OpenVMS example files, and do not need the UETP facility, you can choose not to select the optional save set during the installation. The BLISS support in the optional save set (approximately 7000 blocks) and the examples (over 8500 blocks) are two of the largest single areas that you can easily tailor off.

You might choose not to install the Help Message utility (MSGHLP) because this option is also very large (8900 blocks). Or, you can select it at the expense of other tailorable options later (or at the expense of reduced user capacity).

Once the OpenVMS VAX installation is complete, set up the dump file as required. It is preferable not to have a dump file at all or to use the paging file as described in Section H.6.1. Also, set fixed sizes for the page and dump files so that AUTOGEN does not continually resize them as you proceed with tailoring and installing the DECwindows Motif for OpenVMS layered product. When your environment is complete, you can remove the fixed sizes to allow AUTOGEN to calculate appropriate sizes based on the final space on the disk.

To fit the operating system on an RZ24 disk and have sufficient space to add some layered product or application packages and have user space remaining, you can generally support, at most, one programming language and no online examples or manuals. Use the VMSTAILOR and DECW\$TAILOR utilities to remove software you do not need.

H.4.2 Install DECwindows Motif

Depending on the options and setup of your system, you might have sufficient space to install the entire DECwindows Motif for OpenVMS kit. However, it is likely that you again will need to remove support for all but one programming language and not include the examples. Because the programming support save sets for each language are large, choose only the support for languages you really need. In the case of the example files, you might want to install them if you have the space required, and then tailor them off once you have perused them or copied them to another area.

Remember to use the ANALYZE/DISK/REPAIR command to recover any lost space from partially deleted files.

Small Capacity System Disks

H.5 Upgrading OpenVMS VAX and DECwindows Motif

H.5 Upgrading OpenVMS VAX and DECwindows Motif

The following sections describe how to upgrade to OpenVMS VAX Version 7.1 with the DECwindows Motif Version 1.2–3 layered product from an OpenVMS Version 6.1 or 6.2 system running VMS DECwindows Motif Version 1.1. (Note that Version 1.1 is the *minimum* version of DECwindows Motif that you can run on OpenVMS VAX Version 7.1.)

This option requires the most attention and extra tailoring consideration because the disk blocks used by the DECwindows Motif layered product cannot be used during the OpenVMS VAX upgrade procedure. This means that you might not be able to select even the library save set during the upgrade and that you would need to tailor on portions of it (most notably, the DECnet support).

Depending on your configuration, it might be necessary to tailor off DECwindows Motif and then reinstall it following the upgrade.

H.5.1 Upgrading to OpenVMS VAX Version 7.1

Before beginning the upgrade procedure, prepare the system environment—notably the dump, page, and swap files (see Section H.3.2)—and remove as many excess files from the system disk as possible. Use the tailoring facilities to remove files that will be replaced or obsoleted by the upgrade procedure. This is a good way to get the necessary space (48,950 blocks) to start the upgrade but probably will not contribute to the final additional capacity required.

Tailor off all the OpenVMS programming files, examples, and miscellaneous utilities and any DECwindows Motif support that is not required. Before upgrading the operating system, keep, at most, one language support option, and do not keep any DECwindows Motif examples unless you have sufficient space to get at least the OpenVMS VAX required and library save sets directly in the upgrade.

If you have sufficient space after tailoring to allow both the OpenVMS VAX required and library save sets to be selected, then the upgrade will include DECnet support and DECwindows Motif will start normally after the upgrade.

If you cannot select the library save set, the lack of DECnet support will likely keep DECwindows Motif from starting on your system (at which point you will have only the operator window on your workstation). You can then tailor on the DECnet support to get DECwindows Motif for OpenVMS running again. After you have DECwindows Motif running, tailoring on any other pieces you might not have already acquired from either the library or optional save sets will be easier.

Digital recommends that you not take the optional Help Message utility (unless you install it on an alternate device). You will want to choose the DECwindows device support if you are upgrading a workstation.

Remember to use the ANALYZE/DISK/REPAIR command to clean up any partially deleted files.

H.6 Managing Single or Small System Disk Systems

The primary goal for this type of environment is to reduce the system disk block usage incurred by the OpenVMS VAX system during normal operation. Both dynamic usage and static requirements can be reduced in various ways. Some system processing overhead can also be reduced or eliminated in this fashion, along with a corresponding reduction in system disk I/O.

Small Capacity System Disks

H.6 Managing Single or Small System Disk Systems

H.6.1 System Dump File

One of the best mechanisms for reducing the total block overhead of the system is to carefully define the usage of the system dump file. Normally, this is configured as a separate file, `SYSSYSTEM:SYSDUMP.DMP`, to which the contents of memory are written after a detected system failure. Depending on your system requirements, you might be able to reduce or eliminate this disk usage.

One effective technique is to use part of the system paging file, `SYSSYSTEM:PAGEFILE.SYS`, as a temporary dump file, so that the space used for dump files is not permanently reserved and gets used only in the event of a crash. To do this, you will need to modify some system parameters in `SYSSYSTEM:MODPARAMS.DAT` and delete the actual `SYSDUMP.DMP` file if it exists. This method is most effective for systems having small or medium memory sizes.

Alternately, you might set the `DUMPSTYLE` parameter to use the selective dump mechanism to reduce the size of the dump file. This method is typically used for large memory systems that do not need to preserve the entire memory contents in the event of a system failure. Instead of using selective dumps to the paging file, keep a separate, but smaller, `SYSDUMP.DMP` file.

If you have no need to preserve dump files or are running in a very stable environment, you might want to clear the `DUMPCLEAR` parameter to avoid all dump processing and not write a dump file on failure.

H.6.2 Using `PAGEFILE.SYS` for the Dump File

To use the system paging file as a dump file, add the following lines to the `SYSSYSTEM:MODPARAMS.DAT` file:

```
DUMPCLEAR = 1 ! Enable system dumps (default)
SAVEDUMP = 1 ! Keep dump in pagefile until analysis
DUMPPFILE = 0 ! Disallow AUTOGEN to create or size dump file
```

Then delete the `SYSDUMP.DMP` file by entering the following command:

```
$ DELETE SYSSYSTEM:SYSDUMP.DMP;*
```

Because the system currently has the file open, the delete command will not physically remove the file until the system is shut down and rebooted. Use the `AUTOGEN` facility to reboot the system. When it has rebooted, enter the following command to clean up and finish the deletion of the file (and any others that were in a similar state):

```
$ ANALYZE/DISK/REPAIR SYS$SYSDEVICE:
```

After a system failure that writes dump information to the pagefile, you can analyze the data by entering the following command:

```
$ ANALYZE/CRASH SYSSYSTEM:PAGEFILE.SYS
```

When your analysis is complete, you can free the pages to be used for paging once again by entering the following command:

```
$ ANALYZE/CRASH/RELEASE SYSSYSTEM:PAGEFILE.SYS
```

For more information about the system dump file, see the *OpenVMS VAX System Dump Analyzer Utility Manual*.

Small Capacity System Disks

H.6 Managing Single or Small System Disk Systems

H.6.3 Decompressing Libraries

The OpenVMS help libraries (as well as some programming libraries) are distributed in a compressed format. You can use the `SYSS$UPDATE:LIBDECOMP.COM` procedure to decompress the libraries all at once or individually. For a small system disk, it is almost never worth the extra disk blocks consumed to decompress these libraries. The cost of leaving them compressed is a longer access time when you use them.

If you frequently use help or an individual programming library, it might be worthwhile to individually decompress those libraries. If you only infrequently use help or do not mind the slower response time of the libraries in compressed form, leave them compressed.

H.6.4 Disabling Log File Creation

Depending on your environment, there might be system jobs that create log files of no concern to you or that contain more information than you need.

Unless you are a network manager or experiencing network problems, you probably do not need to log network events. By not logging network events, you can save disk space, a process slot, and some memory in the running system. To disable network logging, enter the following commands:

```
$ MCR NCP PURGE KNOWN LOGGING ALL
$ MCR NCP CLEAR KNOWN LOGGING ALL
```

You need to enter these commands only once; they become permanent unless you reset the DECnet logging information.

To reduce the logging information for other tasks (such as OPCOM, Accounting, Security Auditing, Network Monitor Event Listener, and system-created batch log files), you need to add some commands to your system-specific startup command file, `SYSS$MANAGER:SYSTARTUP_VMS.COM` (previously called `SYSTARTUP_V5.COM`).

Small Capacity System Disks

H.6 Managing Single or Small System Disk Systems

The following is an example SYSTARTUP_VMS.COM command file for a single-user workstation:

```
$ SET NOON      ! Continue thru any problems.
$!
$ DEFINE/USER SYS$COMMAND_OPA0: ! Disable some events from
$ REPLY/DISABLE=(NETWORK,CLUSTER,SECURITY) ! using the operator window.
$ SET TERM/SCOPE/PERM_OPA0: ! If windows do not start, use as scope.
$!
$ SET AUDIT/ALARM - ! Log interesting audit events.
/ENABLE=(AUDIT,AUTHORIZATION,ACL,LOGIN=(LOCAL,DIALUP,NETWORK,REMOTE),-
LOGFAILURE=ALL,BREAKIN=ALL)
$!
$ IF F$SEARCH("SYS$MANAGER:ACCOUNTNG.DAT;-1") .NES. "" THEN -
PURGE SYS$MANAGER:ACCOUNTNG.DAT/KEEP=4 ! Purge old accounting info
$!
$ IF F$SEARCH("SYS$MANAGER:OPERATOR.LOG;-1") .NES. "" THEN -
PURGE SYS$MANAGER:OPERATOR.LOG/KEEP=4 ! Purge old operator info
$!
$ DEFINE/SYSTEM/EXEC SYS$SYLOGIN SYS$MANAGER:SYLOGIN ! Set up system login
$!
$ ENABLE AUTOSTART/QUEUES ! Provide resources for autostart queues
$ START/QUEUE SYS$BATCH ! Start a batch queue
$!
$ SUBMIT/NOKEEP/NOPRINT SYS$MANAGER:STARTNET ! Start net without batch log
$!
$! ... add other system specific and layered product commands here ...
$!
$ EXIT
```

You might have an environment that can function with even less information than that shown in the example. For example, to disable the operator log file, you would use REPLY/NOLOG, or to disable accounting, you would use SET ACCOUNTING/DISABLE. For more information about using these commands, see the *OpenVMS DCL Dictionary*.

H.6.5 Accessing Example and Documentation Files

If you have network access to another OpenVMS system (especially a timesharing system), you do not need to duplicate the example files distributed in the OpenVMS VAX or DECwindows Motif kits if they are available on the remote system. Similarly, remote access to the on line documentation files will also save considerable disk space on any system with constrained disk space.

H.7 Managing Multiple Disk Systems

The following sections describe techniques for managing multiple disk systems. In addition to the goal of reducing the space requirements on the system device, it is possible to simultaneously reduce some of the I/O load to the system disk by redirecting necessary functions to an alternate device.

H.7.1 Alternate Page and Swap Files

Setting up alternate page and swap files is one of the best ways to reduce both the system disk space usage and I/O overhead. If you set up only a small primary page file on the system disk and install additional page and swap files in the startup command file SYS\$MANAGER:SYPAGSWPFILES.COM, you can permanently cause these files to consume the least amount of space on the system device. For more information about setting up alternate page and swap files, see the *OpenVMS System Manager's Manual*.

Small Capacity System Disks

H.7 Managing Multiple Disk Systems

H.7.2 Copying Dump Files

At startup, you can enhance the use of the paging file as a dump file that will automatically copy dump data for later analysis. This releases the disk space in SYS\$SYSTEM:PAGEFILE.SYS to be used for paging automatically as well. Instead of manually invoking the System Dump Analyzer (SDA) to release the pages, you can add the following commands to the SYS\$MANAGER:SYSTARTUP_VMS.COM file:

```
$ ANALYZE/CRASH SYS$SYSTEM:PAGEFILE.SYS
COPY alternate_disk:[dir] dumpname.ext
EXIT
```

Note

The dump file, whether it is SYSDUMP.DMP or PAGEFILE.SYS, must reside on the system disk. This might limit the actual savings you can achieve using alternate page files.

H.7.3 Offloading System Logs and Files

There are several system logs and files that can be redirected to another device. For other system logs and files, it might be easier to reset and start a new log file, copy the old file or files to another device, and purge them from the system disk.

Some files that can be redirected are the system authorization file, the queue manager database, the audit log file, and batch log files. Some files that can be reset, copied, and purged are the operator log file, the accounting log file, and network log files. For more information about these facilities see the *OpenVMS System Manager's Manual*, the *OpenVMS DCL Dictionary*, or the utility reference manual for the utility whose files you want to offload.

H.7.4 Offloading Nonessential Files

Some of the files included with OpenVMS VAX Version 7.1 can be redirected to an alternate device during the installation or upgrade procedure. This can save many valuable system disk blocks while providing quick access to these files. For a small system disk configuration with multiple disks, this approach is recommended if you want the the Help Message utility (MSGHLP) to be available on line.

Glossary

boot, bootstrap

The process of loading system software into a processor's main memory. This guide uses the term *boot* to refer to this process.

boot command procedure

A program, stored on the console fixed disk, that is used to boot the OpenVMS operating system from a specified controller. Digital provides a boot command procedure for each controller that the processor supports.

boot name

The abbreviated name of the boot command procedure you use to boot the system.

boot server

A VAX computer that is part of a local area VAXcluster. The boot server is a combination of a MOP server and a disk server for the satellite system disk. See also satellite node.

CI only VAXcluster

A computer system consisting of a number of VAX computers. It uses only the computer interconnect (CI) to communicate with other VAX computers in the cluster. These computers share a single file system.

computer interconnect (CI)

A type of I/O subsystem. It links VAX computers to each other and to HSC devices. See also *Hierarchical Storage Controller (HSC) device*.

DECW\$TAILOR

A software program that lets you add or remove DECwindows files from your system disk.

device name

The name used to identify a device on the system. A device name indicates the device code, controller designation, and unit number.

disk server

A VAX computer that is part of a local area VAXcluster. This computer provides an access path to CI, CSSI, and locally-connected disks for other computers that do not have a direct connection.

Hierarchical Storage Controller (HSC) device

A self-contained, intelligent, mass storage subsystem that lets VAX computers in a VAXcluster environment share disks. Examples are the HSC50 and the HSC70.

HSC drive

Any disk or tape drive connected to an HSC device is called an HSC drive. A system disk on an HSC drive can be shared by several VAX computers in a VAXcluster environment.

InfoServer

A general-purpose disk storage server that allows you to use the distribution compact disc to install the operating system on remote client systems connected to the same LAN (local area network).

local area VAXcluster

A configuration consisting of one or more VAX computers that act as a MOP server and disk server, and a number of low-end VAX computers that act as satellite nodes. The local area network (LAN) connects all of the computers. These computers share a single file system.

local drive

Any drive that is connected directly to a VAX computer.

media

Any packaging agent capable of storing computer software. Examples: compact discs, magnetic tapes, floppy diskettes, disk packs, tape cartridges.

MOP server

A computer system running DECnet that downline loads VAXcluster satellites using the DECnet MOP protocol.

satellite node

A VAX computer that is part of a local area VAXcluster. A satellite node is downline loaded from a MOP server and then boots remotely from the system disk served by a disk server in the local area VAXcluster. See also boot server, disk server, MOP server.

save set

The format in which the Backup utility stores files. The OpenVMS operating system is shipped in this format.

scratch disk

A blank disk or a disk with files you no longer need.

source drive

The drive that holds the distribution kit during an upgrade or installation.

spin up, spin down

To spin up means to bring a disk drive up to operating speed; to spin down means to bring it to a gradual stop.

standalone BACKUP

A subset of the BACKUP utility that is booted into main memory instead of running under the control of the OpenVMS operating system. Standalone BACKUP is used to back up and restore the system disk and to install OpenVMS operating system software.

standalone system

A computer system with only one VAX computer.

system disk

The disk that contains or will contain the OpenVMS operating system. An OpenVMS system disk is set up so that most of the OpenVMS files can be shared by several VAX computers. In addition, each computer has its own directory on the system disk that contains its page, swap, and dump files.

target drive

The drive that holds the system disk during an upgrade or installation.

transaction log

A log used by DECdtm services to record information about transactions. The Log Manager Control Program (LMCP) is used to create a transaction log.

UETP (User Environment Test Package)

A software package that tests all the standard peripheral devices on your system, various commands and operating system functions, the system's multiuser capability, DECnet for OpenVMS, and the VAXcluster environment.

VAXcluster environment

A computer system consisting of a number of VAX computers. There are three types of VAXcluster environments: CI only, local area, and mixed interconnect.

VMSTAILOR

A software program that lets you add or remove optional OpenVMS files from your system disk.

A

- Accounting logs
 - effect of upgrades on, 5-3
- Accounts
 - disabling during an installation, 3-14
 - setting up after an installation, 4-2
- AGENSINCLUDE files
 - location for upgrades, 5-11
- AGENSPARAMS.REPORT file, 4-7, 8-12
- Allocation classes
 - determining, 2-3
- ALLOCLASS parameter, 2-3
- ANALYZE/DISK_STRUCTURE utility
 - error message, 5-8
 - using before an upgrade, 5-8
- Auditing files
 - replacing after upgrade, 8-2
- AUTOGEN
 - accessing data files during an upgrade, 5-11
- AUTOGEN command procedure
 - feedback data, 5-5
 - running
 - after an installation, 4-7
 - after an upgrade, 8-11
 - at end of an installation, 3-21
 - at end of an upgrade, 7-19
 - before an upgrade, 5-5
- Automatic restart
 - for an upgrade, 5-12

B

- Backing up the system disk, 4-6, 8-11
- BACKUP command
 - using to create a system disk, 3-4
- Backup procedures
 - before an upgrade, 5-6
- Boot command procedures
 - dddGEN, 7-16
 - DEFBOO, 7-16
- Booting
 - from console media, 7-8
 - from [SYSF], C-1 to C-6
 - manually during an upgrade, 7-8
 - with InfoServer ISL file, 3-2

- Building standalone BACKUP, 4-2

C

- C2 systems, 2-3
- Checklists
 - postinstallation, 4-7
 - postupgrade, 8-12
 - preinstallation, 2-6
 - preupgrade, 5-15
- CI only VAXcluster
 - information needed to install, 2-3
- Clusters
 - See also VAXcluster environments
 - group numbers, 2-4
 - passwords, 2-4
- Cluster upgrades
 - See Concurrent upgrades
 - See Rolling upgrades
- CLUSTER_SIZE parameter
 - of system disk, 3-5
- Command procedures
 - checking after an upgrade, 8-3
- Common files
 - coordinating for multiple boot servers, G-2
 - coordinating for multiple system disks, G-2
- Compact disc kit
 - contents of, 1-5
- Computer-specific installation instructions, 3-1
- Concurrent upgrades, 6-1
 - restrictions, 6-1
 - setting QUORUM parameter, 6-2
 - upgrade procedures, 6-2
- CONSCOPY.COM procedure, 5-7
- Console
 - connecting with SYSGEN, 8-4
- Console media
 - automatic update during an upgrade, 5-7
 - backing up after an upgrade, 8-11
 - backing up before an upgrade, 5-7
 - booting from during an upgrade, 7-7
 - copying, 5-7
 - modifying for automatic restart, 5-12
 - modifying to boot from [SYSF], 7-7
 - required for an installation, 2-7
 - required for upgrades, 5-5

- Console media (cont'd)
 - restoring original boot command procedures, 7-16
 - updating after an upgrade, 8-4
 - using backup copies, 5-7
- Creating a system disk, 3-4
 - from InfoServer devices, 3-7
- Customizing the system, 4-2

D

- Date
 - format for entering, 7-6
- dddGEN boot command procedure
 - restoring original version, 7-16
- DECnet
 - configuring after an installation, 4-3
- DECnet for OpenVMS
 - preparing for an upgrade, 5-12
- DECnet node addresses, 2-3
- DECnet node names, 2-3
- DECnet Phase IV, 1-1
 - ignoring during startup, 4-4
 - installing on system, 1-1
 - running with DECwindows Motif, 4-4
- DECnet-Plus, 1-1
 - choosing to install, 3-11, 7-12
 - installing during an installation, 3-20
 - installing during an upgrade, 7-18
 - removing from system, 1-1
- DECnet-Plus license
 - registering after an installation, 4-2
 - registering during an installation, 3-19
 - registering during an upgrade, 7-17
- Decompressing system libraries
 - after an installation, 4-4
 - after an upgrade, 8-7
- DECset Version 11
 - caution before upgrading, 5-2
 - changing the default debugger
 - after upgrading, 5-2
 - before upgrading, 5-2
- DECWSIGNORE_DECNET logical name, 4-4
- DECWSMOTIF_TAILOR utility, H-4
- DECWSTAILOR utility
 - using on a small system disk, H-4
 - using to install optional components, 3-8
 - using to remove files from a system disk, 4-6, 8-8, 10-7, 10-8
- DECwindows Motif for OpenVMS
 - minimum version requirement, 1-2
 - support for, 3-10
 - tailoring, 8-8
 - using with OpenVMS VAX Version 7.1, 2-2
- DECwindows support components, 5-14
 - base support, 3-10, 7-11
 - choosing options
 - during an installation, 3-10

- DECwindows support components
 - choosing options (cont'd)
 - during an upgrade, 7-11
 - customizing, 9-1
 - customizing after an upgrade, 8-9
 - customizing the server, 9-1
 - display server files, E-1
 - distribution media
 - removing from drive, 3-13
 - font files, E-1
 - installing, 2-6, 3-13
 - sizes, 3-10, 7-11
 - TCP/IP transport, 9-5
 - transports, 9-5
 - using customer-written transports, 9-6
 - workstation support, 3-10, 7-11
- Default volume label, 3-7
- DEFBOO boot command procedure
 - restoring original version, 7-16
- Device names
 - determining, 2-4, 3-4
 - format for upgrade, 7-4
 - HSC name format for an upgrade, 7-4
- Devices
 - configuring before an upgrade, 7-2
- DIGITAL Storage Systems Interconnect (DSSI)
 - disks
 - See DSSI disks
- Digital TCP/IP Services for OpenVMS
 - configuring, 9-6
 - function, 9-5
 - installing mandatory update, 4-6, 8-10
- Directories
 - processed during an upgrade, 7-15
- Directory trees
 - merged during an upgrade, 7-15
- Disk drives
 - selecting for an installation, 2-4
- Disk space
 - increasing on the system disk, 8-8, H-1
 - needed for an upgrade, 5-9
 - needed to decompress libraries, 8-7
 - needed to decompress system libraries, 4-4
 - needed to run UETP, 4-4, 8-8
- Distribution kit
 - compact disc, 1-5
 - magnetic tapes, 1-5
 - OpenVMS VAX, 3-2
 - save sets in, 1-4
 - Standalone BACKUP, 3-2
 - tape cartridges, 1-5
 - TK50 tape cartridges in, 3-1
 - with multiple volumes, 3-1
- Distribution media, 1-3
 - loading, 7-3
 - location during an upgrade, 5-3
 - multiple volumes, 7-3

DSSI disks
device name change, 2-2

Dump files
checking size, 8-3
controlling size of, H-3
modifying size, 8-3
purged during an upgrade, 7-13
requirement for an upgrade, 5-8
shared, 5-4, 5-8

E

Editing startup files, 4-2
Error formatter (ERRFMT)
stopped during an upgrade, 7-7
Errors during installation
license messages, 3-6
Errors during upgrades
cluster hang during shutdown, 6-4
console update, 8-5
while entering device code, 7-5
EXPECTED_VOTES parameter, 8-4
setting for rolling upgrade, 6-4

F

Factory installed software
See FIS
Feedback data
checking before an upgrade, 5-5
FIELD account
setting passwords, 3-14
FIS (Factory installed software), xiii

H

Hardware
supported, G-7
Help Message save set
contents, D-2
Help Message utility
installing, 2-5, 3-9
Hierarchical Storage Controller (HSC)
See HSC
HSC
device format for an installation, 3-4
device format for an upgrade, 7-4
displaying name of, 2-4
drives, 1-4
names, 3-4
preparing for installations, 2-4

I

InfoServer devices, 1-4
booting Standalone BACKUP, 3-2
creating the system disk from, 3-7
Initial software load (ISL)
See ISL
Installation
of layered products, 4-6, 8-10
Installation procedure, 1-6
See also Postinstallation tasks
See also Preinstallation tasks
booting standalone BACKUP, 3-1
booting system disk after transferring required
save set, 3-6
computer-specific instructions, 3-1
rebooting the system, 3-22
registering licenses, 3-16
registering OpenVMS VAX license, 3-22
running AUTOGEN, 3-21
selecting optional components, 3-8
setting passwords, 3-14
stages of, 3-1
time zones, 3-20
when to use, 1-6, 2-1
Installing
DECwindows software, 3-13
optional components, 3-7
Installing the operating system, 3-1
C2 systems, 2-3
cautions and restrictions, 2-1
information needed for VAXcluster systems,
2-3
preparing for, 2-3
recording log of, 2-2
VMSINSTAL option G warning, 2-1
ISL (initial software load)
booting, 3-2

K

Keyboards
customizing, 9-2
layout, 9-1
DECwindows keymap, 9-3 to 9-5
model numbers, 9-2
Keymap names
determining, 9-2
KFQSA controller
upgrade requirement, 5-11

L

Layered products

- availability of, 1-3
- effect of upgrade on, 5-5
- installing after OpenVMS VAX installation, 4-6
- installing after upgrade, 8-10

LIBDECOMP.COM procedure, 8-7

- running after an installation, 4-5
- running after an upgrade, 8-7

Libraries

- decompressing after an installation, 4-4
- decompressing after an upgrade, 8-6, 8-7

Library save set

- contents, D-1
- installing, 3-8, 7-9

License Management facility

- See LMF

Licenses

- See also LMF
- See also PAK
- error messages, 3-6
- registering after an installation, 4-2
- registering during an installation, 3-16, 3-18
- registering during an upgrade, 7-17
- required for upgrades, 5-1
- types of, 3-16 to 3-17

License Unit Requirement Table

- See LURT

Limits

- minimum values, 5-9

LMF (License Management facility)

- error messages, 3-18
- example of registration, B-2
- license registration procedure, B-1
- system integrated product licenses, B-7
- using during an installation, 3-18
- Volume Shadowing software, B-7

Local Area VAXcluster

- information needed to install, 2-3
- upgrade requirements, 5-3

Local drives, 1-4

LURT (License Unit Requirement Table), B-3

M

Magnetic tape kit

- contents, 1-5

Manual boot

- after running AUTOGEN, 7-19
- during an upgrade, 7-8, 7-16
- enabling for an upgrade, 5-12

Memory requirements

- restrictions, 1-3

MicroVAX computers

- booting from [SYS0], 7-16
- booting from [SYSF], 7-13, C-1

Minimum startup

- configuring devices after, 7-2
- setting before an upgrade, 5-10

Mixed-interconnect VAXcluster

- information needed to install, 2-3
- upgrade requirements, 5-3

Mixed-version cluster

- upgrading to, 6-3 to 6-5

MODPARAMS.DAT (parameter file), 4-7

- entering parameters in, 5-12
- modifying, 8-4
- modifying values, 8-11

Monochrome workstations, 9-2

Multiversion upgrade, A-1

N

NETCONFIG.COM procedure

- running after an installation, 4-3

Network

- See also DECnet for OpenVMS
- requirements for an upgrade, 5-13
- restriction on upgrades, 5-3

Networks

- configuring the system for, 4-3

NEW_OVER files, F-2

NEW_UNDER files, F-2

O

OPCOM

- stopped during an upgrade, 7-7

OpenVMS library files

- choosing during an upgrade, 7-9

OpenVMS Management Station

- installing, 3-9, 7-10
- postupgrade tasks, 8-10

OpenVMS optional components

- See Optional components

OpenVMS RMS Journaling license

- registering after an installation, 4-2
- registering during an upgrade, 7-17

OpenVMS VAX distribution media

- loading, 3-4

OpenVMS VAX license

- registering after an installation, 4-2

OpenVMS versions

- computer support, B-2
- required for upgrades, 5-4

Operator logs

- effect of upgrades on, 5-3

Optional components

- choosing, 2-5
- installing on alternate disks, 3-8
- installing with DECWSTAILOR, 3-8

Optional components (cont'd)

- installing with VMSTAILOR, 3-8
- selecting, 3-8
- selecting during an installation, 3-7
- selecting during an upgrade, 7-9
- sizes, 3-7

Optional save set

- contents, D-2
- installing, 3-8, 7-10
- upgrading, 7-9

P

Page and swap files

- locating, 2-4

Page files

- checking size, 5-9, 8-3
- controlling size of, H-3
- modifying size, 5-9, 8-3
- purged during an upgrade, 7-13
- recommended location, 5-8
- size required for an upgrade, 5-9

PAK (Product Authorization Key)

- registering after an installation, 4-2
- registering during an upgrade, 7-17
- registering during installation, 3-18

Passwords

- forgotten, 3-23, 7-20
- for system accounts, 2-5
 - setting during installation, 3-14
- minimum length, 3-14
- modifying during upgrade procedure, 7-6
- requirements, 7-6

Phase 1 of upgrade procedure, 7-6

Phase 2 of upgrade procedure, 7-14

Phase 3 of upgrade procedure, 7-15

Phase 4 of upgrade procedure, 7-15

Phase 5 of upgrade procedure, 7-16

Phase 6 of upgrade procedure, 7-17

Postinstallation tasks, 4-1

- adjusting system parameters, 4-2
- backing up the system disk, 4-2, 4-6
- configuring DECnet, 4-3
- creating standalone BACKUP, 4-2
- customizing DECwindows support software, 9-1
- customizing the system, 4-2
- decompressing system libraries, 4-4
- editing startup procedures, 4-2
- installing layered products, 4-6
- registering licenses, 4-2
- removing unwanted system files, 4-6
- running UETP, 4-4
- setting up user accounts, 4-2
- tuning the system with AUTOGEN, 4-7

Postupgrade tasks

- adding and removing files, 8-8
- backing up console media, 8-11

Postupgrade tasks (cont'd)

- backing up system disk, 8-11
- changing MODPARAMS.DAT, 8-4
- checking system file sizes, 8-3
- creating standalone BACKUP, 8-11
- customizing DECwindows support, 8-9
- decompressing system libraries, 8-6 to 8-8
- examining command procedure templates, 8-3
- increasing space on the system disk, 8-8
- installing layered products, 8-10
- modifying size of dump file, 8-3
- modifying size of page file, 8-3
- modifying size of swap file, 8-3
- purging system files, 8-9
- replacing SYSUAF.DAT, 8-2
- replacing VMSSAUDIT_SERVER.DAT, 8-2
- running AUTOGEN, 8-11
- running UETP, 8-8
- tuning the system with AUTOGEN, 8-11
- updating console media, 8-4
- using VMSTAILOR, 8-8

Preinstallation tasks, 2-3

- collecting information, 2-5
- determining HSC name, 2-4
- preparing for VAXcluster environments, 2-3
- preparing tape drives, 2-4

Preupgrade tasks, 5-1

- analyzing and repairing the system disk, 5-8
- backing up console media, 5-7
- backing up the system disk, 5-6
- checking page file size, 5-9
- configuring devices, 7-2
- creating standalone BACKUP, 5-7
- preparing DECnet for OpenVMS, 5-12
- preparing the system disk, 5-7
- preventing interactive logins, 5-12
- running AUTOGEN, 5-5
- setting system parameters, 5-10
- stopping queues, 5-13

Products (VMSINSTAL)

- specifying for an upgrade, 7-5

PURGE command, 8-9

Purging system files, 8-9

Q

Queue database

- creating after an upgrade, 4-2

Queue manager

- restoring preferred node list, 8-2

Queues

- requirements for an upgrade, 5-13
- stopping batch/print, 5-13
- stopping before an upgrade, 5-13

Quorum

- maintaining during rolling upgrades, 6-4

Quorum disk, 2-3
QUORUM parameter
 setting for concurrent upgrades, 6-2
Quotas
 checked during an upgrade, 7-7
 minimum values, 5-9

R

Rebooting
 after an installation, 3-22
 manual, 5-12
Recording an installation, 2-2
Removing unwanted system files, 4-6
Required save set
 transferring to the system disk, 3-4
Restart
 enabling automatic, 5-12
Restrictions
 for installations, 2-2
Rights database
 creating during an installation, 3-15
RIGHTSLIST.DAT file
 creating during an installation, 3-15
RMS Journaling for OpenVMS license
 registering during an installation, 3-19
Rolling upgrades, 6-1
 effect on SYSUAF.DAT, 8-2
 effect on SYSUAF.DAT file, 5-8
 maintaining cluster quorum, 6-4
 restrictions, 6-1, 6-3
 source drive requirement, 6-4
 upgrade procedures, 6-3 to 6-4

S

Satellites nodes
 upgrade requirements, 5-3
Save sets
 installing on an alternate disk, 5-14
 location on magnetic tape, 1-5
 required location, 1-4, 2-2
 tape cartridge containing, 3-2
 transferring to the system disk, 3-4
SCSNODE parameter, 5-10
SCSSYSTEMID parameter, 5-10
Selecting optional components, 7-9
Server
 customizing the DECwindows, 9-1
Shared memory
 restrictions, 1-3
Shutdowns
 before an upgrade, 5-7
Site-specific command procedures
 restored during an upgrade, 7-17, 8-3
Snapshot facility
 resetting the BOOT_STYLE parameter, 5-11

Software Product Descriptions (SPDs)
 See SPDs
Source drives, 1-4
 definition, 7-2
 requirement for VAXcluster upgrade, 6-4
SPDs (Software Product Descriptions)
 location on the distribution kit, 1-5
STABACKIT.COM (procedure to create standalone
 BACKUP), 5-7
Standalone BACKUP
 booting, 3-1
 booting from InfoServers, 3-2
 booting from tape cartridges, 3-1
 booting on VAX 9000 computers, 3-2
 creating after an upgrade, 8-11
 creating a kit, 4-2
 creating before an upgrade, 5-7
 loading media, 3-1
 locating on distribution kit, 3-1
 on multiple volumes, 3-1
 upgrade requirements, 5-7
 using alternative backup procedure, 3-3
Startup files
 editing after an installation, 4-2
STARTUP_P1 parameter
 setting to MIN, 5-10
Swap files
 checking size, 8-3
 controlling size of, H-3
 creating, 5-9
 modifying size, 8-3
 purged during an upgrade, 7-13
 recommended location, 5-8
SWAPFILES.COM procedure
 executing to change system file sizes, 8-3
 to check or modify page file size, 5-9
 to create swap file, 5-9
SYCONFIG.COM procedure
 editing after an installation, 4-2
SYLOGICALS.COM procedure
 editing after an installation, 4-2
SYLOGIN.COM procedure
 editing after an installation, 4-2
SYS\$TIMEZONE.DAT file, 7-8
[SYSF] directory
 booting from during an upgrade, 7-13, C-1
 booting from during upgrade, 7-1
 command to boot MicroVAX and VAXstation
 computers from, 7-13
[SYSF] directory tree
 built by upgrade procedure, 7-8
 deletion of, 7-16
SYSGEN parameters
 See System parameters
SYSGEN utility
 ALLOCLASS parameter, 2-3
 configuring devices, 7-2

SYSGEN utility (cont'd)
 using to connect console, 8-4
 SYSTARTUP_VMS.COM procedure
 editing after an installation, 4-2
 editing to control DECnet Phase IV, 4-4
 SYSTEM account
 forgotten passwords, 3-23, 7-20
 limits, 5-9
 quotas, 5-9
 setting passwords, 3-14
 System disks, 1-4
 analyzing and repairing, 5-8
 backing up, 8-11
 backing up after an installation, 4-2, 4-6
 backing up before an upgrade, 5-6
 booting a backup copy, 5-7
 booting after an installation, 3-22
 booting after transferring required save set,
 3-6
 checking amount of free space on, 4-5
 CLUSTER_SIZE parameter, 3-5
 creating, 3-4
 customizing with DECWSTAILOR, 4-6, 10-7,
 10-8
 customizing with VMSTAILOR, 4-6, 8-8, 10-1
 dealing with limited space, H-1, H-2
 disk space needed to run UETP, 4-4, 8-8
 free space needed for an upgrade, 5-9
 free space needed to decompress libraries, 4-5
 preparing for an upgrade, 5-7
 preparing for installations, 2-4
 removing unwanted files from, 4-6
 required location during an upgrade, 7-16
 restrictions, 1-3
 RZ24, H-2
 space requirements, H-2
 specifying volume label for, 3-7
 System files
 modifying, 8-3
 purging, 8-9
 System Generation utility
 See SYSGEN utility.
 System hang, 7-20
 System libraries
 decompressing, 3-15, 8-6 to 8-8
 sizes after decompressing, 8-6
 System parameters
 adjusting, 4-2
 generated by AUTOGEN feedback, 5-5
 requirements for an upgrade, 5-3, 5-10
 System password dictionary
 restoring after an upgrade, 8-9
 System shutdowns
 after an installation, 3-22
 System time, 4-1, 8-2
 SYSTEST account
 setting passwords, 3-14

SYSTEST_CLIG account
 disabling during an installation, 3-14
 SYSUAF.DAT file
 See UAF

T

Tailored system disks
 See DECWSTAILOR utility
 See VMSTAILOR utility
 Tailoring
 on small system disks, H-2
 Tape cartridge
 containing save sets, 3-2
 containing standalone BACKUP, 3-1
 Tape drives
 preparing for an installation, 2-4
 selecting for an installation, 2-4
 Target disk
 using backup copy for, 5-6
 Target drives, 1-4
 definition, 7-2
 TCP/IP software
 See Digital TCP/IP Services for OpenVMS
 Time
 format for entering, 7-6
 Time zones
 updating during an installation, 3-20
 updating during an upgrade, 7-18
 TK50 tape kit
 contents of, 1-5
 Transferring save sets to the system disk, 3-4

U

UAF (user authorization file)
 effect of rolling upgrades on, 5-8, 8-2
 purged during an upgrade, 7-13
 replacing after upgrade, 8-2
 required location, 5-8
 UETP (User Environment Test Package)
 disk space needed to run, 4-4, 8-8
 when to run, 4-4, 8-8
 UPDATE_CONSOLE.COM procedure
 running after an upgrade, 8-6
 Upgrade and installation supplements
 using, 2-2, 3-1
 Upgrade preparation, 5-11
 Upgrade procedure, 1-9
 automatic update of console media, 5-7
 booting from console media, 7-7, 7-8
 booting from [SYSF], 7-13
 booting manually during, 7-8
 building [SYSF] directory, 7-8
 cautions and restrictions, 5-1
 choosing optional OpenVMS components, 7-9
 concurrent upgrades, 6-2

Upgrade procedure (cont'd)

- console media required, 5-5
 - conversion of VAXVMSSYS.PAR, 7-16
 - correcting directory pointers, 7-15
 - deletion of [SYSF] directory tree, 7-16
 - disk space needed for page files, 5-9
 - disk space requirement, 5-9
 - effect on accounting logs, 5-3
 - effect on command procedures, 8-3
 - effect on layered products, 5-5
 - effect on MODPARAMS.DAT, 8-4
 - effect on operator logs, 5-3
 - enabling automatic restart, 5-12
 - enabling manual reboot, 5-12
 - error entering device code, 7-5
 - files deleted by, 7-8, 7-15, 7-16
 - files purged during, 7-13
 - interrupting before Phase 1, 7-6
 - license requirements, 7-17
 - loading OpenVMS VAX distribution media, 7-3
 - manual reboot after, 7-19
 - manual reboot from [SYS0], 7-16
 - merging directory trees, 7-15
 - modifying console media, 5-12
 - modifying console media to boot from [SYSF], 7-7
 - modifying passwords, 7-6
 - OpenVMS version requirement, 5-4
 - Phase 1, 7-6
 - Phase 2, 7-14
 - Phase 3, 7-15
 - Phase 4, 7-15
 - Phase 5, 7-16
 - Phase 6, 7-17
 - processing user files, 7-15
 - recording logs, 5-5
 - registering licenses, 7-17
 - required location of save sets, 5-3
 - required location of the system disk, 7-16
 - requirement for shared dump files, 5-8
 - requirements, 5-15
 - restoring original dddGEN, 7-16
 - restoring original DEFBOO, 7-16
 - rolling upgrades, 6-3
 - adding a new CPU, 6-5
 - running AUTOGEN, 7-19
 - selecting optional components, 7-9
 - shared dump files, 5-4
 - system files renamed by, 7-8
 - time zones, 7-18
 - using a printer to record output, 5-5
 - VMSINSTAL option G warning, 5-3
 - when to use, 1-9, 2-1
- User authorization file
See UAF
- User files
processed during an upgrade, 7-15

V

- VAXcluster environments
 - building, 4-2
 - cluster group numbers, 2-4
 - cluster passwords, 2-4
 - DECwindows support components for, 3-10, 7-11
 - information required for an installation, 2-3
 - problem upgrading, 7-20
 - types of, 2-3
 - upgrade requirement for shared dump files, 5-8
- VAXcluster license
 - registering after an installation, 4-2
 - registering during an installation, 3-19
 - registering during an upgrade, 7-17
- VAXcluster quorum
 - maintaining during an upgrade, 7-20
 - maintaining during rolling upgrades, 6-4
- VAXcluster QUORUM parameter
 - setting for concurrent upgrades, 6-2
- VAXcluster upgrades
 - See Concurrent upgrades
 - See Rolling upgrades
- VAX computers
 - booting from [SYSF], C-1 to C-6
 - OpenVMS VAX support for, B-2
- VAXft computers
 - booting from [SYSF], C-1
- VAXstation computers
 - booting from [SYS0], 7-16
 - booting from [SYSF], 7-13, C-1
- VAXVMSSYS.PAR parameter files
 - conversion, 7-16
- VMB.EXE
 - copying to console media, 8-4
- VMSSAUDIT_SERVER.DAT file
 - required location, 5-8
- VMSINSTAL command procedure
 - invoking for upgrade, 7-3
 - option G warning, 2-1
- VMSTAILOR utility
 - using on a small system disk, H-4
 - using to install optional components, 3-8, 7-9, 10-3
 - using to remove files from a system disk, 4-6, 8-8, 10-3
- Volume label
 - specifying during an installation, 3-7
- Volume shadowing
 - requirements for an upgrade, 5-13
- Volume Shadowing license
 - registering after an installation, 4-2
 - registering during an installation, 3-19
 - registering during an upgrade, 7-17

VOTES parameter
 checking for rolling upgrades, 6-3
 setting for concurrent upgrades, 6-2
 upgrade requirement, 6-2

W

WELCOME.TXT file

 updating, 8-3
Workstations
 customizing, 9-2

X

X terminals
 DECwindows support components for, 3-10,
 7-11

